

z/OS  
3.2

*MVS Initialization and Tuning Reference*



**Note**

Before using this information and the product it supports, read the information in [“Notices” on page 799](#).

This edition applies to IBM® z/OS® 3.2 (5655-ZOS) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2025-09-30

© **Copyright International Business Machines Corporation 1991, 2025.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

|  |               |
|--|---------------|
| <b>Figures.....</b>  | <b>xxi</b>    |
| <b>Tables.....</b>   | <b>xxiii</b>  |
| <b>About this information.....</b>                           | <b>xxvii</b>  |
| Who should use this information.....                         | xxvii         |
| MVS workload management.....                                 | xxvii         |
| z/OS information.....  | xxvii         |
| How to read syntax conventions.....                          | xxvii         |
| <b>How to provide feedback to IBM.....</b>                   | <b>xxxix</b>  |
| <b>Summary of changes.....</b>                               | <b>xxxiii</b> |
| Summary of changes for z/OS 3.2.....                         | xxxiii        |
| Summary of changes for z/OS 3.1.....                         | xxxiv         |
| <b>Part 1. Overview.....</b>                                 | <b>1</b>      |
| Chapter 1. System tailoring.....                             | 3             |
| MVS hardware configuration definition.....                   | 3             |
| System tailoring at initialization time.....                 | 3             |
| Types of IPL.....  | 4             |
| Operator entry of parameters.....                            | 5             |
| Description and use of the parmlib concatenation.....        | 6             |
| Specifying an alternate nucleus.....                         | 8             |
| Specifying an alternate master (system) catalog.....         | 8             |
| Understanding the master scheduler job control language..... | 9             |
| Where does the master JCL reside?.....                       | 9             |
| Changing the master scheduler JCL.....                       | 9             |
| Setting up started tasks with the Master JCL.....            | 11            |
| Writing your own master scheduler JCL.....                   | 12            |
| Overview of parmlib members.....                             | 14            |
| Implicit system parameters.....                              | 25            |
| Managing system security — APF-authorized library list.....  | 26            |
| Choosing an APF list format.....                             | 26            |
| Specifying the APF list.....                                 | 27            |
| Assigning the RACF TRUSTED attribute.....                    | 28            |
| Specifying installation exits.....                           | 29            |
| Specifying LNKST concatenations.....                         | 29            |
| Chapter 2. Sharing parmlib definitions.....                  | 31            |
| Objectives for sharing parmlib.....                          | 31            |
| What are system symbols?.....                                | 31            |
| Static system symbols.....                                   | 33            |
| Dynamic system symbols.....                                  | 34            |
| Symbols reserved for system use.....                         | 36            |
| Setting up a shared parmlib.....                             | 36            |
| Step 1. Plan to share parmlib members.....                   | 37            |
| Step 2. Determine where to specify system parameters.....    | 39            |

|   |    |
|---|----|
| Step 3. Determine where to specify the system name.....         | 41 |
| Step 4. Create an IEASYMxx parmlib member.....                  | 41 |
| Step 5. Code support for system symbols in LOADxx.....          | 46 |
| Using system symbols in parmlib.....                            | 47 |
| Step 1. Know the rules for using system symbols in parmlib..... | 47 |
| Step 2. Determine where to use system symbols in parmlib.....   | 50 |
| Step 3. Verify system symbols in parmlib.....                   | 51 |
| Changing system symbols.....                                    | 52 |
| Displaying static system symbols.....                           | 55 |
| Diagnosing problems with static system symbols.....             | 55 |
| Indirect volume serial support.....                             | 55 |
| Using indirect volume serial support.....                       | 56 |
| Restrictions.....   | 57 |

## **Part 2. Members of SYS1.PARMLIB.....59**

|  |     |
|--|-----|
| Chapter 3. ADYSETxx (dump suppression).....                | 61  |
| Parameter in IEASYSxx (or supplied by the operator).....   | 61  |
| Syntax rules for ADYSETxx.....                             | 61  |
| Syntax format of ADYSETxx.....                             | 62  |
| IBM-supplied defaults for ADYSETxx.....                    | 62  |
| Statements and parameters for ADYSETxx.....                | 62  |
| Chapter 4. ALLOCxx (allocation system defaults).....       | 67  |
| Parameter in IEASYSxx (or supplied by the operator).....   | 67  |
| Syntax rules for ALLOCxx.....                              | 67  |
| Syntax format of ALLOCxx.....                              | 68  |
| Syntax example of ALLOCxx.....                             | 69  |
| IBM-supplied default for ALLOCxx.....                      | 70  |
| Statements and parameters for ALLOCxx.....                 | 70  |
| Chapter 5. ANTMIN00 (ANTMAIN control parameters).....      | 87  |
| Chapter 6. ANTGIN00 (XRC services).....                    | 89  |
| Chapter 7. APPCPMxx (define APPC/MVS configuration).....   | 91  |
| Changing values.....                                       | 91  |
| Parameter in IEASYSxx (or supplied by the operator).....   | 91  |
| Syntax rules for APPCPMxx.....                             | 91  |
| Syntax format of APPCPMxx.....                             | 92  |
| IBM-supplied default for APPCPMxx.....                     | 92  |
| Statements and parameters for APPCPMxx.....                | 92  |
| Response to errors in APPCPMxx.....                        | 96  |
| Chapter 8. ASCHPMxx (APPC/MVS transaction scheduler).....  | 97  |
| Changing values.....                                       | 97  |
| Default values.....  | 97  |
| Support for system symbols.....                            | 97  |
| Parameter in IEASYSxx (or supplied by the operator).....   | 97  |
| Syntax rules for ASCHPMxx.....                             | 98  |
| Syntax format of ASCHPMxx.....                             | 98  |
| IBM-supplied default for ASCHPMxx.....                     | 98  |
| Statements and parameters for ASCHPMxx.....                | 98  |
| Chapter 9. AUTORxx (auto-reply policy specifications)..... | 103 |
| Parameter in IEASYSxx (or supplied by the operator).....   | 103 |
| Syntax rules for AUTORxx.....                              | 103 |

|  |     |
|--|-----|
| Syntax format of AUTORxx.....  | 103 |
| Syntax example of AUTORxx.....   | 103 |
| IBM-supplied default for AUTORxx.....  | 104 |
| Statements and parameters for AUTORxx.....   | 104 |
| Chapter 10. AXRxx (system REXX options).....                                       | 107 |
| Parameter in IEASYSxx (or supplied by the operator).....                           | 107 |
| Syntax rules for AXRxx.....  | 107 |
| Syntax format of AXRxx.....  | 107 |
| IBM-supplied default for AXRxx.....  | 107 |
| Statements and parameters for AXRxx.....   | 107 |
| Chapter 11. BLSCECT (formatting exits for dump and trace analysis).....            | 109 |
| Parameter in IEASYSxx (or supplied by the operator).....                           | 109 |
| Syntax rules for BLSCECT.....  | 109 |
| IBM-supplied default for BLSCECT.....  | 109 |
| Statements and parameters for BLSCECT.....   | 109 |
| Chapter 12. BLSCUSER (installation customization for dump and trace analysis)..... | 111 |
| Parameter in IEASYSxx (or issued by the operator).....                             | 111 |
| Syntax rules for BLSCUSER.....   | 111 |
| Syntax format of BLSCUSER.....   | 112 |
| IBM-supplied default for BLSCUSER.....   | 112 |
| Statements and parameters for BLSCUSER, BLSCECT, and embedded parmlib members..... | 113 |
| Chapter 13. BPXPRMxx (z/OS UNIX System Services parameters).....                   | 123 |
| Syntax rules for BPXPRMxx.....   | 123 |
| Syntax format of BPXPRMxx.....   | 125 |
| Syntax example of BPXPRMxx.....  | 126 |
| IBM-supplied default for BPXPRMxx.....   | 128 |
| Statements and parameters for BPXPRMxx.....  | 128 |
| Chapter 14. CEAPRMxx (common event adapter parameters).....                        | 159 |
| Syntax rules for CEAPRMxx.....   | 159 |
| Syntax format of CEAPRMxx.....   | 159 |
| IBM-supplied defaults for CEAPRMxx.....  | 160 |
| Statements and parameters for CEAPRMxx.....  | 160 |
| Examples of CEAPRMxx parmlib member.....   | 163 |
| Chapter 15. CEEPRMxx (runtime option parameters).....                              | 165 |
| Parameter in IEASYSxx (or supplied by the operator).....                           | 165 |
| Syntax rules for CEEPRMxx.....   | 165 |
| Syntax format of CEEPRMxx.....   | 166 |
| IBM-supplied default for CEEPRMxx.....   | 166 |
| Statements and parameters for CEEPRMxx.....  | 166 |
| Example of CEEPRMxx parmlib member.....  | 167 |
| Chapter 16. CLOCKxx (time of day parameters).....                                  | 171 |
| Parameter in IEASYSxx (or supplied by the operator).....                           | 171 |
| Syntax rules for CLOCKxx.....  | 171 |
| Syntax format of CLOCKxx.....  | 172 |
| IBM-supplied default for CLOCKxx.....  | 172 |
| Statements and parameters for CLOCKxx.....   | 172 |
| Chapter 17. CNGRPxx (specify console groups).....                                  | 177 |
| Console groups in a sysplex.....   | 177 |
| Selecting a CNGRPxx member.....  | 177 |
| Syntax rules for CNGRPxx.....  | 177 |

|   |     |
|---|-----|
| Syntax format of CNGRPxx.....   | 177 |
| IBM-supplied default for CNGRPxx.....                                       | 178 |
| Statement and parameters for CNGRPxx.....                                   | 178 |
| Chapter 18. CNLcccxx (time and date format for translated messages).....    | 179 |
| Restrictions for CNLcccxx.....  | 179 |
| Parameter in IEASYSxx (or supplied by the operator).....                    | 179 |
| Selecting a CNLcccxx member.....  | 179 |
| Syntax rules for CNLcccxx.....  | 180 |
| Syntax format of CNLcccxx.....  | 180 |
| Syntax example of CNLcccxx.....   | 180 |
| Statements and parameters for CNLcccxx.....                                 | 181 |
| Chapter 19. COFDLFxx (hiperbatch parameters).....                           | 185 |
| Parameter in IEASYSxx (or issued by the operator).....                      | 185 |
| Syntax rules for COFDLFxx.....  | 185 |
| Syntax format of COFDLFxx.....  | 186 |
| Starting DLF.....   | 186 |
| Statements and parameters for COFDLFxx.....                                 | 186 |
| Chapter 20. COFVLFxx (virtual lookaside facility parameters).....           | 187 |
| Collecting VLF statistics.....  | 188 |
| Parameter in IEASYSxx (or issued by the operator).....                      | 188 |
| Syntax rules for COFVLFxx.....  | 188 |
| Syntax format of COFVLFxx.....  | 189 |
| Starting VLF.....   | 189 |
| Statements and parameters for COFVLFxx.....                                 | 189 |
| Chapter 21. COMMNDxx (commands automatically issued at initialization)..... | 191 |
| Parameter in IEASYSxx (or issued by the operator).....                      | 191 |
| Support for system symbols.....   | 192 |
| Syntax rules for COMMNDxx.....  | 192 |
| IBM-supplied default for COMMNDxx.....                                      | 192 |
| Statements and parameters for COMMNDxx.....                                 | 192 |
| Chapter 22. CONFIGxx (standard configuration list).....                     | 193 |
| Comparing the current and standard configurations.....                      | 193 |
| Matching configurations.....  | 193 |
| Nonmatching configurations.....   | 193 |
| Error in CONFIGxx statement.....  | 193 |
| Reconfiguring system elements.....  | 194 |
| Parameter in IEASYSxx:.....   | 194 |
| Syntax rules for CONFIGxx.....  | 194 |
| IBM-supplied default for CONFIGxx.....                                      | 194 |
| Statements and parameters for CONFIGxx.....                                 | 195 |
| Chapter 23. CONSOLxx (console configuration definition).....                | 201 |
| Using CONSOLxx in a sysplex.....  | 201 |
| Related members of parmlib.....   | 202 |
| Related commands.....   | 202 |
| CONSOLE statement.....  | 203 |
| INIT statement.....   | 203 |
| HARDCOPY statement.....   | 204 |
| DEFAULT statement.....  | 204 |
| Parameter in IEASYSxx (or supplied by the operator).....                    | 205 |
| Syntax rules for CONSOLxx.....  | 205 |
| IBM-supplied default for CONSOLxx.....                                      | 206 |
| Statements and parameters for CONSOLxx.....                                 | 206 |

|   |     |
|---|-----|
| Syntax and parameters for the CONSOLE statement.....                        | 206 |
| Syntax and parameters for the DEFAULT statement.....                        | 218 |
| Syntax and parameters for the HARDCOPY statement.....                       | 220 |
| Syntax and parameters for an INIT statement.....                            | 222 |
| Devices used as MCS consoles.....   | 226 |
| Maximum and default specifications for AREA and SEG.....                    | 227 |
| Chapter 24. COUPLExx (cross-system coupling facility (XCF) parameters)..... | 229 |
| Parameter in IEASYSxx (or supplied by the operator).....                    | 229 |
| Syntax rules for COUPLExx.....  | 229 |
| Syntax format of COUPLExx.....  | 230 |
| IBM-supplied default for COUPLExx.....                                      | 230 |
| Statements and parameters for COUPLExx.....                                 | 230 |
| Chapter 25. CSVLLAxx (library lookaside (LLA) list).....                    | 243 |
| Starting LLA.....   | 243 |
| Parameter in IEASYSxx (or supplied by the operator).....                    | 243 |
| Syntax rules for CSVLLAxx.....  | 243 |
| Syntax format of CSVLLAxx.....  | 244 |
| Statements and parameters for CSVLLAxx.....                                 | 244 |
| Chapter 26. CTnccccx (component trace parameters).....                      | 249 |
| Tracing of MVS components.....  | 249 |
| Tracing of installation-provided applications.....                          | 249 |
| Parameter in IEASYSxx (or supplied by the operator).....                    | 249 |
| Syntax rules for CTnccccx.....  | 249 |
| Syntax examples.....  | 250 |
| Syntax format of CTnccccx.....  | 251 |
| IBM-supplied default for CTnccccx.....                                      | 251 |
| Statements and parameters for CTnccccx.....                                 | 251 |
| Chapter 27. CUNUNIx (Unicode Services environment).....                     | 255 |
| Selecting a CUNUNIx member.....   | 255 |
| Parameter in IEASYSxx.....  | 255 |
| Syntax rules for CUNUNIx.....   | 255 |
| Syntax format of CUNUNIx.....   | 256 |
| IBM-supplied default for CUNUNIx.....                                       | 256 |
| Statements and parameters for CUNUNIx.....                                  | 256 |
| Samples for parmlib member CUNUNIx.....                                     | 266 |
| Chapter 28. DEVSUPxx (device support options).....                          | 267 |
| Enhanced security for tape data sets.....                                   | 267 |
| Parameter in IEASYSxx (or issued by the operator).....                      | 268 |
| Syntax rules for DEVSUPxx.....  | 269 |
| Syntax format of DEVSUPxx.....  | 269 |
| IBM-supplied defaults for DEVSUPxx.....                                     | 270 |
| Statements and parameters for DEVSUPxx.....                                 | 271 |
| Volume partitioning parameters.....   | 289 |
| Chapter 29. DFHSSIx (message-formatting initialization member).....         | 293 |
| Chapter 30. DIAGxx (control common storage tracking and GFS trace).....     | 295 |
| Specifying the DIAGxx members.....  | 295 |
| Parameter in IEASYSxx (or specified by the operator).....                   | 296 |
| Syntax rules for DIAGxx.....  | 296 |
| Syntax format of DIAGxx.....  | 297 |
| IBM-supplied default for DIAGxx.....  | 297 |
| Statements and parameters for DIAGxx.....                                   | 298 |

|   |     |
|---|-----|
| Chapter 31. EXITxx (allocation installation exit list).....                   | 311 |
| Parameter in IEASYSxx (or issued by the operator).....                        | 311 |
| Syntax rules for EXITxx.....  | 312 |
| Syntax format of EXITxx.....  | 312 |
| IBM-supplied default for EXITxx.....  | 312 |
| Statements and parameters for EXITxx.....                                     | 312 |
| Chapter 32. EXSPATxx (excessive spin condition actions).....                  | 313 |
| Parameter in IEASYSxx (or issued by the operator).....                        | 313 |
| Syntax rules for EXSPATxx.....  | 313 |
| Syntax example of EXSPATxx.....   | 313 |
| IBM-supplied default for EXSPATxx.....  | 314 |
| Statements and parameters for EXSPATxx.....                                   | 314 |
| Example of EXSPATxx.....  | 315 |
| Chapter 33. FXEPRMxx (IBM Function Registry for z/OS).....                    | 317 |
| Parameter in IEASYSxx (or issued by the operator).....                        | 317 |
| Syntax rules for FXEPRMxx.....  | 317 |
| Syntax format of FXEPRMxx.....  | 317 |
| IBM-supplied default for FXEPRMxx.....  | 317 |
| Statements and parameters for FXEPRMxx.....                                   | 317 |
| Chapter 34. GRSCNFxx (global resource serialization configuration).....       | 319 |
| Parameters in IEASYSxx.....   | 320 |
| Syntax rules for GRSCNFxx.....  | 320 |
| IBM-supplied default for GRSCNFxx.....  | 321 |
| Statements and parameters for GRSCNFxx.....                                   | 321 |
| Chapter 35. GRSMONxx (global resource serialization monitor).....             | 325 |
| Parameters in IEASYSxx.....   | 325 |
| Syntax rules for GRSMONxx.....  | 325 |
| Syntax format of GRSMONxx.....  | 327 |
| IBM-supplied default for GRSMONxx.....  | 327 |
| Statements and parameters for GRSMONxx.....                                   | 327 |
| Chapter 36. GRSRNLxx (global resource serialization resource name lists)..... | 331 |
| Parameter in IEASYSxx (or supplied by the operator).....                      | 331 |
| Support for system symbols.....   | 331 |
| Syntax rules for GRSRNLxx.....  | 331 |
| IBM-supplied default for GRSRNLxx.....  | 333 |
| Statements and parameters for GRSRNLxx.....                                   | 333 |
| Chapter 37. GTFARM (generalized trace facility parameters).....               | 335 |
| Parameter in IEASYSxx (or issued by the operator).....                        | 335 |
| Syntax rules for GTFARM.....  | 335 |
| IBM-supplied default for GTFARM.....  | 337 |
| Statements and parameters for GTFARM.....                                     | 337 |
| Chapter 38. GTZPRMxx (Generic Tracker parameters).....                        | 339 |
| Parameters in IEASYSxx (or supplied by the operator).....                     | 339 |
| Syntax rules for GTZPRMxx.....  | 339 |
| Syntax format of GTZPRMxx.....  | 340 |
| IBM-supplied default for GTZPRMxx.....  | 340 |
| Statements and parameters for GTZPRMxx.....                                   | 340 |
| Chapter 39. HZSPRMxx (manage IBM Health Checker for z/OS checks).....         | 351 |



|   |     |
|---|-----|
| Chapter 40. IARPRMxx (Real Storage Manager controls).....         | 353 |
| Specifying the IARPRMxx members.....                              | 353 |
| Parameter in IEASYSxx (or specified by the operator).....         | 353 |
| Syntax rules for IARPRMxx.....                                    | 353 |
| Syntax format of IARPRMxx.....                                    | 353 |
| Statements and parameters for IARPRMxx.....                       | 353 |
| Example of IARPRMxx parmlib member.....                           | 354 |
| Chapter 41. IDAVDTxx (VSAM dynamic trace parameters).....         | 355 |
| Syntax rules for IDAVDTxx.....                                    | 355 |
| Syntax format for IDAVDTxx.....                                   | 355 |
| IBM-supplied defaults for IDAVDTxx.....                           | 355 |
| Statements and parameters for IDAVDTxx.....                       | 355 |
| Examples of IDAVDTxx parmlib member.....                          | 356 |
| Chapter 42. IEAABD00 (ABDUMP written to a SYSABEND data set)..... | 357 |
| Parameter in IEASYSxx (or specified by the operator).....         | 357 |
| Syntax rules for IEAABD00.....                                    | 357 |
| IBM-supplied default for IEAABD00.....                            | 358 |
| Statements and parameters for IEAABD00.....                       | 358 |
| Chapter 43. IEAAPFxx (authorized program facility list).....      | 361 |
| Parameter in IEASYSxx (or supplied by the operator).....          | 362 |
| Syntax rules for IEAAPFxx.....                                    | 362 |
| IBM-supplied default for IEAAPFxx.....                            | 363 |
| Statements and parameters for IEAAPFxx.....                       | 363 |
| Chapter 44. IEAAPP00 (authorized I/O appendage routines).....     | 365 |
| Syntax rules for IEAAPP00.....                                    | 365 |
| IBM-supplied default for IEAAPP00.....                            | 365 |
| Statements and parameters for IEAAPP00.....                       | 365 |
| Chapter 45. IEACMD00 (IBM-supplied commands).....                 | 367 |
| Parameter in IEASYSxx (or supplied by the operator).....          | 368 |
| Syntax rules for IEACMD00.....                                    | 368 |
| IBM-supplied default for IEACMD00.....                            | 368 |
| Statements and parameters for IEACMD00.....                       | 368 |
| Chapter 46. IEADMCxx (DUMP command parmlib).....                  | 369 |
| Performance implications.....                                     | 369 |
| Syntax rules for IEADMCxx.....                                    | 369 |
| Syntax format of IEADMCxx.....                                    | 369 |
| IBM-supplied default for IEADMCxx.....                            | 369 |
| Statements and parameters for IEADMCxx.....                       | 369 |
| Chapter 47. IEADMP00 (ABDUMP written to a SYSUDUMP data set)..... | 373 |
| Parameter in IEASYSxx (or specified by the operator).....         | 373 |
| Syntax rules for IEADMP00.....                                    | 373 |
| IBM-supplied default for IEADMP00.....                            | 374 |
| Statements and parameters for IEADMP00.....                       | 374 |
| Chapter 48. IEADMR00 (ABDUMP written to a SYSMDUMP data set)..... | 377 |
| Recommendation for IEADMR00 with z/OS UNIX.....                   | 377 |
| Parameter in IEASYSxx (or specified by the operator).....         | 377 |
| Syntax rules for IEADMR00.....                                    | 377 |
| IBM-supplied default for IEADMR00.....                            | 378 |
| Statements and parameters for IEADMR00.....                       | 378 |

|   |     |
|---|-----|
| Chapter 49. IEAFIXxx (fixed LPA list).....                          | 379 |
| Parameter in IEASYSxx (or specified by the operator).....           | 379 |
| Syntax rules for IEAFIXxx.....                                      | 380 |
| Syntax format of IEAFIXxx.....                                      | 380 |
| Syntax example of IEAFIXxx.....                                     | 380 |
| IBM-supplied default for IEAFIXxx.....                              | 381 |
| Statements and parameters for IEAFIXxx.....                         | 381 |
| Chapter 50. IEALPAXx (modified LPA list).....                       | 383 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 383 |
| Syntax rules for IEALPAXx.....                                      | 384 |
| Syntax format of IEALPAXx.....                                      | 384 |
| Syntax example of IEALPAXx.....                                     | 384 |
| IBM-supplied default for IEALPAXx.....                              | 384 |
| Statements and parameters for IEALPAXx.....                         | 385 |
| Chapter 51. IEAOPTxx (OPT parameters).....                          | 387 |
| Syntax rules for IEAOPTxx.....                                      | 388 |
| IBM-supplied default for IEAOPTxx.....                              | 388 |
| Statements and parameters for IEAOPTxx.....                         | 388 |
| Chapter 52. IEAPAKxx (LPA pack list).....                           | 403 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 403 |
| Syntax rules for IEAPAKxx.....                                      | 403 |
| IBM-supplied default for IEAPAKxx.....                              | 404 |
| Statements and parameters for IEAPAKxx.....                         | 404 |
| Chapter 53. IEASLPxx (SLIP commands).....                           | 405 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 405 |
| Syntax rules for IEASLPxx.....                                      | 405 |
| IBM-supplied default for IEASLPxx.....                              | 406 |
| Using system commands.....  | 406 |
| Chapter 54. IEASVCxx (installation-defined SVCs).....               | 409 |
| Parameter in IEASYSxx (or entered by the operator).....             | 409 |
| Syntax rules for IEASVCxx.....                                      | 409 |
| Syntax examples of IEASVCxx.....                                    | 409 |
| IBM-supplied default for IEASVCxx.....                              | 409 |
| Statements and parameters for IEASVCxx.....                         | 410 |
| Chapter 55. IEASYMxx (symbol definitions and IEASYSxx members)..... | 413 |
| Parameter in LOADxx.....  | 413 |
| Performance implications.....                                       | 413 |
| Syntax rules for IEASYMxx.....                                      | 413 |
| Syntax format of IEASYMxx.....                                      | 414 |
| IBM-supplied default for IEASYMxx.....                              | 414 |
| Statements and parameters for IEASYMxx.....                         | 414 |
| Chapter 56. IEASYSxx (system parameter list).....                   | 421 |
| Overview of IEASYSxx parameters.....                                | 421 |
| Changes to initialization parameters.....                           | 425 |
| Support for system symbols.....                                     | 425 |
| Parameter specified by the operator.....                            | 426 |
| Syntax rules for IEASYSxx.....                                      | 426 |
| IBM-supplied default for IEASYSxx.....                              | 427 |
| Specifying the list option for IEASYSxx parameters.....             | 427 |
| Statements and parameters for IEASYSxx.....                         | 427 |

|               |     |
|---------------|-----|
| ALLOC.....    | 427 |
| APF.....      | 428 |
| AUTOR.....    | 428 |
| AXR.....      | 428 |
| BOOST.....    | 429 |
| CATALOG.....  | 430 |
| CEA.....      | 430 |
| CEE.....      | 430 |
| CLOCK.....    | 430 |
| CLPA.....     | 431 |
| CMB.....      | 431 |
| CMD.....      | 432 |
| CON.....      | 433 |
| COUPLE.....   | 433 |
| CRYPCTRS..... | 434 |
| CSA.....      | 434 |
| CSCBLOC.....  | 435 |
| CVIO.....     | 436 |
| DEVSUP.....   | 436 |
| DIAG.....     | 436 |
| DRMODE.....   | 436 |
| DUMP.....     | 437 |
| EXIT.....     | 438 |
| FIX.....      | 438 |
| FXE.....      | 439 |
| GRS.....      | 439 |
| GRSCNF.....   | 440 |
| GRSRNL.....   | 440 |
| GTZ.....      | 441 |
| HVCOMMON..... | 441 |
| HVSHARE.....  | 442 |
| HZS.....      | 442 |
| HZSPROC.....  | 442 |
| ICSF.....     | 443 |
| ICSFPROC..... | 443 |
| IEFOPZ.....   | 443 |
| IKJTSO.....   | 444 |
| IOS.....      | 444 |
| IQP.....      | 444 |
| IXGCNF.....   | 444 |
| IZU.....      | 445 |
| LFAREA.....   | 445 |
| LICENSE.....  | 449 |
| LNK.....      | 450 |
| LNKAUTH.....  | 450 |
| LOGCLS.....   | 450 |
| LOGLMT.....   | 451 |
| LOGREC.....   | 451 |
| LPA.....      | 452 |
| MAXCAD.....   | 453 |
| MAXUSER.....  | 453 |
| MLPA.....     | 454 |
| MSTRJCL.....  | 455 |
| NONVIO.....   | 455 |
| NSYSLX.....   | 456 |
| OMVS.....     | 457 |
| OPI.....      | 457 |
| OPT.....      | 458 |

|   |     |
|---|-----|
| OSPROTECT.....  | 459 |
| PAGE.....   | 459 |
| PAGESCM.....  | 462 |
| PAGTOTL.....  | 462 |
| PAK.....  | 464 |
| PLEXCFG.....  | 464 |
| PRESCPU.....  | 465 |
| PROD.....   | 465 |
| PROG.....   | 466 |
| RACF.....   | 467 |
| RDE.....  | 467 |
| REAL.....   | 467 |
| RER.....  | 468 |
| RSM.....  | 468 |
| RSU.....  | 468 |
| RSVNONR.....  | 470 |
| RSVSTRT.....  | 471 |
| RUCSA.....  | 471 |
| SCH.....  | 472 |
| SMF.....  | 473 |
| SMFTBUFF .....  | 473 |
| SMS.....  | 473 |
| SOLUT.....  | 474 |
| SQA.....  | 474 |
| SSN.....  | 476 |
| SVC.....  | 476 |
| SYSNAME.....  | 476 |
| SYSP .....  | 477 |
| UNI.....  | 478 |
| VAL.....  | 478 |
| VIODSN.....   | 479 |
| VRREGN.....   | 479 |
| WARNUND.....  | 480 |
| WORKINST.....   | 480 |
| ZAAPZIIP.....   | 480 |
| Chapter 57. IECIOSxx (I/O related parameters).....        | 483 |
| Parameter in IEASYSxx (or specified by the operator)..... | 483 |
| IBM-supplied default for IECIOSxx.....                    | 484 |
| Syntax rules for IECIOSxx.....                            | 484 |
| Missing interrupt handler (MIH).....                      | 484 |
| I/O timing.....   | 485 |
| Interaction of MIH and I/O timing processing.....         | 486 |
| I/O timing trigger for HyperSwap.....                     | 486 |
| Statements and parameters for MIH.....                    | 487 |
| Hot I/O (HOTIO).....                                      | 492 |
| Options for HOTIO recovery.....                           | 494 |
| TERMINAL.....   | 494 |
| CTRACE.....   | 495 |
| FICON.....  | 495 |
| STORAGE.....  | 496 |
| CAPTUCB.....  | 496 |
| MIDAW.....  | 496 |
| HYPERPAV.....   | 496 |
| HYPERWRITE.....   | 497 |
| EKM.....  | 497 |
| RECOVERY .....  | 500 |
| DCCF usage.....   | 500 |

|  |     |
|--|-----|
| Limited recovery time.....   | 500 |
| Path recovery.....   | 501 |
| Statements and parameters for RECOVERY .....                               | 503 |
| Syntax example.....  | 504 |
| SPOF.....  | 504 |
| ZHPF.....  | 504 |
| ZHPFOPTS.....  | 505 |
| ZHYPERLINK.....  | 505 |
| Syntax examples for IECIOSxx.....  | 506 |
| Chapter 58. IEFOPZxx (data set optimization configuration).....            | 507 |
| Parameter in IEASYSxx (or supplied by the operator).....                   | 507 |
| Syntax rules for IEFOPZxx.....   | 507 |
| Syntax format of IEFOPZxx.....   | 507 |
| IBM-supplied default for IEFOPZxx.....                                     | 508 |
| Statements and parameters for IEFOPZxx.....                                | 508 |
| Usage notes for IEFOPZxx.....  | 514 |
| Chapter 59. IEFSSNxx (subsystem definitions) - keyword parameter form..... | 515 |
| Restrictions for IEFSSNxx.....   | 515 |
| Parameter in IEASYSxx (or supplied by the operator).....                   | 516 |
| Syntax rules for IEFSSNxx.....   | 517 |
| IBM-supplied default for IEFSSNxx.....                                     | 517 |
| Statements and parameters for IEFSSNxx.....                                | 517 |
| Examples of IEFSSNxx member.....   | 519 |
| Chapter 60. IFAPRDxx (product enablement policy).....                      | 521 |
| Before creating the member.....  | 521 |
| Usage considerations.....  | 522 |
| Parameter in IEASYSxx (or issued by the operator).....                     | 522 |
| Syntax rules for IFAPRDxx.....   | 522 |
| Syntax format of IFAPRDxx.....   | 523 |
| IBM-supplied default for IFAPRDxx.....                                     | 523 |
| Statements and parameters for IFAPRDxx.....                                | 523 |
| Examples of IFAPRDxx statements.....                                       | 527 |
| Chapter 61. IFGPSEDI (enhanced data integrity).....                        | 529 |
| Syntax rules for IFGPSEDI.....   | 529 |
| Syntax examples.....   | 529 |
| Syntax format of IFGPSEDI.....   | 529 |
| IBM-supplied default for IFGPSEDI.....                                     | 530 |
| Statements and parameters for IFGPSEDI.....                                | 530 |
| Chapter 62. IGDSMSxx (storage management subsystem definition).....        | 531 |
| Parameter in IEASYSxx.....   | 531 |
| Defining SMS through the IEFSSNxx member.....                              | 531 |
| Example of an SMS record in IEFSSNxx.....                                  | 532 |
| Starting SMS - at IPL and afterward.....                                   | 533 |
| Specifying SMS parameters through SETSMS and SET SMS.....                  | 533 |
| Syntax rules for IGDSMSxx.....   | 533 |
| Syntax format of IGDSMSxx.....   | 533 |
| IBM-supplied default for IGDSMSxx.....                                     | 535 |
| Required keywords for IGDSMSxx.....  | 535 |
| Optional keywords for IGDSMSxx.....  | 535 |
| Examples of the contents of IGDSMSxx.....                                  | 561 |
| Examples of specifying DFSMSStvs parameters.....                           | 563 |
| Chapter 63. IGGCATxx (DFSMS catalog configuration).....                    | 565 |

|   |     |
|---|-----|
| Parameter in IEASYSxx (or specified by the operator).....           | 565 |
| Syntax rules for IGGCATxx.....                                      | 565 |
| Syntax format of IGGCATxx.....                                      | 566 |
| Statements and parameters for IGGCATxx.....                         | 567 |
| Chapter 64. IKJTSOxx (TSO/E commands and programs).....             | 571 |
| Parameter in IEASYSxx (or specified by the operator).....           | 571 |
| Selecting the IKJTSOxx member.....                                  | 571 |
| Syntax rules for IKJTSOxx.....                                      | 572 |
| Syntax format of IKJTSOxx.....                                      | 573 |
| IBM-supplied default for IKJTSOxx.....                              | 573 |
| Statements and parameters for IKJTSOxx.....                         | 573 |
| Chapter 65. IOEPRMxx (z/OS File System parameters).....             | 585 |
| Specifying the IOEPRMxx concatenation.....                          | 585 |
| Syntax rules for IOEPRMxx.....                                      | 585 |
| Chapter 66. IPCSPRnn (Interactive Problem Control System).....      | 587 |
| Parameter in IEASYSxx (or specified by the operator).....           | 587 |
| Syntax rules for IPCSPRnn.....                                      | 587 |
| IBM-supplied default for IPCSPRnn.....                              | 587 |
| Statements and parameters for IPCSPRnn.....                         | 587 |
| Chapter 67. IQPPRMxx (PCIE related parameters).....                 | 589 |
| Parameter in IEASYSxx (or specified by the operator).....           | 589 |
| Syntax rules for IQPPRMxx.....                                      | 589 |
| Statements and parameters for IQPPRMxx.....                         | 589 |
| Chapter 68. IRRPRMxx (RACF parameters).....                         | 591 |
| IBM-supplied default for IRRPRMxx.....                              | 591 |
| Chapter 69. IVTPRM00 (Communication Storage Manager).....           | 593 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 593 |
| Syntax format of IVTPRM00.....                                      | 593 |
| Syntax rules for IVTPRM00.....                                      | 593 |
| IBM-supplied defaults for IVTPRM00.....                             | 593 |
| Statements and parameters for IVTPRM00.....                         | 594 |
| Chapter 70. IXGCNFxx (system logger initialization parameters)..... | 597 |
| Specifying the IXGCNFxx members.....                                | 597 |
| Related members in parmlib.....                                     | 598 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 598 |
| Syntax rules for IXGCNFxx.....                                      | 598 |
| IBM-supplied defaults for IXGCNFxx.....                             | 598 |
| Syntax format of IXGCNFxx.....                                      | 599 |
| Statements and parameters for IXGCNFxx.....                         | 599 |
| Examples of IXGCNFxx member.....                                    | 608 |
| Chapter 71. IZUPRMxx (configure IBM z/OS Management Facility).....  | 609 |
| Chapter 72. LNKLSTxx (LNKLST concatenation).....                    | 611 |
| Using PROGxx to define LNKLST concatenations.....                   | 611 |
| Using LNKLSTxx.....   | 611 |
| Parameter in IEASYSxx (or supplied by the operator).....            | 611 |
| Syntax rules for LNKLSTxx.....                                      | 611 |
| Syntax format of LNKLSTxx.....                                      | 612 |
| Syntax example of LNKLSTxx.....                                     | 612 |
| IBM-supplied default for LNKLSTxx.....                              | 612 |

|   |     |
|---|-----|
| IBM-supplied sample for LNKLTxx.....  | 612 |
| Chapter 73. LOADxx (system configuration data sets).....                          | 613 |
| Placement of LOADxx.....  | 613 |
| Copying LOADxx members.....   | 614 |
| Filtering with LOADxx.....  | 614 |
| Filtering example.....  | 615 |
| Parameter in IEASYSxx (or supplied by the operator).....                          | 617 |
| Support for system symbols.....   | 617 |
| Syntax rules for LOADxx.....  | 617 |
| Syntax format of LOADxx.....  | 617 |
| IBM-supplied default for LOADxx.....  | 618 |
| Statements and parameters for LOADxx.....   | 618 |
| Example of parmlib concatenation.....   | 634 |
| Chapter 74. LPALSTxx (LPA library list).....                                      | 635 |
| Parameter in IEASYSxx (or supplied by the operator).....                          | 635 |
| Syntax rules for LPALSTxx.....  | 635 |
| Syntax format of LPALSTxx.....  | 636 |
| Syntax example of LPALSTxx.....   | 636 |
| IBM-supplied default for LPALSTxx.....  | 637 |
| Statements and parameters for LPALSTxx.....                                       | 637 |
| Chapter 75. MMSLTxx (MVS message service list).....                               | 639 |
| Selecting an MMSLTxx member.....  | 639 |
| Parameter in IEASYSxx.....  | 639 |
| Sample MMSLTxx member.....  | 639 |
| Syntax rules for MMSLTxx.....   | 639 |
| Syntax format of MMSLTxx.....   | 639 |
| Syntax example for MMSLTxx.....   | 640 |
| IBM-supplied default for MMSLTxx.....   | 640 |
| Statements and parameters for MMSLTxx.....  | 640 |
| Chapter 76. MPFLTxx (message processing facility list).....                       | 643 |
| Parameter in IEASYSxx.....  | 643 |
| Syntax rules for MPFLTxx.....   | 643 |
| Selecting MPFLTxx members.....  | 644 |
| IBM-supplied MPFLTxx member.....  | 644 |
| Controlling message presentation through MPFLTxx.....                             | 644 |
| Syntax for controlling message presentation.....                                  | 644 |
| IBM-supplied defaults for .MSGCOLR.....   | 644 |
| Displaying the message presentation attributes for the current MPFLTxx.....       | 645 |
| MPFLTxx parameters for controlling message presentation.....                      | 645 |
| Controlling message management.....   | 647 |
| Specifying message management.....  | 647 |
| Syntax for controlling message management.....                                    | 648 |
| IBM-supplied defaults for message management.....                                 | 649 |
| Listing the message processing attributes for the current MPFLTxx.....            | 649 |
| Using other methods to suppress messages.....                                     | 649 |
| Controlling foreign message management.....                                       | 649 |
| Syntax for controlling message management.....                                    | 649 |
| Syntax rules for the .FORNSSI statement.....                                      | 650 |
| IBM-supplied defaults for foreign message management.....                         | 650 |
| Displaying the foreign message processing attributes for the current MPFLTxx..... | 650 |
| MPFLTxx parameters for managing foreign messages.....                             | 650 |
| Controlling verbose message production.....                                       | 650 |
| Syntax for controlling the production of verbose messages.....                    | 651 |
| Syntax rules for the .MSGOPTION statement.....                                    | 651 |

|   |     |
|---|-----|
| IBM-supplied default for verbose message production.....                        | 651 |
| Displaying the verbose message production setting for the current MPFLSTxx..... | 651 |
| MPFLSTxx parameters for managing verbose message production.....                | 651 |
| Statements and parameters for MPFLSTxx.....                                     | 651 |
| Controlling command processing using MPFLSTxx.....                              | 657 |
| MPFLSTxx parameters for controlling command processing.....                     | 658 |
| Deactivating a command exit.....  | 658 |
| Approaches to message suppression using MPFLSTxx.....                           | 659 |
| Conservative list of suppressible non-JES messages.....                         | 659 |
| Aggressive list of suppressible non-JES messages.....                           | 660 |
| Conservative list of suppressible JES2 messages.....                            | 661 |
| Aggressive list of suppressible JES2 messages.....                              | 661 |
| Conservative list of suppressible JES3 messages.....                            | 661 |
| Examples of MPFLSTxx members.....   | 662 |
| Chapter 77. MSGFLDxx (message flood automation parameters).....                 | 665 |
| Parameter in IEASYSxx (or issued by the operator).....                          | 665 |
| Syntax rules for MSGFLDxx.....  | 665 |
| IBM-supplied default for MSGFLDxx.....  | 666 |
| Statements and parameters for MSGFLDxx.....                                     | 667 |
| Syntax of the comment statement.....  | 667 |
| Syntax and parameters of the msgtype statement.....                             | 667 |
| Syntax and parameters of the DEFAULT statement.....                             | 668 |
| Syntax and parameters of the DEFAULTCMD statement.....                          | 669 |
| Syntax and parameters of the JOB statement.....                                 | 670 |
| Syntax and parameters of the MSG statement.....                                 | 671 |
| Syntax example.....   | 672 |
| Exempting messages from processing by message flood automation.....             | 673 |
| Chapter 78. MSTJCLxx (master scheduler JCL).....                                | 675 |
| Parameter in IEASYSxx (or supplied by the operator).....                        | 675 |
| Performance implications.....   | 675 |
| Support for system symbols.....   | 675 |
| Syntax rules for MSTJCLxx.....  | 675 |
| IBM-supplied default for MSTJCLxx.....  | 676 |
| Statements and parameters for MSTJCLxx.....                                     | 676 |
| Chapter 79. NUCLSTxx (customizing the nucleus region).....                      | 677 |
| Adding and deleting modules.....  | 677 |
| Contradictory specifications.....   | 677 |
| Restrictions.....   | 677 |
| NUCLSTxx compared with NMLDEF.....  | 677 |
| Relationship to the LOADxx member.....  | 678 |
| Placement of NUCLSTxx.....  | 678 |
| NUCLSTxx specification in LOADxx member.....                                    | 678 |
| Parameter in IEASYSxx (or supplied by the operator).....                        | 678 |
| Syntax rules for NUCLSTxx.....  | 678 |
| Syntax format of NUCLSTxx.....  | 679 |
| IBM-supplied default for NUCLSTxx.....  | 679 |
| Statements and parameters for NUCLSTxx.....                                     | 679 |
| Example of replacing modules.....   | 679 |
| Chapter 80. PFKTABxx (program function key table definition).....               | 681 |
| Parameter in IEASYSxx (or entered by the operator).....                         | 681 |
| Syntax rules for PFKTABxx.....  | 681 |
| Using the display command.....  | 681 |
| IBM-supplied default for PFKTABxx.....  | 682 |
| Statements and parameters for PFKTABxx.....                                     | 682 |



|   |     |
|---|-----|
| Chapter 81. PROGxx (authorized program list, exits, LNKLST sets and LPA).....             | 685 |
| Using the APF statement.....  | 685 |
| Defining aliases in the APF list.....   | 686 |
| Using the IEAAPFPR exec.....  | 686 |
| Using the EXIT statement.....   | 686 |
| Using the SYSLIB statement.....   | 687 |
| Using the LNKLST statement.....   | 688 |
| Using PROGxx instead of LNKLSTxx.....   | 689 |
| Using LNKLST processing.....  | 689 |
| Changing the current LNKLST set.....  | 689 |
| Concatenating data sets to the LNKLST concatenation.....                                  | 690 |
| APF authorization for LNKLST data sets.....   | 691 |
| Cataloging LNKLST data sets.....  | 691 |
| Modifying the contents of LNKLST data sets.....   | 691 |
| Removing an XCFAS ENQ.....  | 692 |
| Removing or compressing a data set in an active LNKLST set.....                           | 692 |
| Placement of SYSLIB and LNKLST statements in PROGxx.....                                  | 692 |
| Using the LPA statement.....  | 693 |
| Using the REFRPROT statement.....   | 694 |
| Using the NOREFRPROT statement.....   | 694 |
| Using the TRACKDIRLOAD statement.....   | 694 |
| Using the NOTRACKDIRLOAD statement.....   | 694 |
| Using the DEFAULTS statement.....   | 694 |
| Parameter in IEASYSxx (or specified by the operator).....                                 | 694 |
| PROG=xx and APF=xx.....   | 695 |
| PROG=xx and EXIT=xx.....  | 695 |
| PROG=xx and LNK=xx.....   | 695 |
| IBM-supplied default.....   | 695 |
| Syntax rules for PROGxx.....  | 695 |
| Syntax format of the APF statement.....   | 695 |
| Example of the APF statement.....   | 696 |
| Syntax format of the EXIT statements.....   | 696 |
| Examples of EXIT statements.....  | 700 |
| Syntax format of the SYSLIB statement.....  | 701 |
| Example of the SYSLIB statement.....  | 702 |
| Syntax format of the LNKLST statements.....   | 702 |
| Examples of the LNKLST statement.....   | 707 |
| Syntax format of the LPA statements.....  | 708 |
| Syntax format of the REFRPROT statement.....  | 711 |
| Syntax format of the NOREFRPROT statement.....  | 711 |
| Syntax format of the TRACKDIRLOAD statement.....  | 711 |
| Syntax format of the NOTRACKDIRLOAD statement.....  | 711 |
| Syntax format of the DEFAULTS statements.....   | 711 |
| Chapter 82. SCHEDxx (PPT, master trace table, and abend codes for automatic restart)..... | 713 |
| Parameter in IEASYSxx (or specified by the operator).....                                 | 713 |
| Modifying the PPT between IPLs.....   | 714 |
| Syntax rules for SCHEDxx.....   | 714 |
| IBM-supplied default for SCHEDxx.....   | 714 |
| IBM-supplied sample member SCHEDxx.....   | 714 |
| Statements and parameters for SCHEDxx.....  | 714 |
| Program properties table (PPT).....   | 720 |
| Chapter 83. SMFLIMxx (specifying region and memlimit values).....                         | 725 |
| Parameter in IEASYSxx (or supplied by the operator).....                                  | 725 |
| Syntax rules for SMFLIMxx.....  | 725 |
| Syntax format of SMFLIMxx.....  | 725 |

|  |            |
|--|------------|
| IBM-supplied default for SMFLIMxx.....   | 726        |
| Statements and parameters for SMFLIMxx.....  | 727        |
| Chapter 84. SMFPRMxx (system management facilities (SMF) parameters).....            | 735        |
| Using the SET command for SMFPRMxx.....  | 736        |
| Using the SETSMF command for SMFPRMxx.....   | 736        |
| Parameter in IEASYSxx (or supplied by the operator).....                             | 736        |
| Support for system symbols.....  | 736        |
| Syntax rules for SMFPRMxx.....   | 736        |
| Syntax format of SMFPRMxx.....   | 737        |
| IBM-supplied default for SMFPRMxx.....   | 739        |
| IBM-supplied sample for SMFPRMxx.....  | 739        |
| Statements and parameters for SMFPRMxx.....  | 739        |
| Using SMFPRMxx parameters.....   | 768        |
| Chapter 85. TSOKEY00 (TSO/VTAM time sharing parameters).....                         | 769        |
| Parameter in IEASYSxx (or supplied by the operator).....                             | 769        |
| Syntax rules for TSOKEY00.....   | 769        |
| IBM-supplied default for TSOKEY00.....   | 769        |
| Statements and parameters for TSOKEY00.....  | 770        |
| Chapter 86. VATLSTxx (volume attribute list).....                                    | 775        |
| Definitions of the mount and use attributes.....                                     | 775        |
| Processing the VATLSTxx members.....   | 776        |
| Parameter in IEASYSxx (or supplied by the operator).....                             | 777        |
| Support for system symbols.....  | 777        |
| Creating a VATLSTxx member.....  | 778        |
| Example of default use attributes.....   | 779        |
| Syntax rules for VATLSTxx.....   | 779        |
| Specifying a generic volume serial number.....                                       | 780        |
| Specifying a generic device type.....  | 781        |
| Example of setting the generic device type.....                                      | 781        |
| Statements and parameters for VATLSTxx.....  | 781        |
| Examples of VATLSTxx entries.....  | 781        |
| IBM-supplied default for VATLSTxx.....   | 783        |
| Chapter 87. XCFPOLxx (XCF PR/SM policy).....   | 785        |
| Parameter in IEASYSxx (or supplied by the operator).....                             | 785        |
| Syntax rules for XCFPOLxx.....   | 785        |
| Syntax format of XCFPOLxx.....   | 786        |
| IBM-supplied default for XCFPOLxx.....   | 786        |
| Statements and parameters for XCFPOLxx.....  | 786        |
| <b>Appendix A. IEFSSNxx (subsystem definitions) - positional parameter form.....</b> | <b>789</b> |
| Parameter in IEASYSxx (or supplied by the operator).....                             | 789        |
| Syntax rules for IEFSSNxx.....   | 789        |
| IBM-supplied default for IEFSSNxx.....   | 790        |
| Statements and parameters for IEFSSNxx.....  | 791        |
| <b>Appendix B. Symbolic Parmlib Parser.....</b>                                      | <b>793</b> |
| Activation.....  | 793        |
| Capabilities.....  | 793        |
| Limitations.....   | 795        |
| <b>Appendix C. Accessibility.....</b>  | <b>797</b> |
| <b>Notices.....</b>  | <b>799</b> |

|   |            |
|---|------------|
| Terms and conditions for product documentation..... | 800        |
| IBM Online Privacy Statement.....                   | 801        |
| Policy for unsupported hardware.....                | 801        |
| Minimum supported hardware.....                     | 801        |
| Programming Interface information.....              | 802        |
| Trademarks.....                                     | 802        |
| <b>Index.....</b>                                   | <b>803</b> |



---

# Figures

|  |     |
|--|-----|
| 1. MSTJCL00 load module in SYS1.LINKLIB.....                           | 9   |
| 2. Example IEASYMxx parmlib member.....                                | 39  |
| 3. Complete IEASYMxx parmlib member.....                               | 44  |
| 4. Coding IEASYMxx for a four-system sysplex.....                      | 45  |
| 5. IEASYMA4 parmlib member.....  | 45  |
| 6. Example IEASYMxx parmlib member.....                                | 46  |
| 7. Example LOADxx parmlib member.....                                  | 47  |
| 8. Example: CNLcccxx message configuration member for Italian.....     | 181 |
| 9. Example: COMMNDxx parmlib member.....                               | 192 |
| 10. Example: Activate a new conversion environment.....                | 266 |
| 11. Example: Delete an inactive conversion environment.....            | 266 |
| 12. Example: Syntax for DEVSUPxx.....                                  | 269 |
| 13. Example of how to specify comments.....                            | 427 |
| 14. Syntax examples for IECIOSxx.....                                  | 506 |
| 15. Keyword format of the SMS record in IEFSSNxx.....                  | 531 |
| 16. Positional format of the SMS record in IEFSSNxx.....               | 531 |
| 17. Example: SMS record in IEFSSNxx.....                               | 532 |
| 18. Example: Contents of IGDSMSxx, example 1.....                      | 561 |
| 19. Example: Contents of IGDSMSxx, example 2.....                      | 562 |
| 20. Example: Contents of IGDSMSxx, example 3.....                      | 562 |
| 21. Example: Contents of IGDSMSxx, example 4.....                      | 563 |
| 22. Example: FILESYSTYPE TYPE(ZFS) statement.....                      | 585 |
| 23. Example: FILESYSTYPE TYPE(ZFS) statement using system symbols..... | 585 |

|   |     |
|---|-----|
| 24. Example: FILESYSTYPE TYPE(ZFS) statement specifying 32 IOEPRMxx members.....  | 585 |
| 25. LOADxx filtering hierarchy.....   | 614 |
| 26. Example of parmlib concatenation (LOADxx).....                                | 634 |
| 27. Example: Creating parmlib member MPFLST7C.....                                | 662 |
| 28. Example: Creating parmlib member MPFLSTDF.....                                | 663 |
| 29. Example: Creating parmlib member MPFLSTRV.....                                | 663 |
| 30. Example: Creating parmlib member MPFLST18.....                                | 663 |
| 31. Example: Creating parmlib member MPFLST02.....                                | 664 |
| 32. Entries in VATLSTxx members that define attributes of DASD.....               | 781 |
| 33. Entries in VATLSTxx members that define mount and use attributes of DASD..... | 782 |
| 34. Symbolic parmlib parser panel.....  | 793 |

---

# Tables

|  |       |
|--|-------|
| 1. Syntax conventions.....   | xxvii |
| 2. Characteristics of parmlib members.....                           | 14    |
| 3. Restrictions on changing the format of the APF list.....          | 27    |
| 4. Static system symbols.....  | 33    |
| 5. Dynamic system symbols.....                                       | 35    |
| 6. Compatibility-only dynamic system symbols.....                    | 36    |
| 7. Names reserved for system use.....                                | 36    |
| 8. Precedence of system parameter specifications.....                | 40    |
| 9. Recommended actions for IEASYSxx members.....                     | 40    |
| 10. Precedence of system name specifications.....                    | 41    |
| 11. Summary of errors in substring syntax.....                       | 49    |
| 12. IEASYMU2 return codes.....                                       | 54    |
| 13. SYSRES volumes and their extensions.....                         | 56    |
| 14. Relationship size of TIOT and maximum number of DDs allowed..... | 74    |
| 15. One-character parameter limit multipliers.....                   | 125   |
| 16. Types of file systems.....                                       | 132   |
| 17. Supported domains.....   | 145   |
| 18. Maximum and default values for MAXSOCKETS by domain.....         | 145   |
| 19. Devices used as MCS consoles.....                                | 226   |
| 20. Maximum and default specifications for AREA and SEG.....         | 227   |
| 21. Without the RETRY(STAT011) DEVSUP keyword.....                   | 285   |
| 22. With the RETRY(STAT011) DEVSUP keyword.....                      | 286   |
| 23. Combining certain GTFPARM options.....                           | 336   |

|  |     |
|--|-----|
| 24. Overview of IEASYSxx parameters.....   | 421 |
| 25. Example: IEASYMxx and IEASYSxx notation.....   | 425 |
| 26. Syntax examples for the LOGREC parameter.....  | 452 |
| 27. Syntax examples for the PAGE parameter.....  | 461 |
| 28. Syntax examples for the VIODSN parameter.....  | 479 |
| 29. HOTIO parameters.....  | 492 |
| 30. Events that you can specify on SELECT and DESELECT (IGDSMSxx parameter).....                                       | 542 |
| 31. Example: Specifying DFSMStvs parameters.....   | 563 |
| 32. LISTBC and SEND results based on CHKBROD and USEBROD settings when installation is using individual user logs..... | 581 |
| 33. IPL results.....   | 616 |
| 34. ARCHLVL statement.....   | 618 |
| 35. DYNCPADD statement.....  | 619 |
| 36. HWNAME statement.....  | 620 |
| 37. Specifying one IEASYMxx member .....   | 620 |
| 38. Specifying one IEASYMxx parmlib member and displaying a list of member names.....                                  | 620 |
| 39. Specifying more than one IEASYMxx parmlib member.....  | 621 |
| 40. INITSQA statement.....   | 621 |
| 41. IODF statement.....  | 622 |
| 42. LPARNAME statement.....  | 626 |
| 43. MACHMIG statement.....   | 626 |
| 44. MTLSHARE statement.....  | 627 |
| 45. NUCLEUS statement.....   | 627 |
| 46. PARMLIB statement.....   | 628 |
| 47. PROCVIEW statement.....  | 629 |
| 48. SYSCAT parameter.....  | 631 |



|   |     |
|---|-----|
| 49. SYSPARM statement (specifying one IEASYSxx parmlib member).....                             | 632 |
| 50. SYSPARM statement (specifying one IEASYSxx parmlib member and displaying the contents)..... | 632 |
| 51. SYSPARM statement (specifying one or more IEASYSxx parmlib members).....                    | 632 |
| 52. SYSPLEX statement.....  | 633 |
| 53. VMUSERID statement.....   | 633 |
| 54. Language codes.....   | 640 |
| 55. Attributes to specify for a message area.....   | 645 |
| 56. Values for msgarea.....   | 646 |
| 57. IBM-supplied system abend codes.....  | 715 |
| 58. IBM-supplied program properties table (PPT) values.....                                     | 720 |
| 59. Explanation of column headings in the PPT table.....  | 723 |
| 60. Default values for the DEFAULTLSNAME subparameters in SET SMF and SETSMF processing.....    | 741 |
| 61. Examples of data set names that use system symbols.....                                     | 744 |
| 62. Default values for the LSNAME subparameters in SET SMF and SETSMF processing.....           | 750 |
| 63. Examples of log stream names that use system symbols.....                                   | 750 |
| 64. SID parameter syntax priority list.....   | 758 |
| 65. Which SMF exits are called for this subsystem?.....   | 762 |
| 66. Which SMF exits are called for this subsystem?.....   | 766 |
| 67. Explanation of VATLSTxx entries.....  | 782 |



# About this information

This information describes the members of SYS1.PARMLIB for z/OS, and the processes related to initializing the system. For each member, the information describes the meaning and use of each parameter, syntax rules, syntax examples, value ranges that are syntactically acceptable, default values, and performance notes where applicable.

This information is a companion to the *z/OS MVS Initialization and Tuning Guide*.

For information about how to install the software products that are necessary to run z/OS, see *z/OS Planning for Installation*.

# Who should use this information

This information is for anyone whose job includes installing hardware and software, and customizing the software. This information is intended to be a reference about how to code system parameters and make other changes required. Usually, these tasks are performed by a systems programmer.

The information assumes that the user can:

- Code JCL statements to execute programs or cataloged procedures.
- Code in assembler language and read assembler, loader, linkage editor, and binder output.

This information is also for anyone who tunes the system. System tuning requires you to determine where the system needs adjustment, to understand the effects of changing the system parameters, and to determine the changes to the system parameters that will bring about the desired effect.

# MVS workload management

Many of the performance functions described in this document can be defined using MVS workload management (WLM). For more information, see *z/OS MVS Planning: Workload Management* and *z/OS MVS Programming: Workload Management Services*.

# z/OS information

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross-document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see *z/OS Information Roadmap*.

# How to read syntax conventions

This topic describes how to read syntax conventions. It defines syntax notations and provides syntax examples that contain these items.

| Table 1. Syntax conventions |   |                    |                           |
|-----------------------------|---|--------------------|---------------------------|
| Notation                    | Meaning   | Syntax example     | Sample entry              |
| Apostrophes                 | Apostrophes indicate a parameter string and must be entered as shown. | SEND 'message',NOW | SEND 'listings ready',NOW |
| Comma                       | Commas must be entered as shown.                                      | DISPLAY C,K        | DISPLAY C,K               |

| Table 1. Syntax conventions (continued) |  |                                    |                                  |
|---|--|------------------------------------|----------------------------------|
| Notation                                | Meaning  | Syntax example                     | Sample entry                     |
| Ellipsis ...                            | Ellipsis indicates that the preceding item or group of items can be repeated one or more times. Do not enter the ellipsis.               | VARY (devspec[,devspec]...),ONLINE | VARY (282,283,287),ONLINE        |
| Parentheses and special characters      | Parentheses and special characters must be entered as shown.   | DUMP COMM=(text)                   | DUMP COMM=(PAYROLL)              |
| Underline                               | Underline indicates a default option. If you select an underlined alternative, you do not have to specify it when you enter the command. | K M[,AMRF={Y   N}]  ,REF           | K M                              |
| Lowercase parameter                     | Lowercase indicates a variable term. Substitute your own value for the item.   | MOUNT devnum                       | MOUNT A30<br>or<br>mount a30     |
| Uppercase parameter                     | Uppercase indicates the item must be entered using the characters shown. Enter the item in either upper or lowercase.                    | DISPLAY SMF                        | DISPLAY SMF<br>or<br>display smf |
| Single brackets                         | Single brackets represent single or group-related items that are optional. Enter one or none of these items.                             | DISPLAY SLIP[=xxxx]                | DISPLAY SLIP=W292                |
| Stacked brackets                        | Stacked brackets represent group-related items that are optional. Enter one or none of these items.                                      | [TERMINAL]<br>[NOTERMINAL]         | NOTERMINAL                       |
| Single braces                           | Single braces represent group-related items that are alternatives. You must enter one of the items. You cannot enter more than one.      | {COMCHECK   COMK}                  | COMK                             |

| Table 1. Syntax conventions (continued)     |   |  |                                    |
|---|---|--|------------------------------------|
| Notation                                    | Meaning   | Syntax example   | Sample entry                       |
| Stacked braces                              | Stacked braces represent group related items that are alternatives. You must enter one of the items. You cannot enter more than one.                              | <pre>MN {DSNAME}    {SPACE}    {STATUS}</pre>  | <pre>MN SPACE</pre>                |
| Or-bar ( )                                  | An or-bar indicates a mutually exclusive choice. When used with brackets, enter one or none of the items. When used with braces, you must enter one of the items. | <pre>ACTIVATE RECOVER=SOURCE   TARGET</pre>  | <pre>ACTIVATE RECOVER=SOURCE</pre> |
| Stacked items with or-bars ( ) and brackets | Stacked items with or-bars indicates a mutually-exclusive choice. Enter one or none of these items.   | <pre>CD RESET [ ,SDUMP      ]             ,SYSABEND             ,SYSUDUMP             ,SYSMDUMP             ,ALL</pre> | <pre>CD RESET ,SYSUDUMP</pre>      |



## How to provide feedback to IBM

---

We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information. For more information, see [How to send feedback to IBM](#).





## Summary of changes

---

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

**Note:** IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under [IBM z/OS Product Documentation Update Policy](http://www.ibm.com/docs/en/zos/latest?topic=zos-product-documentation-update-policy) ([www.ibm.com/docs/en/zos/latest?topic=zos-product-documentation-update-policy](http://www.ibm.com/docs/en/zos/latest?topic=zos-product-documentation-update-policy)).

## Summary of changes for z/OS 3.2

---

The following content is new, changed, or no longer included in z/OS 3.2.

### New

The following content is new.

#### September 2025 release

- For the IECIOSxx parmlib member, information is added in [“Important PATH\\_SCOPE considerations”](#) on page 502.
- The IARPRMxx parmlib member is enhanced to support the following options: RESTRICTPFTCADS and IARR2V\_REQAUTH. See [“Statements and parameters for IARPRMxx”](#) on page 353.
- You can determine whether an executed file is a REXX program with the REXXPARSE statement in the BPXPRMxx parmlib member. These sections are updated:
  - [“Syntax format of BPXPRMxx”](#) on page 125
  - [“Syntax example of BPXPRMxx”](#) on page 126
  - [“Statements and parameters for BPXPRMxx”](#) on page 128.
- The AUTO\_VOLSTATUS\_VTOC keyword is added for IGDSMSxx. For more information, see:
  - [“Optional keywords for IGDSMSxx”](#) on page 535
  - [“Syntax format of IGDSMSxx”](#) on page 533.
- The IHAACEE3PTY structure is added for DIAGxx. For more information, see [“Statements and parameters for DIAGxx”](#) on page 298.
- The IHARMPL, IHAXTLST, and IEFMASTERSWA structures names are added for CBLOC [VIRTUAL24(structure1,structure2, ...)] [VIRTUAL31(structure1,structure2, ...)] [REAL31(structure1,structure2, ...)] [REAL64(structure1,structure2, ...)]. For more information, see [“Statements and parameters for DIAGxx”](#) on page 298.

### Changed

The following content is changed.

#### September 2025 release

- The example CEEPRMxx parmlib member is updated for z/OS 3.2. See [“Example of CEEPRMxx parmlib member”](#) on page 167.
- Chapter 30, [“DIAGxx \(control common storage tracking and GFS trace\)”](#), on page 295 is updated to include a new parameter [“ASCBV31\(NO|YES\)”](#) on page 298.
- In the DEVSUPxx parmlib member, the term "Logical Record Erase" is corrected to "Locate Record Erase." See [“Statements and parameters for DEVSUPxx”](#) on page 271.

- In the IEAOPTxx parmlib member, the description of the CPENABLE parameter is updated and the default setting is changed to CPENABLE=SYSTEM. See [“Statements and parameters for IEAOPTxx” on page 388](#).
- In the IXGCNFxx parmlib member, the description of the KEEPLOCALBUFFERS parameter is updated. See [“Statements and parameters for IXGCNFxx” on page 599](#).
- In the SMFLIMxx parmlib member, the description of the MAXSHARE parameter is updated. See [“Statements and parameters for SMFLIMxx” on page 727](#).

## Deleted

The following content is deleted.

### September 2025 release

- The BPXPRMxx parameters FIXED, SYNCDEFAULT, VIRTUAL, RNODEWAIT, WAITABEND, and BUFFERMONITOR are deleted because they are associated with the HFS file system, which is depreciated.

## Summary of changes for z/OS 3.1

---

The following content is new, changed, or no longer included in z/OS 3.1.

To align with current industry guidelines for inclusive language, the terms *master pseudoterminal* and *slave pseudoterminal* are replaced with *manager pseudoterminal* and *subsidiary pseudoterminal*. As other industry leaders join IBM in embracing the use of inclusive language, IBM continues to update the documentation to reflect those changes.

## New

The following content is new.

### June 2025 refresh

- The WORKINST parameter is added in IEASYSxx; see [“WORKINST” on page 480](#). (APAR OA65240, which also applies to z/OS 2.5)

### May 2025 refresh

- The entry for CBRWOLA is added in the program properties table (PPT). See [Table 58 on page 720](#). (APAR OA66996) <https://www.ibm.com/support/pages/apar/OA66996>

### April 2025 refresh

- The IEARTM2NOSNAPTRC trap is added in DIAGxx; see [“IEARTM2NOSNAPTRC” on page 306](#).

### January 2025 refresh

- The AUTO\_VOLSTATUS\_EXTPOOL parameter is added in [“Optional keywords for IGDSMSxx” on page 535](#). (APAR OA66369)

### September 2024 refresh

- For SMFLIMxx, the REGIONLIMITABOVE, REGIONLIMITBELOW, and CONTINUEMATCHING attributes are added. See [“Statements and parameters for SMFLIMxx” on page 727](#). (APAR OA66028)

### May 2024 refresh

- The IDAVDTxx parmlib member is added to [Table 2 on page 14](#) with the summary details.

### April 2024 refresh

- The IARPRMxx parmlib member is added to [Table 2 on page 14](#).

## September 2023 release

- The following sections have new information regarding Dedicated Memory:
  - Chapter 40, [“IARPRMxx \(Real Storage Manager controls\),”](#) on page 353 is a new PARMLIB member that controls Dedicated Memory.
  - [“RSM”](#) on page 468 is a new IEASYSxx parameter.
  - [“Statements and parameters for SMFLIMxx”](#) on page 727 has a new DEDICATEDMEMORY attribute.
- The AIMANAGEMENT parameter is added in [“Statements and parameters for IEAOPTxx”](#) on page 388.
- The CCImp and CCImpBoost parameters are added in [“Statements and parameters for IEAOPTxx”](#) on page 388.
- The SYSTEM option is added to the CPENABLE parameter in [“Statements and parameters for IEAOPTxx”](#) on page 388.

## Changed

The following content is changed.

### May 2025 refresh

- In support of OA67484: REFVTOC DOES NOT DETECT DUPLICATE FORMAT 8 DSCBS POINTING TO THE SAME FORMAT 9 DSCB ([www.ibm.com/support/pages/apar/OA67484](http://www.ibm.com/support/pages/apar/OA67484)), the examples for the RETRY parameter of the DEVSUPxx member is updated. See [“Statements and parameters for DEVSUPxx”](#) on page 271. (APAR OA67484)
- The entry for AXRINIT is updated in the program properties table (PPT). See [Table 58 on page 720](#). This applies to z/OS V2R4 and later.
- The SUPSBY parameter description is updated. See [“Syntax and parameters for the CONSOLE statement”](#) on page 206.

### April 2025 refresh

- [“Step 2. Determine where to specify system parameters”](#) on page 39 is updated.
- The PPRCSUM parameter description is updated to add a restriction for an MVS guest running under VM. See [“Statements and parameters for DEVSUPxx”](#) on page 271.

### March 2025 refresh

- In the IEAOPTxx member, the description of the RTPIFACTOR parameter is updated. See [“Statements and parameters for IEAOPTxx”](#) on page 388.

### February 2025 refresh

- In the BPXPRMxx member, the default for IPCSHMNSEGS is changed to 500, which is the correct value. See [“Syntax example of BPXPRMxx”](#) on page 126 and [“Statements and parameters for BPXPRMxx”](#) on page 128.
- In the IEASYSxx (system parameter list) member, the CSCBLOC parameter description is updated. See [“CSCBLOC”](#) on page 435.
- The LOGCLS parameter description in IEASYSxx is updated. See [“LOGCLS”](#) on page 450.

### January 2025 refresh

- In [“Statements and parameters for AXRxx”](#) on page 107, for the REXXLIB statement, a space is added between the dataset name parameter and the VOL parameter.
- The AUTOIPL parameter description is updated. See [“Statements and parameters for DIAGxx”](#) on page 298.

## December 2024 refresh

- The default for KERNELSTACKS in the BPXPRMxx member is updated to ABOVE. See [“Statements and parameters for BPXPRMxx”](#) on page 128.
- The SUPSBY and HMCS are updated. See [“Syntax and parameters for the CONSOLE statement”](#) on page 206.
- [“Syntax format of IGDSMSxx”](#) on page 533, [“Examples of specifying DFSMStvs parameters”](#) on page 563, and [“Optional keywords for IGDSMSxx”](#) on page 535 are updated with new keyword AUTO\_VOLSTATUS\_EXTPOOL. (APAR OA66017: NEW FUNCTION - SUPPORT FOR DS8K COMPRESSION ([www.ibm.com/support/pages/apar/OA66017](http://www.ibm.com/support/pages/apar/OA66017)), which also applies to z/OS V2R5 and newer)

## November 2024 refresh

## October 2024 refresh

- SYS1.PARMLIB member IECIOSxx statement [“ZHYPERLINK”](#) on page 505 is updated. (APAR OA66431 ([www.ibm.com/support/pages/apar/OA66431](http://www.ibm.com/support/pages/apar/OA66431)), which also applies to z/OS V2R5)
- The description of IEASYSxx is clarified in [“Step 2. Determine where to specify system parameters”](#) on page 39.

## September 2024 refresh

- The BPXPRMxx parameter MAXASSIZE is updated to indicate that the value limits the amount of storage below 2 GB, including both above and below the 16 MB line. See [“Statements and parameters for BPXPRMxx”](#) on page 128.
- [“Syntax format of DEVSUPxx”](#) on page 269 and [“Statements and parameters for DEVSUPxx”](#) on page 271 is updated with SMF98\_DATASET\_ACTIVITY.
- Syntax rules are updated in the IEASYMxx. See [“Syntax rules for IEASYMxx”](#) on page 413
- The default value for the VSAM\_ZHYPERLINK parameter is updated from YES to NO. See [“Optional keywords for IGDSMSxx”](#) on page 535.
- The TASKMAX parameter description is updated in IGGCATxx. See [“Statements and parameters for IGGCATxx”](#) on page 567.
- For SMFLIMxx, the REQMEMLIMIT filter and MEMLIMIT attribute are updated. See [“Statements and parameters for SMFLIMxx”](#) on page 727. (APAR OA66028)

## August 2024 refresh

- The description of the HWNAME parameter is updated in [“Statements and parameters for LOADxx”](#) on page 618.
- The list of supported file types for the FILESYSTYPE parameter in the BPXPRMxx parmlib member is updated. See [“Statements and parameters for BPXPRMxx”](#) on page 128.

## July 2024 refresh

- [“IBM-supplied defaults for DEVSUPxx”](#) on page 270 is updated.

## May 2024 refresh

- [“Statements and parameters for COUPLExx”](#) on page 230 is updated with information about positional keyword coding for correct syntax.
- [“Statements and parameters for DIAGxx”](#) on page 298 is updated with clarification for structures CNZSSICB and JCLPARM.
- [“Statements and parameters for IARPRMxx”](#) on page 353 is updated with information about the default value for the PROMPT parameter.
- [“Statements and parameters for SMFLIMxx”](#) on page 727 is updated with information about wildcards and corrections to the syntax for the REQMEMLIMIT filter.

### March 2024 refresh

- The BPXPRMxx parmlib member is updated with a new file type (PROC) for the FILESYSTEM statement. See [“FILESYSTEM\('fsname'\) ” on page 141](#). (APAR OA62757, which applies to z/OS 2.5 and z/OS 3.1)
- The IGDSMSxx parmlib member is updated to clarify the description of optional keyword MAXLOCKS. See [“Optional keywords for IGDSMSxx” on page 535](#).

### November 2023 refresh

- Chapter 70, [“IXGCNFxx \(system logger initialization parameters\),” on page 597](#) is updated with new parameter [“LOCALBUFFERLIMIT\(NO | YES\)” on page 602](#). (APAR OA64676, applies to V2R5 and newer)

### September 2023 release

- The list of Dilithium versions that SMF supports is updated in the description of the ARECSIGN TOKENNAME parameter in [“Statements and parameters for SMFPRMxx” on page 739](#).
- The following sections have new information regarding Dedicated Memory:
  - [“RSU” on page 468](#) parameter value OFFLINE is updated.
  - [“Syntax format of SMFLIMxx” on page 725](#) is updated.
  - [“Statements and parameters for IVTPRM00” on page 594](#) is updated.
- [“OSPROTECT” on page 459](#)'s default parameter SYSTEM now has the functions of OSPROTECT=1. OSPROTECT=MIN is added to opt-out of this updated default and retain prior release functions.
- [“Statements and parameters for SMFLIMxx” on page 727](#) is updated with notes to indicate which attributes may be ignored for some system addresses. (APAR OA64426, applies to V2R4 and newer)



---

## Part 1. Overview





---

# Chapter 1. System tailoring

System tailoring is the overall process by which an installation selects its operating system. The process consists of the specification of system options through these mechanisms:

- MVS hardware configuration definition (HCD), which is described in [“MVS hardware configuration definition”](#) on page 3.
- Initialization-time selections which appear in the topic [“System tailoring at initialization time”](#) on page 3.
- Implicit system parameters which appear in the topic [“Implicit system parameters”](#) on page 25.
- After IPL, system tailoring through operator commands. One example of a command that will perform a system tailoring function is the SETPROG command (for example, SETPROG LPA,ADD). You get the same result whether you activate a function by issuing a SETPROG command or by activating the PROGxx parmlib member.

For more information about how to use commands to start, load, initialize, and control your system, see [z/OS MVS System Commands](#).

**Note:** Many system options have defaults. The IBM defaults for some of these options might change in a future release. If you want to continue using the current default, set the default value that you want.

An installation can identify one or more active instances of the operating system. For example, the installation might choose to identify a specific instance to be used only during off-shift hours.

To identify an instance of the operating system, the installation assigns a unique 16-character EBCDIC identifier by using the AMASPZAP program immediately after system initialization, or by creating an alternate nucleus. For more information about AMASPZAP, see [z/OS MVS Diagnosis: Tools and Service Aids](#). For more information about creating an alternate nucleus, see [“Specifying an alternate nucleus”](#) on page 8.

---

## MVS hardware configuration definition

The hardware configuration definition (HCD) allows you to use the HCD dialog to perform the following tasks for hardware configuration:

- Define operating system configuration
- Define the channel subsystem (CSS) configuration
- Define ESCON director (ESCD) and switch configurations
- Activate configuration data
- Maintain I/O definition files
- Query and print configuration data
- Migrate existing configuration data

For information about using the HCD dialogue, see [z/OS HCD User's Guide](#).

---

## System tailoring at initialization time

Initialization-time choices that help to tailor the system can come from several sources:

- Various types of IPLs.
- Operator action, described in [“Operator entry of parameters”](#) on page 5.
- SYS1.PARMLIB and additional parmlib data sets are described in [“Description and use of the parmlib concatenation”](#) on page 6. This data set is one of the main sources of IPL-time parameters.

- Specifying an alternate nucleus or master catalog, described in [“Specifying an alternate nucleus”](#) on page 8 and [“Specifying an alternate master \(system\) catalog”](#) on page 8.
- Specifying different master scheduler JCL, described in [“Understanding the master scheduler job control language”](#) on page 9, which includes information about when you might need different master scheduler JCL and how to establish the JCL you need.
- The JES2 initialization data set. See [z/OS JES2 Initialization and Tuning Guide](#) for more information.

## Types of IPL

There are several types of IPL:

### Cold Start

Any IPL that loads (or reloads) the PLPA, but does not preserve VIO data set pages. The first IPL after system installation is always a cold start because the PLPA is initially loaded. Subsequent IPLs are cold starts when the PLPA is reloaded either to alter its contents or to restore its contents if they were destroyed.

### Quick Start

Any IPL that does not reload the PLPA and does not preserve VIO data set pages. (The system resets the page and segment tables to match the last-created PLPA.)

### Warm Start

Any IPL that does not reload the PLPA, but does preserve journaled VIO data set pages.

## The first IPL after system installation

At the first IPL after system installation, the system automatically loads the PLPA from the LPAIST concatenation. The page data sets for this IPL are those specified in the IEASYS00 parmlib member, plus any specified by the operator.

After the first IPL, you must run IFCDIP00 to initialize the LOGREC data set. This routine must also be run whenever the LOGREC data set is reallocated.

## An IPL at which the PLPA is reloaded

The PLPA must be reloaded: (1) at the first IPL after system initialization, when the system loads it automatically, (2) at an IPL after the installation has added or modified one or more modules in the LPAIST concatenation, has tested the alteration, and now wants to put the replacement module(s) in the PLPA, and (3) at an IPL after the PLPA page data set has been damaged (and is therefore unusable) and its contents must be restored. The PLPA can also be reloaded for other reasons (such as when the addition of more storage causes the nucleus and the PLPA to overlap). Reloading the PLPA should be discretionary; that is, it should not be a common occurrence. It should be done only when necessary because the associated I/O slows down the IPL and because previously existing VIO data set pages are not preserved.

To reload the PLPA from the LPAIST concatenation, the operator enters CLPA (create link pack area) as one of the responses to the SPECIFY SYSTEM PARAMETERS prompt. For more information about loading the PLPA, see the CLPA parameter in [Chapter 56, “IEASYSxx \(system parameter list\),”](#) on page 421.

## An IPL after power-up

The IPL performed after power-up is called a “quick start”, because the PLPA from the previous IPL can be used without reloading from the LPAIST concatenation. For a “quick start”, the CVIO system parameter is used; VIO data set pages are purged, page data sets added (optionally reserved for non-VIO paging). The operator or the IEASYSxx parmlib member can add additional page data sets by specifying the PAGE parameter (with or without the NONVIO system parameter). For information about the CVIO, PAGE, and NONVIO parameters, see [Chapter 56, “IEASYSxx \(system parameter list\),”](#) on page 421.

## An IPL after a system crash

If the operator does not enter the CLPA or CVIO system parameters, the operator can “warm start” the system after a system crash. Existing journaled VIO data set pages and PLPA pages are retained. The

specified parmlib parameter list (IEASYSxx) cannot include the CVIO or CLPA system parameters. (The specification of one or more IEASYSxx members by the operator at IPL time is described in the next topic, [“Operator entry of parameters” on page 5.](#))

Any definitions of existing page data sets as non-VIO local page data sets are preserved. Also the operator can define a local page data set that previously was used for VIO paging as a non-VIO local page data set. During system operation, the VIO pages on the newly designated non-VIO local page data set will migrate to any local page data set used for VIO paging. An installation can remove a local page data set that was designated on the previous IPL as a non-VIO local paging data set. Removing a local page data set before a "warm start" requires that the local page data set contain no VIO pages. If the local page data set contains VIO pages, the system changes the "warm start" into a "quick start". A local page data set specified as NONVIO can contain VIO pages if one of the following conditions exists:

- Directed VIO was turned off while the previous system was active.
- A warning message to the operator indicated that VIO pages spilled to a non-VIO data set because no more space was available on those page data sets that were being used for VIO.

For more information about designating non-VIO page data sets, see the NONVIO system parameter in [Chapter 56, “IEASYSxx \(system parameter list\),” on page 421.](#)

## Operator entry of parameters

If an IEASYSxx identifier is not specified in the LOADxx parmlib member, the operator is prompted to respond to the SPECIFY SYSTEM PARAMETERS message to direct the system components to the desired parmlib members.

**Tip:** Use the LOAD parameter on the system console to allow the operator to force the prompt for system parameters. For more information, see [z/OS MVS System Commands](#).

The operator can select the default general parameter list IEASYS00, or enter SYSP=(aa,bb...) to select one or more alternate general parameter lists, such as IEASYS01, IEASYS02, and so forth. If the operator responds to the SPECIFY SYSTEM PARAMETERS message without specifying the SYSP parameter, the system will use IEASYS00.

The system always processes the IEASYS00 member first, regardless of where you specify IEASYSxx suffixes. If the same parameter appears in both IEASYS00 and a specified alternate IEASYSxx list, the value in the alternate list overrides the value in IEASYS00. Also, a parameter value in a later specified IEASYSxx list overrides the same parameter in an earlier specified list. [Table 8 on page 40](#) shows how the system overrides suffixes. See the description of the IEASYSxx member for more information.

The operator need not enter parameter values directly, except for those cases in which parameters are missing, are syntactically invalid, cannot be read, or must be supplemented to satisfy a special case. (An example of a special case is the operator entry of the PAGE parameter to increase the amount of paging space.)

If an error occurs with certain parmlib members, the operator is prompted to manually enter one or more of the member's parameters. If the parameter cannot be corrected, the operator can accept the system defaults. Most parameters have defaults, either as default parmlib members, or as coded values in system components. If a default does not exist (and if a parameter is not required), the operator can cancel the parameter. (The defaults are listed in the individual descriptions of parmlib members.)

If the parameter list supplied by the operator is longer than one line (there are 80 characters per line), the operator can follow the last parameter with a comma or a blank and CONT. For details about how to continue system parameters, see the description of the REPLY command in [z/OS MVS System Commands](#).

An operator-entered parameter overrides the same parameter specified in parmlib member IEASYS00 or IEASYSxx, except for:

- A parameter for which operator intervention is prohibited (OPI=NO). In this case, the system ignores the parameter that the operator entered (unless the parmlib parameter was syntactically invalid and is being corrected from the console).

- The PAGE parameter. The page data set names that the operator enters are added for the duration of the IPL to those specified in either IEASYS00 or IEASYSxx. (For information about the PAGE parameter, see Chapter 56, “IEASYSxx (system parameter list),” on page 421.)

To determine the LOAD parameter that was used for the current IPL, check ECVTMLPR field in the ECVT data area. The ECVT is mapped by the IHAECVT mapping macro. For a description of the ECVT, you can see *z/OS MVS Data Areas* in the *z/OS Internet library* ([www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary)).

## Description and use of the parmlib concatenation

This topic discusses the parmlib concatenation, its purpose, ways to control the parmlib data set(s), and general syntax rules for creating most members of the data set(s). [Table 2 on page 14](#) contains an overview of all the parmlib members.

The parmlib concatenation is a set of up to 16 partitioned data sets defined through PARMLIB statements in the LOADxx member of either SYSn.IPLPARM or SYS1.PARMLIB which contains many initialization parameters in a pre-specified form in a single logical data set, thus minimizing the need for the operator to enter parameters. SYS1.PARMLIB makes the 17th or last data set in the concatenation and is the default parmlib concatenation if no PARMLIB statements exist in LOADxx. For specific information about how to define a logical parmlib concatenation, see [Chapter 73, “LOADxx \(system configuration data sets\),” on page 613](#). The SYS1.PARMLIB data set itself can be blocked and can have multiple extents, but it must reside on a single volume. The parmlib concatenation used at IPL must be a PDS. However, after IPL you may issue a SETLOAD command to switch to a different parmlib concatenation which contains PDSEs. For information about processing of concatenated data sets see [z/OS DFSMS Using Data Sets](#).

Parmlib contains both a basic or default general parameter list IEASYS00 and possible alternate general parameter lists, called IEASYSaa, IEASYSbb, and so forth. Parmlib also contains specialized members, such as COMMNDxx, and IEALPAxx. Any general parameter list can contain both parameter values and "directors". The directors (such as MLPA=01) point or direct the system to one or more specialized members, such as IEALPA01.

The parmlib concatenation is read by the system at IPL, and later by other components such as the system resource manager (SRM), the TIOC, and SMF, which are invoked by operator commands. The TIOC is the terminal I/O coordinator, whose parameters are described under member IKJPRM00. SMF is the System Management Facility whose parameters are described under member SMFPRMxx.

The system always reads member IEASYS00, the default parameter list. Your installation can override or augment the contents of IEASYS00 with one or more alternate general parameter lists. You can further supplement or partially override IEASYS00 with parameters in other IEASYSxx members or operator-entered parameters. You can specify the IEASYSxx members that the system is to use in:

- The IEASYMxx parmlib member
- The LOADxx parmlib member.

The operator selects the IEASYSxx member using the SYSP parameter at IPL. The parameter values in IEASYS00 remain in effect for the life of an IPL unless they are overridden by parameters specified in alternate IEASYSxx members or by the operator. See [“Step 2. Determine where to specify system parameters” on page 39](#) for details about how the system processes system parameter specifications.

## How to control the parmlib

With a parmlib concatenation, you have more flexibility in managing parmlib members and changes to parmlib members. To control parmlib and ensure that it is manageable, you need to consider the following:

- The RACF® (or other security product) read access is a must for applications that need to read SYS1.PARMLIB.
- Use the ability to have up to 16 installation-defined parmlib data sets separate your parmlib members along organization or function lines and use appropriate RACF security for each data set.

- Include members with installation changes in one of the 16 installation-defined parmlib data sets to avoid having the member overlaid by IBM maintenance on SYS1.PARMLIB.

**Note:** If a member exists more than once within the parmlib concatenation, the first occurrence is used.

- Use an installation-defined parmlib data set to contain any parmlib members to be used on test systems. They can be included in front of your "standard" parmlib concatenation without forcing changes to the "standard" parmlib concatenation.
- Delete unsupported parameters and members. Because most components treat unsupported parameters from previous releases as syntax errors, you probably need to remove the old parameters or build parmlib from scratch. This action minimizes the need for operator responses during an IPL. Then, you can save space by removing unsupported members.
- Use the parmlib members for the appropriate functions. For example, use COMMNDxx to contain commands useful at system initialization. Use IEACMDxx for IBM\*-supplied commands. Use IEASLPxx for SLIP commands. See each member for further information.
- Update the parmlib with new and replacement members, as you gain familiarity with the new release.
- Keep track of which parameters are included in particular parmlib members. This bookkeeping is necessary for two reasons: 1) The system does not keep track of parmlib members and their parameters and 2) The default general parameter list IEASYS00 is always read by the system and master scheduler initialization. The parameters in IEASYS00 can be overridden by the same parameters when they are specified in alternate general lists, such as IEASYS01, or IEASYS02. Then, certain parameters, such as FIX, APF, and MLPA, direct the system to particular specialized members (in this example, IEAFIXxx, and IEALPAXx). The installation should keep records of which parameters and which values are in particular members, and which general members point to which particular specialized members (COMMNDxx, IEALPAXx, and so forth). A grid or matrix for such bookkeeping is very helpful.
- Allocate sufficient space for parmlib. One way to estimate space is to count the number of 80-character records in all members which are to be included in one parmlib data set and factor in the block size of the data set. Then add a suitable growth factor (e.g., 100-300%) to allow for future growth of alternate members. Consult [Table 2 on page 14](#) to determine which members can have multiple alternates. To recapture space occupied by deleted members, use the "compress" function of IEBCOPY. However, should the data set run out of space, you can copy the members to a larger data set, create a new LOADxx member in which you replace the PARMLIB statement for the full data set with a parmlib statement for the new larger data set, and then issue a SETLOAD command to switch to the concatenation with the new data set.
- Ensure EXITxx resides in SYS1.PARMLIB, because you can only access it from SYS1.PARMLIB.
- GTFPARM must also reside in SYS1.PARMLIB unless an alternate data set is used, as discussed in [Chapter 37, "GTFPARM \(generalized trace facility parameters\)," on page 335](#).
- Decide which volumes and devices should hold the parmlib concatenation. You must catalog the data set, unless it resides in SYSRES or its volume serial number is included in the parmlib statement in LOADxx. You can place the data set on a slow or moderate speed device.
- Use a security product (like RACF\*) to protect the data sets. The purpose is to preserve system security and integrity by protecting various members that define authorized programs and libraries, including but not limited to the appendage member (IEAAPxx), the authorized program facility members (IEAAPFxx and PROGxx), the LPA libraries (LPALSTxx, IEALPAXx, PROGxx), and the link libraries (LNKLSTxx). In addition, ensure that you protect any libraries that are named in those members to ensure that only appropriate users with system maintenance responsibility can update them.

## General syntax rules for the creation of members

The following general syntax rules apply to the creation of most parmlib members. You can find the description of the exceptions to these rules under specific members. The general rules are:

- Logical record size is 80 bytes.
- Block size must be a multiple of 80.
- Any columns between 1 and 71 can contain data.

- Statements are entered in uppercase characters.
- Suffix member identifiers can be any combination of A-Z and 0-9, though some member identifiers may allow other characters.
- Columns 72 through 80 are ignored.
- For some parmlib members, continuation is indicated by a comma followed by one or more blanks after the last entry on a record.
- Leading blanks are suppressed. A record therefore need not start at a particular column.
- Suffix member identifiers (such as LNK=A2) can be any alphanumeric combination.
- Comments for some parmlib members are indicated by using /\* and \*/ as the delimiters in columns 1-71, for example:

```
/*comment*/
```

/\* and \*/ characters within a single-quoted string are usually not treated as comment delimiters.

For nested comments, delimiters must be balanced. For example, you can nest comments as follows:

```
/*comment1/*comment2*/*/
```

Some parmlib members require other methods. Check specific parmlib members for information about specifying comments.

## Sharing parmlib members

You can set up parmlib so two or more MVS systems can share parmlib members — even if those systems require unique values in those members. When coding parmlib members, you can use *system symbols* to temporarily replace unique values. Each system defines its own unique values for the system symbols. As with variables in program, each system replaces the system symbols with the defined values when the system symbols are processed. With ability to share parmlib members that require unique values allows, you can view the sysplex as a *single system image* with as little as one SYS1.PARMLIB data set.

For complete details about how to set up parmlib so two or more systems can share it, see [Chapter 2, “Sharing parmlib definitions,”](#) on page 31.

## Specifying an alternate nucleus

Another less common way to change the system at an IPL is to cause the IPL program to read a member of a nucleus data set that is different from IEANUC01, the default nucleus member. One reason for such a nucleus switch may be the need to apply a PTF to the nucleus. You can IPL a secondary (alternate) nucleus by either of the following methods:

- Editing the alternate nucleus character of the LOAD parameter string before selecting the "initialize SCP" function. Use the system control (SYSCCTL) frame of the system console. Modify the last character of the eight-character parameter string to specify the suffix for IEANUC0x. The IPL program retrieves this character from the system console frame and concatenates it as a suffix to IEANUC0 to form the alternate SYS1.NUCLEUS member name.
- Using the NUCLEUS statement of the LOADxx member to specify the desired alternate IEANUC0x member. See [Chapter 73, “LOADxx \(system configuration data sets\),”](#) on page 613 for more information.

**Note:** When you specify an alternate nucleus, the proper architectural extension of the nucleus must also exist. See [ARCHLVL](#) for more information about architectural extensions to the nucleus.

## Specifying an alternate master (system) catalog

Another way to change the system at an IPL is to tell the system to select an alternate master catalog. Use one of the following methods:

- Identify the data set that contains the alternate master catalog on the SYSCAT statement in the LOADxx parmlib member.



- Tell the system to read a member of SYS1.NUCLEUS that is different from SYSCATLG, the default member. Respond to system message IEA347A with a two-character suffix. The two characters are appended to SYSCAT to form the member name that the system is to read.

The system prompts the operator for a SYSCAT suffix only if you:

- Do not specify the SYSCAT statement in LOADxx
- Specify, through the SYSCTL frame, an initialization message suppression indicator (IMSI) on the LOAD parameter that tells the system to prompt for the master catalog response.

## Understanding the master scheduler job control language

The master scheduler JCL data set (commonly called master JCL) controls system initialization and processing. It contains data definition (DD) statements for all system input and output data sets that are needed to communicate between the operating system and the primary job entry subsystem, which can be JES2 or JES3. An IPL is required to add, remove or change any DD statements in the master JCL.

To change system initialization or processing, you can change the information in the member or use an alternate data set. You might need to change the master JCL at an IPL. For example, if you plan to use jobs as the source JCL for started tasks, IBM suggests that you modify the master JCL. See [“Setting up started tasks with the Master JCL”](#) on page 11 for more information.

You can also modify the master scheduler JCL data set to include START commands for other subsystems, along with DD statements necessary to communicate with them. You can also delete DD statements that do not apply to your installation's interactive configuration.

## Where does the master JCL reside?

IBM supplies the default master JCL in the MSTJCL00 load module in SYS1.LINKLIB. [Figure 1 on page 9](#) shows MSTJCL00 as it exists before it is assembled and link-edited into SYS1.LINKLIB:

```
MSTJCL00 CSECT
DC CL80'//MSTJCL00 JOB MSGLEVEL=(1,1),TIME=1440'
DC CL80'// EXEC PGM=IEEMB860'
DC CL80'//STCINRDR DD SYSOUT=(A,INTRDR)'
DC CL80'//TSOINRDR DD SYSOUT=(A,INTRDR)'
DC CL80'//IEFPDSI DD DSN=SYS1.PROCLIB,DISP=SHR'
DC CL80'//SYSUADS DD DSN=SYS1.UADS,DISP=SHR'
DC CL80'/*'
END
```

*Figure 1. MSTJCL00 load module in SYS1.LINKLIB*

MSTJCL00 contains:

- DD statements that are needed to define the internal reader data sets for started task control and TSO/E logons.
- SYS1.UADS, a system data set used in TSO/E logons and terminal communications.

MSTJCL00 does not contain the START command that starts the primary job entry subsystem during master scheduler initialization. You can define and start the primary job entry subsystem using the PRIMARY parameter in the IEFSSNxx parmlib member.

Your installation can either use the default master JCL (shown in [Figure 1 on page 9](#)) or specify an alternate version of the master JCL, as described in [“Changing the master scheduler JCL”](#) on page 9.

## Changing the master scheduler JCL

When making changes to the master JCL, keep the following in mind:

- If you add DD statements to the master JCL, create the associated data sets before you load the initial program that is to use them. If the system cannot allocate a data set that is defined in the master JCL, system initialization fails.
- If you specify the START command in the master JCL for the primary job entry subsystem, specify the NOSTART parameter for the subsystem in the IEFSSNxx parmlib member. For the syntax of the NOSTART parameter, see [Chapter 59, “IEFSSNxx \(subsystem definitions\) - keyword parameter form,” on page 515](#) in this information.
- No work can be done that requires JES input or output services until the primary job entry subsystem is started.

To make changes to the master JCL, you can specify an alternate version of the master JCL in one of the following:

- A MSTJCLxx parmlib member (recommended)
- A MSTJCLxx load module in SYS1.LINKLIB.

If you plan to specify an alternate version of the master JCL in the MSTJCLxx load module in SYS1.LINKLIB, remember that you need to assemble the alternate version and link-edit it into SYS1.LINKLIB each time you make a change. It is easier to change the master JCL when it is specified in the MSTJCLxx parmlib member, because the assemble and link-edit are not required.

**Note:** IBM supplies the IEESMJCL member of SYS1.SAMPLIB as an example of alternate master JCL. The CSECT name in IEESMJCL is MSTJCL05. When specifying an alternate version of the master JCL, IBM suggests that you modify IEESMJCL according to your needs. The statements in IEESMJCL are only examples. They are not necessarily the same values that IBM supplies in the default load module MSTJCL00.

## Coding the parameter in IEASYSxx

The MSTRJCL parameter in the IEASYSxx parmlib member specifies the data set that is to contain the master JCL:

- If the system finds a MSTJCLxx parmlib member with a suffix that matches the value specified or defaulted on the MSTRJCL parameter, it uses the master JCL in the MSTJCLxx parmlib member and does not process the MSTJCLxx load module in SYS1.LINKLIB.
- If the system *does not* find a MSTJCLxx parmlib member that matches the value specified or defaulted on MSTRJCL, it uses the master JCL in the corresponding MSTJCLxx load module in SYS1.LINKLIB.

## Specifying the master JCL in parmlib

Take the following steps to specify the master JCL in a MSTJCLxx parmlib member:

1. Code the master JCL in the MSTJCLxx member, as described in [Chapter 78, “MSTJCLxx \(master scheduler JCL\),” on page 675](#).
2. Code the MSTRJCL=xx system parameter in the IEASYSxx parmlib member or in response to the SPECIFY SYSTEM PARAMETERS prompt. (See [Chapter 56, “IEASYSxx \(system parameter list\),” on page 421](#) for the syntax of the MSTRJCL=xx system parameter.)

## Specifying the master JCL in the MSTJCLxx load module

Take the following steps to specify an alternate version of the master JCL in a MSTJCLxx load module in SYS1.LINKLIB:

1. Code the master JCL in the alternate data set. Assemble the data set. Then link-edit the data set as a module in SYS1.LINKLIB (or a library concatenated to SYS1.LINKLIB, using a LNKSTxx or PROGxx member of of the parmlib concatenation).
2. Code the MSTRJCL=xx system parameter in the IEASYSxx parmlib member or in response to the SPECIFY SYSTEM PARAMETERS prompt. (See [Chapter 56, “IEASYSxx \(system parameter list\),” on page 421](#) for the syntax of the MSTRJCL=xx system parameter.)



3. Ensure that SYS1.PARMLIB does not contain a MSTJCLxx member that matches the suffix specified on the MSTRJCL=xx system parameter. (If such a member exists, the system uses the master JCL in that member, and does not process the master JCL in the MSTJCLxx load module.)

## Setting up started tasks with the Master JCL

The source JCL for a started task can be a job (source JCL that begins with a JOB statement) or a cataloged procedure. See *z/OS MVS JCL Reference* for information that describes the advantages of using one form of source JCL over another (using a job rather than a procedure).

If the source JCL for a started task is a job, the member containing the JCL must be part of a data set in the IEFPDSI DD or the IEFJOBS DD concatenation of MSTJCLxx. (If the member is not part of a data set in the IEFPDSI or IEFJOBS concatenation of MSTJCLxx, the procedures that act as source JCL for other started tasks will not be found.) IBM suggests that you define a new data set in MSTJCLxx (pointed to by the IEFJOBS DD statement) that will contain the tailored JCL to support started tasks.

To create source JCL that is a job (with, for example, JOB, JES2 JECL, and OUTPUT statements) for a started task, you must first decide whether these jobs should be mixed with procedures (part of the IEFPDSI concatenation) or placed into a separate data set (part of the IEFJOBS concatenation) containing only jobs.

### Using IEFJOBS to define started tasks

If MSTJCLxx contains a DD named IEFJOBS, the source JCL for a started task can be placed in one of the data sets within the IEFJOBS concatenation. Doing so allows jobs and the procedures they invoke to have the same name. These jobs can contain the minimum set of JCL needed to define the job level characteristics (for example, JOB statements, JCLLIB, and JECL), and then either invoke an existing procedure or use the INCLUDE keyword to invoke the desired set of JCL.

Use a name that allows you to quickly identify the data set. For example, the entry in MSTJCLxx could appear as:

```
//IEFJOBS DD DSN=SYS1.STCJOBS,DISP=SHR
```

For this example, you can put the source JCL for the started tasks in the SYS1.STCJOBS data set.

Consider these reasons for using IEFJOBS to define started tasks:

- MVS and other products ship procedures placed in procedure libraries. Your modifications to the members that contain your source JCL for started tasks might be lost if a new version of the procedure is received and placed into the procedure library.
- Defining data sets for IEFJOBS allows you to have the member name containing the source JCL invoke a procedure of the same name. For example, member name DUMPCHK in the IEFJOBS data set SYS1.STCJOBS is a job that invokes procedure DUMPCHK in SYS1.PROCLIB. This minimizes the effect on commands that might be issued from a variety of sources, and allows job parameters to be added transparently.

**Note:** Do not attempt to change the IEESYSAS procedure to a started job, or place a member named IEESYSAS in the IEFJOBS data set concatenation. IEESYSAS is reserved for use by the system for starting address spaces.

- Maintaining procedures in procedure libraries and jobs in an IEFJOBS data set can reduce potential confusion. For example, if you place a job in a procedure library, a user could mistakenly assume that the job is a procedure and invoke it as a procedure within a job; a job invoked as a procedure within a job fails.

### Using IEFPDSI to define started tasks

As shipped, MSTJCL00 contains an IEFPDSI DD statement that points to only one procedure library (SYS1.PROCLIB) used by the master subsystem. You can place individual jobs in any other procedure libraries pointed to by the IEFPDSI DD statement.

As an alternative to placing individual jobs in any of the other procedure libraries pointed to by the IEFJOBS DD statement, you can instead put jobs in the members of SYS1.PROCLIB or other data sets in the IEFPDSI concatenation. In this case, you must make sure that there is not another member of the same name in one of the data sets in the concatenation ahead of the data set containing the member with the source JCL.

## Started task processing

When you start a started task, the system determines whether the START command refers to a procedure or a job. (The system validates that the IEFJOBS DD exists within the MSTJCLxx member.) If the IEFJOBS DD exists, the system searches the IEFJOBS DD concatenation for the member requested in the START command. If there is no member by that name in the IEFJOBS concatenation, or if the IEFJOBS concatenation does not exist, the system searches the IEFPDSI DD for the member requested in the START command.

If a member is found, the system examines the first record for a valid JOB statement and, if one exists, uses the member as the JCL source for the started task.

If the member does not have a valid JOB statement in its first record, the system assumes that the source JCL is a procedure and creates JCL to invoke the procedure. After JCL source has been created (or found), the system processes the JCL.

## Writing your own master scheduler JCL

To write your own master scheduler JCL, specify the following JCL statements for the master scheduler JCL data set:

### //MSTJCLxx JOB

A JOB statement is required.

### // EXEC

An EXEC statement is required with PGM=IEEMB860. Program IEEMB860 is the master scheduler that does the IPL processing.

The EXEC statement must contain a time limit of 1440 or the program must be defined as a system task in the program properties table (PPT) to ensure that the master scheduler does not time out. See the description of the SCHEDxx parmlib member in [Chapter 82, “SCHEDxx \(PPT, master trace table, and abend codes for automatic restart\),” on page 713](#) for information about allowing your installation to specify programs in the PPT.

The master scheduler (IEEMB860) is defined in the PPT with several options; among them are SYST (system task) and NODSI (no data set integrity). SYST ensures that the master scheduler does not time out. NODSI means that the master scheduler JCL defined data sets are not enqueued or shared by MVS. This keeps the master scheduler from having to deal with enqueue contention for data sets, such as SYS1.PARMLIB. It also means that it is possible to move members within the data set while the system is trying to read them. This can result in I/O errors. Any manipulation of the data sets defined to the master scheduler JCL should be done with extreme caution.

### //STCINRDR DD

This DD statement defines the internal reader where started tasks are to be sent.

### //TSOINRDR DD

This DD statement defines the internal reader where TSO logon started tasks are to be sent.

### //IEFJOBS DD

This DD statement defines the data set that contains job source JCL for started tasks. This data set can be a PDSE and can be SMS-managed. The data set can also be a concatenation.

### //IEFPDSI DD

This DD statement defines the data set that contains procedure source JCL for started tasks. Normally this data set is SYS1.PROCLIB; it can be a concatenation. For useful work to be performed, the data set must at least contain the procedure for the primary JES.

## //IEFPARM DD

Optionally, this DD statement defines SYS1.PARMLIB or an equivalent for use by the master scheduler address space following master scheduler initialization; it can be a concatenation. Some subsystems and address spaces use other techniques to read parameter information from SYS1.PARMLIB or other sources.

If you specify this DD statement and there are parmlib statements in the LOADxx member of SYS1.PARMLIB, IEFPARM is ignored, a warning message is issued and the LOADxx parmlib data sets are used. If the specified parmlib statements in LOADxx cannot be found, IEFPARM is ignored, a warning message is issued and the system uses SYS1.PARMLIB as the default. If there are no parmlib data sets specified in LOADxx, the system uses the parmlibs on the IEFPARM DD statement.

If you do not specify this DD statement, the system uses the parmlib data sets specified in the LOADxx member of SYS1.PARMLIB. If no parmlib data sets were specified in LOADxx, or if the specified parmlib data sets cannot be found, the system uses SYS1.PARMLIB as the default. If no SYS1.PARMLIB is cataloged, the system uses the SYS1.PARMLIB on the SYSRES volume.

## //SYSUADS DD

Optionally, this DD statement is defined for TSO/E.

## //SYSRACF DD

Optionally, this DD statement is defined for RACF. Use an IRRPRMxx member to specify statements that describe the RACF data set name table and the range table, that were previously defined by ICHRDSNT and ICHRRNG. See [Chapter 68, “IRRPRMxx \(RACF parameters\),” on page 591](#) and [IRRPRMxx parmlib member in z/OS Security Server RACF System Programmer's Guide](#) for more information.

**Note:** You can only specify a primary RACF database name with the SYSRACF DD.

/\*

Ends the JCL.

Also:

- The master scheduler JCL can contain only one step.
- MVS system commands can be placed in the master scheduler JCL. These commands are read in before the master scheduler is executed. They are normally processed before those commands that are specified in the COMMNDxx member of parmlib.
- OUTPUT JCL and DD SYSOUT statements can be placed in the master scheduler JCL.
- The master scheduler JCL can contain a JOBLIB or STEPLIB DD statement (which are usually used for testing).
- Other DD statements that might be needed during master scheduler processing, such as RACF-related DD statements, can be placed in the master scheduler JCL.
- The master scheduler JCL no longer has to point to the broadcast data set. You now specify the broadcast data set in the IKJTSOxx member. The master JCL will no longer allocate the broadcast data set. TSO/E will use either the default (SYS1.BROADCAST) or the BROADCAST parameter in IKJTSOxx to allocate the broadcast data set. If you wish to go on using SYS1.BROADCAST, no action is required. If you want to use a broadcast data set other than SYS1.BROADCAST, specify it in IKJTSOxx.
- All data sets that are defined in the master scheduler JCL and do not specify VOL=SER=volser on the data set name must be cataloged in the master catalog.
- The master scheduler JCL cannot contain any EXEC PROC statements.
- The master scheduler JCL runs in the master scheduler's address space. The TIOT size is 12 K, which means that approximately 600 unit allocations can be done in the master scheduler's address space. Therefore, be careful not to exceed this limit when allocating data sets in the master scheduler JCL. Data sets that reside on multiple volumes or that have a data class with a dynamic volume count greater than 1 use more TIOT space than single volume data sets, reducing the number of data sets that can be allocated. For more information about TIOT space calculations, see the description of the TIOT SIZE parameter in the ALLOCxx parmlib member.
- The master scheduler JCL does not support the following JCL statements:

- ELSE
  - ENDIF
  - IF/THEN
  - INCLUDE
  - JCLLIB
  - The master JCL can contain the JCL statements COMMAND and SET.
  - The master JCL can contain system symbols. Remember, however, that the system does not process symbols in MSTJCLxx in the same way that it processes symbols in parmlib members. Because MSTJCLxx contains JCL, the system processes symbols in MSTJCLxx during JCL processing. The results of symbolic substitution reflect the substitution rules that are in effect during JCL processing.
- See Chapter 2, “Sharing parmlib definitions,” on page 31 for general information about defining and using system symbols in parmlib. See [z/OS MVS JCL Reference](#) for details about using system symbols in JCL.
- The master JCL cannot contain the &SYSUID symbol. &SYSUID, which is normally allowed in JCL, is not defined for the master JCL.

## Overview of parmlib members

Table 2 on page 14 contains an overview of parmlib members. Notice that IBM-supplied parmlib members use 00 for xx.

| Table 2. Characteristics of parmlib members                                       |                      |                               |   |   |  |  |                          |                          |                               |
|---|----------------------|-------------------------------|---|---|--|--|--------------------------|--------------------------|-------------------------------|
| Supplied by IBM   | Required or optional | Affects performance directly? | Read at IPL or at command?  | Allows listing of parameters at IPL or command? | Response to errors (N/A = Not applicable)  |  |                          | System symbols support ? | Concatenated parmlib support? |
|   |                      |                               |   |   | Syntax error   | Read error   | Unsupported parameters   |                          |                               |
| ADYSETxx: Parameters that control dump analysis and elimination (DAE) processing. |                      |                               |   |   |  |  |                          |                          |                               |
| Yes   | Optional             | Yes                           | At IPL and SET DAE command.                                       | No  | Error message requires the operator to correct the parmlib member SET DAE command. | Error message requires the operator to start DAE again (using the SET DAE command) after the problem is fixed. | N/A                      | Yes                      | Yes                           |
| ALLOCxx: Parameters that control installation defaults for allocation values.     |                      |                               |   |   |  |  |                          |                          |                               |
| Yes, in SYS1.SAMPLIB  | Optional             | Yes                           | IPL   | No  | Error message requires the operator to correct the parmlib member.                 | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| ANTMIN00: Parameters that control ANTMMAIN.                                       |                      |                               |   |   |  |  |                          |                          |                               |
| Yes   | Optional             | No                            | IPL, ANTMMAIN startup   | No  | Error message is issued.   | Error message is issued.   | Error message is issued. | No                       | Yes                           |
| ANTXIN00: Parameters that control Extended Remote Copy (XRC).                     |                      |                               |   |   |  |  |                          |                          |                               |
| Yes   | Optional             | Yes                           | XSTART and XSET commands, ANTASnnn ANTCLnnn address space startup | Yes   | Error message is issued.   | Error message is issued.   | Error message is issued. | No                       | Yes                           |
| APPCPMxx: Parameters that define or modify the APPC/MVS configuration.            |                      |                               |   |   |  |  |                          |                          |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM  | Required or optional | Affects performance directly? | Read at IPL or at command?              | Allows listing of parameters at IPL or command? | Response to errors (N/A = Not applicable)                             |   |   | System symbols support ? | Concatenated parmlib support? |
|--|----------------------|-------------------------------|---|---|---|---|---|--------------------------|-------------------------------|
|  |                      |                               |   |   | Syntax error  | Read error  | Unsupported parameters  |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | Yes                           | START APPC or SET APPC operator command | Yes   | Error message requires the operator to correct the parmlib member.    | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>ASCHPMxx:</b> Parameters that define scheduling information for the ASCH transaction scheduler.   |                      |                               |   |   |   |   |   |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | Yes                           | START ASCH or SET ASCH operator command | Yes   | Error message requires the operator to correct the parmlib member.    | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>AUTORxx:</b> Parameters that change the auto-reply processing settings on a system.   |                      |                               |   |   |   |   |   |                          |                               |
| Yes  | Optional             | No                            | IPL and SET AUTOR command               | No  | Error message is issued.  | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>AXR00:</b> Parameters that are needed when installation changes to default settings are required.   |                      |                               |   |   |   |   |   |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | No                            | IPL                                     | No  | Error messages require the operator to correct the parmlib member.    | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>BLSCECT:</b> Parameters that control dump formatting performed by IPCS, and by the system (through the ABEND and SNAP macros).  |                      |                               |   |   |   |   |   |                          |                               |
| Yes  | Optional             | No                            | At IPL and at START BLSJPRMI            | No  | Error message is issued.  | Error message is issued.  | N/A   | Yes                      | Yes                           |
| <b>BLSUSER:</b> Parameters that specify IPCS customization.  |                      |                               |   |   |   |   |   |                          |                               |
| No   | Optional             | No                            | At IPL and at START BLSJPRMI            | No  | Error message is issued.  | Error message is issued.  | N/A   | Yes                      | Yes                           |
| <b>BPXPRMxx:</b> Parameters that control the z/OS UNIX System Services environment and z/OS UNIX file system. The system uses these values when initializing the z/OS UNIX System Services kernel. |                      |                               |   |   |   |   |   |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | No                            | IPL                                     | No  | Error message requires the operator to correct the parmlib member.    | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>CEAPRMxx:</b> Parameters that customize common event adapter (CEA) values.  |                      |                               |   |   |   |   |   |                          |                               |
| Yes, in SYS1. PARMLIB  | Required             | No                            | At IPL and F CEA,CEA= command           | Yes, through F CEA, DISPLAY, PARMS command.     | Error message is issued.  | Error message is issued.  | Error message is issued.  | No                       | Yes                           |
| <b>CEEPRMxx:</b> Parameters that control default Language Environment® runtime options for a system.   |                      |                               |   |   |   |   |   |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | No                            | At IPL and SET CEE command              | Yes   | Error message is issued.  | Error message is issued.  | Error message is issued.  | Yes                      | Yes                           |
| <b>CLOCKxx:</b> Parameters that control operator prompting to set the TOD clock, specifying the difference between the local time and UTC, and ETR usage.  |                      |                               |   |   |   |   |   |                          |                               |
| Yes  | Optional             | No                            | IPL                                     | Yes   | Prompts operator to respecify, or cancel parameter through ENTER key. | Prompts operator to respecify, or cancel parameter through ENTER key. | Prompts operator to respecify, or cancel parameter through ENTER key. | Yes                      | Yes                           |
| <b>CNGRPxx:</b> Parameters that define console groups.   |                      |                               |   |   |   |   |   |                          |                               |

| Table 2. Characteristics of parmlib members (continued)   |                                     |                               |   |  |   |  |                          |                               |                               |
|---|-------------------------------------|-------------------------------|---|--|---|--|--------------------------|-------------------------------|-------------------------------|
| Supplied by IBM   | Required or optional                | Affects performance directly? | Read at IPL or at command?  | Allows listing of parameters at IPL or command?  | Response to errors (N/A = Not applicable)   |  |                          | System symbols support ?      | Concatenated parmlib support? |
|   |                                     |                               |   |  | Syntax error  | Read error   | Unsupported parameters   |                               |                               |
| No  | Optional                            | No                            | At IPL and SET CNGRP command.   | No   | Error message is issued.  | Operator is prompted for a new CNGRPxx member.           | Error message.           | Yes                           | Yes                           |
| <b>CNLcccxx:</b> Defines how translated messages are to be displayed at your installation.  |                                     |                               |   |  |   |  |                          |                               |                               |
| Yes   | Optional                            | No                            | At IPL and SET MMS command.   | No   | Error message is issued.  | Error message is issued.                                 | Error message is issued. | No                            | Yes                           |
| <b>COFDLFxx:</b> Allows a program to store DLF objects that can be shared by many jobs in virtual storage managed by Hiperbatch.  |                                     |                               |   |  |   |  |                          |                               |                               |
| Yes   | Optional                            | Yes                           | At IPL and START DLF command.   | No   | Error message is issued.  | Error message is issued.                                 | Error message is issued. | Yes                           | Yes                           |
| <b>COFVLFxx:</b> Allows an authorized program to store named objects in virtual storage managed by VLF.   |                                     |                               |   |  |   |  |                          |                               |                               |
| Yes   | Optional                            | Yes                           | START VLF command.  | No   | Error message is issued.  | Error message is issued.                                 | Error message is issued. | Yes                           | Yes                           |
| <b>COMMNDxx:</b> Commands to be issued by the control program immediately after initialization. JES commands may Not be included.   |                                     |                               |   |  |   |  |                          |                               |                               |
| No  | Optional                            | No                            | IPL   | No   | Invalid commands are ignored and an error message is issued.                          | No commands are processed.                               | N/A                      | Yes (see Note "4" on page 25) | Yes                           |
| <b>CONFIGxx:</b> Allows the installation to define a standard configuration that is compared with current configuration and to reconfigure processors, storage, and channel paths.  |                                     |                               |   |  |   |  |                          |                               |                               |
| No  | Optional                            | No                            | DISPLAY M command with CONFIG option and CONFIG command with MEMBER option. | No   | Invalid commands are ignored and an error message is issued.                          | Processing is terminated and an error message is issued. | N/A                      | Yes                           | Yes                           |
| <b>CONSOLxx:</b> Parameters to define an installation's console configuration, initialization values for console services, the default routing codes for all WTO/WTOR messages that have None assigned, and the characteristics of the hardcopy message set. CONSOLxx also contains parameters that define the hardcopy medium. |                                     |                               |   |  |   |  |                          |                               |                               |
| Yes, IEACONxx in SYS1.SAMPLIB   | Required (unless joining a sysplex) | No                            | IPL and SET CON= command.   | Yes, if L option is specified with the CON parameter in IEASYSxx or by the operator. The L option is only valid at IPL | Error message is issued.  | Operator is prompted for a new CONSOLxx member.          | Error message.           | Yes                           | Yes                           |
| <b>COUPLExx:</b> Describes the systems complex (sysplex) environment for the system.  |                                     |                               |   |  |   |  |                          |                               |                               |
| Yes   | Required                            | Yes                           | IPL Note: Options changed using SETXCF command                              | No   | Error message is issued. The operator may also be prompted for a new COUPLExx member. | The operator is prompted for a new COUPLExx member.      | Error message.           | Yes                           | Yes                           |
| <b>CSVLLAxx:</b> Allows an installation to list the entry point name or LNKLIST libraries that can be refreshed by the 'MODIFY LLA, UPDATE=xx' command.   |                                     |                               |   |  |   |  |                          |                               |                               |
| No  | Optional                            | No                            | MODIFY LLA and START LLA commands   | Yes  | Error message is issued.  | Error message is issued.                                 | Error message is issued. | Yes                           | Yes                           |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM   | Required or optional   | Affects performance directly?                  | Read at IPL or at command?                   | Allows listing of parameters at IPL or command?                      | Response to errors (N/A = Not applicable)  |  |                          | System symbols support ? | Concatenated parmlib support? |
|---|--|--|--|--|--|--|--------------------------|--------------------------|-------------------------------|
|   |  |  |  |  | Syntax error   | Read error   | Unsupported parameters   |                          |                               |
| CTnccccx: Specifies component trace options.  |  |  |  |  |  |  |                          |                          |                               |
| Yes   | depends on the component   | No   | At IPL or TRACE CT command                   | No   | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| CUNUNlxx: Specifies parameters for Unicode conversion services.   |  |  |  |  |  |  |                          |                          |                               |
| No  | Optional   | No   | Both   | Yes, messages are issued when Unicode conversion services are active | Error message is issued.   | Error message is issued.   | Error message is issued. | No                       | No                            |
| DEVSUPxx: Specifies options for the device support and access method portions of the operating system                             |  |  |  |  |  |  |                          |                          |                               |
| No  | Optional   | No   | IPL or SET DEVSUP command                    | Yes  | Error message is issued.   | Error message is issued.   | Error message is issued. | No                       | Yes                           |
| DFHSSIxx: Specifies message-formatting initialization parameters for the CICS® subsystem of the SYS1.PARMLIB library.             |  |  |  |  |  |  |                          |                          |                               |
| Yes   | Optional   | No   | IPL  | No   | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| DIAGxx: Contains diagNostic commands that control the common storage tracking and GETMAIN/FREEMAIN/STORAGE (GFS) trace functions. |  |  |  |  |  |  |                          |                          |                               |
| Yes   | Optional   | No   | At IPL or SET DIAG command                   | No   | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| EXITxx: Allows an installation to specify installation exits for allocation decisions.  |  |  |  |  |  |  |                          |                          |                               |
| No  | Optional   | No   | IPL  | No   | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | No                            |
| EXSPATxx: Allows an installation to specify actions taken to recover from excessive spin conditions without operator involvement. |  |  |  |  |  |  |                          |                          |                               |
| No  | Optional   | No   | SET EXS command                              | No   | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| FXEPRMxx: Contains statements that let you control the IBM Function Registry for z/OS.  |  |  |  |  |  |  |                          |                          |                               |
| No  | Optional   | No   | At IPL and at SET FXE or DISPLAY FXE command | Yes through the DISPLAY FXE,IPLPARMS command                         | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| GRSCNFxx: Configuration parameters for systems that are to share resources in a global resource serialization complex.            |  |  |  |  |  |  |                          |                          |                               |
| Yes   | Required only if GRS=START, GRS=JOIN or GRS=TRYJOIN is specified.<br><br>Ignored if GRS=NONE is specified. | Yes, by specification of the RESMIL parameter. | IPL  | No   | Error message requires the operator to either correct the parmlib member and restart the system or reply NONE. | Error message requires the operator to either restart the system after the problem is fixed or reply NONE. | N/A                      | Yes                      | Yes                           |
| GRSMONxx: Parameters to control the Global Resource Serialization Monitor   |  |  |  |  |  |  |                          |                          |                               |
| Yes   | Optional   | No   | SETGRS command                               | No   | Error message  | Error message  | N/A                      | Yes                      | No                            |
| GRSRNLxx: Resource name lists (RNLs) that the system uses when a global resource serialization complex is active.                 |  |  |  |  |  |  |                          |                          |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM  | Required or optional   | Affects performance directly?                                 | Read at IPL or at command?                   | Allows listing of parameters at IPL or command? | Response to errors (N/A = Not applicable)  |  |                          | System symbols support ? | Concatenated parmlib support? |
|--|--|---|--|---|--|--|--------------------------|--------------------------|-------------------------------|
|  |  |   |  |   | Syntax error   | Read error   | Unsupported parameters   |                          |                               |
| Yes  | Required only if GRS=START, GRS=JOIN or GRS=TRYJOIN is specified and GRSRNL=EXCLUDE is Not specified.<br><br>Ignored if GRS=NONE is specified. | Yes   | IPL or SET GRSRNL command                    | No  | At IPL: Error message requires the operator to either correct the parmlib member and restart the system or reply NONE. On SET GRSRNL command: Error message and the command is Not done. | At IPL: Error message requires the operator to either restart the system after the problem is fixed or reply NONE. On SET GRSRNL command: Error message and the command is Not done. | N/A                      | Yes                      | Yes                           |
| <b>GTFPRMxx:</b> Parameters to control GTF.  |  |   |  |   |  |  |                          |                          |                               |
| Yes  | Optionally used. Can be modified by installation.  | Indirectly because SRM sysevent trace option is a tuning aid. | START GTF                                    | Yes, automatically at START GTF.                | On any error, prompts for all parameters.  | Same as with syntax error.   | N/A                      | No                       | No                            |
| <b>GTZPRMxx:</b> Contains statements that control the behavior of Generic Tracker.   |  |   |  |   |  |  |                          |                          |                               |
| No   | Optional   | No  | IPL and SET GTZ                              | Yes   | Error message is issued  | Error message is issued  | Error message is issued  | Yes                      | Yes                           |
| <b>HZSPRMxx:</b> Contains statements that define overrides to IBM Health Checker for z/OS check defaults and specify the IBM Health Checker for z/OS policy or policies for managing checks. |  |   |  |   |  |  |                          |                          |                               |
| No   | Optional   | No  | S hzsproc or F hzsproc command.              | Yes, through F hzsproc , DISPLAY command        | Error message is issued.   | Error message is issued.   | Error message is issued. | Yes                      | Yes                           |
| <b>IARPRMxx:</b> Parameters for Real Storage Manager controls  |  |   |  |   |  |  |                          |                          |                               |
| No   | Optional   | Yes   | IPL  | Yes – see F AXR,IAXDMEM                         | Error message is issued  | Error message is issued  | Error message is issued  | No                       | Yes                           |
| <b>IDAVDTxx:</b> Parameters for VSAM dynamic trace.  |  |   |  |   |  |  |                          |                          |                               |
| No   | Optional   | Yes   | S IDAVDT first and then F IDAVDT,READIN[=xx] | Yes, through F IDAVDT,DISPLAY=n                 | Error message is issued  | Error message is issued  | N/A                      | No                       | Yes                           |
| <b>IEAABD00:</b> Default parameters for an ABEND dump when a SYSABEND DD statement has been specified.   |  |   |  |   |  |  |                          |                          |                               |
| Yes  | Optional. However, if member is unavailable, ABEND dumps may Not be possible without DUMPOPT lists.  | No  | IPL  | No  | Message lists valid parameters that were accepted. Invalid parameters are rejected.  | Error message. Parameters are rejected.  | Error message is issued. | No                       | Yes                           |
| <b>IEAAPFxx:</b> Names of authorized program libraries.  |  |   |  |   |  |  |                          |                          |                               |



Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM   | Required or optional   | Affects performance directly? | Read at IPL or at command? | Allows listing of parameters at IPL or command?                                   | Response to errors (N/A = Not applicable)  |   |   | System symbols support ? | Concatenated parmlib support? |
|---|--|-------------------------------|----------------------------|---|--|---|---|--------------------------|-------------------------------|
|   |  |                               |                            |   | Syntax error   | Read error                              | Unsupported parameters                            |                          |                               |
| No  | Optional. SYS1. LINKLIB and SYS1.SVCLIB are always authorized (see Note “5” on page 25).   | No                            | IPL                        | No  | Prompts operator to respecify bad parameters or cancel parameters through ENTER key. | Same as with syntax error.              | N/A   | No                       | Yes                           |
| <b>IEAAP00:</b> Names of authorized installation-written I/O appendage routines.                          |  |                               |                            |   |  |   |   |                          |                               |
| No  | Optional   | No                            | IPL                        | No  | Error message. Partial appendage name table is built, if possible.                   | Same as with syntax error.              | N/A   | Yes                      | Yes                           |
| <b>IEACMD00:</b> IBM-supplied commands that are processed during system initialization.                   |  |                               |                            |   |  |   |   |                          |                               |
| Yes   | Optional   | Yes                           | IPL                        | No  | Ignores invalid command name.  | No commands are processed.              | N/A   | Yes                      | Yes                           |
| <b>IEADMCxx:</b> Parameters for DUMP command.   |  |                               |                            |   |  |   |   |                          |                               |
| No  | Optional   | No                            | DUMP command               | No  | Error message. Parameters are rejected.  | Error message. Parameters are rejected. | N/A   | Yes                      | Yes                           |
| <b>IEADMP00:</b> Default parameters for an ABEND dump when SYSUDUMP DD statement has been specified.      |  |                               |                            |   |  |   |   |                          |                               |
| Yes   | Optional. However, if member is unavailable, ABEND dumps may Not be possible without DUMPOPT lists. Can be modified by installation. | No                            | IPL                        | No  | Message lists valid parameters that were accepted. Invalid parameters are rejected.  | Error message. Parameters are rejected. | N/A   | No                       | Yes                           |
| <b>IEADMR00:</b> Default parameters for an ABEND dump when SYSMDUMP DD statement has been specified.      |  |                               |                            |   |  |   |   |                          |                               |
| Yes   | Optional. However, if member is unavailable, ABEND dumps may not be possible without DUMPOPT lists. Can be modified by installation. | No                            | IPL                        | No  | Message lists valid parameters that were accepted. Invalid parameters are rejected.  | Error message. Parameters are rejected. | N/A   | No                       | Yes                           |
| <b>IEAFIXxx:</b> Names of modules to be fixed in storage for the duration of the IPL.                     |  |                               |                            |   |  |   |   |                          |                               |
| No  | Optional   | Yes                           | IPL                        | Yes, if L option is specified with FIX parameter in IEASYSxx, or by the operator. | Prompts the operator to respecify bad parameters or cancel them through ENTER key.   | Same as with syntax error.              | Error message. Obsolete module names are ignored. | Yes                      | Yes                           |
| <b>IEALPApp:</b> Names of reenterable modules that are to be loaded as a temporary extension to the PLPA. |  |                               |                            |   |  |   |   |                          |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM  | Required or optional                                      | Affects performance directly? | Read at IPL or at command?  | Allows listing of parameters at IPL or command?  | Response to errors (N/A = Not applicable)   |  |  | System symbols support ? | Concatenated parmlib support? |
|--|---|-------------------------------|-----------------------------|--|---|--|--|--------------------------|-------------------------------|
|  |   |                               |                             |  | Syntax error  | Read error   | Unsupported parameters                         |                          |                               |
| No   | Optional  | Yes                           | IPL                         | Yes, if L option is specified with the MLPA parameter in IEASYSxx, or by the operator. | Prompts operator to respecify, or cancel parameter through ENTER key.   | Same as with syntax error.   | Error message. Ignores obsolete module names.  | Yes                      | Yes                           |
| <b>IEAOPTxx:</b> Parameters that control resource and workload management algorithms in the system resources manager.<br>Beginning with z/OS V1R3, WLM compatibility mode is No longer available. Accordingly, you can no longer use any of the IEAOPTxx options that were valid in compatibility mode only. The information has been left here for reference purposes, and for use on previous systems. |   |                               |                             |  |   |  |  |                          |                               |
| IEAOPT00: Yes<br>IEAOPTxx: No  | Optional  | Yes                           | At IPL and SET OPT command. | Yes, if L option is specified with the OPT parameter in IEASYSxx, or by the operator.  | Prompts operator to respecify or cancel parameter through ENTER key. If parameter is canceled, various defaults are used. | Same as with syntax error.   | N/A  | Yes                      | Yes                           |
| <b>IEAPAKxx:</b> "Pack List" names of groups of modules in the LPAIST concatenation that the system will load between page boundaries to minimize page faults.   |   |                               |                             |  |   |  |  |                          |                               |
| No. Optionally, installation can provide before IPL.   | Optional  | Yes                           | IPL                         | No   | Bypasses the pack group that contains the error. Processes the next group pack.   | The pack groups read before the errors are processed. Other pack groups are omitted. | Error message. Ignores obsolete modules names. | Yes                      | Yes                           |
| <b>IEASLPxx:</b> Contains valid SLIP commands.   |   |                               |                             |  |   |  |  |                          |                               |
| Yes, in SYS1. PARMLIB.   | Required if SET SLIP=00 command is specified in IEACMD00. | No                            | At IPL and SET SLIP command | No   | Normal SLIP response to prompt the operator.  | Processing stops.  | Syntax error message is issued.                | Yes                      | Yes                           |
| <b>IEASVCxx:</b> Allows the installation to define its own SVCs in the SVC table.  |   |                               |                             |  |   |  |  |                          |                               |
| No   | Optional  | No                            | IPL                         | Yes, if L option is specified with the SVC parameter in IEASYSxx, or by the operator.  | Message is issued and the statement in error is Not processed. Processing continues with the next statement.              | Same as with syntax error.   | Same as with syntax error.                     | Yes                      | Yes                           |
| <b>IEASYMxx:</b> Specifies, for one or more systems in a multisystem environment, the static system symbols and suffixes of IEASYSxx members that the system is to use. One or more IEASYMxx members are selected using the IEASYM parameter in the LOADxx parmlib member.   |   |                               |                             |  |   |  |  |                          |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM   | Required or optional     | Affects performance directly?                     | Read at IPL or at command?                              | Allows listing of parameters at IPL or command?                                   | Response to errors (N/A = Not applicable)   |   |   | System symbols support ? | Concatenated parmlib support? |
|---|--------------------------|---|---|---|---|---|---|--------------------------|-------------------------------|
|   |                          |   |   |   | Syntax error  | Read error  | Unsupported parameters                            |                          |                               |
| No  | Optional                 | No  | IPL   | The I parameter must be specified with parameter or number.                       | Prompts operator to respecify or cancel parameter through ENTER key. Parameters that are processed before the error are discarded. Also, in some error situations, a wait state occurs. | Same as with syntax error.  | Same as with syntax error.                        | Yes                      | Yes                           |
| <b>IEASYSxx:</b> System parameters that are valid responses to the SPECIFY SYSTEM PARAMETERS message. Multiple system parameter lists are valid. The list is chosen by the operator SYSP parameter or through the SYSPARM statement of the LOADxx parmlib member (see Chapter 73, "LOADxx (system configuration data sets)," on page 613 for more information). |                          |   |   |   |   |   |   |                          |                               |
| No  | See Note "2" on page 25. | See Note "3" on page 25.                          | IPL   | See Note "1" on page 25 (L parameter must be specified with parameter or number). | Prompts operator to respecify, or cancel parameter through ENTER key. Parameters that are processed before the error are retained.  | Parameters that are processed before the error are retained. The operator is asked to specify an alternative member. The new parameters override the ones that were retained. | Obsolete parameters are treated as syntax errors. | Yes                      | Yes                           |
| <b>IECIOSxx:</b> Parameters that control missing interrupt handler (MIH) intervals and update hot I/O detection table (HIDT) values.  |                          |   |   |   |   |   |   |                          |                               |
| No  | Optional                 | No  | IPL or SET IOS command (to change the MIH values only). | No  | Message is issued and the default value is substituted.   | Same as with syntax error.  | Obsolete parameters are treated as syntax errors. | Yes                      | Yes                           |
| <b>IEFOPZxx:</b> Defines the data set optimization configuration.   |                          |   |   |   |   |   |   |                          |                               |
| No  | Optional                 | No  | Both IPL and SET IEFOPZ command                         | Yes, through DISPLAY IEFOPZ   | Error message is issued   | Error message is issued   | Error message is issued                           | Yes                      | Yes                           |
| <b>IEFSSNxx:</b> Parameters that identify what subsystems are to be initialized.  |                          |   |   |   |   |   |   |                          |                               |
| Yes   | Required                 | Yes, depending on the function of each subsystem. | IPL   | No  | Message that identifies the erroneous record is issued. The next record is read and processed.  | Processing of the parmlib members is terminated and an error message is issued.   | N/A   | Yes                      | Yes                           |
| <b>IFAPRDxx:</b> Parameters that define a product enablement policy.  |                          |   |   |   |   |   |   |                          |                               |
| Yes   | Optional                 | No  | At IPL and SET PROD command.                            | No, but information is available through DISPLAY.                                 | Skips to next statement in member.  | Processing is terminated and an error message is issued.  | Skips to next statement in member.                | Yes                      | Yes                           |
| <b>IFGPSEDI:</b> Initializes the Enhanced Data Integrity(EDI) for shared physical sequential data sets function.  |                          |   |   |   |   |   |   |                          |                               |

| Table 2. Characteristics of parmlib members (continued)  |                      |                               |  |  |   |                            |                                  |                          |                               |
|--|----------------------|-------------------------------|--|--|---|----------------------------|----------------------------------|--------------------------|-------------------------------|
| Supplied by IBM  | Required or optional | Affects performance directly? | Read at IPL or at command?   | Allows listing of parameters at IPL or command?  | Response to errors (N/A = Not applicable)   |                            |                                  | System symbols support ? | Concatenated parmlib support? |
|  |                      |                               |  |  | Syntax error  | Read error                 | Unsupported parameters           |                          |                               |
| No   | Optional             | No                            | At IPL and START IFGEDI command.   | No   | Error message requires the operator to correct the parmlib member.                                  | Same as with syntax error. | Same as with syntax error.       | Yes                      | Yes                           |
| <b>IGDMSxx:</b> Initialize the Storage Management Subsystem (SMS) and specify the names of the active control data set (ACDS) and the communications data set (COMMS).   |                      |                               |  |  |   |                            |                                  |                          |                               |
| No   | Required             | No                            | At IPL and SET SMS command.  | Yes  | Default value is substituted.   | Same as with syntax error. | Obsolete parameters are ignored. | Yes                      | Yes                           |
| <b>IGGCATxx:</b> Parameters that define the catalog configuration  |                      |                               |  |  |   |                            |                                  |                          |                               |
| No   | Optional             | Yes, VVRCHECK                 | IPL, Catalog Address Space Restart   | Yes, using the MODIFY CATALOG, REPORT command  | Message IEC386S is issued.  | Message IEC385S is issued. | Message IEC386S is issued.       | No                       | Yes                           |
| <b>IKJTSOxx:</b> For TSO/E specifies authorized commands and authorized program, programs that are authorized when called through the TSO service facility, commands that cannot be issued in the background, and defaults for SEND and LISTBC processing. |                      |                               |  |  |   |                            |                                  |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | No                            | IPL or TSO/E PARMLIB command   | No   | Error message is issued. Processing continues.  | Same as with syntax error. | N/A                              | Yes                      | Yes                           |
| <b>IOEPRMxx:</b> Parameters that control the processing options for the zFS PFS.   |                      |                               |  |  |   |                            |                                  |                          |                               |
| Yes  | Optional             | Yes                           | IPL and start or restart of zFS (using SETOMVS =(xx) or reply R to BPXF032D message) | Yes, using the MODIFY ZFS, QUERY, SETTINGS operator command                              | Ignored.  | Error message is issued.   | Ignored.                         | Yes                      | Yes                           |
| <b>IPCSPRxx:</b> Parameters that are used during an IPCS session.  |                      |                               |  |  |   |                            |                                  |                          |                               |
| Yes  | Optional             | No                            | IPCS command initialization  | No   | Error message is issued. IPCS session continues.  | Same as with syntax error. | Same as with syntax error.       | Yes                      | Yes                           |
| <b>IQPPRMxx:</b> Defines parameters for PCIe-related devices.  |                      |                               |  |  |   |                            |                                  |                          |                               |
| No   | Optional             | Yes                           | Both IPL and SET IQP command   | Yes, if L parameter was specified with the IQP parameter in IEASYSxx, or by the operator | Error message is issued.  | Error message is issued.   | Error message is issued.         | Yes                      | Yes                           |
| <b>IRRPxx:</b> Defines parameters for RACF.  |                      |                               |  |  |   |                            |                                  |                          |                               |
| Yes, in SYS1. SAMPLIB  | Optional             | No                            | IPL  | No   | Operator responds to prompt. System programmer is required to specify primary and backup data sets. | Same as with syntax error. | Same as with syntax error.       | Yes                      | Yes                           |
| <b>IVTPRM00:</b> Sets Communications Storage Manager (ICSM) parameters.  |                      |                               |  |  |   |                            |                                  |                          |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM  | Required or optional   | Affects performance directly?                 | Read at IPL or at command?   | Allows listing of parameters at IPL or command?                                   | Response to errors (N/A = Not applicable)   |  |  | System symbols support ?                                     | Concatenated parmlib support? |
|--|--|---|--|---|---|--|--|--|-------------------------------|
|  |  |   |  |   | Syntax error  | Read error   | Unsupported parameters   |  |                               |
| Yes, as a VTAM® component  | Optional   | Yes   | Initialized by first CREATE _POOL request received.                                | Yes   | Error message is issued. Processing continues.  | Same as with syntax error.   | Same as with syntax error.   | Yes  | Yes                           |
| <b>IXGCNFxx:</b> Parameters that control processing options for system logger.   |  |   |  |   |   |  |  |  |                               |
| Yes, in SYS1. SAMPLIB  | Optional   | Yes   | At IPL and restart of IXGLOGR (through Start IXGLOGRS proc) or SET IXGCNF command. | Yes, merged information is available through DISPLAY LOGGER, IXGCNF command.      | At IPL: Error message is issued and default values are substituted for all parameters.      | Same as with syntax error.   | Same as with syntax error.   | Yes  | Yes                           |
| <b>IZUPRMxx:</b> Specifies options for IBM z/OS Management Facility (z/OSMF).  |  |   |  |   |   |  |  |  |                               |
| Yes, in SYS1. SAMPLIB  | Optional   | Yes, depending on which plug ins are enabled. | At IPL or by using the commands START IZUANG1 and START IZUSVR1.                   | Yes, by using the MODIFY command with the option 'DISPLAY IZU'.                   | Error message is issued.  | Error message is issued.   | Error message is issued.   | Yes  | Yes                           |
| <b>LNKLSTxx:</b> List of data sets to be concatenated to form the LNKLST concatenation. You can also use PROGxx to define the concatenation.     |  |   |  |   |   |  |  |  |                               |
| Yes, in SYS1. SAMPLIB  | Required if PROGxx is Not used for LNKLST concatenation; otherwise, ignored if PROGxx is used. | No  | IPL  | Yes, if L option is specified with LNK parameter in IEASYSxx, or by the operator. | Prompts operator to respecify, or cancel parameter through ENTER key.                       | No data sets are concatenated to SYS1. LINKLIB. Operator can re-IPL to specify an alternate LNKLSTxx member. | Error message. Data sets Not found will Not be concatenated to SYS1. LINKLIB | Yes  | Yes                           |
| <b>LOADxx:</b> Specifies data sets MVS uses to configure your system.  |  |   |  |   |   |  |  |  |                               |
| No. (See the IPXLOADX member of SYS1. SAMPLIB for JCL to create a sample LOADxx member.)   | Required   | No  | IPL - from LOAD parameter on system console  | No  | Wait state is loaded. Error message is issued.  | Wait state is loaded.  | Error message is issued.   | Supports &SYSR1 as a volser. No other system symbol support. | No                            |
| <b>LPALSTxx:</b> List of data sets to be concatenated to SYS1.LPALIB from which the system builds the pageable LPA (PLPA).                       |  |   |  |   |   |  |  |  |                               |
| No   | Optional   | No  | IPL  | Yes, if L option is specified with LPA parameter in IEASYSxx, or by the operator. | Any valid data set definitions preceding the syntax error are concatenated to SYS1. LPALIB. | No data sets are concatenated to SYS1. LPALIB. Operator can reIPL to specify an alternate LPALSTxx member.   | N/A  | Yes  | Yes                           |
| <b>MMSLSTxx:</b> Specifies information that the MVS message service (MMS) uses to control the languages that are available in your installation. |  |   |  |   |   |  |  |  |                               |

Table 2. Characteristics of parmlib members (continued)

| Supplied by IBM  | Required or optional  | Affects performance directly? | Read at IPL or at command?  | Allows listing of parameters at IPL or command?   | Response to errors (N/A = Not applicable)   |   |                            | System symbols support ?      | Concatenated parmlib support? |
|--|---|-------------------------------|---|---|---|---|----------------------------|-------------------------------|-------------------------------|
|  |   |                               |   |   | Syntax error  | Read error  | Unsupported parameters     |                               |                               |
| Yes, in SYS1.SAMPLIB   | Optional  | No                            | IPL using the CONSOLxx member option. Modify with SET MMS command | Yes, through the DISPLAY command  | Message is issued for each invalid member.  | Parameters are rejected.  | Same as with syntax error. | Yes                           | Yes                           |
| <b>MPFLSTxx:</b> Parameters that the message processing facility uses to control message processing and display.   |   |                               |   |   |   |   |                            |                               |                               |
| No   | Optional  | No                            | IPL using the CONSOLxx member option. Modify with SET MPF command | Yes, through the DISPLAY command.   | Message is issued for each invalid member.  | Message is issued; processing continues.                        | Same as with syntax error. | Yes                           | Yes                           |
| <b>MSGFLDxx:</b> Parameters that message flood automation uses to detect and handle message floods.  |   |                               |   |   |   |   |                            |                               |                               |
| Yes, as CNZZMFXX in SYS1.SAMPLIB   | Optional  | No                            | SET MSGFLD command  | Yes, through the DISPLAY MSGFLD command   | Error message is issued. Processing continues.  | Same as with syntax error.                                      | Same as with syntax error. | See Note "6" on page 25       | Yes                           |
| <b>MSTJCLxx:</b> Contains the master scheduler JCL that controls system initialization and processing.   |   |                               |   |   |   |   |                            |                               |                               |
| Yes, in SYS1.LINKLIB   | Required  | No                            | IPL   | Yes   | Abend issued and the statement in error is Not processed. The system abnormally ends master scheduler initialization. | Same as with syntax error.                                      | Same as with syntax error. | Yes (see Note "4" on page 25) | Yes                           |
| <b>NUCLSTxx:</b> Specifies members of SYS1.NUCLEUS to be included in, or excluded from, the nucleus region at IPL-time.  |   |                               |   |   |   |   |                            |                               |                               |
| No   | Optional  | No                            | IPL   | No  | Wait state is loaded; error message is issued.  | Wait state is loaded.   | N/A                        | No                            | No                            |
| <b>PFKTABxx:</b> Parameters contain the definitions for program function key tables (PFK tables).  |   |                               |   |   |   |   |                            |                               |                               |
| No   | Optional  | No                            | IPL or SET PFK command.   | No  | Error message is issued.  | Error message is issued.  | N/A                        | Yes                           | Yes                           |
| <b>PROGxx:</b> Contains statements that define the format and contents of the APF-authorized program library list, control the use of installation exits and exit routines, define the LNKST concatenation, and specify alternate data sets for SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, and SYS1.SIEAMIGE to appear at the beginning of the LNKST concatenation and SYS1.LPALIB to appear at the beginning of the LPALST concatenation. |   |                               |   |   |   |   |                            |                               |                               |
| No   | Optional; required if LNKSTxx is Not used for the LNKST concatenation | No                            | IPL or SET PROG command.  | Yes through DISPLAY PROG  | Error message is issued.  | Error message is issued.  | Error message is issued.   | Yes                           | Yes                           |
| <b>SCHEDxx:</b> Provides centralized control over the size of the master trace table, the completion codes to be eligible for automatic restart and programs to be included in the PPT.  |   |                               |   |   |   |   |                            |                               |                               |
| No   | Optional  | No                            | At IPL and SET SCH command  | Yes, (L) is specified in IEASYSxx or in response to the specify system parameters prompt. | DiagNostic error message is issued. Different processing is done for each statement type in IEASYSxx.                 | DiagNostic error message is issued and the next record is read. |                            | Yes                           | Yes                           |

| Table 2. Characteristics of parmlib members (continued)  |                      |                               |                            |   |  |  |   |                          |                               |
|--|----------------------|-------------------------------|----------------------------|---|--|--|---|--------------------------|-------------------------------|
| Supplied by IBM  | Required or optional | Affects performance directly? | Read at IPL or at command? | Allows listing of parameters at IPL or command?               | Response to errors (N/A = Not applicable)  |  |   | System symbols support ? | Concatenated parmlib support? |
|  |                      |                               |                            |   | Syntax error   | Read error   | Unsupported parameters  |                          |                               |
| SMFLIMxx: Parameters that specify region and memlimit values.  |                      |                               |                            |   |  |  |   |                          |                               |
| No   | Optional             | Yes                           | IPL or SET SMFLIM command  | No  | Error message is issued for statements that are not valid. Processing continues. | Error message is issued.   | Error message is issued.  | Yes                      | Yes                           |
| SMFPRMxx: Parameters that define SMF options.  |                      |                               |                            |   |  |  |   |                          |                               |
| Yes, in SYS1.SAMPLIB   | Optional             | Yes                           | IPL or SET SMF command     | Yes, if PROMPT (list) or PROMPT (ALL) parameter is specified. | Prompts operator to enter parameter or re-IPL.                                   | Same as with syntax error.   | Obsolete parameters are ignored.                                  | Yes                      | Yes                           |
| TSOKEYxx: VTIOC parameters that are used by TSO/VTAM time sharing.   |                      |                               |                            |   |  |  |   |                          |                               |
| No   | Optional             | Yes                           | START TSO command          | Yes, automatically at START TSO.                              | Default value is substituted.  | Default value is substituted.  | N/A   | Yes                      | Yes                           |
| VATLSTxx: Volume attribute list that defines the mount and use attributes of direct access volumes.  |                      |                               |                            |   |  |  |   |                          |                               |
| No   | Optional             | Yes                           | IPL                        | No. Operator has option to get list only if error occurs.     | Error message. Bypasses bad entry. Processes remaining entries.                  | Operator is given choice of processing remaining lists if multiple lists, or specifying new VATLST VATLSTxx member, or reIPLing. | N/A   | Yes                      | Yes                           |
| XCFPOLxx: Specifies the actions that a system in a sysplex on PR/SM is to take when aNother system in the sysplex becomes inactive.  |                      |                               |                            |   |  |  |   |                          |                               |
| Yes  | Optional             | No                            | SETXCF PRSMPOLICY command. | No  | Error message requires the operator to correct the parmlib member                | Error message requires the operator to correct the parmlib member  | Error message requires the operator to correct the parmlib member | Yes                      | No                            |
| <b>Note:</b><br><br>1. These parameters can be listed at IPL: APF, DUMP, FIX, MLPA, SYSP, and OPT.<br>2. The only mandatory parameter is PAGE. Other parameters have coded defaults.<br>3. Performance-oriented parameters in IEASYSxx: CMD, FIX, MLPA, OPT, REAL, and RSU<br>4. System symbols in COMMNDxx and MSTJCLxx are processed differently than system symbols in other parmlib members. See Chapter 21, “COMMNDxx (commands automatically issued at initialization),” on page 191 and Chapter 78, “MSTJCLxx (master scheduler JCL),” on page 675 for details.<br>5. The system also treats all modules that are part of the link pack area (pageable LPA, fixed LPA, modified LPA, and dynamic LPA) as having come from an APF-authorized library.<br>6. System symbols are supported for the JOB statement jobname value, as well as, the following MSGFLDxx msgtype keyword values: INTVLTIME, JOBIMTIME, JOBTHRESH, MSGIMTIME, MSGLIMIT, MSGTHRESH, and SYSIMTIME. |                      |                               |                            |   |  |  |   |                          |                               |

## Implicit system parameters

Various system requirements, although not involving explicit parameters, affect the way the system performs. These system requirements may be considered as “implicit” parameters. They involve DD statements, data sets, hardware choices, and so forth. Some examples are:

- SYSABEND, SYSMDUMP, and SYSUDUMP DD statements. Without these statements, the parameters in parmlib members IEAABD00, IEADMR00, and IEADMP00 and the dump option lists in ABEND macro instructions are meaningless because an ABEND dump cannot be taken.

- The SMF data sets. If these data sets are not allocated on direct access volumes and cataloged, no SMF recording occurs.
- Addition of new modules to the LPALST concatenation through use of IEBCOPY, the Linkage Editor or the binder. Adding new modules affects the size and usefulness of the PLPA that is loaded by specifying the CLPA parameter at IPL.
- Choice of the device on which the PLPA paging data sets will reside. This choice affects the speed at which PLPA modules can be paged into storage and thus influences system performance.
- Definition of page data sets through the DEFINE PAGESPACE command. The PAGE parameter, issued at IPL through parmlib and/or the operator, is significant only if the specified data sets have been previously formatted by the DEFINE PAGESPACE command. (For information about this command, see *z/OS DFSMS Access Method Services Commands*.)

## Managing system security – APF-authorized library list

The authorized program facility (APF) allows your installation to identify system or user programs that can use sensitive system functions. To be APF-authorized, programs must reside in APF-authorized libraries, and be link-edited with authorization code AC=1. The system maintains a list of APF-authorized libraries that contains the following information for each library:

- The library name
- An identifier for the volume that contains the library.

The system automatically places SYS1.LINKLIB and SYS1.SVCLIB in the first two APF list entries. Your installation can specify the remaining entries in the APF list. In addition, any module in the link pack area will be treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

**Note:** When LNKAUTH=APFTAB is specified, the system considers SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, and SYS1.SIEAMIGE to be APF-authorized when they are accessed as part of the concatenation (even when they are not included in the APF list).

### Choosing an APF list format

You can specify the list of APF-authorized libraries in a dynamic or static format. There is only one APF list, the format of which is either static or dynamic. With the dynamic format, you can take the following actions:

- Update the APF list without having to reIPL the system, and
- Specify as many APF-authorized libraries as you need; there is no system-imposed maximum number.

In contrast, you can update a static APF list only at IPL, and it can contain a maximum of 255 entries. IBM suggests that you use a dynamic APF list to take advantage of the dynamic update capabilities.

Before you change the format of the APF list to dynamic, ensure that programs and vendor products are converted to use dynamic APF services (see [Chapter 43, “IEAAPFxx \(authorized program facility list\),”](#) on [page 361](#) for information about converting to a dynamic APF list) and that the proper program products are installed (see [z/OS Planning for Installation](#)).

[Table 3 on page 27](#) describes restrictions that are associated with changing the format of the APF list:

- The first column shows the format of the APF list set at IPL. The next three columns show changes to the APF list that might occur, in order, during normal processing.
- Under the "Format change allowed?" column, the table indicates whether a format change is allowed when the APF list is in the last format listed in the first four columns.
- Under the "Contents of APF list" column, the table shows the contents of the APF list when the format is the last format listed in the first four columns.



| Table 3. Restrictions on changing the format of the APF list |                     |                      |                     |                        |  |
|--|---------------------|----------------------|---------------------|------------------------|--|
| Format set at IPL  | First format change | Second format change | Third format change | Format change allowed? | Contents of APF list   |
| <b>Static</b>  | Not made            | Not made             | Not made            | Yes                    | The libraries included at IPL  |
| <b>Dynamic</b>   | Not allowed         | Not allowed          | Not allowed         | No                     | The libraries included at IPL, and any updates that occur during normal processing   |
| <b>Static</b>  | Dynamic             | Not made             | Not made            | Yes                    | The libraries included at IPL, and any updates that occur during normal processing   |
| <b>Static</b>  | Dynamic             | Static               | Not made            | Yes                    | The libraries included at IPL, but not the updates that occurred during normal processing (when the format was dynamic)                  |
| <b>Static</b>  | Dynamic             | Static               | Dynamic             | Yes                    | The libraries included at IPL, and any updates that occurred during normal processing (during both instances when the format is dynamic) |

IBM suggests that you take the following steps when changing the format of the APF list:

1. IPL with the APF list in a static format; then, when you are ready, change the format to dynamic during normal processing. If you IPL with a dynamic format and you find an error, you cannot convert the format back to static.
2. Convert from a dynamic format back to a static format *only* when you find an error when using the dynamic APF list. For example, a program may not be converted to use CSVAPF services to access the list (see the description of the CSVAPF macro in *z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN* for an example of how to perform this conversion). After you fix the error, you can change the format back to dynamic.
3. Specify a dynamic format for the APF list at the next IPL.

For information about restrictions that are associated with changing the format of the APF list, see [z/OS MVS Programming: Authorized Assembler Services Guide](#).

## Specifying the APF list

The PROGxx and IEAAPFxx parmlib members allow you to define the format and contents of the APF list. You can use either member, but IBM suggests using PROGxx, which offers the following advantages over IEAAPFxx:

- You can specify multiple PROGxx parmlib members using the PROG=xx system parameter
- You can specify a dynamic or static APF list format; the dynamic format allows you to update the APF list at any time during normal processing or at IPL.
- You can specify an unlimited number of libraries in the APF list.

**Note:** You can use both members, but the resulting list is dynamic only when you specify dynamic format in PROGxx.

If you specify a dynamic APF list format in PROGxx, you can specify the PROG=xx system parameter to set one or more current PROGxx parmlib members at IPL, or the operator can enter a SET PROG=xx command to set a current PROGxx parmlib member during normal processing. When the operator enters a SET PROG=xx command to update a dynamic APF list, the updated APF list remains active only for the duration of the current IPL. For information about how to use the SET PROG=xx command to specify the current PROGxx parmlib member, see [z/OS MVS System Commands](#).

If you currently use the IEAAPFxx parmlib member to define the APF list, you can convert the format of IEAAPFxx to a PROGxx format using the IEAAPFPR REXX exec provided by IBM.

## Assigning the RACF TRUSTED attribute

---

You can use RACF to assign the TRUSTED attribute to key started procedures and address spaces. Doing so generally allows the started procedure or address space to bypass RACF authorization checking and to successfully access or create any resource it needs.

A trusted started procedure or address space is treated as a z/OS UNIX superuser if a z/OS UNIX user identifier (UID) is assigned to it in the OMVS segment, even when the assigned UID is not 0.

### Guidelines:

- Assign the TRUSTED attribute when one of the following conditions applies:
  - The started procedure or address space creates or accesses a wide variety of unpredictably named data sets within your installation.
  - Insufficient authority to an accessed resource might risk an unsuccessful IPL or other system problem.
- Avoid assigning TRUSTED to a z/OS started procedure or address space unless it is listed here or you are instructed to do so by the product documentation.

Assign the TRUSTED attribute to the following z/OS started tasks and address spaces:

- CATALOG
- CEA for z/OSMF ISPF applications
- DUMPSRV
- GSKSRVR
- HIS
- IEEVMPCR
- IOSAS
- IXGLOGR
- JES2 or JES3
- JESXCF
- JES3AUX
- LLA
- NFS
- RACF
- RMF
- RMFGAT
- SMF
- TCPIP
- VLF
- VTAM
- WLM
- XCFAS
- SMS

Optional candidates for the TRUSTED attribute include the following:

- APSWPROA, APSWPROB, APSWPROC, APSWPROM, or APSWPROT
- CEA (optional for everything except z/OSMF ISPF applications)
- DFHSM
- DFS

- GPMSEVER
- OMVS
- SMSVSAM
- zFS

For more information, see [Associating started procedures and jobs with user IDs in z/OS Security Server RACF System Programmer's Guide](#), and [Using started procedures in z/OS Security Server RACF Security Administrator's Guide](#).

## Specifying installation exits

---

With the PROGxx and EXITxx parmlib members, you can specify installation exits. You can use either of these members, but IBM suggests using PROGxx. With PROGxx, you can take the following steps, at IPL or while the system is running:

- Add exit routines to an exit
- Change the state of an exit routine
- Delete exit routines from an exit
- Change the attributes of an exit
- Undefine implicitly defined exits
- Specify multiple PROGxx parmlib members using the PROG=xx system parameter.

You can use the PROG=xx system parameter at IPL to specify the particular PROGxx parmlib member the system is to use; or the operator can enter a SET PROG=xx command to set a current PROGxx parmlib member during normal processing. When the operator enters a SET PROG=xx command, the change remains in effect only for the duration of the current IPL. For information about how to use the SET PROG=xx command, see [z/OS MVS System Commands](#).

If you currently use the EXITxx parmlib member to specify installation exits, you can convert the format of EXITxx to the PROGxx format by using the IEFEXPR REXX exec provided by IBM.

The system also allows you to specify SMF exits through the SMFPRMxx parmlib member. You can associate exit routines with these SMF exits by adding EXIT statements to PROGxx that are equivalent to those in SMFPRMxx. The EXIT statements in SMFPRMxx list the exits; the EXIT statements in PROGxx list the associated exit routines. The EXIT statements in SMFPRMxx must remain. See [“Specifying SMF exits to the dynamic exits facility”](#) on page 767 for an example of how to add EXIT statements to PROGxx.

## Specifying LNKST concatenations

---

The PROGxx and LNKSTxx parmlib members allow you to specify the LNKST concatenation. You can use either of these members, but IBM suggests using PROGxx. See [PROG](#).



---

## Chapter 2. Sharing parmlib definitions

This section describes how to set up parmlib so two or more systems can share it. Topics include:

- Objectives for sharing parmlib
- Filter parameters in LOADxx
- What system symbols are
- System-provided system symbols
- Planning tasks for sharing parmlib
- Defining system symbols and changing existing system symbol definitions
- Using system symbols in parmlib.
- A preprocessor to verify symbols without IPLing
- Displaying static system symbols
- Diagnosing problems with static system symbols
- Using indirect volume serial support

---

### Objectives for sharing parmlib

In a multisystem environment, your objective should be to share one parmlib concatenation with as many systems as possible.

- Examine your installation configuration and determine the best way to consolidate all LOADxx information for all MVS images in a sysplex into one LOADxx member using the HWNAME, LPARNAME and VMUSERID parameters. The LOADxx parameters HWNAME, LPARNAME and VMUSERID provide segmentation of the processor hardware name, the logical partition name and the VM Userid. For more information about filter parameters, see [Chapter 73, “LOADxx \(system configuration data sets\),” on page 613](#).
- Determine how many *members* of parmlib you can share with other systems. For example, if two systems use different CLOCKxx members, and only one value in each member is different, chances are that the two systems can share one CLOCKxx member.
- If you cannot share members, determine if you can share system parameter definitions in one IEASYSxx member. For example, if you must use separate CLOCKxx members for two different systems, you can code the CLOCK=xx parameter in a shared IEASYSxx member that specifies the unique CLOCKxx member for each system.

System symbols are the elements that represent unique values in shared members. When determining which members are to be shared, you must consider which system symbols are available to you, the values of those system symbols, and how you can use them to optimize the sharing of parmlib.

The following sections explain how to use system symbols and plan for parmlib sharing.

---

### What are system symbols?

System symbols are elements that allow systems to share parmlib definitions while retaining unique values in those definitions. They act like variables in a program; they can take on different values, based on the input to the program. When you specify a system symbol in a shared parmlib definition, the system symbol acts as a “place holder”. Each system that shares the definition replaces the system symbol with a unique value during initialization.

**Restriction:** A symbol definition will fail if it begins with a number. If any symbol in a symbol file is in error, the entire file of symbols is invalidated.

Before you begin to share parmlib definitions, you must understand the types of system symbols and the elements that comprise them.

The following terms describe the elements of system symbols:

**Symbol Name**

The name that is assigned to a symbol. It begins with an ampersand (&) and optionally ends with a period (.). System symbols should usually be specified in uppercase. There are places, for example, operator commands, where system symbols can be specified in lowercase.

**Substitution Text**

The character string that the system substitutes for a symbol each time it appears. Substitution text can identify characteristics of resources, such as the system on which a resource is located, or the date and time of processing. When you define static system symbols in the IEASYMxx parmlib member (see [“Step 4. Create an IEASYMxx parmlib member”](#) on page 41), the substitution text can contain other static system symbols; the *resolved substitution text* refers to the character string that is produced after all symbols in the substitution text are resolved.

The following terms describe the types of symbols:

**Dynamic System Symbol**

A system symbol whose substitution text can change at any point in an IPL. Dynamic system symbols represent values that can change often, such as dates and times. A set of dynamic system symbols is defined to the system; your installation cannot provide additional dynamic system symbols.

**Static System Symbol**

A symbol whose substitution text is defined at system initialization and remains fixed for the life of an IPL unless the SETLOAD xx,IEASYM command is issued. The SETLOAD xx,IEASYM command can be used to make changes to system symbols in the local system symbol table without initiating an IPL. See *z/OS MVS System Commands*. (One exception, &SYSPLEX, has a substitution text that can change at an additional point in an IPL; see [“Step 5. Code support for system symbols in LOADxx”](#) on page 46 for details.) Static system symbols are used to represent fixed values such as system names and sysplex names.

Static system symbols have two types:

- *System-defined static system symbols* already have their names that are defined to the system. Your installation defines substitution texts or accepts system default texts for the static system symbols, which are:
  - &SYSCONE
  - &SYSNAME
  - &SYSOSLVL (Your installation cannot define substitution text for &SYSOSLVL.)
  - &SYSPLEX
  - &SYSR1 (Your installation cannot define substitution text for &SYSR1.)
  - &SYSALVL (Your installation cannot define substitution text for &SYSALVL.)
- *Installation-defined static system symbols* are defined by your installation. The system programmer specifies their names and substitution texts in the SYS1.PARMLIB data set.

In addition to the static symbols that were previously listed, the system allows you to define and use the following types of symbols:

- *JCL symbol*: A symbol that represents variable information in JCL. You can define JCL symbols on EXEC, PROC, and SET statements in JCL, and use them only in:
  - JCL statements in the job stream
  - Statements in cataloged or in-stream procedures
  - DD statements that are added to a procedure.

For more information about using JCL symbols, see [z/OS MVS JCL Reference](#).

- *IPCS symbol*: A symbol that IPCS uses to represent data areas in dumps that are processed with IPCS subcommands.

For more information about using IPCS symbols, see *z/OS MVS IPCS User's Guide*.

The following sections describe the static and dynamic system symbols that you can define and use in parmlib.

**Note:** Although IBM suggests the use of ending periods on system symbols, the text in the documentation does not specify them, except in examples, out of consideration for readability.

## Static system symbols

The system substitutes text for static system symbols when it processes parmlib members. For static system symbols that the system provides, you can define substitution texts in parmlib or accept the default substitution texts. You can also define at least 800 additional static system symbols. See [“Setting up a shared parmlib” on page 36](#) for more information about how to define static system symbols. [Table 4 on page 33](#) describes the static system symbols.

| Table 4. Static system symbols |   |             |   |                                    |   |
|--------------------------------|---|-------------|---|------------------------------------|---|
| System symbol                  | Description   | Text length | Where defined   | Valid releases                     | Default substitution text   |
| <b>&amp;SYSALVL</b>            | The architecture level of the system.   | 1 char      | LOADxx parmlib member                                   | OS/390® Release 10 and later       | The value specified for ARCHLVL in the LOADxx parmlib member  |
| <b>&amp;SYSCLONE</b>           | Shorthand notation for the name of the system; often used in fields that are limited to two characters. | 1-2 chars   | IEASYMxx parmlib member                                 | MVS/ESA 5.2 and later              | Last two characters of substitution text defined to &SYSNAME system symbol.   |
| <b>&amp;SYSNAME</b>            | The name of the system.   | 1-8 chars   | IEASYMxx or IEASYSxx parmlib member                     | MVS/ESA 5.1 and later              | System name. See <a href="#">“Step 3. Determine where to specify the system name” on page 41</a> for details.   |
| <b>&amp;SYSOSLVL</b>           | The version, release, and modification level of the operating system software product.                  | 8 chars     | Automatically set by the system from the ECVT data area | z/OS Version 2 Release 1 and later | Zxvrrmm where Zx is the operating system (for example, Z1 is z/OS), vv is the version number from ECVTPVER (for example, 02), rr is the release number from ECVTPREL (for example, 01) and mm is the modification number from ECVTPMOD (for example, 00).<br><b>Example:</b> For z/OS 2.1, the value is Z1020100. |
| <b>&amp;SYSPLEX</b>            | The name of the sysplex.  | 1-8 chars   | COUPLExx or LOADxx parmlib member                       | MVS/ESA 5.1 and later              | If LOADxx does not specify the sysplex name, &SYSPLEX will default to LOCAL until the COUPLExx member is processed.   |
| <b>&amp;SYSR1</b>              | The IPL Volume Serial name.   | 1-6 chars   | Set by system to IPL volume serial                      | OS/390 Release 4 and later         | None  |

| Table 4. Static system symbols (continued) |  |             |                         |                       |                           |
|--|--|-------------|-------------------------|-----------------------|---------------------------|
| System symbol                              | Description  | Text length | Where defined           | Valid releases        | Default substitution text |
| <b>Installation defined system symbols</b> | <p>Additional system symbols may be defined by your installation.</p> <p>The maximum number of symbols you can have depends on their size. IBM guarantees you the ability to define 800 symbols of your own, but you can probably define more. You may have as many symbols as you can fit into the symbol table. The symbol table can be up to 32512 bytes long, including a 4-byte header. Each entry in the table consists of:</p> <ul style="list-style-type: none"> <li>• 16-bytes, plus</li> <li>• The symbol name, including the preceding &amp; and trailing . (for example, &amp;MYSYM.)</li> <li>• The substitution text value (for example, "MYVALUE")</li> </ul> | 0-8 chars   | IEASYMxx parmlib member | MVS/ESA 5.2 and later | None                      |

## Dynamic system symbols

This section describes the dynamic system symbols. The names of the following system symbols are changed from previous releases of MVS:

| New symbol | Old symbol |
|------------|------------|
| &YYMMDD    | &DATE      |
| &LYYMMDD   | &LDATE     |
| &HHMMSS    | &TIME      |
| &LHHMMSS   | &LTIME     |

To maintain compatibility, the original system symbols ([Compatibility-only dynamic system symbols](#)) are still supported by the DUMPDS command. However, IBM suggests that you change to use the new system symbols ([Dynamic system symbols](#)) because the substitution texts for the old system symbols might cause buffer overflows.

The system determines the substitution text for dynamic system symbols when the ASASYMBM or ASASYMBF service is called to do the substitution. For example:

- For system symbols within a parmlib member, when the parmlib member is processed.
- For system symbols within JCL, when the JCL undergoes conversion.
- When an application program is running.

See the following tables:

- [Dynamic system symbols](#)
- [Compatibility-only dynamic system symbols](#). Note that IBM recommends against using these system symbols.



Table 5. Dynamic system symbols

| System symbol       | Description   |
|---------------------|---|
| <b>&amp;DAY</b>     | The day of the month, based on Coordinated Universal Time (UTC). Shown in two decimal digits, 01-31. Use &LDAY for local time.  |
| <b>&amp;DS</b>      | The dump section number for multiple data sets in a transaction dump (TDUMP). Shown in three decimal digits, 000-999. &DS is resolved when used by IEATDUMP.  |
| <b>&amp;HHMMSS</b>  | The time. Equivalent to &HR.&MIN.&SEC.. Use &LHHMMSS for local time.  |
| <b>&amp;HR</b>      | The hour of the day, based on UTC. Shown in two decimal digits, 00-23. Use &LHR for local time.   |
| <b>&amp;JDAY</b>    | The Julian day of the year, based on UTC. Shown in three decimal digits, 001-366. Use &LJDAY for local time.  |
| <b>&amp;JOBNAME</b> | <p>The name of the job. Shown in 1-8 characters. In the special case when the job name is *MASTER*, &amp;JOBNAME resolves to #MASTER# to avoid the error of using the asterisk as part of a data set name.</p> <p>Under z/OS, it is valid to define a user ID that is all numeric. Under z/OS UNIX, this all-numeric user ID might be propagated as a job name in the case of a fork() or non-local spawn(); this can lead to allocation failures when &amp;JOBNAME is used in substitution for a data set name.</p> <p>If you specify the &amp;JOBNAME dynamic system symbol in a START command for a started task, the resolved substitution text for &amp;JOBNAME is the name of the job assigned to the address space that calls the symbolic substitution service, not the address space of the started task.</p> <p>Within JCL, the substitution text for &amp;JOBNAME is the name of the job assigned to the address space in which the JCL is converted, not the name of the job being processed. For instance, if JES2 does the conversion, &amp;JOBNAME resolves to JES2.</p> |
| <b>&amp;LDATE</b>   | The local date, based on Coordinated Universal Time (UTC). Equivalent to &YR2.&MON.&DAY..   |
| <b>&amp;LDAY</b>    | The day of the month, based on local time. Shown in two decimal digits, 01-31.  |
| <b>&amp;LHHMMSS</b> | The local time. Equivalent to &LHR.&LMIN.&LSEC.   |
| <b>&amp;LHR</b>     | The hour of the day, based on local time. Shown in two decimal digits, 00-23.   |
| <b>&amp;LJDAY</b>   | The Julian day of the year, based on local time. Shown in three decimal digits, 001-366.  |
| <b>&amp;LMIN</b>    | The minute of the hour, based on local time. Shown in two decimal digits, 00-59.  |
| <b>&amp;LMON</b>    | The month, based on local time. Shown in two decimal digits, 01-12.   |
| <b>&amp;LSEC</b>    | The second of the minute, based on local time. Shown in two decimal digits, 00-59.  |
| <b>&amp;LTIME</b>   | The local time that the dump was requested, Equivalent to &HR.&MIN.&SEC..   |
| <b>&amp;LWDAY</b>   | The day of the week, based on local time. Shown in three characters: SUN, MON, TUE, WED, THU, FRI or SAT.   |
| <b>&amp;LYR2</b>    | The year, based on local time. Shown in two decimal digits, 00-99.  |
| <b>&amp;LYR4</b>    | The year, based on local time. Shown in four decimal digits, 0000-9999.   |
| <b>&amp;MIN</b>     | The minute of the hour, based on UTC. Shown in two decimal digits, 00-59. Use &LMIN for local time.   |
| <b>&amp;MON</b>     | The month, based on UTC. Shown in two decimal digits, 01-12. Use &LMON for local time.  |
| <b>&amp;SEC</b>     | The second of the minute, based on UTC. Shown in two decimal digits, 00-59. Use &LSEC for local time.   |
| <b>&amp;SEQ</b>     | A sequence number for uniqueness. It is required for names of automatically allocated dump data sets. Shown in five decimal digits, 00000-99999. &SEQ is resolved only when used with DUMPDS.   |
| <b>&amp;WDAY</b>    | The day of the week, based on UTC. Shown in three characters: SUN, MON, TUE, WED, THU, FRI or SAT. Use &LWDAY for local time.   |

Table 5. Dynamic system symbols (continued)

| System symbol      | Description  |
|--------------------|--|
| <b>&amp;YR2</b>    | The year, based on UTC. Shown in two decimal digits, 00-99. Use &LYR2 for local time.      |
| <b>&amp;YR4</b>    | The year, based on UTC. Shown in four decimal digits, 0000-9999. Use &LYR4 for local time. |
| <b>&amp;YYMMDD</b> | The date, based on UTC. Equivalent to &YR2.&MON.&DAY.. Use &LYYYMMDD for local time.       |

Table 6. Compatibility-only dynamic system symbols

| System symbol    | Description  |
|------------------|--|
| <b>&amp;DATE</b> | The date, based on Coordinated Universal Time (UTC). Equivalent to &YR2.&MON.&DAY.. Use &LDATE for local date. |
| <b>&amp;TIME</b> | The time that the dump was requested, Equivalent to &HR.&MIN.&SEC.. Use &LTIME for local time.                 |

**Note:** You can specify dynamic system symbols in parmlib. However, be aware that the system substitutes text for dynamic system symbols when it processes parmlib members. For example, if you specify &HHMMSS in a parmlib member, its substitution text will reflect the time when the member is processed.

## Symbols reserved for system use

When you define additional system symbols in the IEASYMxx parmlib member (see “Step 4. Create an IEASYMxx parmlib member” on page 41), ensure that you do not specify the names shown in [Table 7](#) on page 36, which are symbols that are reserved for system use.

Table 7. Names reserved for system use

| Symbol Name          | Symbol Name | Symbol Name |
|----------------------|-------------|-------------|
| <b>&amp;DATE</b>     | &DAY        | &HHMMSS     |
| <b>&amp;HR</b>       | &JDAY       | &JOBNAME    |
| <b>&amp;LDATE</b>    | &LDAY       | &LHHMMSS    |
| <b>&amp;LHR</b>      | &LJDAY      | &LMIN       |
| <b>&amp;LMON</b>     | &LSEC       | &LTIME      |
| <b>&amp;LWDAY</b>    | &LYR2       | &LYR4       |
| <b>&amp;LYYYMMDD</b> | &MIN        | &MON        |
| <b>&amp;SEC</b>      | &SEQ        | &SID        |
| <b>&amp;SYSALVL</b>  | &SYSCONE    | &SYSNAME    |
| <b>&amp;SYSOSLVL</b> | &SYSPLEX    | &SYSR1      |
| <b>&amp;SYSUID</b>   | &TIME       | &WDAY       |
| <b>&amp;YR2</b>      | &YR4        | &YYMMDD     |

## Setting up a shared parmlib

Before you use system symbols to share parmlib definitions that require unique values, you must evaluate the requirements for system symbols at your installation. Determine which members of parmlib require unique definitions. Then determine what system symbols you need so two or more systems can share those members.

Based on that evaluation, you can then take the following actions:

- Define substitution texts for system-defined static system symbols, or accept their default substitution texts
- Determine if you need to define additional static system symbols.

Follow these steps to set up the parmlib for sharing:

1. [“Step 1. Plan to share parmlib members” on page 37](#)
2. [“Step 2. Determine where to specify system parameters” on page 39](#)
3. [“Step 3. Determine where to specify the system name” on page 41](#)
4. [“Step 2. Determine where to use system symbols in parmlib” on page 50](#)
5. [“Step 4. Create an IEASYMxx parmlib member” on page 41](#)
6. [“Step 5. Code support for system symbols in LOADxx” on page 46](#)

## Step 1. Plan to share parmlib members

When planning to share parmlib members, ask yourself the following questions:

### 1. Do two or more systems require identical resource names in the parmlib members to be shared?

If so, you need not specify system symbols in the parmlib members; the systems can share the contents of the parmlib members without the benefit of system symbols. However, if the systems require unique names for resources (such as jobnames) specified in those members, you must specify system symbols to generate unique values for those names.

For example, if every system that shares parmlib uses the same set of APF authorized libraries, the systems can share the PROGxx parmlib member. Because the definitions in PROGxx are identical for each system, there is no need to specify system symbols in PROGxx.

### 2. What resource definitions are good candidates for sharing?

If your goal is to greatly simplify your operating environment, the answer will be: As many as possible! If two or more systems require different names for a resource, define the resource with a system symbol in parmlib; then define different substitution texts for the system symbol on each system that is to share the parmlib definition. Now you have one convenient place to maintain the definition. If you follow the same process with all parmlib definitions that require unique values, you can view a multisystem environment as a *single system image* with one point of control.

Be aware that there are also reasons you might *not* want to share certain resource definitions. Perhaps the release level of MVS prevents you from using system symbols on a particular system; or perhaps one or more systems do not require a particular resource. Whatever the case, your installation must examine the resources it defines in parmlib and determine the extent to which they can be shared.

An example of a resource definition that can be shared is a definition for a page data set. Because systems cannot share page data sets, installations must define unique page data sets for each system in a sysplex. You might want to assign unique names to the page data sets so you can easily identify them. Suppose that you had three systems, named SYS1, SYS2, and SYS3, that share the same IEASYSxx member. To specify unique names for the page data sets on the different systems, you could specify the following in the IEASYSxx parmlib member:

```
PAGE=PAGE.&SYSNAME. .LOCAL1
```

When each system processes IEASYSxx, it calls into use a predefined page data set with the name that results from the symbolic substitution, as follows:

- PAGE.SYS1.LOCAL1 on system SYS1
- PAGE.SYS2.LOCAL1 on system SYS2
- PAGE.SYS3.LOCAL1 on system SYS3

### 3. Do I need to share system parameters that specify unique values in the IEASYSxx parmlib member?

When the systems in your environment require unique parmlib members, you can specify system symbols in one or more shared IEASYSxx members to indicate unique member suffixes. Do this only when it is not possible to share the same members. In other words, try to specify system symbols in parmlib *definitions* first, as described in [“Step 2. Determine where to use system symbols in parmlib” on page 50](#). If you cannot share a member with any degree of efficiency, create a new member with a unique suffix; then specify a system symbol in IEASYSxx that resolves to the suffix you want to use on each system.

For example, suppose systems SYS1, SYS2, and SYS3 require unique CLOCKxx parmlib members. You can take the following steps:

- a. Create three unique members: CLOCKS1, CLOCKS2, and CLOCKS3.
- b. Specify the following in the shared IEASYSxx member:

```
CLOCK=&SYSCONE.
```

If your installation accepts the default substitution text for &SYSCONE (the last two characters in the system name), the CLOCK parameter in IEASYSxx will specify the following for each system:

- CLOCKS1 on system SYS1
- CLOCKS2 on system SYS2
- CLOCKS3 on system SYS3

**4. Do I want to provide substitution texts for static system symbols, or do I want to accept the system defaults?**

The system provides default substitution texts for the &SYSCONE, &SYSNAME, and &SYSPLEX system symbols. See the descriptions of the default substitution texts in [Table 4 on page 33](#). If the default texts are not acceptable to your installation, you can define your own substitution texts in parmlib. For example, if a system always runs on the same logical partition (LPAR), the system might be able to accept the default for the &SYSNAME system symbol (because &SYSNAME can default to the LPAR name).

**5. Do I need to define additional static system symbols?**

The static system symbols that are defined to the system might be sufficient to uniquely identify resources. If your installation requires additional static system symbols, you can define at least 800 additional static system symbols in the IEASYSxx parmlib member.

**6. Do I want to define the &SYSPLEX static system symbol early in system initialization so other parmlib members can use it?**

You can optionally specify the sysplex name in both the COUPLExx and LOADxx parmlib members. The sysplex name is also the substitution text for the &SYSPLEX system symbol. When you specify the sysplex name in both LOADxx and COUPLExx, the substitution text for &SYSPLEX is defined early in system initialization, which allows all parmlib members to use the defined substitution text. When the sysplex name is defined only in COUPLExx, the system does not define the substitution text for &SYSPLEX until late in system initialization. The system substitutes the text **LOCAL** for any instances of &SYSPLEX that occur before COUPLExx is processed.

If you plan to use the &SYSPLEX system symbol in parmlib, IBM suggests that you specify the *same* sysplex name in both LOADxx and COUPLExx. See [“Step 5. Code support for system symbols in LOADxx” on page 46](#) for details.

**7. Do I want to ensure that the substitution text for &SYSCONE is unique on all systems?**

&SYSCONE is a 1-2 character shorthand notation for the system name (unless your installation changes the substitution text to another value). IBM suggests that you use &SYSCONE in places where the substitution text for &SYSNAME is too long, such as parmlib member suffixes.

Each system in a sysplex must specify a unique SYSCONE value. Message IXC217I will be issued if the substitution text for the symbol &SYSCONE is not unique in a sysplex.

**8. Do I plan to use system symbols in other interfaces? If so, are there any considerations to make for those interfaces when I define system symbols in parmlib?**

Parmlib is not the only place where you can use system symbols to share resources that require unique values. After you read this chapter, see the following books for information about sharing resources in the listed interfaces:

**Application or vendor programs**

See the topics on how to substitute text for system symbols in application programs in [z/OS MVS Programming: Assembler Services Guide](#).

**Dynamic allocations**

See the topic on coding dsname allocation text units in [z/OS MVS Programming: Authorized Assembler Services Guide](#).

**Job control language (JCL) for started tasks**

See the topic on how to specify system symbols in JCL in [z/OS MVS JCL Reference](#).

**System commands**

See the topic on using system symbols in system commands in [z/OS MVS System Commands](#).

**Time Sharing Option Extensions (TSO/E) Logon Procedures**

See the topic on how to set up logon processing in [z/OS TSO/E Customization](#).

When defining static system symbols in parmlib, consider that the listed interfaces might want to use those system symbols.

## Step 2. Determine where to specify system parameters

System parameters can be specified in IEASYSxx parmlib members or as a response to the SPECIFY SYSTEM PARAMETERS prompt. The system always processes system parameters from IEASYS00; however, additional IEASYSxx members can be specified. The SPECIFY SYSTEM PARAMETERS prompt allows for the operator to specify additional parameters in the response including additional IEASYSxx parmlib members via the SYSP parameter.

You can specify the suffixes of IEASYSxx members that the system is to use in any of the following places:

- The LOADxx parmlib member
- The IEASYMxx parmlib member
- The SYSP parameter, specified in response to the SPECIFY SYSTEM PARAMETERS prompt.

When different systems in a multisystem environment require different IEASYSxx members, consider specifying the IEASYSxx suffixes in IEASYMxx. You can specify the IEASYSxx suffixes for all systems in one IEASYMxx member.

The specific advantages to using IEASYMxx over LOADxx are as follows:

- IEASYMxx can specify unique IEASYSxx members for as many systems as you need.
- When you use IEASYMxx, LOADxx can point to IEASYMxx; therefore, you do not have to code unique LOADxx and IEASYSxx members for each system.

For example, the SYSPARM statements in the IEASYMxx member in [Figure 2 on page 39](#) specify the IEASYSxx members to be used for three different systems:

---

```
SYSDEF  HWNAME(MVS3090) LPARNAME(SYSCA)
        SYSPARM(01,L)

SYSDEF  HWNAME(MVS3090) VMUSERID(VMSYSGB)
        SYSPARM(03,L)

SYSDEF  HWNAME(SYSCC)
        SYSPARM(01,02,L)
```

---

*Figure 2. Example IEASYMxx parmlib member*

---

See “[Step 4. Create an IEASYMxx parmlib member](#)” on page 41 for more information about how to specify system parameters in IEASYMxx.

Depending on where you specify the suffixes of IEASYSxx members that the system is to use, the system overrides or concatenates the members:

- If you specify the suffixes in IEASYMxx or LOADxx, the system will concatenate the members according to the scheme shown in [Table 8 on page 40](#).
- If you specify the suffixes in IEASYMxx or LOADxx and the operator specifies the suffixes at IPL, the suffixes that are specified by the operator overrides suffixes in IEASYMxx or LOADxx.

The system always processes the IEASYS00 member first, regardless of where you specify IEASYSxx suffixes. If the same parameter appears in both IEASYS00 and a specified alternate IEASYSxx list, the value in the alternate list will override the value in IEASYS00. Also, a parameter value in a later specified IEASYSxx list overrides the same parameter in an earlier specified list. See the description of the IEASYSxx member for more information.

For example, suppose that you create the following IEASYSxx members and specify their suffixes in the indicated places:

- LOADxx - 01,02
- IEASYMxx - 03,04
- Console SYSP (WTOR) - 05,06

[Table 8 on page 40](#) shows how the system concatenates or overrides the suffixes:

| <i>Table 8. Precedence of system parameter specifications</i> |                 |                                       |   |
|---|-----------------|---------------------------------------|---|
| <b>LOADxx</b>   | <b>IEASYMxx</b> | <b>Console SYSP (WTOR) (See note)</b> | <b>Resulting IEASYSxx concatenation</b> |
| <b>None</b>   | None            | None                                  | 00 (default)                            |
| <b>(01,02)</b>  | None            | None                                  | (00,01,02)                              |
| <b>(01,02)</b>  | None            | Null response                         | (00)                                    |
| <b>(01,02)</b>  | (03,04)         | None                                  | (00,01,02,03,04)                        |
| <b>(01,02)</b>  | (03,04)         | (05,06)                               | (00,05,06)                              |
| <b>None</b>   | (03,04)         | None                                  | (00,03,04)                              |
| <b>None</b>   | (03,04)         | (05,06)                               | (00,05,06)                              |
| <b>None</b>   | None            | (05,06)                               | (00,05,06)                              |

**Note:** “None” means that no IEA101A prompt was issued. This is the case when the IMSI prevents the system from prompting the operator for system parameters. This is different from the case where the IEA101A prompt is issued, but the user response to the message is null. A null response is equivalent to a response of SYSP=00.

If any of the IEASYSxx suffixes specified in LOADxx, IEASYMxx, or in response to a WTOR are not valid, the system issues message IEA336A to request that you specify system parameters again.

The number of IEASYSxx members that you use for a multisystem environment depends on the desired result from your system parameter concatenation and your preferences about how the information is organized. See [Table 9 on page 40](#) for more information.

| <i>Table 9. Recommended actions for IEASYSxx members</i> |  |   |
|--|--|---|
| <b>Desired result</b>                                    | <b>Situation</b>                                   | <b>Recommended action</b>   |
| <b>One IEASYSxx member</b>                               | Different systems require unique system parameters | Code one IEASYSxx member; specify system symbols to represent unique system parameters. |
| <b>One IEASYSxx member</b>                               | Different systems use the same system parameters   | Code one IEASYSxx member to be shared by all systems.                                   |

| Table 9. Recommended actions for IEASYSxx members (continued) |  |   |
|---|--|---|
| Desired result  | Situation  | Recommended action  |
| <b>Multiple IEASYSxx members</b>                              | Different systems require unique system parameters | Code separate IEASYSxx members, for each system, where appropriate; specify the IEASYSxx members in a shared IEASYMxx member. |

### Step 3. Determine where to specify the system name

The name of a system is also the substitution text for the &SYSNAME system symbol. You can specify the name of a system in one or more of the following places:

- The IEASYMxx parmlib member
- The IEASYSxx parmlib member
- By the operator, in response to write to operator with reply (WTOR) message IEA101A SPECIFY SYSTEM PARAMETERS.

If you define the system name in only one of the listed places, the system will use that definition. Otherwise, the system will determine the name as follows:

- If the system name is specified in both IEASYMxx and IEASYSxx, the system will use the name in IEASYMxx.
- If the operator specifies the system name in response to the specify system parameters message, the system will use the name specified on the operator response.

IBM suggests that you specify the system name in IEASYMxx.

Table 10 on page 41 shows every possible way to specify the system name and the resulting system action. In the table, IEASYMXX indicates that the system name is specified in the IEASYMxx parmlib member, IEASYSXX indicates that it is specified in the IEASYSxx parmlib member, and WTOR indicates that it is specified in response to the specify system parameters prompt:

| Table 10. Precedence of system name specifications |          |                        |                       |
|--|----------|------------------------|-----------------------|
| IEASYMxx   | IEASYSxx | Console SYSNAME (WTOR) | Resultant system name |
| <b>IEASYMXX</b>                                    |          |                        | IEASYMXX              |
| <b>IEASYMXX</b>                                    | IEASYSXX |                        | IEASYMXX              |
| <b>IEASYMXX</b>                                    |          | WTOR                   | WTOR                  |
| <b>IEASYMXX</b>                                    | IEASYSXX | WTOR                   | WTOR                  |
|  | IEASYSXX |                        | IEASYSXX              |
|  | IEASYSXX | WTOR                   | WTOR                  |
|  |          | WTOR                   | WTOR                  |

If the system name is not defined in any of the listed places, the system name will become, by default, one of the following:

- The processor name that is defined to HCD (if not in LPAR mode)
- The LPAR name that is defined to the processor (if in LPAR mode)
- A VM user ID, if the system is running as a guest of z/VM.

### Step 4. Create an IEASYMxx parmlib member

The main purpose of IEASYMxx is to provide a single place to specify system parameters for each system in a multisystem environment. IEASYMxx contains statements that take the following steps:

- Define static system symbols



- Specify IEASYSxx parmlib members that contain system parameters.

You can apply the statements in IEASYMxx to any system in your environment. Therefore, only one IEASYMxx member is required to define static system symbols and specify system parameters for all systems.

In IEASYMxx, you can define at least 800 additional static system symbols for each system in a multisystem environment. In other words, you can define as many additional static system symbols in IEASYMxx as you like, so long as the resulting symbol table would not exceed the maximum symbol table size of 32512 bytes.

The LOADxx parmlib member specifies the IEASYMxx member that the system is to use. For information about how to specify the suffix of the IEASYMxx member in LOADxx, see [“Step 5. Code support for system symbols in LOADxx”](#) on page 46.

## Contents of IEASYMxx

IEASYMxx contains SYSDEF statements that *optionally* take the following steps for each system:

- Define substitution texts for the existing &SYSCONE and &SYSNAME system symbols, and apply those definitions to one or more systems.
- Define additional static system symbols and apply those definitions to one or more systems (at least 800 additional static system symbols are allowed across all of your IEASYMxx members).
- Control which definitions apply to which systems by specifying values for comparison to the current system hardware name or logical partition (LPAR) name.

See the description of IEASYMxx for descriptions of the parameters that each SYSDEF statement can contain.

## Scope of statements in IEASYMxx

You can code the statements in IEASYMxx so only one IEASYMxx member is needed to define static system symbols and system parameters for all systems in a multisystem environment. If you want, you can code additional IEASYMxx members to organize the definitions more clearly.

When coding IEASYMxx, remember the following rules about the scope of the statements:

- The system processes IEASYMxx members from left to right, in the order which they are specified in the LOADxx parmlib member. Definitions that are specified in previous IEASYMxx members remain in effect until they are overridden by subsequent definitions. For example, suppose you specify the following IEASYMxx members in LOADxx:

```
IEASYM    (01,02,L)
```

The system first processes the IEASYM01 parmlib member. Then the system processes IEASYM02. The definitions from IEASYM01 remain in effect unless definitions from IEASYM02 override them.

- At the beginning of IEASYMxx, you can specify **global** statements that apply to all systems that use the IEASYMxx member. Global statements should specify the values of SYSPARM and SYMDEF that are most common to the systems in your sysplex. Global statements do not use the HWNAME, LPARNAME, and VMUSERID parameters to identify specific systems to which definitions apply.

When specific systems require values that are different from those on global statements, you can override the global statements with *local* statements (see below).

- **Local** statements apply to a subset of systems in your sysplex. Using the HWNAME, LPARNAME, and VMUSERID parameters, local statements identify one or more CPCs or LPARs that are to use specific system symbols and system parameters. The HWNAME, LPARNAME, and VMUSERID values specified on a SYSDEF statement are compared to those of the current system. If they match exactly, the other parameters on the SYSDEF statement will be used. If not, the other parameters will be ignored for this system.
- The system processes IEASYMxx members in the order which they are specified. When two definitions for the same resource appear in IEASYMxx, the most recent definition overrides the previous definition.



Keep this rule in mind when specifying global and local statements: If global statements appear *after* local statements in IEASYMxx, the local statements will not override the global statements.

## Procedure for coding IEASYMxx

IBM suggests that you code one IEASYMxx member that contains only global statements. Specify that member as the first member in the IEASYMxx concatenation in LOADxx (for example, IEASYM01 in the example above). Then code other IEASYMxx members that specify local statements, which override the global statements specified in the first IEASYMxx member. This practice ensures that global and local statements always appear in the proper order.

## Rules for coding IEASYMxx

Follow these rules when coding IEASYMxx:

1. Define new system symbols that are 1 to 16 characters long, excluding the required ampersand and the optional period. For example, you can define a system symbol called &PAGESYM3, which contains an 8-character name, using the following SYMDEF statement:

```
SYMDEF (&PAGESYM3='LOCAL3')
```

2. Do not define resolved substitution texts that are longer than system symbol names (including the required ampersand and excluding the optional period). Before being resolved, a substitution text can contain other system symbols that extend its length beyond the length of the symbol name. However, the substitution text for those symbols must resolve to form a string that is less than the length of the symbol name.

For example, consider the &PAGESYM3 system symbol definition:

```
SYMDEF (&PAGESYM3='LOCAL3')
```

The LOCAL3 substitution text is valid because it contains six characters, which are less than the 9 characters in the symbol name, &PAGESYM3. Notice that the optional period is not included. The following definition is also valid:

```
SYSNAME (SYS1)  
SYMDEF (&PAGESYM3='LOC&SYSNAME.3')
```

Although the LOC&SYSNAME3 substitution text appears longer than the &PAGESYM3 symbol, the &SYSNAME system symbol in LOC&SYSNAME3 resolves to a character string that makes the final resolved substitution text, LOCSYS13, shorter than the symbol name.

If you specify a substitution text that, when resolved, is longer than a symbol name, the system prompts for a valid substitution text.

3. Do not define new system symbols that begin with the characters SYS. Those names are reserved for existing system symbols (like &SYSNAME).
4. You can specify an optional period at the end of a system symbol definition. For example, both of the following statements are valid and define the same system symbol:

```
SYMDEF (&PAGESYM1='LOCAL1')  
SYMDEF (&PAGESYM1.='LOCAL1')
```

5. When coding a single quotation mark as part of a substitution text for an installation-defined static system symbol, specify two consecutive single quotation marks. In the following example, &SYMBOL4 is assigned the string O'HARE:

```
SYMDEF (&SYMBOL4='O''HARE') /* &SYMBOL4 is assigned O'HARE */
```

6. If you intend to use a system symbol to represent a parmlib member suffix in IEASYSxx, see [Chapter 56, “IEASYSxx \(system parameter list\),”](#) on page 421 for special considerations.

If the system finds an error in IEASYMxx, the system issues message IEA013E. If a statement in error applies to the processor or LPAR on which this system is being initialized, the system issues message IEA011A to prompt for a new IEASYMxx parmlib member.

### **Example of coding IEASYMxx**

Use the following example as a model when coding IEASYMxx for your installation. The example explains how to code IEASYMxx for the sysplex that is shown in [Figure 4 on page 45](#).

1. Enter a global SYSDEF statement that specifies:

- The IEASYSxx member, IEASYS01, that specifies system parameters for systems SYSCA, SYSCB, and SYSCD. SYSCC requires two IEASYSxx members, which are specified on a local SYSDEF statement in the parmlib member.
- The global definition for the installation-defined system symbol &LNKSYM;

```
SYSDEF  SYSPARM(01,L)
        SYMDEF(&LNKSYM='GLOBALP')
```

2. Enter a local SYSDEF statement that identifies the LPAR on which system SYSCA is running. The statement specifies:

- The hardware name and LPAR name (the system name defaults to the LPAR name).
- A local definition for the installation-defined system symbol &LNKSYM, which is to override the global definition that is specified earlier. The local definition for &LNKSYM is used only by system SYSCA.

```
SYSDEF  HWNAME(MVS3090) LPARNAME(SYSCA)
        SYMDEF(&LNKSYM='LOCALP1')
```

3. Enter a local SYSDEF statement that identifies the CPC on which system SYSCC is running. The statement specifies:

- The hardware name for the CPC (the system name defaults to the hardware name)
- The IEASYSxx members that contain the system parameters for system SYSCC. The IEASYSxx members are used only by system SYSCC. The other systems use the IEASYSxx members that are identified in the global definition.

```
SYSDEF  HWNAME(SYSCC)
        SYSPARM(01,02,L)
```

In this example, no local SYSDEF statements are necessary for systems SYSCB or SYSCD because they do not require unique definitions for system symbols or system parameters.

The complete IEASYMxx parmlib member is:

---

```
SYSDEF  SYSPARM(01,L)
        SYMDEF(&LNKSYM='GLOBALP')

SYSDEF  HWNAME(MVS3090) LPARNAME(SYSCA)
        SYMDEF(&LNKSYM='LOCALP1')

SYSDEF  HWNAME(SYSCC)
        SYSPARM(01,02,L)
```

*Figure 3. Complete IEASYMxx parmlib member*

---




Figure 4. Coding IEASYMxx for a four-system sysplex

Figure 5 on page 45 shows an example of how to use one IEASYMxx member to specify global statements (IEASYMA4) and another to specify local statements (IEASYMA5). IEASYMA4 defines system symbols for all systems that share the member:

```
SYSDEF SYMDEF(&LNKLST1='CS,52')
        SYMDEF(&LNKLST2='44,42,L')
        SYMDEF(&LPALST1='52,CS')
        SYMDEF(&LPALST2='ST,L')
        SYMDEF(&MLPALS1='44')
        SYMDEF(&MLPALS2='43,42')
        SYMDEF(&SVCNAME='44')
        SYMDEF(&MVSRLSE='52')
        SYMDEF(&SMFPARM='44')
```

Figure 5. IEASYMA4 parmlib member

IEASYMA5 (shown in Figure 6 on page 46) defines local system symbols and system parameters for processors J50 and J60.

```

SYSDEF HWNAME(J50)
      SYSPARM(02)
      SYSNAME(J50)
      SYSCLONE(J5)
      SYMDEF(&NODE='55')
      SYMDEF(&LOGCLS='M')
SYSDEF HWNAME(J60)
      SYSPARM(02)
      SYSNAME(J60)
      SYSCLONE(J6)
      SYMDEF(&NODE='56')
      SYMDEF(&LOGCLS='O')

```

Figure 6. Example IEASYMxx parmlib member

See [Figure 7 on page 47](#) for a sample LOADxx member that points to IEASYMA4 and IEASYMA5.

## Step 5. Code support for system symbols in LOADxx

The LOADxx parmlib member provides sysplex-related definitions early in system initialization so other parmlib members can use those definitions. It optionally specifies the IEASYMxx parmlib member that the system is to use.

If you use IEASYMxx to define names for the systems in your environment, you will not be required to code a unique LOADxx member for each system.

### Contents of LOADxx

LOADxx specifies the following parameters that relate to replication:

| Parameter | Description  |
|-----------|--|
| IEASYM    | Specifies the suffixes of one or more IEASYMxx members that define system symbols and specify system parameters. |
| SYSPARM   | Specifies the suffixes of one or more IEASYSxx parmlib members that contain system parameters                    |
| SYSplex   | Specifies the name of the sysplex (which is the substitution text for the &SYSplex system symbol)                |

### Procedure for coding LOADxx

Take the following steps to code the parameters in LOADxx that relate to the sharing of system resources:

1. Optionally specify the sysplex name on the SYSplex parameter in the LOADxx parmlib member. For example, to name a sysplex EXMPLEX, code:

```
SYSplex  EXMPLEX
```

**Note:** LOADxx defines the substitution text for &SYSplex early in system initialization so other parmlib members can use it. Therefore, if you plan to use the &SYSplex system symbol in parmlib, specify the sysplex name in LOADxx. You can also specify the sysplex name on the SYSplex parameter in the COUPLExx parmlib member. To ensure that the name in COUPLExx matches the one in LOADxx, IBM suggests that you specify the following in COUPLExx:

```
SYSplex(&SYSplex.)
```

If you do not specify the SYSplex parameter in LOADxx, the system will temporarily assign the value LOCAL to the &SYSplex system symbol. When the system processes the SYSplex parameter in COUPLExx, it assigns the value specified on that parameter to &SYSplex. If the value is SYSplex(&SYSplex;), the value of &SYSplex will remain LOCAL.

2. On the IEASYM statement, specify the suffixes of the IEASYMxx members that the system is to use.

3. Determine if you need to specify one or more IEASYSxx suffixes on the SYSPARM parameter:
  - If the systems in your environment require unique system parameters, specify the system parameters in IEASYMxx (see [“Step 4. Create an IEASYMxx parmlib member” on page 41](#)); do not respecify the system parameters in LOADxx.
  - If the systems in your environment use the same system parameters, they can share the same LOADxx member; specify the system parameters in LOADxx.

If you specify system parameters in *both* LOADxx and IEASYMxx, the system will use the scheme shown in [Table 10 on page 41](#) to determine which IEASYSxx members to use.

Figure 7 on [page 47](#) is an example of a LOADxx member that includes support for system symbols. The IEASYM statement specifies that IEASYMxx members IEASYMA4 and IEASYMA5 are to be used. The SYSPLEX statement specifies a sysplex name of UTCPLXJ4.

```
IODF      A1 IODFST   B710      A1
IEASYM    (A4,A5)
SYSPLEX   UTCPLXJ4
SYSCAT    CMNJ4C113CCATALOG.J40CAT
```

Figure 7. Example LOADxx parmlib member

## Using system symbols in parmlib

After you set up parmlib for sharing, take the following steps to specify system symbols in parmlib definitions:

1. [“Step 1. Know the rules for using system symbols in parmlib” on page 47](#)
2. [“Step 2. Determine where to use system symbols in parmlib” on page 50](#)
3. [“Step 3. Verify system symbols in parmlib” on page 51](#)

### Step 1. Know the rules for using system symbols in parmlib

Follow these rules and recommendations when using system symbols in parmlib:

1. Specify system symbols that:
  - Begin with an ampersand (&)
  - Optionally end with a period (.)
  - Contain 1-16 characters between the ampersand and the period (or the next character, if you do not specify a period).

**Note:** Symbols are character strings and can only be used as such. Even though a character string can consist of only numeric characters, it cannot be used as a number. For example, a symbol cannot be used for the `start` or `number` value in a substring.

If the system finds a system symbol that does not end with a period, it will substitute text for the system symbol when the next character is one of the following:

- Null (the end of the text is reached)
- A character that is not alphabetic, numeric, or special (@, #, or \$).

**Recommendation:** End all system symbols with a period. Omitting the period that ends a system symbol could produce unwanted results under certain circumstances. For example, if the character string (2) follows a system symbol that does not have an ending period, the system will process the (2) as substring syntax for the system symbol, regardless of how you intended to use the string in the command. For more information about substringing system symbols, see [“Using substrings of system symbols” on page 48](#).

2. Use a small set of system symbols so they are easy to manage and remember.

3. Code two consecutive periods (..) if a period follows a system symbol. For example, code &DEPT..POK when the desired value is D58.POK and the substitution text D58 is defined to the system symbol &DEPT.
4. When using system symbols in data set name qualifiers, keep the rules for data set naming in mind. For example, if you use &SYSNAME as a data set qualifier, ensure that the substitution text begins with an alphabetic character.
5. Ensure that resolved substitution texts do not extend parameter values beyond their maximum lengths. For example, suppose that the following command is to start CICS:

```
S CICS, JOBNAME=CICS&SYSNAME. . . .
```

The resolved substitution text for &SYSNAME cannot exceed four characters because job names are limited to eight characters (the four characters in CICS plus up to four character in &SYSNAME). A substitution text of SYS1 is valid because it resolves to the job name CICSSYS1. However, a substitution text of SYSTEM2 is not valid because it resolves to the job name of CICSSYSTEM2, which exceeds the allowable maximum of eight characters.

6. If you use &SYSNAME, ensure that its substitution text is unique on each system. See [“Step 3. Determine where to specify the system name” on page 41](#) for more information.
7. Do not specify system symbols in the values on the OPI and SYSP parameters in the IEASYSxx parmlib member.
8. Do not specify any system symbols in parmlib members that do not support system symbol substitution. See [“Overview of parmlib members” on page 14](#) for information about the parmlib members that support system symbols.

## Using substrings of system symbols

*Substringing* allows you to specify a subset of characters in a substitution text. This function is particularly useful when specifying a symbol in a field that accepts only a small number of characters.

The syntax for substringing symbols is:

```
&SYMBOL(start:number).
```

-OR-

```
&SYMBOL(start).
```

### start

The character position where the substring is to start. The first character in the original system symbol is position 1, the second is position 2, and so on. If *start* is positive, the system will count from the starting position to the end of the string. If *start* is negative (in other words, a minus sign appears before it), the system will count backwards from the ending position of the string.

### number

The number of characters, from the starting position to the ending position of the string, that the substring is to contain. If *number* is not specified, the substring length will default to 1. Do not specify a negative number for *number*.

For example, assume that you want to specify &SYSNAME as the second-level qualifier in a data set name, and you want to limit the qualifier to two characters. If the system defined a four-character value to &SYSNAME, such as SYS1, you can specify the third and fourth characters of SYS1 using the following notation:

```
HILEVELQ.&SYSNAME(3:2) . . LOWLVLQ
```

In this case, the system substitutes the third and fourth characters of SYS1 (which are S1) as the second-level qualifier, yielding:

## Procedure for substringing symbols

Follow these steps when specifying substrings for symbols:

1. Start the substring notation with a left parenthesis and end it with a right parenthesis.

If you specify only the left and right parentheses, the “substring” is the entire substitution text. For example, if the system symbol &YR8; is assigned the substitution text 2008 in all cases below, the following system symbols will specify the same substitution text:

| Symbol            | Resulting Substring |
|-------------------|---------------------|
| <b>&amp;YR8</b>   | 2008                |
| <b>&amp;YR8()</b> | 2008                |

2. Specify the character position, from the *start* of the original string, where the substring is to begin. For example:

| Symbol             | Resulting Substring |
|--------------------|---------------------|
| <b>&amp;YR8(4)</b> | 8                   |
| <b>&amp;YR8(2)</b> | 0                   |

Use a minus sign (-) before the start position to indicate that the system is to count backwards from the *end* of the substitution text. For example:

| Symbol              | Resulting Substring |
|---------------------|---------------------|
| <b>&amp;YR8(-4)</b> | 2                   |
| <b>&amp;YR8(-1)</b> | 8                   |

3. Specify the number of characters, from the starting position, that the substring is to contain. Separate this number from the start position with a colon (:). For example:

| Symbol                | Resulting Substring |
|-----------------------|---------------------|
| <b>&amp;YR4(3:2)</b>  | 08                  |
| <b>&amp;YR4(-4:2)</b> | 20                  |

## Errors in substringing

It is important that you specify substrings carefully. The syntax can become complicated, and it is very easy to make mistakes. When the system finds an error in substring notation, it tries to assign a value whenever possible. For example, when a substring length of zero is specified, the system assigns a length of one.

Table 11 on page 49 summarizes the errors that might occur in substring syntax. Always, assume that the dynamic system symbol &YR8. is assigned the substitution text **2008**.

| Table 11. Summary of errors in substring syntax |   |  |                     |
|---|---|--|---------------------|
| System Symbol                                   | Description of Error  | System Action                          | Resulting Substring |
| <b>&amp;YR8(-5:1)</b>                           | The start position is not valid (it exceeds the length of the substitution text). | The system assigns start position one. | 2                   |
| <b>&amp;YR8(0:1)</b>                            | The start position is zero.   | The system assigns start position one. | 2                   |
| <b>&amp;YR8(4:0)</b>                            | The length is zero.   | The system assigns a length of one.    | 8                   |

Table 11. Summary of errors in substring syntax (continued)

| System Symbol         | Description of Error   | System Action   | Resulting Substring |
|-----------------------|--|---|---------------------|
| <b>&amp;YR8(5:1)</b>  | The start position is beyond the length of the substitution text.  | The system assigns a length of zero.  | Null                |
| <b>&amp;YR8(3:3)</b>  | The length exceeds the length of the substitution text beyond the specified start position.                          | The system assigns the substring from the start position to the end of the substitution text. | 08                  |
| <b>&amp;YR8(-2:a)</b> | The “a” character is not valid substring notation.   | The system treats the substring notation as normal text.                                      | 2008(-2:a)          |
| <b>&amp;YR8.(3:3)</b> | The optional period indicates the end of the string. The system does not apply the substring notation to the string. | The system treats the substring notation as normal text.                                      | 2008(3:3)           |

### Using double ampersand notation

You can use double ampersand notation to:

- Defer the processing of a symbol until a later time
- Tell the system to process an ampersand as a literal character (instead of a character that indicates the beginning of a symbol).

When the system finds two consecutive ampersands at the beginning of a valid symbol, the first ampersand is removed and the second is kept in place. A subsequent process can then substitute text for the symbol in later processing, or the second ampersand can remain as a literal character.

**Note:** Defer the processing of system symbols only if a function specifically states that it supports double ampersand notation (for example, the naming of dump data sets with the DUMPDS command, which is described in *z/OS MVS System Commands*). If a function does not specifically state that it supports double ampersand notation, the system might not perform the desired substitution.

When you code:

```
&&DAY .
```

The system removes the first ampersand:

```
&DAY .
```

## Step 2. Determine where to use system symbols in parmlib

System symbols offer the greatest advantage when two or more systems require different data sets, jobs, procedures, or entire parmlib members. This section provides examples of how to specify system symbols when naming certain resources in parmlib.

**Data sets:** A good example of using system symbols in data set names is the DSNAME parameter in the SMFPRMxx parmlib member, which specifies data sets to be used for SMF recording. Assume that each system in your sysplex requires one unique data set for SMF recording. If all systems in the sysplex use the same SMFPRMxx parmlib member, you can specify the following naming pattern to create different SMF recording data sets on each system:

```
SY&SYSCONE . . SMF . DATA
```

When you IPL each system in the sysplex, the &SYSCONE system symbol resolves to the substitution text that is defined on the current system. For example, if a sysplex consists of two systems named SYS1 and SYS2, accepting the default value for &SYSCONE will produce the following data sets:

```
SYS1.SMF.DATA on system SYS1
SYS2.SMF.DATA on system SYS2
```



Note that the use of &SYSCONE provides unique data set names while establishing a consistent naming convention for SMF recording data sets.

**Parmlib members:** You can apply the same logic to system images that require different parmlib members. For example, assume that system images SYS1 and SYS2 require different CLOCKxx parmlib members. If both systems share the same IEASYSxx parmlib member, you can specify &SYSCONE in the value on the CLOCK parameter:

```
CLOCK=&SYSCONE;
```

When each system in the sysplex initializes with the same IEASYSxx member, &SYSCONE resolves to the substitution text that is defined on each system. Accepting the default value for &SYSCONE produces the following:

```
CLOCK=S1      (Specifies CLOCKS1 on system SYS1)
CLOCK=S2      (Specifies CLOCKS2 on system SYS2)
```

**Started Task JCL:** If JCL is for a started task, you can specify system symbols in the source JCL or in the START command for the task. You cannot specify system symbols in JCL for batch jobs, so you might want to change those jobs to run as started tasks.

If a started task is to have multiple instances, determine if you want the started task to have a different name for each instance. Started tasks that can be restarted at later times are good candidates. The different names allow you to easily identify and restart only those instances that require a restart. For example, you might assign different names to instances of CICS because those instances might be restarted at later points in time. However, instances of VTAM, which are generally not restarted, might have the same name on different systems.

When you start a task in the COMMNDxx parmlib member, you can specify system symbols as part of the job name. Assume that system images SYS1 and SYS2 both need to start customer information control system (CICS). If both system images share the same COMMNDxx parmlib member, you can specify the &SYSNAME system symbol on a START command in COMMNDxx to start unique instances of CICS:

```
S CICS,JOBNAME=CICS&SYSNAME;...
```

When each system in the sysplex initializes with the same COMMNDxx member, &SYSNAME resolves to the substitution text that is defined on each system. If &SYSNAME is defined to SYS1 and SYS2 on the respective systems, the systems will start CICS with the following jobnames:

```
CICSSYS1 on system SYS1
CICSSYS2 on system SYS2
```

Note that the *resolved* substitution text for &SYSNAME is eight characters long, which is the maximum length for jobnames.

### Step 3. Verify system symbols in parmlib

IBM provides you with tools to verify symbol usage in parmlib. The parmlib symbolic preprocessor tool allows you to test symbol definitions before you IPL the system to use them. This tool shows how a parmlib member will appear after the system performs symbolic substitution. For information about setting up and using the parmlib symbolic preprocessor tool, see [Appendix B, “Symbolic Parmlib Parser,”](#) on page 793.

If you only need to verify a new parmlib member's use of the current system symbols, you can run the IEASYMCK sample program to see how the contents of the parmlib member will appear after symbolic substitution occurs.

IEASYMCK is located in SYS1.SAMPLIB. See the program prolog for details.

## Changing system symbols

System symbols can be changed, added, or deleted by the SETLOAD xx,IEASYM command (see *z/OS MVS System Commands* for full details) and can be changed or added by the IEASYMU2 program. Updated symbols cannot be transported to other systems and therefore may not be usable, for example, for job JCL interpretation or automatic restart manager (ARM) processing. Update symbols with care. If you are not careful in how you update symbols, you could end up with different tasks using different values for a symbol you have changed. For example, if you have a long-running REXX exec, it could obtain the value of a symbol when it starts, and then continue to use that value thereafter. So even though you have updated the value of the symbol, that REXX exec will continue to use the old value. One safe use of updated symbols is for symbols that are used only in catalog aliases.

When you update symbols, the entire system symbol table is rebuilt. When IEASYMU2 is used:

Rebuilding re-calculates the substitution values only for symbols identified in the input.

As a result, substitution values for the other symbols will not change even if the substitution value for any of those symbols was based on the value of a symbol being changed by IEASYMU2.

The old system symbol table remains in storage; this storage is never freed, for system integrity reasons.

The system symbol table is in subpool 245 (ESQA) and can be as large as 57088 bytes. The size depends upon the number of symbols that you have defined. In general, the number of bytes in the table can be calculated as the sum of:

- 4
- Number\_Of\_Symbols multiplied by 16
- Length of every symbol name (including the leading ampersand and trailing period)
- Length of the value for every symbol

The size of the current system symbol table can be viewed by the DISPLAY SYMBOLS,SUMMARY command. An example of the command output is:

```
SY1 IEA994I STATIC SYSTEM SYMBOL INFO
SYMBOLS DEFINED: 12
CURRENT TABLE SIZE: 344 BYTES
MAX TABLE SIZE: 57088 BYTES
```

Also, z/OS V2R1 provides CHECK(IBMSUP,SUP\_SYMBOL\_TABLE\_SIZE) as part of the IBM Health Checker for z/OS to let you view the current size and to let you set a threshold so that you are alerted if the current size approaches the maximum size too closely.

The IEASYMU2 program is provided in SYS1.LINKLIB in z/OS V2R1 as a replacement for the IEASYMUP program, which had been provided only by OBJ in SYS1.SAMPLIB and with documentation only in the IBM Redbook SG24-5451. As of z/OS V2R1, IEASYMUP must not be used. If the IEASYMUP OBJ provided in SYS1.SAMPLIB is re-linked and then executed, it will indicate that you must use either the new SETLOAD xx,IEASYM command or the IEASYMU2 program. Do not use a pre-z/OS V2R1 IEASYMUP on a z/OS V2R1 system.

IBM recommends that you not use both the IEASYMU2 program and the SETLOAD xx,IEASYM command unless you do so intentionally and carefully. Updates made by the IEASYMU2 program are temporary and will be lost if you subsequently issue the SETLOAD xx,IEASYM command unless you have made corresponding updates in the appropriate IEASYMxx parmlib members. You could use RACF profiles to enforce that either IEASYMU2 or SETLOAD xx,IEASYM not be used. The SETLOAD xx,IEASYM command is protected by the MVS.SETLOAD.IEASYM entity in the OPERCMDS class; the IEASYMU2 program is protected by IEASYMUP.symbolname entities in the FACILITY class.

IEASYMU2 processing re-calculates the substitution values only for symbols identified in the input. As a result, substitution values for the other symbols will not change even if the substitution value for any of those symbols was based on the value of a symbol being changed by IEASYMU2.

The IEASYMU2 program must be invoked in problem state. To execute the IEASYMU2 program, run the following JCL (noting that IEASYMU2 will be in the LNKLST so no joblib or steplib should be used):

```
//IEASYMU2 JOB ...  
//IEASYMU2 EXEC PGM=IEASYMU2,PARM='...'
```

The input parameter is specified using the PARM keyword on the EXEC card, in the format:

```
PARM='SYMNAME1=VALUE1 SYMNAME2=VALUE2 ...SYMNAMEN=VALUEN'
```

where:

- All updates by IEASYMU2 are controlled by RACF facility class entity IEASYMUP.symbolname (without the leading ampersand and trailing period). If the security product does not grant UPDATE access to the requester for every symbol requested by the job, the job does not complete successfully and the symbol table is not updated.
- The name of each "SymnameN" should not contain the leading "&" or the trailing ".".
- The symname is not thoroughly checked as a valid symbol as in IEASYMxx parmlib processing or SETLOAD xx,IEASYM command processing.
- The first symname=value specification must begin at the first character of the parameter. Each symname=value specification must be separated from the preceding one by exactly one blank.
- There must be no trailing blanks at the end of the parm string.
- The value must not have blanks.
- No translation to uppercase is done by the processing, so be careful to put everything in uppercase as needed.
- You can change the values of symbols (including the length).
- You can add new symbols.
- You cannot have an "&" as part of the symbol name
- You can use symbolics in defining the value if you invoke this as a started task or started job. In this case, the symbols are resolved by the system before IEASYMU2 runs.
- When there are symbolics used in defining the value that are not resolved by the system before IEASYMU2 runs (perhaps because you ran this as a batch job):
  - They must be resolvable by the system symbol table that existed before this running of IEASYMU2.
  - The resolved value must be no longer than the initial unresolved value.
  - The input parameter area can be modified by the IEASYMU2 processing.
- The specified symbol name must be no longer than 16 characters (as it does not contain the leading "&" or the trailing ".").
- You cannot specify the system-defined symbols SYSPLEX, SYSNAME, SYSCONE, SYSR1, SYSALVL, SYSOSLVL.
- The specified value must be no longer than the specified symbol name plus one unless the symbol name ends with an underscore, in which case the value must be no longer than 44.
- Less syntax checking of operands might be done for the IEASYMU2 program than is done for the SETLOAD xx,IEASYM command.
- If the parameter string exceeds 100 bytes (or even if it does not), you can use the PARMD (also known as LONGPARM) support of z/OS V2R1 to specify the parameters within the DD identified by using PARMD=ddname on the EXEC PGM= statement of the JCL. Care must be taken if using PARMD, due to the PARMD rule of stripping off all trailing blanks on a given line. Thus:
  - The first symname=value pair must start in column 1 of the first line
  - Do not split a symname=value pair across lines (primarily for clarity)
  - When continuing onto a second or subsequent line, begin that line with the symname=value pairs starting in column 2

- For example, (the first line of the example is not part of your input; it is just used for showing the starting column)

```
1-----
SYMNAME1=VALUE1 SYMNAME2=VALUE2
SYMNAME3=VALUE3
SYMNAME4=VALUE4 SYMNAME5=VALUE5
```

- You cannot provide more than 255 input symbols
- The resulting system symbol table must not exceed 57088 bytes.
- Output messages are written by WTO with routing code 11 and MCSFlag indicating hardcopy-only.
- As with the SETLOAD xx,IEASYM command, a change to the system symbol table results in sending ENF signal 73 and also rerunning CHECK(IBMSUP,SUP\_SYMBOL\_TABLE\_SIZE).
- Messages IEASYMU01I, IEASYMU02I, IEASYMU03I, and IEASYMU04I might be issued.

## IEASYMU2 return codes

In the return code descriptions in [Table 12 on page 54](#), "xxxxxx" identifies which input symbol is the source of the error ("000001" corresponds to the first input symbol, and so on).

| Table 12. IEASYMU2 return codes |   |
|---------------------------------|---|
| Return code                     | Explanation   |
| <b>0</b>                        | Success   |
| <b>00000008</b>                 | Missing parameter.<br>No parameters were provided. Correct the input.   |
| <b>xxxxxx0C</b>                 | Symbol name contains ampersand<br>The symbol name has an ampersand; this is not allowed. Correct the input.   |
| <b>xxxxxx10</b>                 | Bad symbol name length<br>A symbol name length is not in the range 1-16. Correct the input.   |
| <b>xxxxxx14</b>                 | Bad symbol value length<br>A symbol value length is longer than the symbol name length plus one (when the name does not end with an underscore) or 44 (when the name does end with an underscore). Correct the input. |
| <b>00010018</b>                 | Too many symbols<br>More than 255 input symbols were specified. Correct the input.  |
| <b>xxxxxx1C</b>                 | Reserved symbol<br>An attempt to define or change a reserved symbol (one of the symbols defined by z/OS - SYSPLEX, SYSNAME, SYSCONE, SYSR1, SYSALVL, SYSOSLVL). Correct the input.                                    |
| <b>xxxxxx20</b>                 | RACF denied access<br>RACF denied access to this symbol. Correct the input or contact the security administrator to gain access.  |
| <b>xxxxxx24</b>                 | Symbol value contains ampersand after substitution<br>The symbol value still has an ampersand after all symbol substitution has been done; this is not allowed. Correct the input.                                    |

| Table 12. IEASYMU2 return codes (continued) |  |
|---|--|
| Return code                                 | Explanation  |
| <b>xxxxxx28</b>                             | Too much symbol data<br><br>The resulting symbol table would exceed the maximum symbol table size. Correct the input.  |
| <b>xxxxxx2C</b>                             | Bad symbol value length due to a substitution<br><br>The symbol value specification contained a symbol or symbols and the resolved symbol value was longer than the symbol value specification - this is not allowed.  |
| <b>xxxxxx30</b>                             | Underscore conflict<br><br>The symbol violated one of the following rules: <ul style="list-style-type: none"> <li>• An existing symbol cannot be a substring of a new symbol if the next character of the new symbol is an underscore.</li> <li>• A new symbol cannot be a substring of an existing symbol if the next character of the existing symbol is an underscore.</li> </ul> |
| <b>00000FFF</b>                             | Improper release<br><br>The IEASYMU2 program cannot be used on this release of z/OS. Use IEASYMU2 on z/OS V2R1 or later.   |

## Displaying static system symbols

You can enter the DISPLAY SYMBOLS operator command to display the static system symbols and associated substitution texts that are in effect for a system. See [z/OS MVS System Commands](#) for information about how to enter DISPLAY SYMBOLS.

## Diagnosing problems with static system symbols

You can use the SYMDEF interactive problem control system (IPCS) subcommand to diagnose problems in static system symbol definitions. See [z/OS MVS IPCS Commands](#) for information about how to use the SYMDEF subcommand.

## Indirect volume serial support

Indirect volume serial support allows the system to dynamically resolve volume and device type information for non-VSAM data sets that reside on either the system residence volume (SYSRES) or one or more logical extensions to the SYSRES volume. If all the SYSRES data sets do not fit on a single DASD volume, you can use additional volumes as "logical extensions" to SYSRES and refer to them indirectly. This allows you to change the volume serial number or device type of SYSRES or its logical extension volumes without having to recatalog the non-VSAM data sets on that volume.

The indirect volume serial is specified by one of two methods, either six asterisks (\*\*\*\*\*) or a system symbol. The method used depends on whether the data set will be cataloged on the SYSRES volume or on one of the SYSRES logical extension volumes.

- For data sets that will reside on the SYSRES volume, you can specify either:
  - a string of six asterisks (\*\*\*\*\*) in place of the volume serial, or
  - the &SYSR1 static symbol in place of the volume serial. (See [“Restrictions”](#) on page 57.)

The system dynamically resolves \*\*\*\*\* or &SYSR1 to the volume serial of the volume from which the system was IPLed (the SYSRES volume).

- For data sets that will reside on the logical extensions to SYSRES, you must specify a static system symbol in place of the volume serial. This static symbol must be defined in the IEASYMxx parmlib member.

**Note:** If you establish a naming convention for your SYSRES volume and associated logical extensions, you can define a system symbol in IEASYMxx that allows you to derive the logical extensions from whatever SYSRES volume is IPLed. This eliminates the need to update the IEASYMxx parmlib member if your installation IPLs with different SYSRES volumes. A naming convention example is shown in the following section.

## Using indirect volume serial support

The following information is a guide to help you use indirect volume serial support:

- Use access method services (IDCAMS) DEFINE NONVSAM to catalog the data sets that will reside on SYSRES or its logical extension volumes.

For a data set that will be cataloged on the SYSRES volume, specify \*\*\*\*\* or the &SYSR1 static symbol in the VOLUMES parameter and a value of 0000 on the DEVICETYPES parameter.

For a data set that will be cataloged on a SYSRES logical extension volume, specify a static system symbol in the VOLUMES parameter. IBM suggests using &SYSR2 for the first logical extension volume, &SYSR3 for the second, and so on. If you decide to use symbols with names different than &SYSR2, &SYSR3, and so on, keep in mind that the symbol name must be no smaller than the volume serial it represents, and no longer than six characters. This length includes the & but not the period.

- Define static symbols &SYSR2, &SYSR3, and so on, in the IEASYMxx parmlib member. (The system sets &SYSR1 to the volume serial of the IPL volume. You cannot define &SYSR1.)

For example, if the logical extension for the SYSRES volume used to IPL your production system is P1RES2 and the logical extension for the SYSRES volume used to IPL your test system is TSTRS2, your IEASYMxx member might contain statements such as:

```
/* Symbols for production system, P1 */
SYSDDEF .
:
:
SYMDEF(&SYSR2='P1RES2') /* Logical extension volume for P1 */
/* Symbols for test system, TST */
SYSDDEF .
:
:
SYMDEF(&SYSR2='TSTRS2') /* Logical extension volume for TST */
```

If your installation IPLs with different SYSRES volumes and you establish a naming convention for the SYSRES and its logical extension volumes, you can create a single IEASYMxx member that can be used regardless of which SYSRES volume is used to IPL the system. To do this, use substrings of the SYSRES volume serial (&SYSR1) in defining the symbols for the extension volume serials. For example, check to see if you have the SYSRES volumes and logical extension as described in [Table 13 on page 56](#).

*Table 13. SYSRES volumes and their extensions*

| <b>SYSRES</b> | <b>Extensions</b> |
|---------------|-------------------|
| <b>S01RES</b> | S01RS2,S01RS3     |
| <b>S02RES</b> | S02RS2,S02RS3     |
| <b>DEVRES</b> | DEVRS2,DEVRS3     |

If you do, then you can refer to them using a single IEASYMxx parmlib member with the following statements:

```
SYSDDEF .
:
SYMDEF(&SYSR2='&SYSR1(1:3).RS2') /* second SYSRES logical
                                extension */
```

```

SYMDDEF(&SYSR3='&SYSR1(1:3).RS3') /* third SYSRES logical
                                extension */
:

```

- If you use parmlib member PROGxx to specify authorized libraries, and any of those libraries are on SYSRES and its logical extensions, you can use static system symbols to identify the volumes. If, however, you still use parmlib member IEAAPFxx for this purpose, symbols will **not** work.

**Note:** You can use the CSVLNKPR tool to convert IEAAPFxx to PROGxx.

- In RACF, you may be able to remove the volser from PROGRAM profiles that refer to SYSRES and its logical extensions. See *z/OS Security Server RACF Security Administrator's Guide* for more information.
- In DFSMSHsm, a recovered or recalled data set catalog entry will not reflect system symbols used for indirect volume serials and may not return to its original volume. You may want to prevent migration of these data sets. See APAR OW24928 for more information.

## Restrictions

- Indirect volume serial support can only be used for data sets residing on SYSRES and its logical extensions. These are typically data sets that are installed as part of a system build process. Use with user or application data sets is not supported.
- Cataloged data sets must be non-VSAM and non-SMS-managed.
- The volume must be mounted and online when a request is made to retrieve information from the catalog.
- You are responsible for managing volumes where the data sets reside. If you move a data set from one volume to another, you must make the related changes. Changes include:
  - setting up parmlib, proclib, and JCL.
  - establishing system management procedures such as security, backup, and recovery.
- The following cannot be cataloged with a system symbol:
  - SYS1.PARMLIB
  - Any parmlib data set listed in LOADxx without a volume name.

Any parmlib data set (including SYS1.PARMLIB) can be cataloged with six asterisks (\*\*\*\*\*).





---

## Part 2. Members of SYS1.PARMLIB



## Chapter 3. ADYSETxx (dump suppression)

ADYSETxx controls dump analysis and elimination (DAE) processing, which suppresses dumps that are unnecessary because they duplicate previously taken dumps. DAE suppresses ABEND dumps that would be written to a SYSMDUMP data set (SYSMDUMPs), transaction dumps (IEATDUMP), and SVC dumps, when the symptom data of a dump duplicates the symptom data of a dump of the same dump type previously taken. DAE uses the ADYSETxx parmlib member to determine the actions DAE is to perform.

To change the ADYSETxx parmlib member specification, use the SET DAE command.

DAE can take the following actions for SYSMDUMP dumps, transaction dumps, and SVC dumps in either a single system or in a sysplex:

- Matching, which means that DAE compares each dump occurrence for a dump type (SVC dump, or SYSMDUMP and Transaction dumps) to dumps previously recorded in the DAE data set.
- Updating, which means that DAE records either a unique symptom or an occurrence of a duplicate symptom string in the DAE data set.
- Suppressing, which means that DAE prevents a dump from being taken if the dump's symptom data duplicates the symptom data of a previous dump (of the same dump type) recorded in the DAE data set. Dump suppression must also be permitted through one of the following:
  - The SUPPRESS option is specified in the ADYSETxx parmlib member, and the VRADAE key is contained in the variable recording area of the SDWA.
  - The SUPPRESSALL option is specified in the ADYSETxx parmlib member, and the VRANODAE key is absent from the variable recording area of the SDWA.

For more information, see the following references:

- [z/OS MVS Diagnosis: Tools and Service Aids](#), for information about DAE.
- [z/OS MVS System Commands](#), for information about the SET DAE command.

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Syntax rules for ADYSETxx

The following rules apply to the creation of ADYSETxx:

- Use one of the following rules for comments:
  - Put comments in columns 1-71. They must begin with /\* and end with \*/.
  - An asterisk (\*) in column one indicates a comment record. Comment records cannot be continued and that comments cannot appear on a parameter record.
- DAE= must appear first on a parameter record, and START or STOP must appear on the record. (Specify one or the other; START and STOP are mutually exclusive parameters.)
- Use commas or blanks to separate parameters and to separate subparameters. If you use a parameter (such as RECORDS or SVCDUMP) that requires a subparameter, you must enclose the subparameter in parentheses.

## Syntax format of ADYSETxx

```

DAE={START[,RECORDS(400|n)]}
    [,EXPIRE(60|n)]}
    [,SVCDUMP([MATCH][,SUPPRESS|SUPPRESSALL][,UPDATE]
    [,NOTIFY(3,30)])]}
    [,SYSDUMP([MATCH][,SUPPRESS|SUPPRESSALL][,UPDATE)])]}
    [,SHARE(DSN[,OPTIONS])]}
    [,DSN(datasetname)]}
    [,GLOBAL([DSN][,OPTIONS])]}
{STOP [,GLOBALSTOP]}

```

Syntax examples:

```

DAE=START,RECORDS(400),SVCDUMP(MATCH,UPDATE),EXPIRE(10)
DAE=START,EXPIRE(1),SYSDUMP(MATCH,UPDATE,SUPPRESS),
RECORDS(600)
DAE=START,SVCDUMP(MATCH,UPDATE,SUPPRESSALL,NOTIFY(5,60)),
EXPIRE(100)
DAE=START,SVCDUMP(MATCH,SUPPRESSALL),SHARE(DSN,OPTIONS),
DSN(SYS1.DAESHARE)
DAE=START,SVCDUMP(UPDATE,SUPPRESS),SHARE(DSN,OPTIONS),
EXPIRE(180),DSN(SYS1.DAESHARE2),GLOBAL(DSN,OPTIONS)
DAE=STOP
DAE=STOP,GLOBALSTOP

```

## IBM-supplied defaults for ADYSETxx

IBM supplies three ADYSETxx parmlib members:

- **ADYSET00** automatically starts DAE. It contains:

```

DAE=START,RECORDS(400),SVCDUMP(MATCH,SUPPRESSALL,UPDATE,NOTIFY(3,30))
SYSDUMP(MATCH,UPDATE)

```

**Note:** At system initialization, the ADYSET00 member is automatically in effect (DAE is active) because the IEACMD00 parmlib member contains the command SET DAE=00. If you do not want automatic activation of DAE, modify ADYSET00 to specify DAE=STOP.

- **ADYSET01** allows the operator to stop DAE processing by issuing the command SET DAE=01. ADYSET01 contains:

```

DAE=STOP

```

**Tip:** If the systems in a sysplex are sharing the DAE data set, update the ADYSET01 member as follows:

```

DAE=STOP,GLOBALSTOP

```

DAE is stopped on each system in the sysplex that shares the DAE data set. For more on dump suppression, see *z/OS MVS Diagnosis: Tools and Service Aids*.

- **ADYSET02** allows the operator to start DAE processing by issuing the command SET DAE=02. ADYSET02 contains the same options as ADYSET00.

## Statements and parameters for ADYSETxx

### DSN(*datasetname*)

Specifies the data set name to be used as the DAE data set. The data set must be accessible from each system that wants to share the data set.

The *datasetname* cannot be longer than 20 characters. SYS1.DAE is the default if you are not sharing the DAE data set. If you specify SHARE(DSN) and omit the DSN parameter, the DAE data set name is the data set already in use in the sysplex. For example, if the systems of the sysplex are sharing the DAE data set named SYS1.DAESHARE and the next system to join the sysplex specifies SHARE(DSN)

without specifying the DSN parameter, that system will share the DAE data set SYS1.DAESHARE already in use by the sysplex.

If you share the DAE data set across the systems in a sysplex, IBM suggests that you use a data set name other than SYS1.DAE.

### **GLOBAL([DSN],[OPTIONS])**

Specify GLOBAL when you want to change either the data set name, the DAE options (MATCH/SUPPRESS|SUPPRESSALL/UPDATE), or both for each system in the sysplex sharing the DAE data set.

When you specify GLOBAL(DSN), you must also specify SHARE(DSN), and DSN with the name of the DAE data set the sysplex is to use. DAE then uses the new DAE data set on all systems in the sysplex that sharing the DAE data set. If you specify GLOBAL(DSN) without specifying DSN or without specifying SHARE(DSN), the system issues error message ADY002I.

When you specify OPTIONS, you can change the following for each system sharing the DAE options:

- The SYSMDUMP memory dump options: MATCH, SUPPRESS, SUPPRESSALL, or UPDATE.
- The SVCDUMP memory dump options: MATCH, SUPPRESS, SUPPRESSALL, NOTIFY, or UPDATE.

When you specify GLOBAL(OPTIONS), you must also specify SHARE(OPTIONS). If you specify GLOBAL(OPTIONS) without specifying SHARE(OPTIONS) and SVCDUMP and/or SYSMDUMP, the system issues error message ADY002I.

### **GLOBALSTOP**

Specifies that DAE is to be stopped on each system in the sysplex currently sharing the DAE data set. This parameter is valid only when both of the following are true:

1. You specify STOP in this parmlib member.
2. You specified SHARE(DSN) when DAE was started.

If you do not specify GLOBALSTOP, you must specify STOP on each system in the sysplex.

### **MATCH**

Specifies that DAE is to compare the symptoms from the current memory dump to those that have already been recorded in the DAE data set. (Coding MATCH does not indicate that DAE suppresses duplicate memory dumps or update the DAE data set.)

### **NOTIFY(nnnn,tttt)**

Specifies the threshold at which an event notification facility (ENF) signal (event code 47) will be generated to notify a listener about SVC dumps completed, or suppressed, for a particular symptom string. The values, *nnnn* and *tttt* are decimal digits ranging 1 - 9999 that specify the number of memory dumps and time interval in minutes. The time interval is measured from successive memory dump completions or suppressions and not dumps initiations. The default is three memory dumps in 30 minutes for a particular symptom string.

#### **Note:**

1. NOTIFY is only valid when used with SVCDUMP.
2. UPDATE must be specified in order for NOTIFY to be effective.

### **RECORDS(nnnn)**

Specifies the maximum number of symptom records to be placed in virtual storage, where *nnnn* is a decimal digit in the range 1 - 9999. The default is 400 records.

Note that the system obtains records in multiples of 20. Therefore, if you specify RECORDS(23), the system rounds up the number of records you specified to the next multiple of 20, and place 40 records in storage instead of the 23 specified.

Each record includes information about each symptom, including:

- The date of the first and last occurrence of an error.
- The time of the first and last occurrence of an error.
- The system name of the first and last system to encounter an error.

- The actual symptom.

**EXPIRE(nnn)**

Specifies the symptom records expiration time in days. Valid values range 1 - 180. For example, if EXPIRE is set to 1, a memory dump with the same symptoms will not be suppressed the next calendar day. When the EXPIRE parameter is not specified, default is 60 (days).

**SHARE(DSN[,OPTIONS])**

Specify SHARE when you want each system in the sysplex to share either:

- The DAE data set or
- The DAE data set and options for SVCDUMP and SYSMDUMP.

When you specify OPTIONS, you can set up the following for each system sharing the DAE options:

- The SYSMDUMP memory dump options: MATCH, SUPPRESS or SUPPRESSALL, and UPDATE.
- The SVCDUMP memory dump options: MATCH, SUPPRESS or SUPPRESSALL, UPDATE, and NOTIFY(3,30).

Specify OPTIONS only with DSN.

**START**

Specifies that DAE is to be started. If already active, DAE is first stopped and then started again.

**Note:** If you specify only DAE=START, the system does not issue an error message. However, unless you also specify SVCDUMP or SYSMDUMP, DAE does not perform memory dump processing and elimination.

**STOP**

Specifies that DAE is to be stopped and that all storage used by DAE is to be freed. The DAE data set is closed and deallocated.

**SUPPRESS**

Specifies that duplicate memory dumps are to be suppressed when all other criteria for matching and suppressing memory dumps are met, including that the VRADAE key is present in the variable recording area of the SDWA. (Coding SUPPRESS indicates that DAE will also match symptoms from the current memory dump to those already recorded; it does not indicate that DAE updates the DAE data set with any new symptoms.)

SUPPRESS and SUPPRESSALL are mutually exclusive. If you specify both SUPPRESS and SUPPRESSALL, the system issues message ADY001I.

If you specify SUPPRESSALL, DAE suppresses more memory dumps because the VRADAE key in the SDWA is not required to suppress a memory dump. If you omit both SUPPRESS and SUPPRESSALL, DAE will not suppress any memory dumps.

**SUPPRESSALL**

Specifies that duplicate memory dumps are to be suppressed when all criteria for matching and suppressing memory dumps are met except for the VRADAE key. When SUPPRESSALL is specified, the system does not require the VRADAE key to be present in the variable recording area of the SDWA.

If SUPPRESSALL is specified and the VRANODAE key is present in the variable recording area of the SDWA, DAE will not suppress the memory dump. (Coding SUPPRESSALL indicates that DAE will also match symptoms from the current memory dump to those already recorded; it does not indicate that DAE updates the DAE data set with any new symptoms.)

SUPPRESSALL and SUPPRESS are mutually exclusive. If you specify both SUPPRESS and SUPPRESSALL, the system issues message ADY001I.

If you specify SUPPRESSALL, DAE suppresses more memory dumps because the VRADAE key in the SDWA is not required to suppress a memory dump. If you omit both SUPPRESS and SUPPRESSALL, DAE will not suppress any memory dumps.

**SVCDUMP(dump options)**

Requests that DAE process SVC memory dumps, by using one or more of the following subparameters:

- MATCH
- SUPPRESS or SUPPRESSALL
- UPDATE
- NOTIFY

NOTIFY(3,30) is the default if UPDATE is specified with SVCDUMP.

### **SYSDUMP(dump options)**

Requests that DAE process SYSDUMPs and transaction memory dumps by using one or more of the following subparameters; there is no default.

- MATCH
- SUPPRESS or SUPPRESSALL
- UPDATE

To enable suppression of duplicate SYSDUMPs and transaction memory dumps, specify

```
SYSDUMP (MATCH , SUPPRESS , UPDATE)
           or
SYSDUMP (SUPPRESSALL , UPDATE)
```

then enter,

```
SET DAE=xx
```

at the MVS console.

To suppress all SYSDUMPs and transaction memory dumps, enter the following from the MVS console:

```
CHNGDUMP SET , SYSDUMP , NODUMP
```

### **UPDATE**

Specifies that the DAE data set is to be updated with the results of matching. The update can be a new record for a new set of symptoms or an increase to the count of occurrences for a duplicate set of symptoms. (Coding UPDATE indicates that DAE will also match symptoms from the current memory dump to those already recorded; it does not indicate that DAE suppresses any duplicate memory dumps.)

If you do not specify UPDATE, DAE does not update the DAE data set. Specify UPDATE if you plan to suppress memory dumps, or to be notified when a threshold is reached for SVC dumps completed or suppressed for a particular symptom string.





## Chapter 4. ALLOCxx (allocation system defaults)

Use the ALLOCxx member of SYS1.PARMLIB to define installation defaults for:

- Unit names (dynamic allocation, unit-affinity-ignored, and redirection from TAPE)
- Space attributes
- TIOT size
- Handling allocation requests
- Catalog error policies.

These installation defaults for handling allocation requests can be overridden by installation exit routines specified in the EXITxx parmlib member. For information about the allocation exit routines, see [z/OS MVS Installation Exits](#). After IPL, use the SETALLOC command to change any of the defaults (except for 2DGT\_EXPDT).

### Parameter in IEASYSxx (or supplied by the operator)

```
ALLOC= {aa }
       {(aa,bb...)}{}
```

The two-character identifier (*aa*, *bb*, and so forth) is appended to ALLOC to identify the ALLOCxx member. Multiple members can be specified. If you specify a parameter in more than one member, the system uses the value in the first member, and ignores the values in the subsequent members.

The system does not set default to ALLOC00. If the ALLOC= parameter is not specified, the system uses the defaults that are identified in [“Statements and parameters for ALLOCxx”](#) on page 70.

### Syntax rules for ALLOCxx

The following syntax rules apply to ALLOCxx:

- Use columns 1 through 71. Do not use columns 72 through 80 for data; these columns are ignored.
- At least one delimiter (space or comma) is required between a statement and keyword. Delimiters are not required between keywords.
- Put comments in columns 1-71. They must begin with /\* and end with \*/.

## Syntax format of ALLOcxx

```

[SPACE [PRIMARY(primary-space)]
       [SECONDARY(secondary-space)]
       [DIRECTORY(directory-space)]
       [MEASURE(AVEBLK | TRK | CYL)]
       [BLKLNGTH(block-len)]
       [NOROUND | ROUND]
       [PRIM_ORG(CONTIG | MXIG | ALX)]
       [RLSE | NORLSE] ]

[UNIT [NAME(unit-name)]
      [UNITAFF(unit-name)]
      [REDIRECTED_TAPE(TAPE | DASD)] ]

[TIOT SIZE(tiot-size)]

[SDSN_WAIT WAITALLOC(NO | YES)]

[VOLUME_ENQ POLICY(WTOR | CANCEL | WAIT)]

[VOLUME_MNT POLICY(WTOR | CANCEL)]

[SPEC_WAIT [POLICY(WTOR | WAITHOLD | WAITNOH | CANCEL)]
           [MAXNWAIT(number-of-waits)]
           [POLICYNW(WTOR | CANCEL)] ]

[ALLC_OFFLN [POLICY(WTOR | WAITHOLD | WAITNOH | CANCEL)]
            [MAXNWAIT(number-of-waits)]
            [POLICYNW(WTOR | CANCEL)] ]

[CATLG_ERR [FAILJOB(NO | YES)]
           [ERRORMSG(NO | YES)] ]

[2DGT_EXPDT POLICY(ALLOW | WARN | FAIL)]

[VERIFY_VOL POLICY(YES | NO)]

[SYSTEM [IEFBR14_DELMIGDS(LEGACY | NORECALL)]
        [TAPELIB_PREF(BYDEVICES | EQUAL)]
        [REMIND_INTV(interval)]
        [TEMPDSFORMAT(INCLUDELABEL | UNIQUE)]
        [VERIFY_UNCAT(FAIL | TRACK | MSGTRACK | LOGTRACK)]
        [MEMDSENQMGMT(DISABLE | ENABLE)]
        [BATCH_RCLMIGDS(SERIAL | PARALLEL)]
        [OPTCDB_SPLIT(EXPLICIT | CATALOG)]
        [SWBSTORAGE(SWA | ATB)] ]

```

## Syntax example of ALLOcxx

```

2DGT_EXPDT    POLICY(ALLOW)           /*Allow data set allocation with two-digit date*/
SPACE          PRIMARY(10)             /*Primary Space Quantity*/
               SECONDARY(50)          /*Secondary Space Quantity*/
               BLKLNTH(1000)          /*Block Length*/
               DIRECTORY(0)           /*Default to Sequential*/
               MEASURE(AVEBLK)        /*Average Block Length*/
               PRIM_ORG(CONTIG)       /*Contiguous Organization*/
               RLSE                   /*Release Unused Space*/

UNIT           NAME(SYSALLDA)          /*SYSALLDA is Default*/
               UNITAFF(CART)          /*Cartridge is the default
                                       esoteric for tape*/
               REDIRECTED_TAPE(DASD)  /*Treat unopened
                                       batch-allocated DASD
                                       data sets, which have
                                       been redirected from
                                       TAPE as DASD. Default
                                       is TAPE.*/

TIOT           SIZE(32)                /*32K TIOT Size*/

SDSN_WAIT      WAITALLOC(NO)           /*Do not wait for
                                       special data sets*/

VOLUME_ENQ     POLICY(CANCEL)          /*Always cancel job*/

VOLUME_MNT     POLICY(WTOR)            /*Always issue the WTOR*/

SPEC_WAIT      POLICY(WAITNOH)         /*Wait while
                                       not holding resources*/
               MAXNWAIT(7)            /*7 "wait nohold"
                                       decisions allowed*/
               POLICYNW(CANCEL)       /*Cancel if wait is
                                       not allowed*/

ALLC_OFFLN     POLICY(WAITNOH)         /*Wait
                                       while not holding resources*/
               MAXNWAIT(7)            /*7 "wait nohold"
                                       decisions allowed*/
               POLICYNW(CANCEL)       /*Cancel if wait is
                                       not allowed*/

CATLG_ERR       FAILJOB(YES)           /*Fail the job*/
               ERRORMSG(YES)         /*Issue the WTOR*/

VERIFY_VOL     POLICY(YES)             /*Requests verification of premounted
                                       or PASSED/RETAINED volumes on
                                       AutoSwitchable (AS) Tape devices.*/

SYSTEM         IEFBR14_DELMIGDS(LEGACY) /*Indicates that the system is to
                                       automatically recall HSM-migrated
                                       data sets before deletion.*/
               TAPELIB_PREF(EQUAL)    /*Indicates that for non-specific
                                       tape library requests, such
                                       as scratch tape requests, all
                                       tape libraries must be treated
                                       as equal, and receive an
                                       equal share of the non-specific
                                       tape requests.*/
               REMIND_INTV(90)        /*90 seconds between each IEF882I
                                       or IEF883I reminder message.*/
               TEMPDSFORMAT(UNIQUE)   /*Creates unique
                                       temporary data
                                       set names.*/
               VERIFY_UNCAT(FAIL)     /*Indicates that UNCATLG
                                       requests fail if the data set
                                       information is not retrieved
                                       from the catalog.*/
               MEMDSENQMGMT(ENABLE)   /*Allows jobs and subsystems to use the
                                       memory-based ENQ management*/
               SWBSTORAGE(SWA)        /*Indicates that SWBs will be
                                       created in 24 or 31 bit storage,
                                       according to the SWA definition in use by the job.*/
               OPTCDB_SPLIT(EXPLICIT) /*Indicates that the
                                       system should treat
                                       multi-volume data sets
                                       in system-managed tape
                                       libraries as separate
                                       DD statements only
                                       when DCB=OPTCD=B is
                                       is specified with
                                       explicit volume serial
                                       numbers.*/

```

## IBM-supplied default for ALLOCxx

---

The system does not set default to ALLOC00. If neither the IEASYSxx member nor the operator specifies an ALLOC= parameter, the system uses all of the defaults identified in [“Statements and parameters for ALLOCxx” on page 70](#). If an ALLOCxx member is specified, but any individual parameters are not specified in that ALLOCxx member, the system uses the default for that parameter identified in [“Statements and parameters for ALLOCxx” on page 70](#).

## Statements and parameters for ALLOCxx

---

### SPACE

Specifies the installation defaults for some space allocation parameters. These defaults apply to only dynamic allocation and VIO requests. Space allocations specified on JCL (for VIO requests), on dynamic allocation, or in SMS data classes take precedence over the values that are coded on this statement.

When SPACE is specified at least one of the optional subparameters must be specified.

#### PRIMARY(primary-space)

Specifies one of the following:

- For TRK, the number of tracks to be allocated.
- For CYL, the number of cylinders to be allocated.
- For AVEBLK, the number of average data blocks in the data set. Use the BLKLNGTH parameter to specify the length of the average data block.

When you specify TRK or CYL for a partitioned data set (PDS), the primary quantity includes the space for the directory. When you specify a block length for a PDS, the primary quantity does not include the directory space; the system assigns the directory space outside the primary space assignment.

One volume must have enough available space for the primary quantity. If you request a particular volume and it does not have enough space available for your request, the system ends the job step. Allow for track overflow when computing track requirements.

To request an entire volume, specify in the primary quantity the number of tracks or cylinders on the volume minus the number that is used by the volume table of contents (VTOC). The volume must not contain other data sets.

**Value range:** 0 - 16777215

**Default:** 4

#### SECONDARY(secondary-space)

Specifies the number of additional tracks, cylinders, blocks, or records to be allocated, if more space is needed. The system does not allocate more space until it is needed.

If PRIMARY specifies the average block length, the system computes the number of tracks for the secondary quantity from the SECONDARY value that is multiplied by one of the following, in order:

1. The SPACE average block length subparameter.
2. The block length in the BLKSIZE field of the data control block.

When you specify SECONDARY and the data set requires more space, the system allocates the specified quantity:

1. In contiguous tracks or cylinders, if available.
2. If not, in up to five extents.

The system can allocate up to 16 extents for a data set on a volume. An extent is space that might or might not be contiguous to other space allocated to the data set. The extents for a data set include the primary quantity space and user-label space.

**Restriction:** BDAM data sets cannot be extended.

After the program fills the allocated space on a volume for a sequential data set, the system determines where the following data is written as follows:

- If the disposition of the data set is NEW or MOD and the limit on the number of extents on a volume has not been reached, the system attempts to allocate the secondary quantity on the same volume.
- If the disposition of the data set is OLD or SHARE, the system examines the next volume that is specified for the data set.
  - If space was allocated on the next volume for the data set, the next volume is used for the data set.
  - If space was not allocated on the next volume for the data set, secondary space is allocated on the next volume for the data set.
  - If there is not another volume that is specified for the data set, the system attempts to allocate the secondary quantity on the current volume.

The program should not write with a disposition of DISP=SHR unless you take precautions to prevent other programs from writing at the same time.

If the requested volumes have no more available space and if at least one volume is demountable, the system asks the operator to mount scratch (nonspecific) volumes until the secondary allocation is complete. If none of the volumes are demountable, the system abnormally ends the job step.

**Value range:** 0 - 16777215

**Default:** 24

#### **DIRECTORY(directory-space)**

Specifies the number of 256-byte records that are needed in the directory of a PDS.

When you are creating a PDS, you must request space for a directory.

**Value range:** 0 - 8388607.

**Default:** 0

#### **MEASURE([AVEBLK | TRK | CYL])**

Specifies the unit of measure of the space allocation.

##### **AVEBLK**

Requests that the system is to decide how many tracks to allocate based on the average block size. The size of the average block is specified by using the BLKLNGTH parameter, and the number of blocks is specified by using the PRIMARY parameter.

##### **TRK**

Specifies that space should be allocated in tracks.

##### **CYL**

Specifies that space should be allocated in cylinders.

**Default:** AVEBLK

#### **BLKLNGTH(block-len)**

Specifies, in bytes, the average block length of the data. The system computes how many tracks to allocate.

**Note:** BLKLNGTH is ignored when MEASURE(TRK) or MEASURE(CYL) is specified.

**Value range:** 0 - 65535

**Default:** 8192

#### **NOROUND | ROUND**

When MEASURE(AVEBLK) is specified, requests whether (ROUND) or not (NOROUND).

**Note:** ROUND/NOROUND is ignored when MEASURE(TRK) or MEASURE(CYL) is specified.

**Default:** NOROUND

### **PRIM\_ORG([CONTIG | MXIG | ALX])**

Specifies the organization of the primary space allocation.

#### **CONTIG**

Requests that space allocated to the data set be contiguous. If CONTIG is specified and contiguous space is not available, the system ends the job step.

#### **MXIG**

Requests that space that is allocated to the data set must be the largest area of available contiguous space on the volume and equal to or greater than the value specified on the PRIMARY parameter.



**CAUTION:** Use extreme care with this parameter. Large amounts of storage might be allocated, depending on how much free space is available at the time the request is made. If you code this parameter, also code the RLSE parameter to release any unused space.

Do not code MXIG for an indexed sequential data set.

MXIG can also be specified in a job's JCL.

#### **ALX**

Requests that up to five of the largest separate areas of available contiguous space are to be allocated to the data set, and each area must be equal to or greater than the value specified on the PRIMARY parameter.

For example, assume the following space extents (in tracks) are available: 910, 435, 201, 102, 14, 12, and 8.

If your job requests 14 tracks as its primary allocation, and ALX is in effect, the job receives the following five extents: 910, 435, 201, 102, and 14.

However, if the job requests 15 tracks as its primary allocation, it would receive four extents: 910, 435, 201, and 102. The job does not receive the 14-track extent because it is less than the primary space allocation.

Be careful when you are coding this parameter. Large amounts of storage might be allocated, depending on how much free space is available at the time the request is made. If you code this parameter, also code the RLSE parameter to release any unused space.

**Note:** ALX can also be specified in a job's JCL.

**Default:** None.

### **RLSE | NORLSE**

Requests whether (RLSE) or not (NORLSE) space that is allocated to an output data set, but not used, is to be released when the data set is closed, and the CLOSE macro does not specify TYPE=T. Unused space is released only if the data set is OPEN with the OUTPUT, OUTIN, INOUT, EXTEND or OUTINX option, and the last operation was OPEN, WRITE (and CHECK), PUT, or CLOSE with TYPE=T. Coding RLSE for primary allocation does not prohibit the use of secondary allocation. The secondary request for space is still in effect.

The system ignores a request to release unused space when a data set is closed if any of the following situations occur:

- Another job is sharing the data set.
- Another task in the same job is processing an OPEN, CLOSE, EOVS, or FEOVS request for the data set.
- Another data control block is open for the data set.
- The data set is an indexed sequential data set.

**Default:** RLSE

**UNIT**

Specifies the installation default for the device on which the system is to place data sets.

When UNIT is specified at least one of the optional subparameters must be specified.

**NAME(unit-name)**

Requests a group of devices to place data sets on. The installation must have assigned the name to the devices during system initialization or IBM must have assigned the name. This default applies only to dynamic requests.

A group name can identify a single device or a group of devices. A group can consist of devices of the same or different types. For example, a group can contain both direct access storage devices (DASD) and tape devices.

The system assigns any available device from the group. If a group consists of only one device, the system assigns that device. If the group consists of more than one device type, the units requested are allocated from the same device type. For example, if GPDA contains 3330 Disk Storage and 3350 direct access storage devices (DASD), a request for two units would be allocated to two 3330s or to two 3350s.

If a data set that was created by using the group-name subparameter is to be extended, the system allocates additional devices of the same type as the original devices. However, the additional devices might not necessarily be from the same group.

**Dynamic allocation consideration:** If a time sharing user's dynamic allocation request does not include unit information, the system obtains a unit description from:

- The PDF\_DEFAULT\_UNIT parameter for certain ISPF/PDF data sets. See [Data set allocation settings in z/OS ISPF Planning and Customizing](#) for specific information.
- The SYS1.UADS entry for all other ISPF/PDF data sets and for all non-ISPF/PDF TSO data sets.

If the user is not a time sharing user or if the SYS1.UADS entry does not contain a unit description. The system uses the unit name that is specified on the UNIT keyword of the ALLOCxx parmlib member as the default.

The unit description you supply in your dynamic allocation request can override the unit type for a cataloged data set. However, the unit description from the SYS1.UADS cannot override the unit information in the catalog.

**Value range:** 1 to 8 alphanumeric characters.

**Default:** SYSALLDA, which contains all DASD defined to the system.

**UNITAFF(unit-name)**

Specifies the installation default for the unit name on which the system is to place data sets when the following conditions are true:

- The data set for the referencing DD, that is, the DD that specifies UNIT=AFF, DISP=NEW or DISP=MOD (MOD treated as NEW), and is not SMS-managed.
- The data set for the referenced DD, that is, the DD statement pointed to by the UNIT=AFF subparameter, is SMS-managed.
- The allocation is not part of a data set collection involving data set stacking.
- The system cannot obtain a unit name from the primary DD statement in the unit affinity chain.

The installation must have assigned the name to the devices during system initialization, or IBM must have assigned the name.

The unit name can be a group name. A *group-name* can identify a single device or a group of devices. A group can consist of devices of the same or different types. For example, a group can contain both direct reel tape devices (3400) and cartridge tape devices (3480).

The system assigns any available device from the group. If a group consists of only one device, the system assigns that device. If the group consists of more than one device type, the units requested are allocated from the same device type. For example, if TAPEGRP contains both 3400

devices and 3480 devices, a request for two units would be allocated to two 3400s or to two 3480s.

If a data set that was created using the UNITAFF subparameter is to be extended, the system allocates additional devices of the same type as the original devices. However, the additional devices might not necessarily be from the same group.

If the name specified by UNITAFF does not exist in the eligible devices table (EDT), the system default is used instead and a warning message is issued.

**Note:** If the UNITAFF subparameter is not specified for any given system, make sure the device preference order is the same on all systems. In this case, a system-derived default is used, that is, the tape generic highest in the device preference table.

**Value range:** 1 to 8 alphanumeric characters.

**Default:** The tape generic that is highest in the device preference table. This generic must be available on every IODF used on the system between this IPL and the next IPL. If there is no tape generic that is highest in the device preference table (because there are no tape devices defined to the system), SYSALLDA is used as the default.

### REDIRECTED\_TAPE(TAPE | DASD)

Allows the installation to specify whether unopened batch-allocated DASD data sets that were redirected from tape should be treated as DASD or TAPE.

#### TAPE

Specifying REDIRECTED\_TAPE(TAPE) causes unopened batch allocated data sets that have been redirected from TAPE to DASD to be deleted during final disposition processing. These unopened redirected data sets are deleted regardless of the disposition requested.

#### DASD

Specifying REDIRECTED\_TAPE(DASD) causes unopened batch allocated data sets that have been redirected from TAPE to DASD to be processed according to the original disposition, as they would have been if they had been directed to DASD and not redirected to DASD from TAPE.

Dynamic allocation of SMS DASD data sets that were redirected from TAPE continues to be treated as DASD during dynamic allocation.

**Default:** TAPE

### TIOT

Specifies the installation defaults for the task I/O table (TIOT).

#### SIZE(tiot-size)

Specifies the size of the TIOT. The TIOT contains an entry for each DD statement. The size of the TIOT controls how many DDs are allowed per job step. By specifying an integer from 16 to 64 as the value of this parameter, the installation controls the default DD allowance. Table 14 on page 74 shows the relationship between the size of the TIOT and the maximum number of DDs allowed.

Table 14. Relationship size of TIOT and maximum number of DDs allowed

| Dec | Hex | Size of TIOT | Maximum number of DDs allowed whenever DD requests a single unit | Maximum number of DDs allowed when every DD requests the maximum number of units (59) |
|-----|-----|--------------|--|---|
| 16  | 10  | 16384 (16 K) | 816  | 64  |
| 17  | 11  | 17408 (17 K) | 867  | 68  |
| 24  | 18  | 24576 (24 K) | 1225   | 97  |
| 25  | 19  | 25600 (25 K) | 1277   | 101   |
| 32  | 20  | 32768 (32 K) | 1635   | 129   |
| 40  | 28  | 40960 (40 K) | 2045   | 162   |



Table 14. Relationship size of TIOT and maximum number of DDs allowed (continued)

| Dec | Hex | Size of TIOT | Maximum number of DDs allowed whenever DD requests a single unit | Maximum number of DDs allowed when every DD requests the maximum number of units (59) |
|-----|-----|--------------|--|---|
| 48  | 30  | 49152 (48 K) | 2454   | 194   |
| 56  | 38  | 57344 (56 K) | 2864   | 227   |
| 64  | 40  | 65536 (64 K) | 3273   | 259   |

**Notes:**

- For SMS-managed DASD data sets, each volume requires a unit. If the data set is associated with a data class that has a Dynamic Volume Count defined, the system must reserve space for each potential unit (volume) in the TIOT even if that data set has not expanded to that number of volumes. When calculating the TIOT space needed, you should use the larger of the actual volume count and the Dynamic Volume Count. For example, a data set on a single volume that is associated with a data class that defines the Dynamic Volume Count of 59 will require 252 bytes ('FC'x) of TIOT space.
- For a VSAM KSDS, the number of 4-byte entries in the TIOT for the data set depends on whether the data set is defined as reusable. The count of entries in the TIOT is the count of candidate volumes for the data and index components plus:
  - For a reusable data set, the number of volumes that are used by the data component plus the number of volumes that are used by the index component.
  - For a nonreusable data set, the number of volumes in the set of volumes that are used by the data and index component.
- Use the following to calculate the maximum number of DDs allowed per job step:
  - The TIOT Prefix, Header, and Trailer consume 60 ('3C'x) bytes of the total TIOT space available to a Job Step.
  - A DD statement requesting a single unit requires 20 bytes ('14'x) of TIOT space. The TIOT space requirement for entire step is 80 bytes.

```
//TAPEJOB  JOB
//STEP1    EXEC  PGM=IEFBR14
//DD1      DD    UNIT=3490    ** DD requires 20 bytes *
```

- A DD statement requesting two units require 24 bytes ('18'x) of TIOT space. Twenty bytes for the basic information for the first unit and an additional 4 bytes for the second unit. The TIOT space requirement for entire step is 84 bytes.

```
//TAPEJOB  JOB
//STEP1    EXEC  PGM=IEFBR14
//DD1      DD    UNIT=(3490,2) ** DD requires 24 bytes *
```

- A DD requesting the maximum number of units allowed, fifty nine (59), uses two hundred fifty two (252) bytes ('FC'x) of TIOT space. The TIOT space requirement for entire step is 312 bytes.

```
//TAPEJOB  JOB
//STEP1    EXEC  PGM=IEFBR14
//DD1      DD    UNIT=(3490,59) ** DD requires 252 bytes *
```

- A job step with three DD statements and each DD requesting one more unit than the previous DD would use the following TIOT space. The TIOT space requirement for entire step is 132 bytes.

```
//TAPEJOB  JOB
//STEP1    EXEC  PGM=IEFBR14
//DD1      DD    UNIT=3490    ** DD requires 20 bytes *
```

```
//DD2      DD      UNIT=(3490,2)  ** DD requires 24 bytes *
//DD3      DD      UNIT=(3490,3)  ** DD requires 28 bytes *
```

**Value range:** 16 - 64 kilobytes

**Default:** 32 kilobytes

## **SDSN\_WAIT**

Specifies the installation policy for batch jobs that must wait to enqueue on special types of data set names.

### **WAITALLOC([NO | YES])**

Specifies whether to cancel jobs that must wait to enqueue on the following types of data set names:

- GDG absolute generation data set name (unless the absolute generation data set name is specified on the JCL). See *z/OS MVS JCL Reference* for a discussion of how the system generates absolute generation names and how the system enqueues on absolute generation names when a relative generation name is specified.
- Real data set name (when its corresponding alias data set name is specified on the JCL).

#### **NO**

The system cancels the job, releases its resources, and issues message IEF211I.

#### **YES**

When YES is specified, and a batch job's enqueue request cannot be satisfied, the system issues messages IEF861I, IEF863I, and IEF458D. The job waits, holding any resources that it might have acquired. The system operator can choose to cancel the job in response to message IEF458D, or allow the job to continue waiting until the enqueue becomes available. If the operator cancels the job, the system writes an informational message (IEF330I) to the job log.

Use caution when specifying YES. Allowing jobs to wait for data set availability can cause deadlocks with other jobs in the system.

When you specify YES, the system does not allow the job to wait for a data set when both of the following conditions are true:

1. This job plus one (or more) other jobs have the data set allocated as DISP=SHR.
2. This job requests that its use of the data set be upgraded from DISP=SHR to DISP=OLD.  
The system ends this job and issues message IEF211I.

**Default:** NO

The WAITALLOC option only applies to batch allocation requests (that is, allocation requests specified in the job's JCL).

## **VOLUME\_ENQ**

Specifies the installation policy for enqueueing on volumes when an allocation request has to wait for a volume or a series of volumes.

### **POLICY([WTOR | CANCEL | WAIT])**

Specifies the default action to take. An installation exit can override the policy.

#### **WTOR**

The installation policy is to issue the message and let the operator make the decision about the allocation request. The system displays one of the following messages on the operator's console:

- IEF690I - The following volumes are unavailable to <jobname>...
- IEF235D - <jobname> is waiting for volumes. To cancel wait, reply no.

In addition, the system issues message IEF369D (invalid reply) in response to an invalid reply to IEF235D.

**CANCEL**

The installation policy is to cancel a job that needs an unavailable volume. The system cancels the job, releases its resources, and issues message IEF251I.

**WAIT**

The installation policy is to let a job that needs an unavailable volume wait until the volume is available.

**Caution:** When WAIT is used as the default, deadlocks with other jobs in the system might arise for tape volumes.

**Default:** WTOR

**VOLUME\_MNT**

Specifies the installation policy for mounting a volume when an allocation request requires a volume to be mounted. This policy applies when processing mount requests for single volumes or the first volume of a multi-volume request. This policy does not apply for tape mount requests that specify the DEFER subparameter on the UNIT parameter in JCL, or the corresponding dynamic allocation text units. This policy does not apply for tape mount requests for the second and subsequent volumes of a multi-volume request. This policy can be overridden by the IEF\_VOLUME\_MNT installation exit. Use the EOVS exit routine to handle second and subsequent volumes (see [z/OS DFSMS Installation Exits](#) for information).

**POLICY([WTOR | CANCEL])**

Specifies the default action to take. The IEF\_VOLUME\_MNT installation exit can override the policy.

**WTOR**

The installation policy is to issue the message and let the operator make the decision about the volume mount. The system displays one or more of the following messages on the operator's console:

- IEF233A (Mount volume <ser>.)
- IEF233D (Mount volume <ser> or respond to IEF455D message.)
- IEF455D (Mount <ser> on <device> for <jobname> or reply no.)
- IEF488I (Must wait for a unit, or volume on unit).

In addition, the system issues message IEF369D (invalid reply) in response to an invalid reply to IEF455D.

**CANCEL**

The installation policy is to cancel a job that needs a volume mounted. The system cancels the job, releases its resources, and issues message IEF251I.

**Default:** WTOR

**SPEC\_WAIT**

Specifies the installation policy to be followed when an allocation request must wait for a specific volume or unit.

When SPEC\_WAIT is specified, at least one of the optional subparameters must be specified.

**POLICY([WTOR | WAITHOLD | WAITNOH | CANCEL])**

Specifies the default action to take. An installation exit can override the policy.

**WTOR**

The installation policy is to issue the message and let the operator make the decision about the wait request. The system displays one or more of the following messages on the operator's console:

- IEF238D - Reply [device name] [,] ['wait'] or 'cancel'
- IEF244I - Unable to allocate <nnn> units. At least <nnn> allocated or offline units are needed.
- IEF433D - Wait requested. Reply hold or nohold.

- IEF488I - Must wait for a unit, or volume on unit.

In addition, the system issues one or more of the following messages in response to an invalid reply to the preceding messages.

- IEF434D - Invalid reply (to message IEF433D). Reply hold or nohold.
- IEF490I - Invalid reply (to message IEF238D) for one of the following reasons:
  - Device is not accessible. No paths are available, boxed, or cannot be assigned.
  - Required system-managed volume is not available.
  - Required volume is not available.
  - Replied device is not eligible.
  - Device is found in an offline library.
  - Coupling facility error.

### **WAITHOLD**

The installation policy is for the system to not release any of the devices that have already been allocated to this job before it waits for the required units or volumes. The system issues message IEF289E.

Using the WAITHOLD policy might cause a deadlock situation, particularly when the device is being used by a job that is going to wait. The system does not release any nonsharable devices (that is, non-DASD) that have already been allocated to the job before it waits for required units and volumes. To avoid this problem, do not specify WAITHOLD.

When devices for a job are held during a wait, and a device that was eligible for allocation to the job becomes ineligible for allocation (because of its use by a system utility, for example), the job might fail because it does not have enough devices to complete successfully. Message IEF700I in the job log identifies this failure. See message IEF700I for information about how to respond to this failure.

### **WAITNOH**

The installation policy is to let the job wait while not holding the obtained resources. The system releases those devices that were allocated to this job, but that cannot be shared with other jobs. The system issues message IEF289E.

For an example of the WAITHOLD versus WAITNOH options, consider that JOBA owns an automatically switchable device and is waiting for a printer. JOBB owns the printer JOBA needs and is waiting for the automatically switchable device JOBA owns.

- If the reply is WAITHOLD for each job, the two jobs wait until one job is canceled. This deadlock can be even more complex depending on the number of jobs that are waiting.
- If the reply is WAITNOH for each job, allocation responds on a first-come, first-served basis. After the first job finishes using a resource, it is available to the second.

### **CANCEL**

The installation policy is to cancel the allocation request. If a TSO/E user issued the allocation request, the user receives an error message. If a batch job or started task issued the request, the system cancels the job or task, releases its resources, and issues message IEF251I.

**Default:** WTOR

### **MAXNWAIT(number-of-waits)**

Specifies the number of WAITNOH decisions that are allowed to be made for the specific volume or unit allocation request before the default that is specified on the POLICYNW parameter takes effect. The WAITNOH decisions that are counted are those that are specified either through the default on the POLICY parameter or through the IEF\_SPEC\_WAIT installation exit. WAITNOH decisions that are made by the operator are not included in the MAXNWAIT count.

**Value range:** 1 - 255

**Default:** 5

**POLICYNW(WTOR | CANCEL)**

Specifies how the system should handle the allocation request under the following circumstances:

- Either WAITHOLD or WAITNOH is specified on the POLICY parameter and the system does not allow the job to wait for resources.
- The maximum number of "WAITNOH" decisions (specified on the MAXNWAIT parameter) was exceeded.

**WTOR**

Issues a write to operator with reply (WTOR) message. The system issues the messages listed earlier under WTOR.

**CANCEL**

Cancels the allocation request depending on how the request was issued. If a TSO/E user issued the allocation request, the user receives an error message. If a batch job or started task issued the request, the system cancels the job or task, releases its resources, and issues message IEF251I.

**Default:** WTOR

**ALLC\_OFFLN**

Specifies the installation policy to be followed when an allocation request needs a device that is offline, or must wait for a nonspecific volume or unit.

If all eligible devices are offline, they cannot be brought online without operator intervention. In this case, the system ignores the WAITHOLD and WAITNOH options and issues the WTOR immediately.

When ALLC\_OFFLN is specified, at least one of the optional subparameters must be specified.

**POLICY(WTOR | WAITHOLD | WAITNOH | CANCEL)**

Specifies the default action to take. An installation exit can override the policy.

**WTOR**

The installation policy is to issue the message and let the operator decide about the needed device. The system displays one or more of the following messages on the operator's console:

- IEF157E - <jobname> needs <nnn> units. All eligible units are currently allocated.
- IEF238D - Reply [device name] [,] ['wait'] or 'cancel'
- IEF244I - Unable to allocate <nnn> units. At least <nnn> allocated or offline units are needed.
- IEF433D - Wait requested. Reply hold or nohold.

In addition, the system issues one or more of the following messages in response to invalid replies to the preceding messages:

- IEF434D - Invalid reply (to message IEF433D). Reply hold or nohold.
- IEF490I - Invalid reply (to message IEF238D) for one of the following reasons:
  - Device is not accessible.
  - Required system-managed volume is not available.
  - Required volume is not available.
  - Replied device is not eligible.
  - Device might not be found in the configuration.
  - Device found in an offline library.

**WAITHOLD**

The installation policy is for the system to not release any of the devices that have already been allocated to this job before it waits for the required units or volumes. The system issues message IEF289E.

Using the WAITHOLD policy might cause a deadlock situation, particularly when the device is being used by a job that is going to wait. The system does not release any nonsharable devices

(that is, non-DASD) that have already been allocated to the job before it waits for required units and volumes. To avoid this problem, do not specify WAITHOLD.

When devices for a job are held during a wait, and a device that was eligible for allocation to the job becomes ineligible for allocation (because of its use by a system utility, for example), the job might fail because it does not have enough devices to complete successfully. Message IEF700I in the job log identifies this failure. See message IEF700I for information about how to respond to this failure.

### **WAITNOH**

The installation policy is to let the job wait while not holding the obtained resources. The system releases those devices that were allocated to this job, but that cannot be shared with other jobs. The system issues message IEF289E.

For an example of the WAITHOLD versus WAITNOH options, consider that JOBA owns an automatically switchable device and is waiting for a printer. JOBB owns the printer JOBA needs and is waiting for the automatically switchable device JOBA owns.

- If the reply is WAITHOLD for each job, the two jobs wait until one job is canceled. This deadlock can be even more complex depending on the number of jobs that are waiting.
- If the reply is WAITNOH for each job, allocation responds on a first-come, first-served basis. After the first job finishes using a resource, it is available to the second.

### **CANCEL**

The installation policy is to cancel the allocation request. If a TSO/E user issued the allocation request, the user receives an error message. If a batch job or started task issued the request, the system cancels the job or task, releases its resources, and issues message IEF251I.

**Default:** WTOR

### **MAXNWAIT(number-of-waits)**

Specifies the number of WAITNOH decisions that are allowed to be made for the allocation request before the default that is specified on the POLICYNW parameter takes effect. The WAITNOH decisions counted are those that are specified either through the default on the POLICY parameter or through an IEF\_ALLC\_OFFLN installation exit. WAITNOH decisions that are made by the operator are not included in the MAXNWAIT count.

**Value range:** 1 - 255

**Default:** 5

### **POLICYNW(WTOR | CANCEL)**

Specifies how the system should handle the allocation request under the following circumstances:

- Either WAITHOLD or WAITNOH is specified on the POLICY parameter and the system does not allow the job to wait for the needed device.
- The maximum number of WAITNOH decisions (specified on the MAXNWAIT parameter) has been exceeded.

The system is to either cancel the allocation request (CANCEL) or issue a WTOR. When WTOR is selected, the system issues the messages listed earlier under WTOR. When CANCEL is selected, the system cancels the allocation request depending on how the request was issued. If a TSO/E user issued the allocation request, the user receives an error message. If a batch job or started task issued the request, the system cancels the job or task, releases its resources, and issues message IEF251I.

**Default:** WTOR

### **CATLG\_ERR**

Specifies the installation policy for handling certain types of errors that might occur when the system processes the disposition of batch deallocated data sets (data sets that have been deallocated at step termination time). The CATLG\_ERR statement applies when the system is unable to:

- Catalog a new data set for which the user specified a disposition of CATLG.

- Catalog an old uncataloged data set for which the user specified a disposition of CATLG.
- Recatalog an old cataloged data set for which the volume list was extended, and for which the user specified a disposition of CATLG, KEEP or PASS.
- Roll an SMS-managed generation data set into the GDG base.

The CATLG\_ERR statement does not apply when the user deallocates a data set before step termination through the following methods:

- Dynamic deallocation (DYNALLOC macro)
- Having previously specified FREE=CLOSE on the allocation request (DYNALLOC macro or DD statement in the job's JCL).
- CATLG, UNCATLG, KEEP, PASS, or DELETE a new or old SMS-managed data set, including when the SMS subsystem is not available.
- CATLG, UNCATLG, KEEP, PASS, or DELETE a new or old VSAM data set, including when the SMS subsystem is not available.

The CATLG\_ERR statement does not apply when the user deallocates a data set before step termination through the following methods:

- Dynamic deallocation (DYNALLOC macro).
- Having previously specified FREE=CLOSE on the allocation request (DYNALLOC macro or DD statement in the job's JCL).

When CATLG\_ERR is specified at least one of the optional subparameters must be specified.

#### **ERRORMSG(NO | YES)**

Specifies whether the system is to issue an error message to the operator if one of the preceding errors occurs. When you specify ERRORMSG=YES, the system issues message IEF377I only if no other error messages were issued. If FAILJOB(YES) is also specified, the system terminates the job, releases its resources, and issues message IEF378I.

**Default:** NO

#### **FAILJOB(NO | YES)**

Specifies whether the system is to terminate the job if one of the preceding errors occurs. When a job is terminated by FAILJOB(YES), the termination is considered a post-execution error. Post-execution errors, which include but are not limited to FAILJOB(YES) terminations, are indicated by a 1 in the SMF30SYE bit in the SMF30STI field of the SMF30 subtype4 record.

#### **Notes:**

1. The setting of the condition code is not affected.
2. The job is not abnormally ended, unless the step that encountered the error had itself previously abnormally ended. Terminated means that subsequent steps are not taken.
3. The normal disposition for data sets is taken, unless the step that encountered the error had already abnormally ended, in which case the abnormal or conditional disposition is taken.

**Default:** NO

#### **2DGT\_EXPDT**

Identifies the action to be taken if a new data set allocation request specifies a two-digit year (*yyddd*) Expiration Date. Use one of the following options:

- EXPDT (Batch JCL two-digit year Expiration Date Keyword)
- DALEXPDT (Dynamic Allocation Expiration Date specification short form)

A two-digit year is always treated as 19yy (*yyddd*).

Dates of 00000, 98000, 99000, 99365, and 99366 are allowed regardless of the Policy in force.

**POLICY(ALLOW | WARN | FAIL)****ALLOW**

Allow the data set allocation with no Expiration Date related message.

**WARN**

Allow the data set allocation but issue a warning message. If a 2-digit year is specified on a JCL DD statement (EXPDT), warning message IEF428I is written to both the System Message and JCL Message portions of the job log. If the 2-digit year is specified on a Dynamic data set allocation (DALEXPDT), warning message IEF405I is written to the operator, and Dynamic code '0054'x is returned to the SVC 99 caller.

**FAIL**

Fail the data set allocation and issue a failure message. If a 2-digit year is specified on a JCL DD statement (EXPDT), failure message IEF429I is written to both the System Message and JCL Message portions of the job log. If the 2-digit year is specified on a Dynamic data set allocation (DALEXPDT), failure message IEF406I is written to the operator, and Dynamic Allocation Error Return Code '000C'x with Class 3 Reason Code '03B8'x is returned to the SVC 99 caller.

**Default:** POLICY(ALLOW).

**VERIFY\_VOL**

Specifies the installation policy for verifying premounted or PASSEd/RETAINED volumes on AutoSwitchable (AS) tape devices.

The OPEN, FEOV and CLOSE macros allow the specification of a positioning parameter, and that the LEAVE option of these macros is treated the same as RETAIN.

An AS Tape device that is connected, and possibly used, outside of this allocation's tape management scheme can be "stolen" for temporary use by allocation on a system outside this scheme and cause the volume status for the device to change, unbeknownst to this allocation's scheme. In this case, if the volume had been premounted, or is PASSEd/RETAINED, this allocation scheme might then be causing inadvertent read/write activity on a volume. This can result in data loss or data integrity exposures.

If, for a given DD statement, MVS allocation selects an AS tape device and the UCB for that device shows any currently mounted volume to be the required volume for that DD, the system can optionally cause volume verification to occur when an OPEN is performed for that DD.

This becomes a significant consideration if:

1. AS Tape devices within the scope of this allocation's tape management scheme are also connected to, and usable by, systems outside of that scheme.
2. Allocation on this system might encounter volumes that are premounted onto an AS tape device or PASSEd/RETAINED via JCL while mounted on an AS device.

Some examples of AS Tape devices that are connected outside the scope of allocation's tape management scheme include:

1. AS tape devices online to LPARs running other operating systems, such as Linux<sup>®</sup> on z Systems<sup>®</sup> or z/VM<sup>®</sup>.
2. AS tape devices online to at least one system in a sysplex and also online to one or more distinct, stand-alone systems.
3. AS tape devices online to systems in two or more distinct sysplexes.

**POLICY(YES | NO)**

Specifies whether the system is to perform volume verification of an apparently premounted or PASSEd/RETAINED AS tape device at open time.

**YES**

Volume verification is to be done by OPEN for Standard, ISO/ANSI Version 1, or ISO/ANSI/FIPS Version 3 labeled tape volumes that are premounted or PASSEd/RETAINED on an AS tape device. Both volume serial and tape position are verified.



**NO**

No specific volume verification is to be done by OPEN on premounted or PASSEd/RETAINED volumes on an AS tape device. Only select this policy option if it is certain there is no exposure to the "stolen" AS device for premounted or PASSEd/RETAINED volumes as described in the previous scenarios. For example, specify POLICY(NO) if all systems within a sysplex are z/OS V1R2 or later, and tape devices that are defined as AS to systems within that sysplex are not shared with any systems, or sysplexes, outside of that sysplex.

**Default:** YES

**SYSTEM**

Specifies the system defaults.

When SYSTEM is specified at least one of the optional subparameters must be specified.

**IEFBR14\_DELMIGDS(LEGACY | NORECALL)**

Specifies the policy on whether to recall a migrated data set when you use an IEFBR14 JCL program with DD DISP=(x,DELETE) to delete the data set. The recall is, in most cases, unnecessary, as the data set is being deleted anyway.

**LEGACY**

Indicates that the system is to recall HSM-migrated data sets before deletion.

**NORECALL**

Indicates that the system can delete (through HSM HDELETE processing) the data set without first recalling the data set to the primary storage.

**Default:** LEGACY

**TAPELIB\_PREF(BYDEVICES | EQUAL)**

Specifies the policy for balancing nonspecific tape library requests (for example, scratch tape requests) across multiple tape libraries.

**BYDEVICES**

Indicates that nonspecific tape library requests must be balanced across all tape libraries according to the number of online and deallocated tape devices in the tape library. Tape libraries with more online tape devices receive more nonspecific tape requests than libraries with fewer online devices when all devices have the same attributes.

This setting is useful when there are multiple tape libraries with different numbers of online tape devices. A tape library with, for example, 512 online tape devices would be able to handle more requests than a tape library with only 16 online tape devices. This setting allows MVS Device Allocation to better balance the requests across dissimilar libraries.

It is recommended that you use the BYDEVICES option when using the system-managed tape libraries.

**EQUAL**

Indicates that for nonspecific tape library requests, all tape libraries must be treated as equal, and receive an equal share of the requests.

**Default:** BYDEVICES

**REMIND\_INTV(interval)**

Specifies the number of seconds for how often the message IEF882E and IEF883E are displayed, letting an operator know of an outstanding IEF238D, IEF433D, or IEF434D message. This interval indicates how many seconds between reminder messages, or 0 to disable them.

**Value range:** 0 or 10-999

**Default:** 90

**TEMPDSFORMAT(INCLUDELABEL | UNIQUE)**

Specifies how the system generates data set names for temporary data sets that include &&label as the specified data set name. This statement affects only the data sets that specify DSN=&&mysdsn, but not the data sets that do not specify DSNAME at all.

**INCLUDELABEL**

Indicates that when the system processes JCL that includes temporary data sets with DSN=&&LABEL, the generated data set name includes the &&label specified in the JCL. See [z/OS MVS JCL Reference](#) for more information.

**Note:** When this parameter is specified and the Job Entry Subsystem (JES) allows multiple jobs with the same job name to execute at the same time, jobs with the same name, executing simultaneously, might fail with a duplicate data set name error.

**UNIQUE**

Indicates that when the system processes JCL that includes temporary data sets with DSN=&&LABEL, the generated data set name is in the form SYSyyddd.Thhmmss.RA000.jjobname.Rggnnnnn, which does not include the &&label that is specified in the JCL. All references to &&mysdn throughout the JCL correctly refer to the same data set. Using TEMPDSFORMAT=UNIQUE ensures that jobs with the same job name running simultaneously do not create temporary data sets with the same names. See [z/OS MVS JCL Reference](#) for more information.

**Default:** INCLUDELABEL

**VERIFY\_UNCAT(FAIL | TRACK | MSGTRACK | LOGTRACK)**

Specifies the policy for handling UNCATLG requests in JCL and dynamic allocation when the data set information is not retrieved from the catalog.

**FAIL**

Fails the request. This option prevents a job from accidentally uncataloging a cataloged data set with the same name as the data set that is allocated.

**TRACK**

Allows the data set to be uncataloged, and tracks the request in the tracking facility. Specifying this option allows a job to uncatalog a cataloged data set with the same name as the data set that is allocated. This option is provided as a migration option to assist the installation in finding and correcting the existing JCL that might have been uncataloging data sets incorrectly.

**Note:** This option is provided for migration purposes. It might be removed from the system in the future.

The tracking facility must be active for UNCATLG requests to be tracked. Whenever a job attempts to uncatalog a data set for which the data set information is not retrieved from the catalog, the job is tracked with the Tracking information containing the string IEFALC 01, followed by the step name and the DD name.

- For batch allocated DDs, the program name contains IEFIIC.
- For dynamically allocated DDs, the program name is the offending program if it can be determined, or SVC-099 if it cannot be determined.
- The VALUE field is unused, and contains zeros.

Instances of the IEFALC 01 event should be corrected by the installation rather than reported to IBM. For more information about the tracking facility, see [z/OS MVS Planning: Operations](#).

**MSGTRACK**

Allows the data set to be uncataloged, tracks the request in the tracking facility, and issues a message. Specifying this option allows a job to uncatalog a cataloged data set with the same name as the data set that is allocated. This option is provided as a migration option to assist the installation in finding and correcting the existing JCL that might have been uncataloging data sets incorrectly.

**Note:** This option is provided for migration purposes. It might be removed from the system in the future.

The tracking facility must be active for UNCATLG requests to be tracked. When a job attempts to uncatalog a data set for which the data set information is not retrieved from the catalog, the

job is tracked with the Tracking information containing the string IEFALC 01, followed by the step name and the DD name.

- For batch allocated DDs, the program name contains IEFIIC.
- For dynamically allocated DDs, the program name is the offending program if it can be determined, or SVC-099 if it cannot be determined.
- The VALUE field is unused, and contains zeros.

Instances of the IEFALC 01 event should be corrected by the installation, rather than reported to IBM. For more information about the tracking facility, see [z/OS MVS Planning: Operations](#).

In addition to tracking the event, message IEF384I indicates that the data set is uncataloged, but the volume information is not retrieved from the catalog. This message informs the submitter of the job that the JCL should be corrected. For details, see [z/OS MVS System Messages, Vol 8 \(IEF-IGD\)](#).

## LOGTRACK

Allows the data set to be uncataloged, tracks the request in the tracking facility, and issues a message. Specifying this option allows a job to uncatalog a cataloged data set with the same name as the data set that is allocated. This option is provided for migration purposes to assist you in finding and correcting the existing JCL that might have been uncataloging data sets incorrectly. It might be removed from the system in the future.

The tracking facility must be active for UNCATLG requests to be tracked. When a job attempts to uncatalog a data set for which the data set information is not retrieved from the catalog, the job is tracked with the Tracking information containing the string IEFALC 01, followed by the step name and the DD name.

- For batch allocated DDs, the program name contains IEFIIC.
- For dynamically allocated DDs, the program name is the offending program if it can be determined, or SVC-099 if it cannot be determined.
- The VALUE field is unused, and contains zeros.

Instances of the IEFALC 01 event should be corrected by the installation, rather than reported to IBM. For more information about the tracking facility, see [z/OS MVS Planning: Operations](#).

In addition to tracking the event, message IEF384I indicates that the data set is uncataloged, but the volume information is not retrieved from the catalog. This message informs the submitter of the job that the JCL should be corrected. For more information, see [z/OS MVS System Messages, Vol 8 \(IEF-IGD\)](#).

**Default:** FAIL

## MEMDSENQMGMT(DISABLE | ENABLE)

Specifies whether the MEMDSENQMGMT feature is available for exploitation by jobs and subsystems.

### DISABLE

Disables jobs and subsystems from using memory-based data set ENQ management for dynamically allocated data sets.

### ENABLE

Allows jobs and subsystems to use memory-based data set ENQ management for dynamically allocated data sets. Memory-based data set ENQ management is faster than the other option, SWA-based data set ENQ management, for jobs that allocate many data sets. In addition to the parmlib setting, a job or subsystem that is to use the new management system must enable the feature by using the IEFDDSRV service (for example, IEFDDSRV MODIFY TYPE=FEATURE, DSENQMGMT=MEMORY). Note that this feature makes the job or subsystem nonrestartable through the checkpoint/restart interface.

**Default:** DISABLE

### **BATCH\_RCLMIGDS(SERIAL | PARALLEL)**

Specifies how migrated data sets are recalled.

#### **SERIAL**

The system allows the CATALOG LOCATE function to recall data sets on its behalf, resulting in serial recall processing.

#### **PARALLEL**

The system notes which data sets are migrated and recalls them in parallel. Using this option might reduce job execution time.

**Default:** SERIAL

### **OPTCDB\_SPLIT(EXPLICIT | CATALOG)**

Specifies how Allocation should process requests for data sets whose volumes reside in one or more system-managed tape libraries when DCB=OPTCD=B is specified. See the description of OPTCD=B in *z/OS MVS JCL Reference* and Data sets that span libraries in *z/OS MVS JCL User's Guide* for additional information about using DCB=OPTCD=B.

#### **EXPLICIT**

Indicates that when OPTCD=B is specified for a multi-volume tape data set in one or more system-managed tape libraries, the data set is eligible to be allocated as a concatenation of individual volumes when volume serial numbers are explicitly specified on the request. Requests where the volume information is retrieved from the catalog are not eligible to be allocated as a concatenation.

#### **CATALOG**

Indicates that when OPTCD=B is specified for a multi-volume tape data set in one or more system-managed tape libraries, the data set is eligible to be allocated as a concatenation of individual volumes when volume serial numbers are explicitly specified on the request or when the volume information is retrieved from the catalog.

**Default:** EXPLICIT

### **SWBSTORAGE(SWA | ATB)**

Defines whether Scheduler Work Blocks (SWBs) for dynamically allocated data sets are eligible to be placed in 64-bit storage.

#### **SWA**

Indicates that SWBs will be created in 24 or 31 bit storage, according to the SWA definition in use by the job.

#### **ATB**

Indicates that SWBs are eligible to be created in 64 bit storage. Programs must indicate that they support SWBs in 64-bit storage by enabling the IEFDDSRV feature SWBSTORAGE=ATB.

**Default:** SWA

---

## Chapter 5. ANTMIN00 (ANTMAIN control parameters)

Use the ANTMIN00 member to specify ANTMAIN control parameters. ANTMAIN is the DFSMS concurrent copy address space. For more information, see the documentation on the [ANTMIN00 parmlib](#) in [z/OS DFSMS Advanced Copy Services](#).



---

## Chapter 6. ANTXIN00 (XRC services)

Use the ANTXIN00 member to tailor DFSMS extended remote copy (XRC) services. XRC services provide backup and recovery of data if a disaster occurs to your data center. For more information, see the documentation on the [ANTXIN00 parmlib parameters](#) in *z/OS DFSMS Advanced Copy Services*.





## Chapter 7. APPCPMxx (define APPC/MVS configuration)

The APPCPMxx parmlib member contains a combination of statement types that define or modify the APPC/MVS configuration. These statements define APPC/MVS local LUs, indicate whether they are associated with a transaction scheduler, and name their associated administrative VSAM files. For more information about using APPC, see [z/OS MVS Planning: APPC/MVS Management](#).

An installation can control its APPC/MVS configuration with different versions of the APPCPMxx parmlib member. One member might contain startup values while other members contain customized values.

To initialize the APPC address space and set up the APPC/MVS configuration, specify APPCPMxx with a START APPC command. To modify the APPC/MVS configuration after initialization, specify APPCPMxx with the SET APPC operator command, or use the SETAPPC command to modify the configuration without using parmlib. See [z/OS MVS System Commands](#) for further information regarding the usage of this command.

You can specify more than one APPCPMxx parmlib member on a START or a SET APPC command. If you specify more than one member on the START or SET command, APPC processes the statements in the order specified and creates a cumulative configuration. If you specify one or more members that do not exist, APPC/MVS issues an informational message. For more information about the START and SET commands, see [z/OS MVS System Commands](#).

If you do not specify a parmlib member with the START command, the system searches for an APPCPM00 member, by default. If APPCPM00 does not exist, APPC/MVS issues an informational message.

### Changing values

An installation can change configuration values established by an APPCPMxx parmlib member by creating another APPCPMxx parmlib member containing LUDEL statements that delete previous statements, or the parmlib member can contain LUADD and SIDEINFO statements with new parameter values to modify previous statements. Examples of parmlib members used to delete and modify configurations are in [z/OS MVS Planning: APPC/MVS Management](#).

**Note:** When modifying previous statements, the parmlib statements have a cumulative effect, and any one parmlib member might not reflect the current configuration.

In addition to the SET APPC command, the SETAPPC command allows the installation to perform the same functions, but without having to update the APPC parmlib member. See [z/OS MVS System Commands](#) for further information.

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Syntax rules for APPCPMxx

- Use column 1 through 71. Do not use columns 72-80, because the system ignores these columns.
- Comments may appear in columns 1-71 and must begin with /\* and end with \*/.
- A statement must begin with a valid statement name followed by at least one blank.
- A statement ends with the beginning of the next valid statement name or End Of File (EOF).
- A statement can be continued even though there is no explicit continuation character.
- A statement contains only uppercase characters. Lower case is not accepted.
- Multiple occurrences of a statement are accepted.

- Keywords must be separated by valid delimiters. Valid delimiters are a comma, a blank, or column 71.
- Multiple occurrences of a delimiter are accepted but treated as one.
- Keyword values must be set off by parenthesis.
- Do not use blanks, commas, or comments in the middle of a parameter, between the parameter and the left parenthesis before the value, or in the middle of a value.

## Syntax format of APPCPMxx

```

LUADD      ACBNAME (luname)
           [SCHED(schedname )|NOSCHED]
           [BASE ]
           [PSTIMER(value) ]
           [TPDATA(dsname) ]
           [TPLEVEL{(SYSTEM)} ]
           [          {(GROUP)} ]
           [          {(USER)} ]
           [ALTLU  {(scheduler-supplied value)} ]
           [USERVAR{(scheduler-supplied value)} ]
           [GRNAME{(genericname)} ]
           [NQN | NONQN]

LUDEL      ACBNAME {(luname)}
           {PERSIST | NOPERSIST }

SIDEINFO   DATASET(dsname)

```

## IBM-supplied default for APPCPMxx

There is no default APPCPMxx parmlib member supplied by IBM. A sample parmlib member, APPCPMXX, is provided in SYS1.SAMPLIB.

## Statements and parameters for APPCPMxx

### LUADD

The LUADD statement defines a local APPC/MVS LU that is to be added to the APPC configuration. The LUADD statement contains:

- The LU name
- An indication of whether the LU is associated with a transaction scheduler
- The name of the transaction scheduler, if one is to be associated with this LU
- The amount of time the LU's sessions will persist in the event the LU becomes unavailable
- The TP profile file that is associated with the LU
- The level of TP profile from which the LU starts to search
- Optional values to be passed to an alternative transaction scheduler, or to any other member of the APPC XCF group, such as an APPC/MVS server
- A VTAM generic resource name to associate with the LU
- An indication of whether the LU is enabled to support network-qualified names for its partner LUs.

Each LU managed by APPC/MVS must be defined with an LUADD statement.

When an installation uses the ASCH transaction scheduler exclusively, only one LU is required. If other transaction schedulers are used, each scheduler requires a separate LU. An installation might choose to define more LUs to isolate TPs for security or testing.

An installation can also define LUs that are not associated with transaction schedulers. These LUs handle work that is processed by APPC/MVS servers, rather than scheduled by a transaction scheduler. Such LUs are indicated by coding the NOSCHED keyword on LUADD. Installations can also use NOSCHED LUs when they want to flow outbound allocate requests without having a transaction

scheduler active. (APPC/MVS servers can also run under LUs that are associated with transaction schedulers.)

You can modify an LU by overriding a previous LUADD statement with another LUADD statement that names the existing LU and changes the parameters to be modified. The only parameters that you cannot modify with an overriding LUADD are the SCHED, NOSCHED, ALTLU, USERVAR, GRNAME, NQN, and NONQN parameters. To change these parameters, you must first delete the LU with an LUDEL statement and then reidentify the LU with a new LUADD that changes the parameters.

The following example defines LU MVSLU01 to be associated with the transaction scheduler provided with APPC/MVS.

```
LUADD
  ACBNAME (MVSLU01)
  SCHED (ASCH)
  TPDATA (SYS1.APPCTP)
  TPLEVEL (USER)
```

### **ALTLU(scheduler-supplied value)**

This parameter allows optional, installation-supplied data to be passed to a member of the APPC XCF group, such as an alternative transaction scheduler or an APPC/MVS server. If specified, the data is passed to the APPC XCF group member at the activation and deactivation of the associated LU. For information about the APPC XCF group, see *z/OS MVS System Messages, Vol 3 (ASB-BPX)*.

**Value range:** A one- to eight-byte character string of uppercase letters A through Z, numerics 0-9, or national characters (@, \$, #), with the exception that the first character cannot be numeric (0-9).

**Default:** None.

### **BASE**

An optional parameter that designates the LU as the base LU. Base LUs are default LUs assigned to handle outbound work. A base LU can be the default LU associated with a particular transaction scheduler or a NOSCHED LU.

When a NOSCHED LU is defined with the BASE option, the LU becomes the system base LU. That means the LU is to be the default LU used for outbound allocate requests from MVS programs, such as batch jobs, TSO/E users, started tasks, and other work requests that attempt to enter the network without being associated with a scheduler or an LU.

The following example defines a NOSCHED LU, MVSLU02, to be the system base LU.

```
LUADD
  ACBNAME (MVSLU02)
  NOSCHED
  BASE
  TPDATA (SYS1.APPCTEST)
  TPLEVEL (SYSTEM)
```

If you do not define a NOSCHED LU as a base LU, the base LU defined for the APPC/MVS transaction scheduler (ASCH) becomes the system base LU. If no system base LU exists, APPC/MVS rejects conversations that are allocated by MVS programs that are not associated with a scheduler or an LU.

**Note:** Define one LU per transaction scheduler as the base LU for the scheduler. In addition, define a NOSCHED LU as the system base LU if you want to allow outbound requests from the system when no transaction schedulers are active.

When more than one LU is defined as the base LU, the one most recently defined is the base.

### **GRNAME(genericname)**

This optional parameter specifies a VTAM generic resource name to be associated with the LU. The LU can be one of multiple LUs in the same generic resource group, represented by *genericname*. This parameter cannot be dynamically modified or added to an existing LU definition.

See *z/OS MVS Planning: APPC/MVS Management* for advice and restrictions about selecting a generic resource name, and deciding which LUs should become members of a generic resource group.

**Value range:** A one- to eight-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@, \$, #) and must begin with an alphabetic or national character.

**Default:** None. If the GRNAME parameter is not specified, the LU is activated but is not part of a generic resource group.

## NQN

### NONQN

An optional parameter that specifies whether the APPC/MVS LU is enabled to use a network-qualified partner LU name when first allocating outbound conversations. If you specify NQN, APPC/MVS uses the 17-byte network-qualified LU name when verifying the partner LU and sending the outbound Allocate request to the partner LU. If you specify NONQN (or allow the system to use the default), APPC/MVS uses the entire name when verifying the partner, but only the 8-byte network-LU-name portion when sending the outbound Allocate request.

See *z/OS MVS Planning: APPC/MVS Management* for the requirements for enabling APPC/MVS LUs to support network-qualified names.

**Default:** NONQN

### PSTIMER(value)

An optional parameter that sets the maximum amount of time for which the LU's sessions persist (are maintained) during interruptions in APPC/MVS or a transaction scheduler's service.

When you specify a valid value other than NONE, the LU's sessions persist when the APPC address space is canceled, forced, terminated, or automatically restarted. The sessions also persist during interruptions in scheduler service. Any conversations that were active at the time of the interruption are lost. When APPC service is resumed, the conversation partners can re-establish these conversations, if desired.

Sessions do not persist if the LU is deleted.

**Value range:**

- 0 or INDEFINITE (Sessions persist indefinitely)
- 1 - 86400 (Number of seconds the sessions can persist)
- NONE (Sessions are not to persist)

**Default:** NONE

### SCHED(ASCH|schedname)

#### NOSCHED

An optional parameter that indicates whether the LU is to be associated with a transaction scheduler. LUs associated with a transaction scheduler cannot become active until that scheduler identifies itself to APPC/MVS. LUs not associated with a transaction scheduler become active as soon as APPC/MVS becomes active.

SCHED indicates that the LU is associated with a transaction scheduler. *schedname* must match the name the transaction scheduler specifies when it calls the Identify service. For more information about the Identify service and its scheduler\_name parameter, see *z/OS MVS System Messages, Vol 3 (ASB-BPX)*.

NOSCHED indicates that the LU is not to be associated with a scheduler. When NOSCHED is specified, the LU becomes active as soon as APPC/MVS becomes active. Installations can use NOSCHED LUs to isolate work from schedulers when the work is to be processed by APPC/MVS servers. Installations can also use NOSCHED LUs to flow outbound allocate requests without having a transaction scheduler active.

For *schedname*, the value is a one- to eight-byte character string and each character must be an uppercase letter (A-Z) or a numeral (0-9).

**Note:** SCHED and NOSCHED are mutually exclusive keywords; you cannot specify both SCHED and NOSCHED in a single LUADD statement. Doing so causes the system to ignore the statement and issue message ATB041I to the system operator.

When you omit both SCHED(schedname) and NOSCHED, the default is SCHED(ASCH).

### **TPDATA(dsname)**

n optional parameter that specifies the name of the VSAM key-sequenced data set that contains TP profiles, along with an optional database token for the LU. The database token is used for verifying access authority to TP profiles. If this LU is a NOSCHED LU, APPC/MVS uses only the data set's database token, if any. The data set specified on TPDATA must be cataloged in either a user catalog or the master catalog.

**Value range:** Up to 44 characters in length consisting of one- to eight-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@,\$,#) and must begin with an alphabetic or national character.

**Default:** SYS1.APPCTP

### **TPLEVEL({SYSTEM|GROUP|USER})**

An optional parameter that identifies the level of TP profiles for which the LU searches in response to an inbound allocate request. TPLEVEL limits the search to the levels desired.

Each TP can have different levels of TP profiles with scheduling characteristics associated with a user, a group of users, or all users (system). The TPLEVEL parameter tells the LU which of those levels of TP profile to search.

**Value range:** The value range is as follows:

SYSTEM means that the LU searches for system-level TP profiles only (not for a specific user or group of users).

GROUP means that the LU searches for TP profiles that are associated with a specific group of users and system-level TP profiles, in that order.

USER means that the LU searches for TP profiles that are associated with a specific user, a group of users, and system-level TP profiles, in that order.

If you specify NOSCHED, TPLEVEL must be SYSTEM. Also, TP profile entries in the data set specified in TPDATA are not used for NOSCHED LUs. Only the database token is used.

**Default:** SYSTEM

### **USERVAR(scheduler-supplied value)**

This parameter allows optional, installation-supplied data to be passed to a member of the APPC XCF group, such as an alternative transaction scheduler or an APPC/MVS server.

If specified, the data is passed to the APPC XCF group member at the activation and deactivation of the associated LU. For information about the APPC XCF group, see [\*z/OS MVS System Messages, Vol 3 \(ASB-BPX\)\*](#).

**Value range:** A one- to eight-byte character string of uppercase letters A through Z, numerics 0-9, or national characters (@, \$, #), with the exception that the first character cannot be numeric (0-9).

**Default:** None.

### **LUDEL**

The LUDEL statement deletes a local APPC/MVS LU from the APPC configuration. One LUDEL statement must be specified for each LU to be deleted. The LUDEL statement contains:

- The LU name
- An indication of whether APPC/MVS should keep all persistent sessions active between this LU and all of its partners

When an LUDEL statement is processed, incoming allocation requests to the named LU are rejected; however, all active conversations are allowed to continue until completed. The LU is removed only after all active conversations have ended.

### **ACBNAME(luname)**

The required name of the LU that APPC/MVS is to remove. If this LU was defined to VTAM, its association with VTAM is terminated after active conversations end.

**Value range:** A one- to eight-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@,\$,#) and must begin with an alphabetic or national character.

**Default:** None. This parameter is required.

#### **PERSIST | NOPERSIST**

An optional parameter that specifies whether APPC/MVS deactivates all sessions between this LU and its partners when the LU is deleted. If you specify PERSIST, and if the LU was previously enabled to support persistent sessions with the PSTIMER keyword on the LUADD statement, APPC/MVS does not deactivate sessions between the LU and its partners. VTAM keeps these sessions active as long as the LU is readed to the APPC configuration on the same z/OS image within the PSTIMER time limit (single-node persistent sessions) or in any z/OS image in the sysplex within the PSTIMER time limit (multi-node persistent sessions). See *z/OS MVS Planning: APPC/MVS Management* for further information. If you specify NOPERSIST (or allow the system to use the default), APPC/MVS deactivates all sessions between this LU and its partners when the LU is deleted.

**Default:** NOPERSIST

#### **SIDEINFO**

The SIDEINFO statement names the VSAM key sequenced data set that contains side information. Only one side information file is allowed per MVS system.

#### **DATASET(dsname)**

An optional parameter that specifies the name of the VSAM key sequenced data set that contains side information. The file must be cataloged in either a user catalog or the master catalog.

**Value range:** Up to 44 characters in length consisting of one- to eight-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@,\$,#) and must begin with an alphabetic or national character.

**Default:** SYS1.APPCSI

## **Response to errors in APPCPMxx**

---

If a syntax error is found in an APPCPMxx parmlib member, a message is sent to the originating console and the statement(s) in error are rejected. All syntactically valid statements are processed normally.

When such an error is reported, the system programmer should create a parmlib member containing corrected statements and retry the operation.

## Chapter 8. ASCHPMxx (APPC/MVS transaction scheduler)

The ASCHPMxx parmlib member contains scheduling information for the ASCH transaction scheduler. The statements define classes of transaction initiators and provide default scheduling information when it is missing from a TP profile.

For more information about using APPC, see [z/OS MVS Planning: APPC/MVS Management](#).

An installation can control scheduling characteristics with different versions of the ASCHPMxx parmlib member. One member might contain startup values and other members contain customized values.

To start the ASCH address space and set up classes and defaults for the ASCH transaction scheduler, specify ASCHPMxx with a START ASCH command. To modify classes and defaults after initialization, specify ASCHPMxx with the SET ASCH operator command. More than one ASCHPMxx parmlib member can be specified on a START or a SET ASCH command. If you specify more than one member on the START or SET command, APPC processes the statements in the order specified and creates a cumulative configuration. For more information about the START and SET commands, see [z/OS MVS System Commands](#).

If you do not specify a parmlib member with the START command, the system uses the default member, ASCHPM00. If ASCHPM00 does not exist, APPC/MVS issues an informational message.

### Changing values

An installation can change scheduling information established by an ASCHPMxx parmlib member by creating another ASCHPMxx parmlib member containing CLASSDEL statements that delete previous statements, or the parmlib member can reissue statements with new parameter values to modify previous statements.

Examples of deleting and modifying statements are in [z/OS MVS Planning: APPC/MVS Management](#).



**Attention:** When modifying previous statements, the parmlib statements have a cumulative effect, and any one parmlib member might not contain the current scheduling characteristics.

### Default values

When parmlib statements are initially specified, omitted parameters receive default values. When, however, parmlib statements are respecified, omitted parameters in the CLASSADD statement assume the defaults, but omitted parameters on the OPTIONS and TPDEFAULT statements do not assume the defaults.

For example, in the CLASSADD statement, the MAX parameter has a default value of 1. When you initially define a class with the START ASCH command and omit MAX, the class defaults to the maximum of 1 initiator. If, however, you initially set MAX to 10, when the class is modified with a SET ASCH command and MAX is not specified, the maximum of 10 is overridden with the maximum of 1 default.

### Support for system symbols

You can specify static symbolics in ASCHPMxx. For information about how to use static symbolics, see Chapter 2, “Sharing parmlib definitions,” on page 31.

### Parameter in IEASYSxx (or supplied by the operator)

None



## Syntax rules for ASCHPMxx

- Use column 1 through 71. Do not use columns 72-80, because the system ignores these columns.
- Comments may appear in columns 1-71 and must begin with "/\*" and end with "\*/".
- A statement type consists of 1-10 characters.
- A statement must begin with a valid statement type followed by at least one blank.
- A statement ends with the beginning of the next valid statement type or End Of File (EOF).
- A statement can be continued even though there is no explicit continuation character.
- Multiple occurrences of a statement type are accepted.
- A statement contains only uppercase characters. Lower case is not accepted.
- Operands must be separated by valid delimiters. Valid delimiters are a comma, a blank, or column 71.
- Multiple occurrences of a delimiter are accepted but treated as one.
- Keyword values must be set off by parenthesis.
- Do not use blanks, commas, or comments in the middle of a parameter, between the parameter and the left parenthesis before the value, or in the middle of a value.

## Syntax format of ASCHPMxx

```

CLASSADD  CLASSNAME(classname)
          [MAX(nnnnn)
          [MIN(nnnnn)
          [RESPGOAL(nnnnnnnn)]
          [MSGLIMIT(nnnnn) ]

CLASSDEL  CLASSNAME(classname)
          WORKQ      {(PURGE|DRAIN)}

OPTIONS   DEFAULT(classname)
          SUBSYS(ssname)

TPDEFAULT REGION      {(nnnnK)}
          {(nnnnM)}

          TIME        {(NOLIMIT)}
          {(minutes,seconds)}

          MSGLEVEL(1,n)
          OUTCLASS(n)

```

## IBM-supplied default for ASCHPMxx

There is no default ASCHPMxx parmlib member. A sample parmlib member, ASCHPMxx, is provided in SYS1.SAMPLIB.

## Statements and parameters for ASCHPMxx

### CLASSADD

The CLASSADD statement identifies a class of transaction initiators to the APPC/MVS transaction scheduler configuration. The CLASSADD contains the class name, the maximum and minimum number of transaction initiators to assign to the class, the response time goal, and the message limit. Each class for the APPC transaction scheduler must be defined with a CLASSADD statement.

At least one class definition is required for work that is assigned to the APPC/MVS transaction scheduler. If work comes in for a class that is not defined by a CLASSADD statement, the work is rejected.

You can modify a class by overriding a previous CLASSADD statement with another CLASSADD statement that names the existing class and changes the parameter values to be modified. When



more than one CLASSADD statement exists for the same class, the most recently processed statement is in effect.

### **CLASSNAME(classname)**

A required parameter that specifies the name of a class of transaction initiators. When a class name is specified in a TP profile, the APPC/MVS transaction scheduler assigns the TP to run in that class. If no class name is specified in a TP profile, the default class from the OPTIONS statement is used. If the class in the TP profile does not match any class name that is specified on a CLASSNAME statement and there is no default class, the TP cannot run.

SRM uses the class of transaction initiators as one of the items to determine dispatching priority.

**Value range:** A 1- to 8-byte character string of uppercase letters A through Z, numerals 0-9, and national characters (@, \$, #). The range must begin with an alphabetic or national character.

**Default:** None

### **MAX(nnnnn)**

An optional parameter that specifies the maximum number of transaction initiators that are allowed for a particular class of transaction initiators. After this limit is reached, no new address spaces are created and incoming requests are queued to wait until existing initiator address spaces become available. The value must exceed the maximum number of address spaces that are allowed by your installation. Be aware of competing products on the system that will also require address spaces.

If this value is too high, system resources that might be needed elsewhere are not available. If this value is set too low, transaction programs will wait on the queue until an existing initiator becomes available, jeopardizing the response time goal for the class. To optimize performance while still meeting resource goals, specify a value that is a percentage of the total number of possible transactions that are running in the class at a time. You can determine the exact percentage after considering the number of transaction initiators available for all the classes, and experimenting with various values until one meets performance requirements.

**Value range:** 1 - 64000

**Default:** 1

### **MIN(nnnnn)**

An optional parameter that specifies the minimum number of transaction initiators that are brought up for a particular class of transaction initiators when the ASCH address space starts or changes dynamically with a SET command. If the MIN value exceeds the MAX value, the MIN value is set to the MAX value. The number of transaction initiators available in each class never goes below the MIN number. In setting this value, consider the type of transaction programs that will run in this class. You might want certain classes to have initiators that are always available, while others classes require fewer initiators.

If this value is set too high, system resources that might be needed elsewhere are left idle. If this value is too small, the scheduler might waste time and resources when creating and deleting transaction initiators. To optimize performance while still meeting resource goals, specify a value that is a percentage of the total number of possible transactions that are running in the class at a time. You can determine the exact percentage after considering the number of transaction initiators available for all the classes, and experimenting with various values until one meets performance requirements.

**Value range:** 0 - 64000

**Default:** 0

### **MSGLIMIT(nnnnn)**

An optional parameter that, for all transaction programs running within the class, specifies the maximum number of messages that are written to the message log each time the transaction program runs. For more information about selecting an MSGLIMIT value, see the topic about logging transaction program processing in [\*z/OS MVS Planning: APPC/MVS Management\*](#).

**Value range:** 1-15000 messages

**Default:** 500 messages

### **RESPGOAL(nnnnnnnn)**

An optional parameter that specifies the response time goal for transaction programs that are executing within this class. The RESPGOAL value is the total time in seconds that an installation wants to allow for queuing and running a transaction in this class. To meet this goal, APPC/MVS can create additional transaction initiators for the class until the MAX value is reached.

To determine how well response time is being met, you can see transaction run times in the RMF Monitor I Workload Activity Report. transaction program run times can also be obtained via SMF reports.

The response time goal should be set by determining the average run time for transactions in a class and adding in an allowable queue delay time. The additional queue delay time provides the APPC transaction scheduler some control to attempt to optimize overall system overhead that is associated with creating and deleting transaction initiators.

**Value range:** 0.000001 - 31536000 seconds (365 days)

**Default:** 1

### **CLASSDEL**

The CLASSDEL statement deletes a class of transaction initiators from the APPC/MVS transaction scheduler configuration. One CLASSDEL statement must be specified for each class of transaction initiators that is to be deleted.

#### **CLASSNAME(classname)**

A required parameter that specifies the name of an existing class of transaction initiators to be deleted.

The value range is a 1- to 8-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@,\$,#) and must begin with an alphabetic or national character.

**Default:** There is no default. A value must be specified.

### **WORKQ({PURGE|DRAIN})**

A parameter that specifies whether a class work queue is to be drained or purged when the work class is deleted.

#### **DRAIN**

When you specify DRAIN on the WORKQ keyword, new work for the class is rejected; however, work that was assigned before the class was deleted is allowed to finish.

#### **PURGE**

When you specify PURGE on the WORKQ keyword, all work that is queued up for this class is rejected. An error message is returned to the issuers of the ALLOCATE request. However, work that is running is allowed to complete its processing.

**Default:** DRAIN

### **OPTIONS**

The OPTIONS statement defines class options for the APPC transaction scheduler. Options include naming a default class to be used when a transaction program profile does not specify a class, and naming a subsystem to which transaction initiators are assigned.

You can modify these options by overriding a previous OPTIONS statement with another OPTIONS statement that changes parameter values to be modified. When more than one OPTIONS statement exists, the most recently processed parameter values are in effect.

#### **DEFAULT(classname)**

An optional parameter that specifies the default class of transaction initiators in which to run a transaction program when a class name is not specified in a transaction program profile.

If the transaction program profile does not specify a class name, and there is no default that is defined by this parameter, the request to run the transaction program is denied. If the DEFAULT parameter names a class that does not exist, an error message is displayed on the console.

To delete the previously specified default class, specify a null value for DEFAULT. The format for a null value is: DEFAULT()

**Value range:** Null or a 1- to 8-byte character string of uppercase letters A through Z, numerals 0-9, national characters (@, \$, #) and must begin with an alphabetic or national character.

**Default:** None

### SUBSYS(ssname)

An optional parameter that specifies the name of the subsystem under which all newly created APPC/MVS transaction initiators are started. This value applies to all defined classes of transaction initiators.

If you specify a JES subsystem, it must be defined to the system in an IEFSSNxx parmlib member.

When running APPC transaction programs that do not require JES services (such as SYSOUT processing), you can specify SUBSYS(MSTR). Also, if you are using a version of JES2 lower than 4.2.0, or a version of JES3 lower than 4.2.1., specify SUBSYS(MSTR) because APPC/MVS does not support JES services at these lower levels.

To delete the previously specified subsystem, specify a null value for SUBSYS. The format for a null value is: SUBSYS()

**Value range:** Null or 1- to 4-characters. The name must begin with an alphabetic or national character (@, \$, #). The remaining characters, if any, can be alphanumeric or national.

**Default:** The primary JES subsystem.

### TPDEFAULT

The TPDEFAULT statement supplies default information when it is missing from the scheduler JCL section of a TP profile that is scheduled by the APPC/MVS transaction scheduler. Defaults include the region size of the transaction program, time limit for running the transaction program, the level of messages to appear in the message log, and the output class for TP SYSOUT.

You can modify defaults by overriding a previous TPDEFAULT statement with another TPDEFAULT that changes parameter values to be modified. When more than one TPDEFAULT statement exists, the most recently processed parameter values are in effect.

### MSGLEVEL(1,n)

An optional parameter that specifies the level of messages that are generated for TPs that do not specify MSGLEVEL in the form MSGLEVEL(1,n). This MSGLEVEL is similar to the JCL MSGLEVEL parameter, but it behaves differently in APPC/MVS. TP profile JCL is processed in two phases, which are reflected in the two subparameters (1,n).

The first subparameter 1 controls the listing of statements, procedure statements, and substitution JCL messages, which occur during TP profile add and modify processing. These statements and messages are listed in the APPC administration utility output file (SYSPRINT). The value for this parameter must be 1.

The second subparameter n controls the generation of messages that occur when the TP profile is accessed to run a TP. If you specify 0 for this subparameter, allocation and termination messages are generated only if the TP abnormally terminates. If you specify 1 for this subparameter, allocation/termination messages are always generated.

This subparameter works with the KEEP\_MESSAGE\_LOG parameter of the TP profile. Messages are generated according to the MSGLEVEL parameters and are written to the TP message log according to the KEEP\_MESSAGE\_LOG parameter. If the value of KEEP\_MESSAGE\_LOG is *error* and MSGLEVEL is (1,0) or (1,1), messages are written to the logon error. If the value of KEEP\_MESSAGE\_LOG is *always* and MSGLEVEL is (1,1), messages are always written to the TP message log. (When KEEP\_MESSAGE\_LOG is *always* and MSGLEVEL is (1,0), allocation and termination messages are generated only when the TP abnormally terminates.) If the value of KEEP\_MESSAGE\_LOG is *never*, no messages are written regardless of the value of MSGLEVEL.

The value for the first subparameter must be 1, which results in the following format:

```
MSGLEVEL=(1,messages)
```

**Value range:** The value range for messages is as follows:

- (0) Allocation/termination messages are generated only if the TP abnormally terminates.
- (1) Allocation/termination messages are always generated.

**Default:** MSGLEVEL(1,0)

### OUTCLASS(n)

An optional parameter that specifies the default value for MSGCLASS when MSGCLASS is not specified on the JOB statement in the TP profile.

**Note:** In APPC/MVS, MSGCLASS does not assign the output class for a job log (TP message log). However, MSGCLASS can affect SYSOUT processing. For more information, see the MSGCLASS keyword in [z/OS MVS JCL Reference](#).

**Value range:** A - Z, 0 - 9.

**Default:** A

### REGION({nnnnK|nnnnM})

An optional parameter that specifies the default region size that is assigned to TP profiles that do not specify a region size.

**Value range:** 0 K - 9999 K or 0 M - 2047 M

**Default:** 2 M

### TIME(NOLIMIT|mmmm[,ss])

An optional parameter that specifies the default step time limit that is assigned to TPs that do not specify a time limit. The time limit is of the following format:

```
TIME(minutes,seconds) or TIME(NOLIMIT) or TIME(minutes) or  
TIME(,seconds)
```

When time is in minutes only, do not include the comma. When time is in seconds only, include the comma before the seconds. TIME(NOLIMIT) is equivalent to TIME(1440).

**Value range:** The value range is as follows:

- Minutes: 1 - 1440
- Seconds: 1 - 59
- NOLIMIT

**Default:** TIME(1440)

## Chapter 9. AUTORxx (auto-reply policy specifications)

Use the parmlib member AUTORxx to activate auto-reply processing on a system. The member AUTOR00 contains the auto-reply policy suggested by IBM. You can modify the member (which is not recommended), or define another AUTORxx member to customize the auto-reply policy. The member AUTOR00 also contains comments that provide the message text for each WTOR and the rule used to select the WTOR.

### Parameter in IEASYSxx (or supplied by the operator)

```
AUTOR=(xx,yy,...)
```

### Syntax rules for AUTORxx

The following syntax rules apply to the AUTORxx parmlib member:

- Data is specified in columns 1-71.
- Comments can start in any column and can span lines, and must start with /\* and end with \*/. Comments may appear in any place where a blank is accepted, except within quoted strings.
- Generally, syntax errors cause the auto-reply changes to be rejected, while in the following cases, syntax errors are ignored and allow the changes to become active:
  1. The maximum number of message IDs is reached.
  2. Duplicate message IDs are specified.
  3. NOTIFYMSGs is specified in different members.

### Syntax format of AUTORxx

```
[NOTIFYMSGs({HC|CONSOLE})]
[MSGID(['msgid['] {NOAUTOREPLY}
                        {DELAY(nnn[M|S]) REPLY([']replytext['] [,[']replytext[']...)]
[RATELIMIT(nnn)]}]
```

### Syntax example of AUTORxx

```
notifymsgs(hc)
/*****
/* $HASP811 REPLY Y TO CONTINUE OR N TO TERMINATE START PROCESSING */
Msgid(?HASP811) Delay(30S) Reply(Y)
/*****
/* ANTU2220D "READY FOR FLASHCOPY. REPLY 'I' TO INITIATE, 'C' TO
/* CANCEL"
Msgid(ANTU2220D) Delay(60S) Reply(C)
```

To set the rate limit value to 30 replied WTORs per second per message ID, you can specify RATELIMIT(030) on the MSGID statement.

```

NOTIFYMSGSGS(HC)
/*****
/* ABD123D IS THE SKY BLUE?
/* REPLY 'Y'-YES OR 'N'-NO
Msgid(ABD123D) Delay(0S) Reply(Y) RateLimit(030)
/*****
/* ABD456D READY FOR WORK. REPLY 'B' TO BEGIN, 'C' TO CANCEL
Msgid(ABD456D) Delay(60S) Reply(C)

```

## IBM-supplied default for AUTORxx

The IBM-supplied default for AUTORxx is AUTOR00.

## Statements and parameters for AUTORxx

### MSGID()

The first keyword of the message definition.

#### *msgid*

Must be in the range of 1 to 10 characters. The message ID must be enclosed in quotation marks if it contains non-alphanumeric characters, such as equal signs and parentheses. The quotation marks do not count as part of the message ID. If enclosed in quotation marks, the *msgid* is not converted to uppercase.

Wildcards are partially supported in the *msgid*:

- The question mark ? is supported because some messages (such as JES2 messages) start with an installation-specified character (not always \$). For instance, ?HASP1234 is allowed.
- The asterisk \* is not treated as a wildcard in a *msgid*. If a *msgid* contains both a question mark and an asterisk, the message definition is rejected.
- Multiple question marks in the *msgid* is supported. For instance, eight question marks ???????? would match on any eight character message ID.

**Note:** The maximum number of message IDs that do not contain wildcards is limited to 10,413. The maximum number of message IDs that contain wildcards is limited to 1,500.

### DELAY(*nnn*{M|S})

Can appear in any order and on different lines from REPLY() and MSGID(). *nnn* is the minimum amount of time, in minutes (M) or seconds (S), to delay after the WTOR is issued but before the system issues a reply. Only three digits are supported, which gives a limit of 999 minutes (16.65 hours) or 999 seconds (16.65 minutes). The delay value of 0 is supported, but specifying the value of 0 can prevent automation or an operator from providing a reply.

### NOAUTOREPLY

Can be specified to cause subsequent MSGID() specifications of this message ID (in this member or subsequent members) to be ignored. With the NOAUTOREPLY option, you can have your own AUTORxx member and use it to remove messages that are specified in the AUTOR00 member without removing the AUTOR00 statements. No auto-reply processing is performed for this message ID.

### REPLY(['*replytext*'] [, ['*replytext*'] [...]])

Can appear in any order and on different lines from DELAY() and MSGID(). A null reply can be provided by specifying REPLY('').

*replytext* is limited to 64 characters. If the reply contains blanks, non-alphanumeric characters, or is not to be folded to uppercase, enclose the reply in single quotation marks. The single quotation marks count towards the total of 64 characters. If the reply is too long for the WTOR requester, the notification message CNZ2608I is issued when the WTOR is issued. Where message CNZ2608I appears depends on the setting of NOTIFYMSGSGS. It is displayed on consoles that receive routing codes 2 (operator information) or 10 (system programmer information), and also appears in the hardcopy log.

- To specify quotation marks in the reply, specify two contiguous single quotation marks, like `REPLY('That's all folks.')`. The reply might contain system symbolics that are resolved when the parmlib member is processed. If you want to have the symbolic resolved when the `REPLY` command is issued, specify two contiguous ampersands, like `REPLY('Here is the '&&SYSNAME';')`. The symbolic must be in uppercase and enclosed in quotations along with the two contiguous ampersands `&&`.
- If the autoreply policy entry contains a symbolic (like `&&name`) that is to be resolved when the reply is issued, auto-reply is unable to validate that the reply length would be acceptable by the WTOR issuer. If the reply with the symbolic resolved is longer than what the WTOR issuer expects, when auto-reply processing issues the reply, the `REPLY` command rejects the reply with:

```
IEE700I REPLY xxxx IGNORED; REPLY TOO LONG FOR REQUESTOR
```

Auto-reply no longer monitors this WTOR, and the response to the `D AUTOR,WTORS` command (`CNZ2604I`) indicates that the WTOR has been replied to.

- Do not have the reply text span parmlib source lines. Otherwise, the use of symbolics might cause problems. For example, if you specify

```
REPLY('system=&SYSNAME.,option1
,option2')
```

and `&SYSNAME` resolves to `SY1`, the reply text is

```
'system=SY1,option1      ,option2'
```

To prevent the substitution from causing problems, split the reply text into separate strings. A correct specification is:

```
REPLY('system=&SYSNAME.',
      ',option1,option2')
```

and the reply text is

```
'system=SY1,option1,option2'
```

- Auto-reply processing can concatenate the strings that are specified in `REPLY`. For example, if you specify `REPLY('String1')`, the quotations are part of the reply `'String1'`. If you specify `REPLY('String1','String2')`, auto-reply processing concatenates the strings and the reply is `'String1String2'`. The leading and trailing quotations are part of the reply.

You can also have a mixture of strings. By specifying

```
REPLY(Word1,'String1',Word2,'String2')
```

you get a reply of

```
WORD1'String1'WORD2'String2'
```

- The `REPLY` command accepts only one quoted string if the first character of the reply is a quotation mark. For example:

```
'This is the reply' but not this
```

The `REPLY` command will only pass

```
This is the reply
```

to the WTOR issuer. The WTOR issuer does not see

```
but not this
```

Although it is possible that auto-reply can build this type of string, but it might not yield the results that you wanted.

**RATELIMIT(*nnn*)**

*nnn* is the rate limit value that can be set to indicate (for a specific message ID) the number of replies that can be issued per second. After 1 second has passed, the message count is reset. Only three digits are supported, which gives a limit of 999 replies per second for the specified message ID. The rate value of 001 is the lowest value supported. The default value for rate limit has been set to 020. RATELIMIT is only valid when DELAY is set to 0; otherwise it is rejected.

**Note:**

1. Both DELAY() and REPLY() are required if NOAUTOREPLY is not specified.
2. Duplicate DELAY() or REPLY() keywords for an MSGID() are rejected and cause the MSGID() specification to be rejected.
3. Specification of the same message ID in different message definitions results in the first definition being used.

**NOTIFYMSGSGS**

Can only appear once in a parmlib member. If multiple members are specified in the SET AUTOR= command, the first NOTIFYMSGSGS value is accepted. The other specifications are ignored.

**HC**

Indicates that the auto-reply notification messages (CNZ2605I, CNZ2606I, and CNZ2608I) only appear in the hardcopy log. If NOTIFYMSGSGS is not specified, HC is the default value.

**CONSOLE**

Indicates that the auto-reply notification messages (CNZ2605I, CNZ2606I, and CNZ2608I) are displayed on consoles that receive routing codes 2 (operator information) or 10 (system programmer information) and also appear in the hardcopy log.

**Default:** HC



## Chapter 10. AXRxx (system REXX options)

The AXRxx parmlib member specifies options for system REXX. SYS1.SAMPLIB contains a copy of the AXRxx member that you can copy to SYS1.PARMLIB and modify.

### Parameter in IEASYSxx (or supplied by the operator)

```
AXR={aa      }
    {(aa,bb,...)}
```

The 2-character identifier (*aa*, *bb*, and so forth) is appended to AXR to identify the AXRxx member of SYS1.PARMLIB. If AXR= is not provided in IEASYSxx, AXR00 is used.

### Syntax rules for AXRxx

- Data must be contained in columns 1-71
- Comments may appear in columns 1-71 and must be delimited with /\* and \*/
- If a parameter is specified multiple times, the first valid instance is accepted
- System symbolics may be used anywhere.

### Syntax format of AXRxx

```
CPF('<cpf value>',SYSTEM|SYSPLEX)
AXUSER(<Userid>)
REXXLIB ADD DSN(Rexxlib data set name) VOL(<volser>)
MAXWORKERTASKS(nn)
MAXTSOSERVERS(nn)
TIMEINT(nn)
```

### IBM-supplied default for AXRxx

The IBM-supplied default for AXRxx is AXR00, and the AXRxx member is optional.

### Statements and parameters for AXRxx

#### AXRUSER(<userid>)

Specifies a 1-8 character user ID that is used to define the security environment that an exec initiated using the AXREXX macro when SECURITY=BYAXRUSER is specified. The exec runs with the level of authorization that is associated with the specified user ID.

The installation needs to provide the user ID with SAF access to the resource SYSREXX.<userid>. The installation security product must be active when system REXX initializes; otherwise, system REXX initialization is delayed.

**Default:** None. If it is omitted, any subsequent AXREXX invocation using AXRUSER is rejected.

For information about AXRUSER and the RACF resource that is used, see the topic on planning to use SYSTEM REXX and the section on security in *z/OS MVS Programming: Authorized Assembler Services Guide*. The resource is a SURROGAT class resource, and the required access is READ.

#### CPF('cpf value'),SYSTEM|SYSPLEX

Defines a 1-8 character command prefix value for System REXX that can be used instead of specifying the MODIFY AXR command. This prefix can be defined as either SYSTEM or SYSPLEX in scope.

- SYSTEM indicates that the CPF is only recognized on the system it is defined on.
- SYSPLEX indicates that it is recognized throughout the SYSPLEX and the command is routed to the system on which it is defined.

**Default:** The default is as follows:

```
CPF ( 'REXX&SYSCLONE.' ,SYSPLEX)
```

For more information about CPF, see the topic on [Using the command prefix facility in z/OS MVS Planning: Operations](#).

To obtain information about System REXX, enter @SYSREXX STATUS instead of MODIFY AXR,SYSREXX STATUS.

```
CPF ( '@' ,SYSTEM)
```

### **MAXTSOSERVERS(nn)**

The maximum number of TSO server address spaces.

**Value range:** 1 to 16

**Default:** 8

### **MAXWORKERTASKS(nn)**

Specifies the maximum number of worker tasks that are running TSO=NO work in the AXR address space.

**Value range:** 4 to 32. If a value greater than 32 is specified, the default of 32 is used and message ASA008I is issued.

**Default:** 32

### **REXXLIB ADD DSN(data\_set\_name) VOL(volume)**

The REXXLIB concatenation is an ordered list (by appearance in AXRxx) of data sets specified by REXXLIB ADD. When the AXREXX macro is called directly or indirectly from the operator console, System REXX searches this list for the specified exec. If the cataloged SYS1.SAXREXEC is not among the data sets specified, it is appended to the end. All data sets specified in the REXXLIB concatenation must have the same record type and record length as SYS1.SAXREXEC. The data set must either be a PDS or PDSE.

The number of data sets that you can add to form the REXXLIB concatenation is limited by the total number of DASD extents that the data sets will occupy. A partitioned data set extended (PDSE) counts as one extent. The total number of extents must not exceed 255 that is the current system limit.

The system concatenates as many of the REXXLIB data sets as possible until the system limit of 255 extents is reached. If each data set in the REXXLIB concatenation occupies just a single extent, 255 data sets can be concatenated. The effective size of the concatenation is reduced if data sets in the concatenation occupy secondary extents. Each secondary extent reduces the concatenation size by one. The total reduction is the sum of all secondary extents. When the system limit is exceeded, message AXR0115E is issued, and no further requests are processed by System REXX.

#### **Notes:**

1. VOLSER (or VOL) is optional when the data set is cataloged.
2. The <volser> can be a quoted string.

For more information, see [z/OS DFSMS Using Data Sets](#).

### **TIMEINT(nn)**

Specifies the default time limit on REXX execs, overriding the current default of 30 seconds.

**Value range:** A value in seconds from 0-21474536, the current maximum TIMEINT value that is supported on the AXREXX macro.

**Default:** When 0 is specified, the default is no time limit. If the TIMEINT option is omitted, the default remains 30 seconds.

## Chapter 11. BLSCECT (formatting exits for dump and trace analysis)

The BLSCECT member specifies, through embedded parmlib members, the names of IBM-supplied exit routines. The routines analyze and format dump and trace data. While analyzing a dump or trace, you can enter interactive problem control system (IPCS) subcommands to run the routines.

IPCS accesses the BLSCECT parmlib member through the IPCSPARM DD statement. If you allocate FILE(IPCSPARM), IPCS uses this data set for BLSCECT and the embedded parmlib members. If IPCSPARM is not allocated, the current concatenation is allocated, used, and then freed.

See [PARMLIB](#) for information about parmlib concatenation. For information about IPCS, see the following references:

- For information about using IPCS, see [z/OS MVS IPCS User's Guide](#).
- For information about the IPCS commands and subcommands, see [z/OS MVS IPCS Commands](#).
- For information about formatting exits, see [z/OS MVS IPCS Customization](#).

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Syntax rules for BLSCECT

These rules apply to the creation of BLSCECT:

- IPCS processes each statement as one or more lines of TSO/E Command Language. See [z/OS TSO/E Command Reference](#) and [z/OS TSO/E User's Guide](#).
- Comments may appear in columns 1-71 and must begin with /\* and end with \*/.
- BLSCECT supports system symbols.

### IBM-supplied default for BLSCECT

The default member is BLSCECT. When the system reads BLSCECT, it processes the parmlib members specified on IMBED statements in the order in which the statements appear.

The IBM-supplied BLSCECT member contains an IMBED statement for the BLSCECTX parmlib member. BLSCECTX contains formatting exit routines for IBM components other than the MVS base control program.

### Statements and parameters for BLSCECT

The statements and parameters that are used in BLSCECT and in the parmlib members that are embedded by its IMBED statements are described for the BLSCUSER parmlib member. For more information, see [“Statements and parameters for BLSCUSER, BLSCECT, and embedded parmlib members”](#) on page 113.

#### Recommendation:

- Use the IBM-supplied BLSCECT without changing it or adding to it.
- Use the IBM-supplied BLSCECTX without changing it or adding to it.
- Specify your customization in BLSCUSER.

In this way, you can upgrade to a new release without having to move your customization from the old BLSCECT to the new BLSCECT and without changing BLSCECTX.

## **BLSCECT**

The IMBED statements in the IBM-supplied BLSCECT and BLXCECTX members are required.

## Chapter 12. BLSCUSER (installation customization for dump and trace analysis)

The BLSCUSER member contains installation-supplied customization to the interactive problem control system (IPCS). For example, it can contain:

- The name of an installation-supplied routine to analyze a data area or structure.
- Specification of an installation-supplied analysis dialog to be added to the IPCS dialog.
- The name of an installation-supplied exit routine that can analyze and format dump or trace data.
- The name of an installation-supplied parmlib member to be embedded.
- Specification of a message.
- The definition of an installation-supplied input or help panel to be added to the IPCS dialog.
- The definition of a special symbol.
- The name of the sysplex dump directory, if the default of SYS1.DDIR is not used.
- A TSO/E command or CLIST to be run when the parmlib member is being activated.

During system initialization, the BLSCUSER member supplies guidance on formatting support for SNAP and ABEND dumps formatted by the system at the time of error. During system initialization it also supplies the name of the sysplex dump directory to be used by SDUMP to log unformatted system dumps. ENVIRONMENT options on various statements permit filtering of information, for example, whether environments that exploit freeway architecture are supported.

During initialization of an IPCS session, the BLSCUSER member supplies guidance for a broad range of analysis and formatting actions that may take place during that session. ENVIRONMENT options here permit filtering of information only intended for use by SNAP. During initialization of a session, IPCS does not know it whether it will need to analyze dumps of systems running in ESA mode, z/Architecture® mode, or both. As a result, BLSCUSER processes information needed to handle dumps from both modes.

The BLSCUSER member must be in the same parmlib as the BLSCECT member. See [Chapter 11, “BLSCECT \(formatting exits for dump and trace analysis\),”](#) on page 109 for more information.

The statements in BLSCUSER, BLSCECT, and embedded parmlib members generate standard IPCS return codes. These codes can be tested by CLISTs. Any serious or terminating error in processing any of the statements will prevent the system from using the parmlib data for a SNAP or ABEND dump and will cause an IPCS session to be abnormally ended.

For information about IPCS, see:

- [z/OS MVS IPCS User's Guide](#) for information about using IPCS
- [z/OS MVS IPCS Commands](#) for the IPCS commands and subcommands
- [z/OS MVS IPCS Customization](#) for information about formatting exits

### Parameter in IEASYSxx (or issued by the operator)

None.

### Syntax rules for BLSCUSER

IPCS processes each statement as a line of TSO/E Command Language. See [z/OS TSO/E Command Reference](#) and [z/OS TSO/E User's Guide](#).

- All statements are optional.
- BLSCUSER can contain all statements, except SYSDDIR, more than once.

- Comments may appear in columns 1-71; they must begin with /\* and end with \*/.
- BLSCUSER supports system symbols.

## Syntax format of BLSCUSER

```

CTRACE COMPONENT(component-name)
      FORMATTABLE(table-epname)
      [ENVIRONMENT(arch)]

DATA   {AREA(namelist)      }
      {STRUCTURE(namelist) }
      [FIND(epname)        ]
      [FORMAT(name[,level]) ]
      [PROCEDURE(procname)  ]
      [GROUP(groupname)    ]
      [MODEL(modelname)    ]
      [SCAN(scanname[,level])]
      [ENVIRONMENT(program ,arch)]

DIALOG NAME(dialogname)
      [ABSTRACT('text') ]
      [PARM('text')    ]
      [ENVIRONMENT(arch)]

END
EXIT  EP(pgmname[,level])
      [ANALYZE          ]
      [ASCB             ]
      [CBSTAT(name)    ]
      [FORMAT(name)    ]
      [TCB              ]
      [VERB(name)      ]
      [ABSTRACT('text') ]
      [AMASK(X'00FFFFFF' | X'7FFFFFFF') ]
      [ENVIRONMENT(arch)]
      [HELP(name)      ]
      [PARM('text')    ]

IMBED MEMBER(membername)
      [REQUIRED ]
      [ENVIRONMENT(program)]

```

```

NOTE  ['text' ]
      [CAPS | ASIS ]
      [PAGE | NOPAGE ]
      [SPACE[count]] | NOSPACE | OVERTYPE ]
      [TOC([indentation | 1] [toc-text]) | NOTOC ]
      [ FLAG(severity) ]
      [ PRINT | NOPRINT ]
      [ TERMINAL | NOTERMINAL ]
      [ TEST | NOTEST ]

PANDEF SUBCMD(CTRACE)
      [COMPONENT(component name) ]
      {INPUT(panel name) }
      {HELP(panel name) }
      [ENVIRONMENT(ALL,[arch])]

SYMBOL [PREFIX(prefixname) ]
      [SUFFIX(suffix)      ]
      [NAME(name)          ]
      [AREA(name)          ]
      [STRUCTURE(name)     ]
      [ENVIRONMENT(arch)]

SYSDDIR dsname
      [ENVIRONMENT(arch)]

TSO [ [ [%]clistnm | [%]
      rexnm | tsocmd ] [operands] ]

```

## IBM-supplied default for BLSCUSER

None.

## Statements and parameters for BLSCUSER, BLSCECT, and embedded parmlib members

---

These statements and their parameters can be used in the BLSCUSER member, the BLSCECT member, and all parmlib members that are embedded in these members.

### CTTRACE statement

Enables components to collect CTRACE data without necessarily registering, get the data into an unformatted dump, and have the IPCS subcommand CTRACE COMP(component-name) . . . accepted to locate the component's CTRACE data in a dump.

#### COMPONENT(component-name)

Specifies the name of the component.

#### ENVIRONMENT(arch)

##### arch

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

#### FORMATTABLE(table-epname)

Specifies the entry point of the format table containing the component-supplied find routine.

### DATA statement

Associates specific types of areas or structures with an exit routine, a model, or a group of areas or structures. Use one DATA statement for each type of data specification. For information about the exit routines, see [z/OS MVS IPCS Customization](#).

#### AREA(namelist)

#### STRUCTURE(namelist)

Identifies one or more names of areas or structures. Each name in the *namelist* is 1 to 31 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase. Separate names with blanks or commas, or in other ways that are used in TSO/E commands.

#### ENVIRONMENT(program [,arch])

##### arch

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following architectures:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

##### program

A required indicator of whether IPCS should process the DATA type in IPCS, SNAP, or ALL environments. It must be one of the following environments:

- IPCS
- SNAP
- ALL (indicating both IPCS and SNAP environments)

**Default:** IPCS

**FIND(*epname*)**

Specifies the name of the entry point in a find exit routine that is used to locate the data types within this group. (See the description of the GROUP parameter.) See the find exit routine in [z/OS MVS IPCS Customization](#).

The *epname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

**FORMAT(*name*[,*level*])**

Specifies the name of the control block formatter exit routine to be used to format the data types within this group. See the control block formatter exit routine in [z/OS MVS IPCS Customization](#).

The *name* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

The *level* is a function systems mode ID (FMID), which indicates a version and release of the MVS system and which associates the formatter with that level application programming interface (API) support. The *level* option can be specified as one of the following values:

- JBB2125 indicates that the formatter expects the structure that it formats will reside in 31-bit virtual or real storage, storage that can be described without the use of BLSRESSY structures.
- HBB3310 indicates that the formatter expects the structure that it formats will reside in 31-bit storage. The description may be provided by one or more 31-bit BLSRESSY structures or using the JBB2125 API.
- HBB7703 indicates that the formatter expects the structure that it formats will reside in 64-bit storage. The description may be provided by one or more 31-bit or 64-bit BLSRESSY structures or using the JBB2125 API.

**Default:** HBB3310

**GROUP(*groupname*)**

Specifies the name of a control block group, such as RBs and UCBs. Pointers in other control blocks (such as TCBs) may address one of these blocks, and IPCS might need to record the existence of the block in the dump directory before it is determined whether the block is, in fact, a PRB instead of another type of RB or a UCBTape instead of another type of UCB.

The *groupname* specifies the type of control blocks to be associated with each type of data being defined by this DATA statement. Do not reference an area or structure as a *groupname* if the AREA or STRUCTURE parameter references another group data type. If an attempt is made to establish such a relationship, IPCS detects an error, and the group data type associated with the explicitly referenced group is used instead.

The *groupname* is 1 to 31 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

**MODEL(*modelname*)**

Specifies a model to format data types within this group. See format models in [z/OS MVS IPCS Customization](#).

The *modelname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

**PROCEDURE(*procname*)**

An alternative data definition to FORMAT that specifies the designated data type. FORMAT and PROCEDURE are mutually exclusive keywords. When the CBFORMAT subcommand or service routine is asked to format the designated data type during the session, issue the procedure command with the syntax: %*procname* X.



**SCAN(*scanname*[,*level*])**

Specifies the name of a scan routine that is to verify each instance of a data type in this group. See the scan exit routine in [z/OS MVS IPCS Customization](#).

The *scanname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

The *level* is a function systems mode ID (FMID), which indicates a version and release of the MVS. The *level* option can be specified as one of the following values:

- Omission of *level* indicates that the scan routine expects the structure that it scans will reside in 31-bit storage. The description is provided to the scan routine by a 31-bit BLSRSASY structure, and the results of the scan should be returned in that format.
- HBB7703 indicates that the scan routine expects the structure that it scans will reside in 64-bit storage. The description will be provided to the scan routine by a 64-bit BLSRSASY structure, and the result of the scan should be returned in that format.

**Note:** The BLSRSASY structure passed to a scan routine contains a field that indicates whether it is in 31-bit or 64-bit format. If a scan routine needs to be written for use with the HBB7703 API as well as the earlier API, it can use this information to determine the format of the BLSRSASY structure.

**DIALOG statement**

Specifies an analysis dialog that a user can select from the IPCS MVS Dump Component Data Analysis panel of the IPCS dialog. See option 2.6 in [z/OS MVS IPCS User's Guide](#).

**ABSTRACT('text')**

Specifies text to appear on the IPCS MVS Dump Component Data Analysis panel. The text describes the analysis dialog processing.

The format of the line displayed on the panel is:

```
dialogname - text
```

The *text* is 1 to 60 alphabetic characters and must be enclosed in single quotation marks. Uppercase and lowercase letters are accepted; both cases are shown on the panel.

**ENVIRONMENT(*arch*)*****arch***

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

**NAME(*dialogname*)**

Specifies the name for the analysis dialog. The *dialogname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase. Each *dialogname* must be unique. It must not duplicate another dialog name on a DIALOG statement or a verb name on an EXIT statement that is specified in BLSCECT and its embedded parmlib members.

**PARM('text')**

Specifies data to be passed to the ISPF SELECT service when the analysis dialog is active. The *text* is 1 to 32,767 alphanumeric characters and must be enclosed in single quotation marks. Lowercase alphabetic characters are accepted and treated as uppercase.

**END statement**

Ends processing of an embedded parmlib member. Any statement following an END statement in an embedded parmlib member is not processed. Processing of the member containing the IMBED statement continues.

If a parmlib member contains a CLIST, the system considers the CLIST as part of the member. If a CLIST generates an END statement, the CLIST generating the END statement, any other CLIST invoked by the currently embedded member, and the currently embedded member are ended.

An END statement is useful to prevent processing of a block of statements that you want IPCS to ignore for the time being.

**EXIT statement**

Specifies an exit routine. The user can invoke the exit routine during IPCS processing by a subcommand:

- By an ANALYZE subcommand if ANALYZE is specified
- By an ASCBEXIT subcommand if ASCB is specified
- By a CBSTAT STRUCTURE(*name*) subcommand if CBSTAT(*name*) is specified
- By a TCBEXIT subcommand if TCB is specified
- By a VERBEXIT *verbname* subcommand if VERB(*verbname*) is specified

The ABSTRACT, HELP, and PARM parameters tell IPCS how to make the component analysis from your exit routine available through the IPCS dialog.

**EP(*pgmname*[,*level*])**

The *pgmname* option specifies the name of the entry point for the exit routine. The *pgmname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @).

The *level* is a function systems mode ID (FMID), which indicates a version and level of the MVS system. The *level* option pertains to CBSTAT and post-formatting exits and can be specified as one of the following values:

- Omission of *level* indicates that the scan routine expects the structure of interest will reside in 31-bit storage. The description is provided by a 31-bit structure.
- HBB7703 indicates that the routine expects the structure of interest will reside in 64-bit storage. The description is provided by a 64-bit structure.

**Note:** The structure that is passed contains a field that indicates whether it is in 31-bit or 64-bit format. If a routine needs to be written for use with the HBB7703 API as well as the earlier API, it can use this information to determine the format of the structure.

**ABSTRACT('text')**

Specifies text to appear on the IPCS MVS Dump Component Data Analysis panel. The text describes the exit routine processing. Specify this parameter when VERB is also specified.

The format of the line displayed on the panel is:

```
verbname - text
```

The *text* is 1 to 60 alphabetic characters and must be enclosed in single quotation marks. Uppercase and lowercase letters are accepted; both cases are shown on the panel. If an exit routine is invoked by multiple verb names, the first verb name associated with the exit in the parmlib members is used on the panel.

**AMASK(X'00FFFFFF' | X'7FFFFFFF')**

Specifies a logical AND mask. The exit routine uses the mask when it passes storage addresses to the dump access service. Any TSO/E INTEGER specification equivalent to these values is accepted. A TSO/E integer can be specified as decimal, hexadecimal, or binary. Hexadecimal is recommended.

The following example is for VTAM.

```
EXIT EP(VTAMMAP) AMASK(X'00FFFFFF')
```

**Default:** X'7FFFFFFF'

## ANALYZE

Specifies that IPCS invoke the exit routine during contention analysis in response to an ANALYZE subcommand. The system invokes the ANALYZE exit routines in the order they are specified in BLSCECT and its embedded parmlib members. See the ANALYZE exit routine in [z/OS MVS IPCS Customization](#).

If VERB(*verbname*) is also specified, the exit routine will also be invoked by the VERBEXIT *verbname* subcommand. If ABSTRACT is also specified, the exit routine will also be invoked through the IPCS MVS Dump Component Data Analysis panel of the IPCS dialog.

In the following example, the exit routine analyzes GRS ENQ contention.

```
EXIT EP(ISGDCONT) ANALYZE
```

## ASCB

Specifies that IPCS invoke the exit routine when an ASCBEXIT subcommand is entered. The system invokes the ASCB exit routines in the order they are specified in BLSCECT and its embedded parmlib members. See the ASCB exit routine in [z/OS MVS IPCS Customization](#).

If VERB(*verbname*) is also specified, the exit routine will also be invoked by the VERBEXIT *verbname* subcommand.

## CBSTAT(*name*)

Specifies that IPCS invoke the exit routine when a CBSTAT STRUCTURE(*name*) subcommand is entered and, for CBSTAT exit routines that are associated with units of work, when an ANALYZE subcommand is entered for the unit of work. See the ANALYZE and CBSTAT exit routines in [z/OS MVS IPCS Customization](#).

The *name* is 1 to 31 alphanumeric characters and must begin with an EBCDIC letter (A-Z). Lowercase alphabetic characters are accepted and treated as uppercase.

This example is for an RTM ASCB status exit.

```
EXIT EP(IEAVTRCA) CBSTAT(ASCB)
```

## ENVIRONMENT(*arch*)

### *arch*

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

## FORMAT(*name*)

Specifies that IPCS invoke the exit routine when the following are entered:

- A SUMMARY subcommand
- A CBFORMAT subcommand with an EXIT parameter and a STRUCTURE(*cbname*) parameter.

See the post-formatting exit routine in [z/OS MVS IPCS Customization](#).

For the SUMMARY subcommand, the system invokes the FORMAT exit routines in the order they are specified in BLSCECT and its embedded parmlib members.

The *name* is 1 to 31 alphanumeric characters and must begin with an EBCDIC letter (A-Z). Lowercase alphabetic characters are accepted and treated as uppercase.

### **HELP(*name*)**

Specifies the name of the help panel that is to be displayed when a user enters a question mark in the selection field of a exit selection panel in the IPCS dialog. The help panel should be an online description of the content of the report that is generated by the exit routine. Specify this parameter when ABSTRACT is also specified.

The *name* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

### **PARM('text')**

Specifies a parameter that IPCS is to pass to the exit routine when it is invoked from the IPCS MVS Dump Component Data Analysis panel. Specify this parameter when ABSTRACT is also specified.

The *text* is 1 to 32,767 alphanumeric characters and must be enclosed in single quotation marks. Mixed uppercase and lowercase alphabetic characters are accepted and passed as is to the routine.

### **TCB**

Specifies that IPCS invoke the exit routine when a TCBEXIT subcommand is entered. The system invokes the TCB exit routines in the order they are specified in BLSCECT and its embedded parmlib members. See the TCB exit routine in [z/OS MVS IPCS Customization](#).

If VERB(*verbname*) is also specified, the exit routine will also be invoked by the VERBEXIT *verbname* subcommand.

The following example provides COMM TASK TCB exit for WTORs.

```
EXIT EP(IEAVG701) CBSTAT(TCB)
```

### **VERB(*verbname*)**

Specifies that IPCS invoke the exit routine when a VERBEXIT *verbname* subcommand is entered. See the verb exit routine in [z/OS MVS IPCS Customization](#).

If ANALYZE, ASCB, or TCB is also specified, the exit routine will also be invoked by the ANALYZE, ASCBEXIT, or TCBEXIT subcommand.

The *verbname* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase. Each *verbname* must be unique. It must not duplicate another verb name on an EXIT statement or a dialog name on a DIALOG statement that is specified in BLSCECT and its embedded parmlib members.

To specify more than one *verbname* for the same EP *pgmname*, code a separate EXIT statement for each *verbname*.

The following example specifies a VERBEXIT VLFDATA subcommand, which analyzes VLF control blocks.

```
EXIT EP(IGVSFMAN) VERB(VLFDATA)
```

### **IMBED statement**

Embeds other parmlib members. The embedded parmlib members can embed additional parmlib members.

### **ENVIRONMENT(*program*)**

#### **program**

A required indicator of whether IPCS should process the DATA type in IPCS, SNAP, or ALL environments. It must be one of the following environments:

- IPCS

- SNAP
- ALL (indicating both IPCS and SNAP environments)

**Default:** IPCS

### **MEMBER(*membername*)**

Specifies the name of the parmlib member that IPCS should process before the processing of the current parmlib member is resumed.

The *membername* is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

### **REQUIRED**

Specifies that IPCS treat a failure to locate the parmlib member as an error. If you omit the REQUIRED parameter, IPCS accepts failure to locate the member and issues no messages.

### **NOTE statement**

Transmits messages to the terminal, to FILE(IPCSPRNT), or to both. The statement is a problem determination aid for construction and maintenance of parmlib members that are embedded in BLSCECT and in members that are embedded in BLSCECT.

The syntax of the NOTE statement is identical to the syntax of the IPCS NOTE subcommand.

### **PANDEF statement**

Specifies an input panel or help panel that is to be displayed in the IPCS dialog.

In the parameters on the PANDEF statement, each name is 1 to 8 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

### **COMPONENT(*component name*)**

Specifies the name of the component that defines the options to be captured (input panel) or explained (help panel).

### **ENVIRONMENT(ALL[,*arch*])**

#### **ALL**

A space holder that is required text to specify *arch*.

#### ***arch***

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

### **HELP(*panel name*)**

Specifies the name of the help panel that is displayed to describe component-specific options to the user.

### **INPUT(*panel name*)**

Specifies the name of the input panel that is used to obtain user specifications of component-specific options.

### **SUBCOMD(CTRACE)**

Specifies the name of the IPCS subcommand with which the panel is to be associated; only the CTRACE subcommand supports the PANDEF statement.

### **SYMBOL statement**

Defines a group of special symbols to IPCS.

**AREA(*name*)****STRUCTURE(*name*)**

Specifies the data type for the symbol. The *name* is 1 to 31 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are accepted and treated as uppercase.

This parameter allows an IPCS user to enter a shortened version of a command. For example, an IPCS user can enter:

```
list cvt
```

This subcommand is the same as:

```
list cvt structure(cvt)
```

**ENVIRONMENT(*arch*)*****arch***

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

**NAME(*name*)**

Specifies the complete name of the symbol. The *name* is 1 to 30 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, @, #). Lowercase alphabetic characters are accepted and treated as uppercase.

Examples are: CVT, GDA, or PRIVATE.

**PREFIX(*prefixname*)**

Specifies the initial characters, *prefixname*, for a group of special symbols, such as ASCBnnnnn, TCBnnnnnaaaaa, UCBxxxx, or ASTnnnnn.

The *prefixname* is 1 to 30 alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, #, @). Lowercase alphabetic characters are treated as uppercase. The number of characters that are allowed in the *prefixname* depends on the associated suffix:

| <b>SUFFIX value</b> | <b>Maximum prefix length</b>                                |
|---------------------|---|
| <b>COUNT0</b>       | 1 to 26 characters  |
| <b>COUNT1</b>       | 1 to 26 characters  |
| <b>COUNT1NAME</b>   | 1 to 25 characters  |
| <b>CPU</b>          | 1 to 29 characters  |
| <b>DUALCOUNT</b>    | 1 to 21 characters  |
| <b>NAME</b>         | No longer than 31 characters minus the length of the prefix |
| <b>UNIT</b>         | 1 to 26 characters  |

**SUFFIX(*suffix*)**

Specifies the syntax requirements for the final characters for a group of special symbols. The values for the *suffix* are:

**COUNT0**

Specifies a decimal suffix of 0 - 99999. An example is the suffix of 0 in the symbol AST0.

**COUNT1**

Specifies a decimal suffix of 1 - 99999. Some examples are the suffixes of 5 in the symbol ASCB5 and of 534 in ASXB534.

**COUNT1NAME**

Specifies a suffix of a decimal number of 1 - 99999 plus a name. The name consists of alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, @, #). An example is the suffix of 75PSFA in the symbol WTRFSCB75PSFA.

**CPU**

Specifies a suffix of a decimal number of 0 - 99. Some examples are the suffixes of 0 in the symbol LCCA0, of 15 in PCCA15, and of 7 in PSA7.

**DUALCOUNT**

Specifies a suffix of two numbers:

- First, a decimal number of 1 - 99999
- Second, a number of 1 - 5 EBCDIC letters (A-Z), which is a base-26 value in which leading A's can be omitted.

Some examples are the suffixes of 34C in the symbol JSABA34C, of 1A in PGT1A, and of 5F in TCB75F.

**NAME**

Specifies a suffix that is a name. The name consists of 1 or more alphanumeric characters and must begin with an EBCDIC letter (A-Z) or national character (\$, @, #). An example is the suffix of ABC in the symbol JOBABC.

**UNIT**

Specifies a suffix of a hexadecimal number of 0-1FFFF and is intended to be a device number. An example is the suffix of 01D0 in the symbol UCB01D0.

**SYSDDIR *dsname* statement**

Identifies the name of the data set for the sysplex dump directory. The *dsname* must be fully qualified. The name can be specified with or without apostrophes enclosing it.

**Default:** SYS1.DDIR

**ENVIRONMENT(*arch*)*****arch***

An optional indicator of whether IPCS should process the DATA type for dumps that are taken in z/Architecture or ESA/390 architecture. It must be one of the following environments:

- ESA (indicates ESA/390 architecture)
- ESAME (indicates z/Architecture)
- ZARCH (indicates z/Architecture)
- ZARCHITECTURE (indicates z/Architecture)

**Default:** ZARCHITECTURE

**TSO *command* statement**

Invokes a TSO/E command, CLIST, or REXX exec during the processing of the parmlib member. TSO statement syntax is identical to the syntax of the IPCS TSO subcommand.

Use the TSO statement when the TSO/E command, CLIST name, or REXX exec name duplicates the name of a BLSCUSER statement. A TSO/E command with a name that does not duplicate a BLSCUSER statement name can be specified without TSO before it.

A CLIST that generates BLSCUSER statements can also be specified in the parmlib member; place a percent sign (%) before the CLIST name.

TSO/E commands and REXX execs can use the TSO/E stack to leave BLSCUSER statements for processing after the command or exec ends processing.

TSO/E commands that are supplied with IPCS, IPCS primary commands and IPCS subcommands try to lighten this burden in two ways: Some keywords that you tend to use often, for example, CHARACTER, support explicit, short aliases, C in this case. All keywords can be truncated, entering just enough of their characters to make what you have entered unambiguous. For example, LENGTH is a keyword that is accepted on many subcommands. Entering LEN instead of LENGTH is unambiguous on them all. If you are composing a command procedure that you hope remains useful for a long time, do not truncate keywords in it. As IPCS responds to new demands, new keywords can be introduced that make truncations ambiguous. Support for truncation is solely intended to make manual entry of commands and writing command procedures that are intended for brief use faster and easier.



## Chapter 13. BPXPRMxx (z/OS UNIX System Services parameters)

BPXPRMxx contains the parameters that control the z/OS UNIX System Services (z/OS UNIX) environment and the file systems.

To make it easier to migrate from one release to another, especially when using the ServerPac method of installation, use two BPXPRMxx parmlib members. One member defines the values to be used for system setup and the other member defines the file systems.

To specify which BPXPRMxx parmlib member to start with, the operator has two choices:

- Include OMVS=xx in the reply to the IPL message.
- Include OMVS=xx in the IEASYSxx parmlib member. The two alphanumeric characters, represented by xx, are appended to BPXPRM to form the name of the BPXPRMxx parmlib member.

If OMVS=xx is not specified in the reply to the IPL message, defaults are used for each parameter and the kernel services are started in minimum mode. If OMVS=DEFAULT is specified, defaults are also used for each parameter and the kernel services are also started in minimum mode. For more information about running in minimum mode and full function mode, see [Setting up kernel services in minimum mode](#) and [Setting up kernel services in maximum mode in z/OS UNIX System Services Planning](#). If the operator specifies OMVS=xx in the reply to the IPL message, it overrides the OMVS=xx that was specified in IEASYSxx.

**Restriction:** The START OMVS,OMVS=xx command is not valid when issued from the command console. OMVS=xx is not valid in parmlib COMMNDxx.

You can use multiple parmlib members to start OMVS as shown in the following reply to the IPL message:

```
R 0,CLPA,SYSP=R3,LNK=(R3,R2,L),OMVS=(AA,BB,CC)
```

You can also specify multiple BPXPRMxx parmlib members using the OMVS keyword in IEASYSxx. For example:

```
OMVS=(AA,BB,CC)
```

If the same parameters are specified in more than one member, the first instance of the keyword that is specified in the leftmost member is used. The MOUNT statements are processed in the order that they are specified in left to right sequence.

If you are using SYSPLEX(YES) and mixed releases of z/OS UNIX, you can IPL specifying OMVS=(*delta,common*) for each unique release, where *delta* identifies the member containing the new keywords for that release, and *common* identifies the common keywords for all releases.

To modify BPXPRMxx parmlib settings without reloading the initial program, you can use the SETOMVS operator command. You can also dynamically change the BPXPRMxx parmlib members that are in effect by using the SET OMVS operator command. For more information, see [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#). For more information about the SETOMVS command, see [SETOMVS command in z/OS MVS System Commands](#). For more information about the SET OMVS command, see [SET command in z/OS MVS System Commands](#).

### Syntax rules for BPXPRMxx

When customizing BPXPRMxx, these rules apply:

- Statements that contain limiting keywords (like MAXUIDS, which limits the number of concurrent z/OS UNIX users), should not be duplicated in the same BPXPRMxx member. You can have duplicates of limiting keywords across BPXPRMxx members, but only the last occurrence is used. Resource defining

keywords (like MOUNT, which specifies a file system that z/OS UNIX is to logically mount onto the root file system or another file system) are cumulative. Resource defining keywords can be duplicated in the same BPXPRMxx member. Each time you specify a resource defining keyword, its value is added to the previous values.

- If a statement that has a default is omitted, the default is used.
- Use columns 1 through 71 for data; columns 72 through 80 are ignored.
- Enter one or more statements on a line, or use several lines for one statement.
- Use blanks as delimiters. Multiple blanks are interpreted as a single blank. Blanks are allowed between parameters and values; for example, MAXPROCSYS(500) and MAXPROCSYS (500) are allowed and have the same meaning.
- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.
- Enter values in uppercase, lowercase, or mixed case. The system converts the input to uppercase, except for values that are enclosed in single quotation marks, which are processed without changing the case.
- These values require single quotation marks and are the only ones that are allowed to be in single quotation marks.
  - STEPLIBLIST
  - USERIDALIASTABLE
  - FILESYSTEM in the ROOT, MOUNT, and ALTROOT statements
  - MOUNTPPOINT in the MOUNT and ALTROOT statement
  - PARM in the FILESYSTYPE, ROOT, MOUNT, SUBFILESYSTYPE, and ALTROOT statements
  - RUNOPTS
  - VERSION
  - AUTHPGMLIST
  - SC\_EXITTABLE
- Enclose values in single quotation marks, using the following rules:
  - Two single quotation marks next to each other on the same line are considered as a single quotation mark. For example, John ' 's file is considered to be John's file. One quotation mark in column 71 and another in column 1 of the next line are not considered as a single quotation mark. This input is treated as two strings or an error.
  - Because some values can be up to 1023 characters, a value can require multiple lines. Place one quotation mark at the beginning of the value, stop the value in column 71 of each line, continue the value in column 1 of the next line, and complete the value with one quotation mark as follows:

|        |   |        |
|--------|---|--------|
| column |   | column |
| 1      |   | 71     |
|        |   |        |
|        | MOUNT FILESYSTEM('ZFS.WORKDS') MOUNTPPOINT('/u/john/namedir1/namedir2 |        |
|        | /namedir3/namedir4') TYPE(ZFS) MODE(RDWR)                             |        |

Rather than defining parameter limit values in their full decimal or hexadecimal form, you can use a one-character multiplier (denomination values) suffix when specifying them. This value will also be used in displays when the system returns responses to respective D OMVS commands. The multipliers are listed in [Table 15 on page 125](#).

#### Restrictions:

1. Only those SETOMVS parameters that support this C suffix specifically note that support and refer to [Table 15 on page 125](#).
2. Values that contain a multiplier are limited to 8 digits (nnnnnnnC) and those values are limited to X'00FF FFFF' (16 777 215 decimal).
3. Values that do not contain a multiplier are limited to X'7FFF FFFF' (2 147 483 647 decimal).

**Tip:** A complete description of the D OMVS output can be found in message BPX0040I. To look up that message, go to [Shell and Utilities messages in z/OS UNIX System Services Messages and Codes](#).

Table 15. One-character parameter limit multipliers

| Denomination value | One-character abbreviation | Bytes                 |
|--------------------|----------------------------|-----------------------|
| null               | n/a                        | 1                     |
| Kilo               | K                          | 1,024                 |
| Mega               | M                          | 1,048,576             |
| Giga               | G                          | 1,073,741,824         |
| Tera               | T                          | 1,099,511,627,776     |
| Peta               | P                          | 1,125,899,906,842,624 |

## Syntax format of BPXPRMxx

```
{AUTOCVT(ON|ALL|OFF)}
{MAXIOBUFUSER(nnnnn)}
{LOSTMSG(ON|OFF)}
{SMFUPDATE(ON|OFF)}
{PWT(SMF|SMFENV|ENV)}
{MAXPROCSYS(nnnnn)}
{MAXPROCUSER(nnnnn)}
{MAXUIDS(nnnnn)}
{MAXFILEPROC(nnnnnn)}
{MAXTHREADTASKS(nnnnn)}
{MAXTHREADS(nnnnnn)} {MAXPIPEUSER(nnnnn)}
{MAXPTYS(nnnnn)}
{MAXFILESIZE(nnnnn|NOLIMIT)}
{MAXCORESIZE(nnnnn)}
{MAXASSIZE(nnnnn)}
{MAXCPUPTIME(nnnnn)}
{MAXMMAPAREA(nnnnn)}
{RESOLVER_PROC(nnnnn|DEFAULT|NONE)}
{SHRLIBRGNSIZE(nnnnn)}
{SHRLIBMAXPAGES(nnnnn)}
{PRIORITYGOAL(service_class_name1,...service_class_name40|NONE)}
{IPCMSGNIDS(nnnnn)}
{IPCMSGQBYTES(nnnnn)}
{IPCMSGQMNUM(nnnnn)}
{IPCSEMNIDS(nnnnn)}
{IPCSEMNOPS(nnnnn)}
{IPCSEMNSEMS(nnnnn)}
{IPCshmMPAGES(nnnnn)}
{IPCshmNIDS(nnnnn)}
{IPCshmNSEGS(nnnnn)}
{IPCshmSPAGES(nnnnn)}
{FORKCOPY(COPY)}
{SUPERUSER(user_name)}
{TTYGROUP(group_name)}
{CTRACE(parmlib_member_name)}
{STEPLIBLIST('/etc/steplib')}
{USERIDALIASTABLE('/etc/tablename')}
{SERV_LPALIB('dsname', 'volser')}
{SERV_LINKLIB('dsname', 'volser')}
{FILESYSTYPE TYPE(type_name)
    ENTRYPOINT(entry_name)
    PARM('parm')}
    ASNAME(proc_name, 'start_parms')}
{SYSPLEX(YES|NO)}
{VERSION('nnnn'[,UNMOUNT|NOUNMOUNT])}

{ROOT FILESYSTEM('fspath') or DDNAME(ddname)
    TYPE(type_name)
    MODE(access)
    PARM('parameter')}
```

```

SETUID|NOSETUID
SYSNAME(sysname)
TAG(NOTEXT|TEXT,ccsid)
AUTOMOVE|NOAUTOMOVE
MKDIR('pathname')

{MOUNT FILESYSTEM('fsname') or DDNAME(ddname)
  TYPE(type_name)
  MOUNTPOINT('pathname')
  MODE(access)
  PARM('parameter')
  SETUID|NOSETUID
  SECURITY|NOSECURITY
  SYSNAME(sysname)
  TAG(NOTEXT|TEXT,ccsid)
  AUTOMOVE[(INCLUDE,sysname1,sysname2,...,[sysnameN|*])]
  |[(EXCLUDE,sysname1,sysname2,...,sysnameN)]
  |NOAUTOMOVE|UNMOUNT
  MKDIR('pathname')}

{NETWORK DOMAINNAME(sockets_domain_name)
  DOMAINNUMBER(sockets_domain_number)
  MAXSOCKETS(nnnnn)
  TYPE(type_name)
  INADDRANYPORT(starting_port_number)
  INADDRANYCOUNT(number_of_ports_to_reserve)}

{SUBFILESYSTYPE NAME(transport_name)
  TYPE(type_name)
  ENTRYPOINT(entry_name)
  PARM('parameter')
  DEFAULT}

{STARTUP_PROC(procname)}

{STARTUP_EXEC('dsname(membername)',class)}

{RUNOPTS('string')}

{SYSCALL_COUNTS(YES|NO)}

{MAXQUEUEDSIGS(nnnnnn)}

{LIMMSG(NONE|SYSTEM|ALL)}
{AUTHPGMLIST('/etc/authfile')|NONE}

{SWA(ABOVE|BELOW)}

{ALTROOT FILESYSTEM('fsname')
  PARM('parameter')
  MOUNTPOINT('pathname')}

  {ALTROOT NONE}

{NONEMPTYMOUNTPT(NOWARN|WARN|DENY)}

{MAXUSERMOUNTSYS(nnnnn)}

{MAXUSERMOUNTUSER(nnnnn)}

{SC_EXITTABLE('/etc/tablename')}
{REXXPARSE(SHELL|TSO)}

```

## Syntax example of BPXPRMxx

```

AUTOCVT(OFF)
MAXPROCSYS(400)
MAXPROCUSER(16)
MAXUIDS(200)

```

```

MAXFILEPROC(20)
MAXPIPEUSER(8730)
MAXTHREADTASKS(100)
MAXTHREADS(500)
MAXPTYS(100)
MAXFILESIZE(1000)
/*--- or --- MAXFILESIZE(300M) -----*/
MAXCORESIZE(4194304)
/*--- or --- MAXCORESIZE(1K) -----*/
MAXASSIZE(41943040)
/*--- or --- MAXASSIZE(10M) -----*/
MAXCPU(1000)
MAXMMAPAREA(4096)
/*--- or --- MAXMMAPAREA(16M) -----*/
PRIORITYGOAL(CICS4,CICS4,CICS4,CICS3,CICS2,CICS1,TS02,TS01,BAT3,BAT2)
IPCMSGNIDS(500)
IPCMSGQBYTES(262144)
IPCMSGQMNUM(100000)
IPCSEMNIDS(500)
IPCSEMNOPS(25)
IPCSEMNSEMS(25)
IPCSHMMPAGES(256)
/*--- or --- IPCSHMMPAGES(55M) -----*/
IPCSHMNIDS(500)
IPCSHMNSEGS(500)
IPCSHMSPAGES(262144)
/*--- or --- IPCSHMSPAGES(300K) -----*/
FORKCOPY(COPY)
SUPERUSER(BPXROOT)
TTYGROUP(TTY)
CTRACE(CTCBPX23)

STEBLIBLIST('/etc/steplib')
USERIDALIASTABLE('/etc/tablename')
SYSPLEX(YES)
  VERSION('REL9')
  FILESYSTYPE TYPE(ZFS)
    ENTRYPOINT(IOEFSCM)
    ASNAME(ZFS)
ROOT  FILESYSTEM('OMVS.ROOT')
      TYPE(ZFS)
      MODE(RDWR)
      SYSNAME(SY1)
      TAG(NOTEXT,0)
      AUTOMOVE

MOUNT  FILESYSTEM('OMVS.USER.JONES')
      TYPE(ZFS)
      MOUNTPOINT('/u/jones')
      MODE(RDWR)
      SYSNAME(SY1)
      TAG(TEXT,1047)
      AUTOMOVE(INCLUDE,SYS1,SYS2,*)

ALTRoot  FILESYSTEM('OMVS.ALTRoot')
      MOUNTPOINT('/sysalt')
      PARM(' ')

FILESYSTYPE TYPE(INET)
  ENTRYPOINT(EZBPFINI)
NETWORK  DOMAINNAME(AF_INET)
  DOMAINNUMBER(2)
  MAXSOCKETS(64000)
  TYPE(INET)
STARTUP_PROC(OMVS)
STARTUP_EXEC('OMVS.ROOT(REXX01)',A)
RUNOPTS('')
SYSCALL_COUNTS(YES)
MAXQUEUEDSIGS(1000)
RESOLVER_PROC(DEFAULT)
AUTHPGMLIST('/etc/authfile')
LOSTMSG(ON)

```

```
SWA (ABOVE)
NONEMPTYMOUNTPT (DENY)
MAXUSERMOUNTSYS (100)
MAXUSERMOUNTUSER (2)
SC_EXITTABLE ('/etc/tablename')
REXXPARSE (TSO)
```

**Notes:**

1. This is an example only; the values presented here are not optimal nor recommended values for your installation.
2. The bold comments present alternate specifications of those parameters that support the use of multipliers. Refer to [Table 15 on page 125](#) for information concerning the use of multipliers.

## IBM-supplied default for BPXPRMxx

---

There is no default BPXPRMxx parmlib member. SYS1.SAMPLIB provides a sample parmlib member BPXPRMXX.

## Statements and parameters for BPXPRMxx

---

For information about selecting values for the statements, see [Customizing z/OS UNIX](#) in *z/OS UNIX System Services Planning*.

### **ALTROOT FILESYSTEM('fsname') PARM('parameter') MOUNTPPOINT('pathname')**

Specifies the alternate sysplex root file system that automatically replaces the current one when it becomes uncrowned. It is mutually exclusive with ALTROOT NONE.

When the replacement occurs, the alternative sysplex root file system is unmounted. Then it is mounted again as the current sysplex root on all systems in the shared file system configuration. If the replacement is successful, the failed sysplex root is unmounted.

The alternative sysplex root file system is always mounted in the READ mode and designated as AUTOMOVE=YES when it becomes the current sysplex root file system. The previous mount mode and AUTOMOVE settings of the alternative sysplex root and the failed sysplex root are ignored. The mount parameters are preserved when the alternative sysplex root file system becomes the current sysplex root file system.

To manually replace the failed or failing sysplex root file system, use the MODIFY OMVS,NEWROOT operator command with the COND=FORCE option. To validate the syntax of the ALTROOT statement, use the SETOMVS SYNTAXCHECK operator command. For instructions on how to replace the failed or failing sysplex root, see [Steps for dynamically replacing the sysplex root file system](#) in *z/OS UNIX System Services Planning*.

#### **FILESYSTEM('fsname')**

The name of the alternative sysplex root file system.

#### **PARM('parameter')**

The parameter to be passed directly to the file system type.

#### **MOUNTPPOINT('pathname')**

The absolute path name, or a symbolic link that resolves to the path name of the directory onto which the file system is to be mounted. MOUNTPPOINT must be specified in the ALTROOT statement. The mount point for the alternate sysplex root file system must be in the root directory of the current sysplex root file system, or the mount of the ALTROOT will fail. The absolute path name can be up to 64 characters.

### **ALTROOT NONE**

Removes the ALTROOT support and deletes any outstanding eventual action messages. It is mutually exclusive with ALTROOT FILESYSTEM(). It does not unmount the ALTROOT file system that was established by using the ALTROOT FILESYSTEM statement. The ALTROOT file system is left unmounted as a regular file system.

**AUTHPGMLIST('/etc/authfile')|NONE**

Specifies the path name of a z/OS UNIX file that contains the lists of APF-authorized path names and program names. If you do not specify a value for AUTHPGMLIST, or if you specify NONE, invocations of APF-authorized and program-controlled programs are not checked against a list of authorized programs or authorized path names. If you specify a path name for the AUTHPGMLIST parameter, the system checks this list during hfsload, exec, and spawn processing. If the target program of an exec or spawn has an authorization code of 1 (AC=1), then that program name must appear in the authorized program list.

Use the SETOMVS or SET OMVS command to dynamically change the value. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

**AUTOCVT(ALL|ON|OFF)**

Activates and deactivates automatic conversion of I/O data using coded character sets for the program and its associated files. The coded character set identifiers (CCSIDs) are specified by the program or by setting the appropriate environment variables at run time. The system AUTOCVT indicator can be overridden by individual programs at a thread or file descriptor level. AUTOCVT is a controlling global switch only for existing programs that do not explicitly establish their own conversion environment.

**ALL**

Enables Unicode Services conversion of data during read and write I/O operations.

**OFF**

Automatic conversion is not enabled.

**ON**

Enables Enhanced ASCII conversion of data during read and write I/O operations. Conversion is limited to the EBCDIC (1047) and ASCII (819) code pages.

OFF is the default.

Use the SETOMVS or SET OMVS commands to change the value of AUTOCVT between ALL, ON, and OFF. Changing this conversion mode does not affect conversion of opened files for which I/O has already started.

**Tip:** When AUTOCVT(ALL) or AUTOCVT(ON) is set, every read and write operation for a file must be checked to see whether conversion is necessary. This check incurs a performance penalty, even if no conversion occurs. If possible, keep AUTOCVT(OFF) and enable each program for conversion by setting the compile or runtime environment variables that control conversion or using programmable function. For more information, see [Converting files between code pages in z/OS UNIX System Services Planning](#).

Automatic conversion can also be controlled individually by a program that has either the ThliCvtOn or ThliCvtOn flag in the thread Thli control block (BPXYTHLI)

- The ThliCvtOn flag activates automatic conversion for this thread.
- The ThliCvtOff flag deactivates automatic conversion for this thread.

Both bits must not be on at the same time.

Automatic conversion is accomplished between programs and files that are tagged with different CCSIDs when a conversion table exists for that CCSID pair in the system. CCSID values are defined in *Character Data Representation Architecture*. For more information about supported Unicode Services CCSIDs, see [z/OS Unicode Services User's Guide and Reference](#).

**AUTOMOVE|NOAUTOMOVE**

The AUTOMOVE and NOAUTOMOVE parameters apply only in a sysplex where systems are participating in a shared file system. They indicate what happens to the ownership of the file system when a shutdown, PFS termination, dead system takeover, or file system move occurs.

**AUTOMOVE**

Indicates that ownership of the file system automatically changes to another system that is participating in the shared file system.

**NOAUTOMOVE**

Indicates that ownership of the file system is not moved if the owning system goes down; as a result, the file system becomes inaccessible. When you specify NOAUTOMOVE, the file system becomes inaccessible when the owning system goes down. But it still exists in the file system hierarchy. The file system remains unowned until the original owning system reIPLs.

Use AUTOMOVE for the sysplex root file system and the version file system. For file systems that are associated with a single system, specify UNMOUNT. The specification includes /etc, /tmp, /var, /dev, and other system-specific file systems. For descriptions of the sysplex root, system-specific, and version file systems, see [Sharing file systems in a sysplex in z/OS UNIX System Services Planning](#).

The default is AUTOMOVE. To ensure that the root is always available, use AUTOMOVE.

**CTRACE(*parmlib\_member\_name*)**

Specifies the parmlib member that contains the initial tracing options to be used for the z/OS UNIX component. Use CTRACE to provide tracing while the kernel is starting and to avoid having to issue a TRACE operator command to set tracing options.

The default is CTIBPX00.

**FILESYSTYPE TYPE(*type\_name*) ENTRYPOINT(*entry\_name*) PARM('parm')  
ASNAME(*proc\_name*['start\_parms'])**

Specifies the type of file system that is to be started. BPXPRMxx can contain more than one FILESYSTYPE statement.

When SYSPLEX(YES) is specified, each FILESYSTYPE in use within the participating shared file system group must be defined for all systems that are participating in a shared file system. The easiest way to accomplish this is by having a single BPXPRMxx member that contains file system information for each system that is participating in the shared file system. If you decide to define a BPXPRMxx for each system, the FILESYSTYPE statements must be identical on each system. For more information about shared file systems, see [Customizing BPXPRMxx for a shared file system in z/OS UNIX System Services Planning](#).

Any facilities that are required for a particular FILESYSTYPE must be initiated on all systems that are participating in a shared file system. For example, NFS requires TCP/IP, so if you specify an NFS FILESYSTYPE, you must also initialize TCP/IP on NFS initialization.

Use the SETOMVS RESET command to dynamically specify new FILESYSTYPE statements. To make a permanent change, edit the BPXPRMxx member that is used for IPLs. For more information, see [Dynamically adding FILESYSTYPE statements in BPXPRMxx in z/OS UNIX System Services Planning](#).

The parameters are as follows:

**ASNAME(*proc\_name*['start\_parms'])**

*proc\_name* specifies the name of a procedure in SYS1.PROCLIB that is to be used to start the address space that is initialized by the physical file system (PFS). Specify ASNAME for any PFS that does not run in the kernel address space. The name that you specify is also used for the name of the address space.

*start\_parms* is an optional quoted string that is to be appended to the *proc\_name* when the address space is started. The string can be up to 100 characters long. The *start\_parms* are not validated; they are passed to the system when the address space is started with an internal command. Refer to the START command in [z/OS MVS System Commands](#) or the ASCRE macro in [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

By default the address space started with ASNAME is started under JES. You can change , but this can be changed by including the additional start\_parms **SUB=MSTR**.

ASNAME is an optional parameter. *proc\_name* is 1 to 8 characters; the system converts the name to uppercase. If you do not specify ASNAME, or specify *proc\_name* as the name of the kernel address space, the PFS is initialized in the kernel address space.

Refer to the documentation for the specific physical file system for valid ASNAME operands.



**PARM('parm')**

Provides a parameter to be passed directly to the file system type. The parameter format and content are specified by the file system type.

PARM is an optional parameter. The parameter is up to 1024 characters long; the characters can be in uppercase, lowercase, or both. The parameter must be enclosed in single quotation marks.

For information about specifying the TFS configuration parameters, see [Parameter key options for the FILESYSTYPE statement in z/OS UNIX System Services Planning](#). For example:

**-ea count**

The TFS file system automatically grows *count* times.

**-em count**

The TFS file system manually grows *count* times.

If the physical file system specified does not expect a PARM operand, it ignores all PARM operands.

PRM=(*aa, bb, ..., zz*) is valid for the z/OS File System (zFS).

If a syntax error is found in FSFULL, the system issues an error message and sets the parameters to the default values.

**PRM=(*aa, bb, ..., zz*)**

Defines the IOEPRMy members of the logical parmlib concatenation for specifying zFS configuration parameters, where *aa, bb, ..., zz* specifies the suffixes of the IOEPRMxx parmlib members in the order in which they are to be concatenated. Up to 32 suffixes can be specified. Suffixes must be in uppercase. Defining an IOEFSPRM configuration file with an IOEZPRM DD card in the zFS procedure overrides the PRM specification (that is, cause it to be ignored). For more information, see [“Specifying the IOEPRMxx concatenation” on page 585](#).

**FSFULL(*threshold,increment*)**

FSFULL(*threshold,increment*) is supported by TFS and z/OS File System (zFS).

- *threshold* specifies the percentage of the file system capacity at which an operator message is generated. The default is 100%.
- *increment* specifies the percentage of change above the file system capacity at which an operator message is generated. Messages are generated by either an increase or decrease greater than *increment*. The default is 5%.

You can specify *threshold* and *increment* values for the file system. The values can also be set on the MOUNT command for a specific file system. Parameters on the MOUNT command override parmlib values. If no values are specified in either place, no threshold checking is done. If a threshold value is specified but no increment is given, the increment defaults to 5%. The increment value applies both to upgrading the message when the file system continues to fill and to removing the message when more space becomes available due to either deleting files. It also applies to extending the file system. The values are in terms of percent full. The values that are applied to a file system can be changed only when the file system is mounted.

**zFS restriction:** The MOUNT statement for zFS must have values provided for both *threshold* and *increment* when FSFULL is specified. The default value is not provided if either parameter is omitted. If you omit the entire FSFULL parameter line, the default values (*threshold*=100%, *increment*=5%) will apply in zFS.

**TYPE(*type\_name*)**

Specifies the name of the file system type that is to control the file system. TYPE is a required parameter. The name is 1 to 8 characters; the system converts the name to uppercase. In the FILESYSTYPE statement, you can specify a supported file system type.

For a complete list of supported file types, see the following table:

| Table 16. Types of file systems. The table lists the file system type and the corresponding module name. |  |             |
|--|--|-------------|
| File system type   | Description  | Module name |
| <b>AUTOMNT</b>   | Handles automatic mounting and unmounting of file systems.<br><br>The AUTOMNT file system is mounted as AUTOMOVE(YES). However, if the parent file system has the automove unmount attribute, then the automount file system will have that attribute instead of AUTOMOUNT(YES).   | BPXTAMD     |
| <b>CINET</b>   | Handles requests for the AF_INET and AF_INET6 family of sockets. This enables many different AF_INET or dual AF_INET/AF_INET6 physical file systems to be active on the system.<br><br>If you want to use CINET, you must be using z/OS Communications Server (TCP/IP Services).<br><br>If you use CINET, you cannot use INET. | BPXTCINT    |
| <b>INET</b>  | Handles requests for the AF_INET and AF_INET6 family of sockets. You must be using z/OS Communication Services (TCP/IP Services).<br><br>If you use INET, you cannot use CINET.  | EZBPFINI    |
| <b>NFS</b>   | Handles Network File System requests for access to remote files.<br><br>For NFS Client, you must create a procedure to run a PFS in a colony address space.  | GFSCINIT    |
| <b>PROC</b>  | Manages files that contain process and system information.   | BPXUPINT    |
| <b>TFS</b>   | Handles requests to the temporary file system (TFS).   | BPXTFS      |
| <b>UDS</b>   | Handles socket requests for the AF_UNIX address family of sockets.   | BPXTUINT    |
| <b>UFS</b>   | Obtains merged view of two or more directories.  | BPXUNINT    |
| <b>ZFS</b>   | Handles z/OS File System requests.   | IOEFSCM     |

For planning information, see [FILESYSTYPE](#) in *z/OS UNIX System Services Planning*.

#### **FORKCOPY(COPY)**

Specifies that fork() immediately copies the parent storage to the child, whether or not the suppression-on-protection (SOP) hardware feature is available. Use this option to avoid any additional ESQA use in support of fork.

Use the SETOMVS or SET OMVS command to dynamically change the value. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

#### **IPCMSGNIDS(ipcmsgnids)**

Specifies the maximum number of unique system-wide message queues.

The value range is a decimal value from 1 to 20000. The default is 500.

You can increase but not decrease the value, as described in [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#). Use the SETOMVS or SET OMVS command to change the value of IPCMSGNIDS dynamically. The new minimum is the current value. The new maximum is calculated as follows:

```
MIN(initial maximum, MAX(4096, 3*initial value))
```

#### **IPCMSGQBYTES(ipcmsgqbytes)**

Specifies the maximum number of bytes in a single message queue.

The value range is a decimal value from 0 to 2147483647. The default is 2147483647 (2 G). The high end of this range is not obtainable due to storage constraints. The actual maximum range varies due to storage allocation and system usage.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCMSGQMNUM(*ipcmsgqmnum*)**

Specifies the maximum number of system-wide messages for each queue.

The value range is a decimal value from 0 to 2147483647. The default is 10000. The high end of this range cannot be obtained due to storage constraints. The actual maximum range varies due to storage allocation and system usage.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCSEMNIDS(*ipcsemnids*)**

Specifies the maximum number of unique system-wide semaphore sets.

The value range is a decimal value from 1 to 20000. The default is 500.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCSEMNOPS(*ipcsemnops*)**

Specifies the maximum number of operations for each semop call.

The value range is a decimal value from 0 to 32767. The default is 25. This is a system-wide limit.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCSEMNSEMS(*ipcsemnsems*)**

Specifies the maximum number of semaphores for each semaphore set.

The value range is a decimal value from 0 to 32767. The default is 1000.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCSHMMPAGES(*ipcshmmpages*)**

Specifies the maximum number of pages for shared memory segments.

The value range is a decimal value from 1 to 4 petabytes (that is,  $4 * 1\,125\,899\,906\,842\,624$ ). The default is 25600.

If you obtain memory segments below the 2-gigabyte address range, then a realistic maximum is about 1.5 gigabytes; the actual maximum range varies due to storage allocation and system usage. If you obtain memory segments above the 2-gigabyte address range, the maximum depends on the IEASYS HVSHARE parameter, which specifies the size of the high virtual shared area.

The denomination value is retained and used within a subsequent D OMVS command.

Use the SETOMVS or SET OMVS command to change the value dynamically.

### **IPCSHMNIDS(*ipcshmuids*)**

Specifies the maximum number of unique system-wide shared memory segments.

The value range is a decimal value from 1 to 20000. The default is 500. You can increase but not decrease the value, as described in [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#).

Use the SETOMVS or SET OMVS command to change the value dynamically. The new minimum is the same as the current value. The new maximum is calculated as follows:

```
MIN(initial maximum, MAX(4096, 3 * initial value))
```

### **IPCSHMNSEGS(*ipcshmensegs*)**

Specifies the maximum number of attached shared memory segments for each address space.

The value range is a decimal value from 0 to 1000. The default is 500.

Use the SETOMVS or SET OMVS command to change the value dynamically.

**IPCSHMSPAGES(ipcshmspages)**

Specifies the maximum number of system-wide shared pages that are created by calls to the fork and 31-bit shmat functions.

You can increase, but not decrease, the value, as described in [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#). Shared memory segments that are obtained above the 2-gigabyte range in 64-bit programs do not affect this limit.

The value range is a decimal value from 0 to 2621440. The default is 262144. You can increase but not decrease the value, as described in [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#).

You can set a denomination (or multiplier) value when you define this value. The C suffix can have a one-character value as presented in [Table 15 on page 125](#), but must not exceed the parameter-specific upper limit. The denomination value is retained and is used again within a subsequent D OMVS command.

Use the SETOMVS or SET OMVS command to dynamically change the value. The new minimum is the same as the current value. The new maximum is calculated as follows:

```
MIN(initial maximum,MAX(4096,3*initial value))
```

Because each page of shared storage requires the associated consumption of extended system queue area (ESQA) storage, limiting the shared storage usage provides a way to limit the ESQA usage by z/OS UNIX users. If you use the \_\_IPC\_MEGA or \_\_MAP\_MEGA options, then the shared pages limits are not affected because MEGA does not affect the system ESQA overhead.

**KERNELSTACKS(ABOVE)**

Specifies that kernel slacks are allocated from above the bar storage. Specifying KERNELSTACKS increases thread limit to a maximum of 500,000; the actual amount varies, depending on work load and system configuration. Usage of real storage in the kernel address space is also increased.

ABOVE is the default.

**Notes:**

1. You cannot change the value of KERNELSTACKS dynamically with the SETOMVS or SET OMVS command.
2. You cannot change the value of KERNELSTACKS on an OMVS RESTART.
3. Any changes to the BPXPRMxx member for KERNELSTACKS do not take effect until the next IPL.

**LIMMSG(ALL|SYSTEM|NONE)**

Specifies how console messages that indicate when parmlib limits are reaching critical levels are to be displayed.

**ALL**

Displays console messages for both the system limits and the process limits, regardless of which process reaches a process limit.

**NONE**

Does not display console messages when any of the parmlib limits are reached.

**SYSTEM**

Displays console messages for all processes that reach system limits. In addition, messages are displayed for each process limit of a process if any of the following conditions are met:

- The process limit or limits are defined in the OMVS segment of the owning user ID.
- The process limit or limits were changed with a SETOMVS PID=*pid*,*process\_limit*.

SYSTEM is the default.

**LOSTMSG(ON|OFF)**

LOSTMSG(ON) detects lost and duplicate XCF messages in a shared file system configuration. It is ignored if the file system does not have a shared file system configuration; for example, when SYSPLEX(NO) is specified. While LOSTMSG can be specified differently for each member in the

sysplex, the same LOSTMSG setting should be specified throughout the sysplex. To disable the detecting of lost and duplicate messages, specify LOSTMSG(OFF).

Do not use LOSTMSG(ON) when z/OS UNIX sysplex traffic is high, such as when many file systems that are not sysplex-aware are being accessed remotely because performance might be affected.

The default is ON.

### **MAXASSIZE(maxassize)**

Specifies the RLIMIT\_AS resource values that are established as the initial values for new processes. RLIMIT\_AS indicates the address space region size. For more information about RLIMIT\_AS, see [setrlimit \(BPX1SRL, BPX4SRL\) — Set resource limits in z/OS UNIX System Services Programming: Assembler Callable Services Reference](#).

The value range is a decimal value from 10485760 (10 megabytes) to 2147483647 (2 gigabytes). The default is 209715200.

**Note:** The MAXASSIZE value limits the amount of storage below 2 GB, including both above and below the 16 MB line.

The soft limit is obtained from MVS; if it is greater than the MAXASSIZE value, the soft limit is set to the hard limit. This value is also used when processes are initiated by a daemon process using an `exec()` after `setuid()`. In this case, both the RLIMIT\_AS hard and soft limit values are set to the MAXASSIZE specified value.

When processes are initiated by a daemon process using an `exec()` after `setuid()`, this value is used. Therefore, MAXASSIZE is the region size for all processes that are created through `rlogin` or `telnet`. In this case, both the RLIMIT\_AS hard and soft limit values are set to the MAXASSIZE value.

A superuser can override this value by specifying a new region size in the spawn inheritance structure on `__spawn()`. Or you can change the value of MAXASSIZE dynamically by using the SETOMVS or SET OMVS command. This change only affects the new processes that are created after the change was made.

**Note:** The IEFUSI user exit can modify the region size of an address space. Users are discouraged from altering the region size of address spaces in the OMVS subsystem category.

You can set a denomination (or multiplier) value when you define this value. The C suffix can have a one-character value as presented in [Table 15 on page 125](#), but must not exceed the parameter-specific upper limit. The denomination value is retained and is used again within a subsequent D OMVS command.

Use the SETOMVS or SET OMVS command to dynamically increase or decrease the value of MAXASSIZE. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

The MAXASSIZE value limits the combined size of above and below the 16 M line storage. If MAXASSIZE is greater than LDALIMIT (the <16M limit), then the LDAELIM (the >16M limit) is set to MAXASSIZE - LDALIM.

For planning information, see [MAXASSIZE](#) in *z/OS UNIX System Services Planning*.

### **MAXCORESIZE(maxcoresize)**

Specifies the RLIMIT\_CORE soft and hard resource values that are established as the initial values for new processes. RLIMIT\_CORE indicates the maximum core dump file size (in bytes) that a process can create. It also specifies the limit when they are initiated by a daemon process using an `exec()` after a `setuid()`. For more information about RLIMIT\_CORE, see [setrlimit \(BPX1SRL, BPX4SRL\) — Set resource limits in z/OS UNIX System Services Programming: Assembler Callable Services Reference](#).

The value range is a decimal value from 0 to 2147483647 (2 gigabytes). The default is 4194304 (4 megabytes). Specifying a value of 2147483647 (2 gigabytes) indicates an unlimited core file size.

When you define the MAXCORESIZE value, you can set a denomination (or multiplier) value. The C suffix can have a one-character value as presented in [Table 15 on page 125](#), but must not exceed the parameter-specific upper limit. The denomination value is retained and is used again within a subsequent D OMVS command.

Use the SETOMVS or SET OMVS command to dynamically increase or decrease the value of MAXCORESIZE. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

### **MAXCPU**TIME**(*maxcuputime*)**

Specifies the RLIMIT\_CPU resource values that are established as the initial values for new processes. RLIMIT\_CPU indicates the CPU time, in seconds, that a process can use. For more information about RLIMIT\_CPU, see [setrlimit \(BPX1SRL, BPX4SRL\) — Set resource limits in z/OS UNIX System Services Programming: Assembler Callable Services Reference](#).

If the soft limit value from MVS is greater than the MAXCPU**TIME** value, the soft limit is set to the hard limit. This value is also used when processes are initiated by a daemon process using an `exec()` after `setuid()`. In this case, both the RLIMIT\_CPU hard and soft limit values are set to the MAXCPU**TIME** value.

A superuser can override this value by specifying a new time limit in the spawn inheritance structure on `__spawn()`.

For processes that are running in or forked from TSO or BATCH, the MAXCPU**TIME** value has no effect. The TIME limit is inherited from the parent. If a TIME parameter is specified on the JCL for the started task, then that value is used. If not, then the TIME value is taken from the default time value for JES.

For processes created by the `rlogind` command or other daemons, MAXCPU**TIME** is the time limit for the address space.

Specifying a MAXCPU**TIME** or CPU**TIME**MAX of 86400 seconds disables the JWT, SWT, or TWT timeout the same way that JCL TIME=1440 does. See [“Statements and parameters for SMFPRMxx” on page 739](#) for details on the JWT, SWT, and TWT parameters.

*maxcuputime* is a decimal value from 7 to 2147483647 seconds. The default is 1000.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXCPU\*\*TIME\*\*](#) in *z/OS UNIX System Services Planning*.

### **MAXFILE**PROC**(*maxfileproc*)**

Specifies the maximum number of descriptors for files, sockets, directories, and any other file system objects that a single process can have concurrently active or allocated. MAXFILE**PROC** is the same as the OPEN\_MAX variable in the POSIX standard.

The value range is a decimal value from 3 to 524287. The default is 64000.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

On the ADDUSER command, you can increase the maximum number of open descriptors on a per process basis. The FILE**PROC**MAX parameter on the ADDUSER command overrides the MAXFILE**PROC** parameter in the BPXPRMxx profile.

For planning information, see [MAXFILE\*\*PROC\*\*](#) in *z/OS UNIX System Services Planning*.

### **MAXFILE**SIZE**(*maxfilesize*|**NOLIMIT**)**

Specifies the RLIMIT\_FSIZE soft and hard resource values that are established as the initial values for new processes. RLIMIT\_FSIZE indicates the maximum file size (in 4 KB increments) that a process can create. It also specifies the limit when they are initiated by a daemon process using an `exec()` after a `setuid()`. For more information about RLIMIT\_FSIZE, see [setrlimit \(BPX1SRL, BPX4SRL\) — Set resource limits in z/OS UNIX System Services Programming: Assembler Callable Services Reference](#).

The value range is a decimal value from 0 to 2147483647, which indicates an unlimited file size. The default is NOLIMIT.

If MAXFILE**SIZE** is not specified or MAXFILE**SIZE**(NOLIMIT) is specified, there is no limit to the size of files created, except for the architectural limit of the system.

You can set a denomination (or multiplier) value when defining this value. The C suffix can have a one-character value as presented in [Table 15 on page 125](#), but must not exceed the parameter-specific



upper limit. The denomination value is retained and is used again within a subsequent D OMVS command.

If you specify 0, the process does not create any files. Omitting this statement indicates an unlimited file size.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used in IPLs.

### **MAXIOBUFUSER(*maxiobufuser*)**

Specifies that maximum amount of persistent I/O virtual storage that z/OS UNIX obtains on behalf of a user when a process performs I/O in a Unicode Services conversion environment (that is, the AUTOCVT setting is ALL). This storage remains allocated for the life of an open file. The amount that is allocated for each open depends on the CCSID of the file and the size of a read or write requests that are used by the process. The limit does not apply to UID 0 processes.

The value range is 2 to 2 G, representing the number of megabytes of storage. Thus, 2 G represents  $2\text{G} \times 1\text{M} = 2\text{P}$  (petabytes) of storage. The default is 2048, which is equivalent to 2 G of storage).

### **MAXMMAPAREA(*maxmmaparea*)**

Specifies the maximum amount of data space storage space (in pages) that can be allocated for below-the-bar memory mappings of z/OS UNIX files. Storage is not allocated until the memory mapping is active.

Using memory map services causes a large amount of system memory to be consumed. For each page (4 KB) that is memory-mapped, 96 bytes of ESQA are consumed when a file is not shared with any other users. When a file is shared by multiple users, each user after the first causes an additional 32 bytes of ESQA to be consumed for each shared page. Assuming that the default of 40960 pages is taken, and assuming that no sharing is done by mmap() users, a maximum of 3840 KB of ESQA could be consumed. The ESQA storage is consumed when the mmap() function is invoked rather than when the page is accessed by the memory mapping application program.

If you have applications using the \_\_MAP\_MEGA option, you can map very large files without the system overhead in ESQA. For more information, see [Using extended system queue area \(ESQA\) in z/OS UNIX System Services Planning](#).

The value range is a decimal value from 1 to 16777216. The default is 40960.

You can set a denomination (or multiplier) value when defining this value. The C suffix can have a one-character value as presented in [Table 15 on page 125](#), but must not exceed the parameter-specific upper limit. The denomination value is retained and is used again within a subsequent D OMVS command.

You can change the value of MAXMMAPAREA dynamically using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXMMAPARE](#) in *z/OS UNIX System Services Planning*.

### **MAXPIPEUSER(*maxpipeuser*)**

Specifies the maximum number of z/OS UNIX named or unnamed pipes that a real UID can open concurrently. The value only applies to non-UID=0 users. For UID=0 users, the MAXPIPERUSER limit of 8730 is always enforced.

The value range is a decimal value from 256 to 8730. The default is 8730.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXPIPEUSER](#) in *z/OS UNIX System Services Planning*.

### **MAXPROCSYS(*maxprocsys*)**

Specifies the maximum number of processes that the system allows.

The value range is a decimal value from 5 to 32767. The default is 900.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs. If you are using SETOMVS or

SET OMVS to change the value, the new value must be within a certain range, or you get an error message. The range that you can use has a minimum value of 5; the maximum value is based on the following calculation:

```
MIN(32767,MAX(4096,3*initial value))
```

The initial value is the MAXPROCSYS value that was specified during BPXPRMxx initialization. You cannot use a value less than 5. If you want to use a value greater than the current maximum (as calculated by the formula) but lower than the initial maximum (32767), you must change the value in BPXPRMxx and re-IPL. For an example of how to calculate the maximum value in the range, see [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#).

### **MAXPROCUSER(maxprocuser)**

Specifies the maximum number of processes that a single z/OS UNIX user ID can have concurrently active, regardless of how the processes were created. MAXPROCUSER is the same as the CHILD\_MAX variable in the POSIX standard.

The value range is a decimal value from 3 to 32767. The default is 25. A value of 25 is required for FIPS 151-2 compliance and a value of 16 is required for POSIX.1 (ISO/IEC 9945-1:1990[E] IEEE Std 1003.1-1990) standard compliance.

The number of processes is tracked by user ID (UID). When a user attempts to create a new process, the limit value for the user (defined by either the user profile or the default OPTN value) is compared to the value maintained for the user's UID. If the user maximum is larger than the current process count for the UID, the user can create another process. If not, the user is not allowed to create a new process. For example, if user A, with a user-defined limit of 10, tries to create a process and the UID limit is already 12, user A is not allowed to create the new process. Since only 12 processes are currently created, user B, with a user-defined limit of 20, is allowed to create a new process.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

There are certain cases when a new process can be created with a UID that has already reached the MAXPROCUSER number of processes. Super users (with UID=0) and processes blind dubbed with the default OMVS segment are not limited by MAXPROCUSER.

For planning information, see [MAXPROCUSER in z/OS UNIX System Services Planning](#).

### **MAXPTYs(maxpty)**

Specifies the maximum number of pseudoterminals (pseudo-TTYs or PTYs) for the system.

The value range is a decimal value from 1 to 10000. The default is 800.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

If you are using SETOMVS or SET OMVS to change the value, the new value must be within a certain range. If it is outside the range, you get an error message. To use a value that is outside this range, you must change the MAXPTYs specification in BPXPRMxx and re-IPL. The range's minimum value is 1 and the maximum is based on the following calculation:

```
MIN(10000,MAX(256,2*initial value))
```

The initial value is the MAXPTYs value that was specified during BPXPRMxx initialization. For an example of how to calculate the maximum value in the range, see [Dynamically changing certain BPXPRMxx values in z/OS UNIX System Services Planning](#).

For planning information, see [MAXPTYs in z/OS UNIX System Services Planning](#).

### **MAXQUEUEDSIGs(maxqueuedsigs)**

Specifies the maximum number of signals that z/OS UNIX allows to be concurrently queued within a single process.

The value range is a decimal value from 1 to 100000. The default is 1000.



You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for future IPLs.

### **MAXTHREADS(maxthreads)**

Specifies the maximum number of pthread\_created threads, including running, queued, and exited but undetached, that a single process can have concurrently active. Specifying a value of 0 prevents applications from using pthread\_create.

*maxthreads* is a decimal value from 0 to 100000. The default is 200.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXTHREADS](#) in *z/OS UNIX System Services Planning*.

### **MAXTHREADTASKS(maxthreadtasks)**

Specifies the maximum number of MVS tasks that a single process can have concurrently active for threads created by pthread\_create.

*maxthreadtasks* is a decimal value from 0 to 32768. The default is 1000.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXTHREADTASKS](#) in *z/OS UNIX System Services Planning*.

### **MAXUIDS(maxuids)**

Specifies the maximum number of z/OS UNIX user IDs (UIDs) that can operate concurrently.

*maxuids* is a decimal value from 1 to 32767. The default is 200.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

For planning information, see [MAXUIDS](#) in *z/OS UNIX System Services Planning*.

### **MAXUSERMOUNTSYS(maxusermountsys)**

Specifies the maximum number of nonprivileged user mounts for the system or for the shared file system configuration environment. The MAXUSERMOUNTSYS limit applies only to nonprivileged users and does not affect privileged mounts.

The value range is a decimal value from 0 to 35000 that indicates the maximum number of nonprivileged user mounts allowed in the system. For those using a shared file system configuration, this value is the maximum number of nonprivileged user mounts allowed in the shared file system environment. The most recent specification prevails for all of the systems that are participating in a shared file configuration.

The default is 0.

You can change the value dynamically by using the SETOMVS or SET OMVS command. . To make a permanent change, edit the BPXPRMxx member that is used for IPLs. If MAXUSERMOUNTSYS is not specified, default values are used. The default value indicates that user mounts are not allowed in the system.

For planning information, see [MAXUSERMOUNTSYS](#) in *z/OS UNIX System Services Planning*.

### **MAXUSERMOUNTUSER(maxusermountuser)**

Specifies the maximum number of nonprivileged user mounts allowed for each nonprivileged user.

For a single system, the default value is 0. For the first IPLed system in the shared file system configuration, the default value is 0. For a subsequently IPLed system in the shared file system configuration, the default value is what other systems have at the time when the subsequent system is IPLed.

For planning information, see in [MAXUSERMOUNTUSER](#) in *z/OS UNIX System Services Planning*.

**MOUNT FILESYSTEM('fsname') DDNAME(ddname) TYPE(type\_name) MOUNTPOINT('pathname')  
MODE(access) PARM('parameter') TAG(NOTEXT|TEXT,ccsid) SETUID|NOSETUID**

**SECURITY|NOSECURITY AUTOMOVE[(INCLUDE,sysname1,sysname2,...,sysnamen|\*)]  
 [(EXCLUDE,sysname1,sysname2,...,sysnamen)]  
 |NOAUTOMOVE|UNMOUNT SYSNAME(sysname) MKDIR('pathname')**

Specifies a file system that z/OS UNIX is to logically mount onto the root file system or another file system.

Mount statements are processed in the sequence in which they appear. If they are cascading, the system mounts the first file system first. Make sure that a mount point exists before the file system is mounted. If you mount a file system over an existing directory that contains files, you cover up the existing files.

The MOUNT statement is optional; the BPXPRMxx member can contain one or more MOUNT statements. The MOUNT parameters are:

**AUTOMOVE[(INCLUDE|EXCLUDE,sysname1,sysname2,...,{sysnameN| \*})]  
 NOAUTOMOVE|UNMOUNT**

The AUTOMOVE, NOAUTOMOVE, and UNMOUNT parameters apply only in a sysplex where systems are participating in shared file system. The parameters indicate what happens if the system that owns a file system goes down.

AUTOMOVE indicates that ownership of the file system automatically changes to another system that is participating in shared file system. You can specify AUTOMOVE on its own to allow the system to randomly select a new owner for the file system. You can direct the system how to choose a new owner for the file system by using the indicators INCLUDE (I) or EXCLUDE (E).

Specify INCLUDE with a system list to provide a prioritized list of systems to which the file system can be moved if the owning system goes down. For example, AUTOMOVE(INCLUDE,SYS1,SYS4,SYS9) tells the system that the file system can be moved to SYS1, SYS4, or SYS9, in that order, or AUTOMOVE(INCLUDE,SYS1,SYS4,\*) tells the system that the file system can be moved to SYS1 or SYS4, in that order, then to any other available system. This selection is not totally random; rather, MVS attempts to move the file system to a new server system in which the file system is actively in use.

**Restriction:** If specified, the asterisk must be listed last or listed as the only system name in the INCLUDE system list.

Specify EXCLUDE with a system list to provide a list of systems to which the file system cannot be moved. For example, AUTOMOVE(EXCLUDE,SYS3,SYS5,SYS7) tells the system that the file system can be moved to any system except SYS3, SYS5, and SYS7. If the file system cannot be moved as you directed in the system list, the file system is unmounted when the owning system goes down.

NOAUTOMOVE indicates that ownership of the file system is not moved in some situations; as a result, the file system becomes inaccessible.

When specifying NOAUTOMOVE, although the file system becomes inaccessible when the owning system unexpectedly goes down, it still exists in the file system hierarchy. The file system remains unowned until the original owning system re-IPLs. Changing the AUTOMOVE value in BPXPRMxx of an unowned file system before re-IPLing does not change the AUTOMOVE value of this file system since it is already mounted. To change the AUTOMOVE value, the file system must be unmounted before the IPL.

UNMOUNT indicates that the file system should be unmounted in certain situations.

For more information about the behavior of the AUTOMOVE options, see [Managing the movement of data in z/OS UNIX System Services Planning](#).

**Note:**

1. Use AUTOMOVE for the version file system and the sysplex root file system.
2. For file systems that are associated with a single system, specify UNMOUNT. The file systems include /etc, /tmp, /var, /dev, and the system-specific file system. For descriptions of the sysplex root, system-specific, and version file systems, see [Sharing file systems in a sysplex in z/OS UNIX System Services Planning](#).

Default: AUTOMOVE

### **DDNAME(ddname)**

The ddname on the JCL DD statement that defines the file system. To use the DDNAME parameter, a DD statement for the HFS data set containing the mountable file system should be placed in the OMVS cataloged procedure. Either FILESYSTEM or DDNAME is required; do not specify both. The name is 1 to 8 characters; the system converts the ddname to uppercase.

**Restriction:** Because zFS does not support DDNAME, the FILESYSTEM keyword must be used.

### **FILESYSTEM('fsname')**

The name of the file system. The name must be unique in the system.

In the FILESYSTYPE statement, you can mount the following file systems:

- zFS for a z/OS File System (zFS). See [Mount in z/OS File System Administration](#).
- NFS for accessing remote files. See [Mount processing parameters in z/OS Network File System Guide and Reference](#).
- TFS for a temporary file system (TFS). See [Mounting the TFS in z/OS UNIX System Services Planning](#).
- UFS for the union file system. See [Mounting a union file system in z/OS UNIX System Services Planning](#).
- PROC for the PROC file system. See [Managing the PROC file system in z/OS UNIX System Services Planning](#).

Either FILESYSTEM or DDNAME is required; do not specify both. The name is 1 to 44 characters; the characters can be in uppercase, lowercase, or both. Case sensitivity is preserved; file names are not automatically converted to uppercase. The name must be enclosed in single quotation marks.

### **MEMLIMIT=maxmemlimit**

Specifies the maximum amount (*maxmemlimit*) of allocated, nonshared, 1-megabyte storage segments above the bar allowed for the address space. Both the hard and soft RLIMIT\_MEMLIMIT values are set to this value, and the address space *memlimit* is modified to reflect this value.

You can set a denomination (or multiplier) value when you define this value (*maxmemlimitC*), where *maxmemlimit* ranges from 1M - 16383P (noting values are rounded up) and C can have a 1-character value as presented in [Table 15 on page 125](#). Also, be aware that SMF set override limits to the values you set here.

The denomination value is retained and used within a subsequent D OMVS command.

### **MKDIR('pathname')**

Specifies the name of a directory that the system creates dynamically after the file system has been successfully mounted. This allows the system to create mount points that subsequent MOUNT statements can reference. MKDIR is an optional keyword.

You can specify more than one MKDIR keyword on each ROOT or MOUNT statement. The directories are created in the order they are listed. Currently, the maximum number of MKDIR statement that is allowed for each ROOT or MOUNT statement is 50.

You must specify a relative path name; the path name cannot start with a slash (/). Enclose the path name in single quotation marks.

The path name is relative to the file system mount point specified on the MOUNTPPOINT keyword.

The path name can contain intermediate directories, but these intermediate directories must exist in the file system hierarchy. If these intermediate directories do not exist, you can use additional MKDIR keywords to create the necessary intermediate directories.

The directory to be created must be in a file system that was mounted as RDWR. The permission bits for the created directory is 755. The UID and GID is inherited from this directory's parent. These attributes are overlaid when this directory is used as a mount point.

Do not use the MKDIR keyword for file systems that mount asynchronously, such as the NFS file system. When a file system is mounted asynchronously, message BPXF025I is issued to the system log. Similarly, do not use MKDIR with the SYSNAME keyword, when SYSNAME identifies a remote system to perform the mount. The results are unpredictable.

A failure to create a directory does not cause a failure of the mount. A message is written to the system log when a problem occurs during the creation of the directory. If the directory exists, no message is written.

#### **MODE(*access*)**

Specifies access to the mounted file system by all users. With READ access, users can only read the file system that is being mounted. With RDWR access, users can read and write in the file system that is being mounted.

RDWR is the default.

#### **MOUNTPPOINT('pathname')**

Specifies the absolute path name, or a symbolic link that resolves to the path name of the directory onto which the file system is to be mounted.

Mount point restrictions are as follows:

- The mount point must be a directory.
- Any files in the directory are not accessible while the file system is mounted.
- Only one mount can be active at any time for a mount point.
- A file system can be mounted at only one directory at any time.

MOUNTPPOINT is required and must specify an absolute path name. The path name is up to 1023 characters long; the characters can be in uppercase, lowercase, or both.

#### **PARM('parameter')**

Provides a parameter to be passed directly to the file system type. The parameter format and content are specified by the file system type.

PARM is an optional parameter. The parameter is up to 500 characters long; the characters can be in uppercase, lowercase, or both. The parameter must be enclosed in single quotation marks.

For information about specifying the TFS configuration parameters, see [Parameter key options for the FILESYSTYPE statement in z/OS UNIX System Services Planning](#). For example:

##### **-ea *count***

Allows the TFS file system to automatically grow count times.

##### **-em *count***

Allows the TFS file system to manually grow count times.

If the physical file system specified does not expect a PARM operand, it ignores all PARM operands. Refer to the documentation for the specific physical file system for valid entry point names.

#### **FSFULL(*threshold,increment*)**

FSFULL(*threshold,increment*) is supported by TFS and z/OS File System (zFS).

- *threshold* specifies the percentage of the file system (TFS) capacity at which an operator message is generated. The default is 100%.
- *increment* specifies the percentage of change above the file system capacity at which an operator message is generated. Messages are generated by either an increase or decrease greater than *increment*. The default is 5%.

You can specify *threshold* and *increment* values for all file systems. The values can also be set on the MOUNT command for a specific file system. Parameters on the MOUNT command override parmlib values. If no values are specified in either place, no threshold checking is done. If a threshold value is specified but no increment is given, the increment defaults to 5%. The increment value applies both to upgrading the message when the file system

continues to fill and to removing the message when more space becomes available due to either deleting files, or to extending the file system. The values are in terms of percent full. The values that are applied to a file system can be changed only when the file system is mounted.

### **SYSNAME(sysname)**

For systems that are participating in a shared file system, SYSNAME specifies the particular system on which a mount should be performed. This system then becomes the owner of the file system mounted. This system must be IPLed with SYSPLEX(YES).

The default is the name of the system, if IPLed with SYSPLEX(YES), that the mount is processed on.

#### **Notes:**

1. Use the defaults for SYSNAME and AUTOMOVE to ensure that the root is always available.
2. Only specify a SYSNAME() value if you want only the specified system to be the file system owner.
3. During z/OS UNIX initialization processing, the MOUNT statement is ignored if SYSNAME() specifies another system.
4. For SET OMVS and SETOMVS processing, the MOUNT statement is processed and the MOUNT is function-shipped to the system specified by SYSNAME(). If SYSNAME() is used with a value that resolves to another system, do not include any subsequent parmlib MOUNT statements that specify a MOUNTPPOINT() with a path name that includes a directory in this file system.

### **TAG (NOTEXT|TEXT,ccsid)**

Specifies whether implicit file tags are assigned to untagged files in the mounted file system. File tagging controls whether a file's data can be converted during file reading and writing. "Implicit" in this case means that the tag is not permanently stored with the file. Instead, the tag is associated with the file during reading and writing, or when stat() type functions are issued. Either TEXT, or NOTEXT, and ccsid must be specified when TAG is specified.

NOTEXT specifies that none of the files in the file system are automatically converted during file reading and writing.

TEXT specifies that each untagged file is implicitly marked as containing pure text data that can be converted.

ccsid names the coded character set identifier to be implicitly set for the untagged file. ccsid is specified as a decimal value from 0 to 65536. However, when TEXT is specified, the values of 0 and 65536 are not allowed because those values imply no conversion. Other than this, the value is not checked as being valid and the corresponding code page is not checked as being installed.

For example:

- TAG(TEXT,819) identifies text files that contain ASCII (ISO-8859-1) data.
- TAG(TEXT,1047) identifies text files that contain EBCDIC ((ISO-1047) data.
- TAG(NOTEXT,65536) tags files as containing binary or unknown data.
- TAG(NOTEXT,0) is the equivalent of not specifying the TAG parameter.
- TAG(NOTEXT,273) tags the file with the German code set (ISO-273) but is not eligible for automatic conversion.

The default is NOTEXT.

### **SECURITY|NOSECURITY**

SECURITY specifies that security checks should be performed. NOSECURITY specifies that security checks are not performed.

The default is SECURITY.

### **SETUID|NOSETUID**

SETUID specifies that the setuid() and setgid() mode bit on an executable file is supported.

NOSETUID specifies that the setuid() and setgid() mode bit on an executable file is not supported. The UID or GID is not changed when the program is executed and the APF and Program Control extended attributes are not honored. The entire z is uncontrolled.

The default is SETUID.

#### **TYPE(type\_name)**

Specifies the name of a file system type that is identified in a FILESYSTYPE statement.

The TYPE(type\_name) parameter must be the same as the TYPE(type\_name) parameter on a FILESYSTYPE statement. TYPE is a required parameter. The name is 1 to 8 characters; the system converts the name to uppercase.

For more information, see [mount - Logically mount a file system](#) in *z/OS UNIX System Services Command Reference*.

#### **NETWORK DOMAINNAME(sockets\_domain\_name) DOMAINNUMBER(sockets\_domain\_number) MAXSOCKETS(number) TYPE(type\_name) INADDRANYPORT(starting\_port\_number)**

#### **INADDRANYCOUNT(number\_of\_ports\_to\_reserve)**

Specifies that a socket physical file system domain should be readied for use. The TYPE in this statement matches the TYPE on the previous FILESYSTYPE statement.

Use the SETOMVS RESET command to dynamically change the MAXSOCKET value or add a new NETWORK. To make a permanent change, edit the BPXPRMxx member that is used for IPLs. For more information, see [Dynamically adding FILESYSTYPE statements in BPXPRMxx](#) in *z/OS UNIX System Services Planning*.

Provide a NETWORK statement for each socket file system domain to be initialized.

- For AF\_UNIX file systems, always include a FILESYSTYPE statement that specifies ENTRYPOINT(BPXTUINT) and a NETWORK statement with a matching TYPE, usually TYPE(UDS), on both.
- For TCP/IP sockets, always include a FILESYSTYPE statement that specifies ENTRYPOINT(EZBPFINI) and a NETWORK statement with a matching TYPE, usually TYPE(INET), on both.
- To activate an Internet Protocol Version 6 (IPv6) socket on a system, you must configure both the AF\_INET domain and the AF\_INET6 domain. You cannot code a NETWORK statement for domain name AF\_INET6 without coding a NETWORK statement for domain name AF\_INET.
- For CINET sockets, include a FILESYSTYPE statement with ENTRYPOINT (BPXTCINT) and a NETWORK statement with a matching TYPE, usually TYPE(CINET), that specifies INADDRANYPORT and INADDRANYCOUNT. For more information, see [Specifying INADDRANYPORT and INADDRANYCOUNT](#) in *z/OS UNIX System Services Planning*.

#### **DOMAINNAME(sockets\_domain\_name)**

The 1 - 16 character name by which this socket file system domain is to be known.

#### **DOMAINNUMBER(sockets\_domain\_number)**

A number that matches the value that is defined for this domain name. The currently supported values for this field are:

**1**

AF\_UNIX

**2**

AF\_INET

**19**

AF\_INET6

Table 17 on page 145 shows some supported domain names, domain numbers, and their associated entry point names. See the documentation for the physical file system you are using to get the correct entry point name.

Table 17. Supported domains

| Domain name | Domain number | Entry point        |
|-------------|---------------|--------------------|
| AF_UNIX     | 1             | BPXTUINT           |
| AF_INET     | 2             | EZBPFINI, BPXTCINT |
| AF_INET6    | 19            | EZBPFINI, BPXTCINT |

**INADDRANYCOUNT(*number\_of\_ports\_to\_reserve*)**

Specifies the number of ports that the system reserves, starting with the port number specified in the INADDRANYPORT parameter. This value is only needed for CINET.

*number\_of\_ports\_to\_reserve* is a decimal value from 1 to 8000.

If INADDRANYPORT or INADDRANYCOUNT is not specified, the default for INADDRANYCOUNT is 1000. Otherwise, no ports are reserved (0).

**INADDRANYPORT(*starting\_port\_number*)**

Specifies the starting port number for the range of port numbers that the system reserves for use with PORT 0, INADDR\_ANY binds. This value is only needed for CINET.

*starting\_port\_number* is a decimal value from 1024 to 65534. Ports 1 – 1023 are well-known ports that cannot be reserved for use with PORT 0, INADDR\_ANY binds.

If INADDRANYPORT or INADDRANYCOUNT is specified, the default for INADDRANYPORT is 63000. Otherwise, no ports are reserved (0).

If you do not want to support INADDRANY with CINET, you should specify INADDRANYPORT(xx), where xx is a valid value, without specifying INADDRANYCOUNT.

If you are activating IPv6 on a system, the INADDRANYPORT is shared across domains. The INADDRANYPORT value is taken from the NETWORK statement for the AF\_INET domain. Any INADDRANYPORT value that is specified for the AF\_INET6 domain is ignored.

**MAXSOCKETS(*maxsockets*)**

Specifies the maximum number of sockets that are supported by this file system for this address family. You can specify a value from 0 to 16777215. This is an optional parameter. The maximum value for this field is defined by each domain. If a value larger than the maximum is specified, an informational message is issued and the value that is used is the maximum.

Ensure that this number is large enough for socket connections for all applications using your z/OS UNIX environment. This upper limit is set when the NETWORK statement is processed during IPL. It can only be changed if the NETWORK statement is changed using the SETOMVS RESET command.

When the Common Event Adapter (CEA) is active, each CEA client requires two socket connections for communication with the CEA server.

For AF\_UNIX, MAXSOCKETS will be ignored if it is specified. The maximum number of AF\_UNIX sockets is 10000.

When activating IPv6 on a system, you can specify separate MAXSOCKETS values for domains AF\_INET and AF\_INET6. If you do not specify a MAXSOCKETS value for the AF\_INET6 domain, the default is the MAXSOCKETS value specified or defaulted to for the AF\_INET domain.

Table 18 on page 145 shows the maximum and default values for MAXSOCKETS by domain.

Table 18. Maximum and default values for MAXSOCKETS by domain

| Domain name | MAXSOCKETS maximum | MAXSOCKETS default                    |
|-------------|--------------------|---------------------------------------|
| AF_UNIX     | 10000              | 10000                                 |
| AF_INET     | 16777215           | 64000                                 |
| AF_INET6    | 16777215           | Same as the current value for AF_INET |



**TYPE(*type\_name*)**

Specifies the name of a file system type that is identified in a FILESYSTYPE statement. The *type(type\_name)* must be the same as the TYPE(*type\_name*) parameter on a FILESYSTYPE statement. TYPE is a required parameter. The name is 1 to 8 characters; the system converts the name to uppercase.

**NONEMPTYMOUNTPT(NOWARN|WARN|DENY)**

Specifies how the system is to mount any file system on a mount point when it is a nonempty directory. If NONEMPTYMOUNTPT is not specified, default values are used.

**NOWARN**

Causes the system to mount any file system on mount point without any warning message when the mount point is a nonempty directory. The contents of that directory are hidden for the duration of the mount.

**WARN**

Causes the system to mount any file system on mount point with a warning message when the mount point is a nonempty directory. The contents of that directory are hidden for the duration of the mount.

**DENY**

Specifies that the system is not to mount any file system when the mount point is a nonempty directory.

The default is NOWARN.

**PRIORITYGOAL(*service\_class\_name1*,...*service\_class\_name40*)**

Specifies a list of 1 to 40 service class names of 8 characters or less separated by commas, which are used in association with the setpriority, nice and chpriority callable services when the system is running in goal mode. These functions allow a program to alter the priority of one or more processes.

Generally, it is recommended that you not set PRIORITYGOAL unless the nice(), setpriority() or chpriority() values is enabled.

If the list has less than 40 entries, the system propagates the last service class specified into the remaining unspecified entries in the table. For example:

```
PRIORITYGOAL(CICS4,CICS4,CICS4,CICS3,CICS2,CICS1,TS02,TS01,BAT3,BAT2)
```

If you do not specify this statement, arrays are not created for it. All service classes that are specified on the PRIORITYGOAL statement must also be specified in your workload management service policy.

PRIORITYGOAL(NONE) means that there are no values. If you do not specify PRIORITYGOAL, that means that there are no values.

If you do not want to allow users to increase the priority but still want to enable the nice() and setpriority() functions, define a range of service classes with priority increments on a base that is normal for the users. Using these functions lets the user order the priority of processes, but will not let a user improve performance over that of other users.

*service\_class\_name* is a 1 - 8 character value.

There is no default.

Use the SETOMVS or SET OMVS command to dynamically change the value. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

**PWT(SMF|SMFENV|ENV)**

Allows installations to time out z/OS UNIX processes that are waiting on terminal activity. When specified, the timeout value applies to all z/OS UNIX processes that are waiting on terminal activity. To override that value for a specific process, the \_BPXK\_TIMEOUT environment value can be set for an individual process. The PWT value can be changed with the SETOMVS PWT operator command. Unless a BPXK\_TIMEOUT value is set, timeouts do not occur.



**ENV**

Allows the `_BPXK_TIMEOUT` variable be set. Only processes setting the `_BPXK_TIMEOUT` value are timed out.

**SMF**

Honors the SMFPRMxx JWT|TWT|SWT values for the timeout value. The `_BPXK_TIMEOUT` environment value is ignored. An individual process cannot override the system settings.

**SMFENV**

Honors the SMFPRMxx JWT|TWT|SWT value and to allow the `_BPXK_TIMEOUT` settings to override the setting.

The default is ENV.

**RESOLVER\_PROC(*procname*|DEFAULT|NONE)**

Specifies how the resolver address space is processed during z/OS UNIX initialization. The resolver is used by TCP/IP applications for name-to-address or address-to-name resolution. In order to create a resolver address space, a system must be configured with an AF\_INET or AF\_INET6 domain.

**DEFAULT**

Causes an address space named RESOLVER to start, using the system default procedure of IEESYSAS. The address space is started with SUB=MSTR so that it runs under the MASTER address space instead of the JES address space.

**NONE**

Specifies that no address space is to be started. If you are using z/OS Communications Server IP, the resolver must be started before TCP/IP can be started. TCP/IP does not initialize until the resolver address space is started.

***procname***

The name of the address space for the resolver and the procedure member name in the appropriate proclib. *procname* is one to eight characters long. The procedure must reside in a data set that is specified by the MSTJCLxx parmlib member's IEFPSI DD card specification.

**REXXPARSE(SHELL|TSO)**

Uses either the z/OS UNIX shell or TSO criteria to determine whether an executed file is a REXX program.

**SHELL**

The REXX program must begin with a comment on the first line with the opening `/*` followed by any number of spaces, which are immediately followed by the string `'REXX'`. The string is not case-sensitive. For example:

```
/* REXX */
```

**TSO**

The REXX program must begin with a comment on the first line, but the string `'REXX'` can be anywhere in the first line after any other character. The string is not case-sensitive. For example:

```
/* This is a REXX program */
```

The default is SHELL.

Use the SETOMVS or SET OMVS command to dynamically change the value of REXXPARSE. To make a permanent change, edit the BPXPRMxx member that is used for IPLs. If REXXPARSE is not specified, the default value is used.

**RUNOPTS('string')**

Specifies the `_CEE_RUNOPTS` environment variable that is used when z/OS UNIX initialization invokes `/etc/init` or `/usr/sbin/init`. z/OS UNIX passes the `_CEE_RUNOPTS` value and all programs that are invoked from `/etc/rc` to the shell.

To change the value of RUNOPTS, edit the BPXPRMxx member and then re-IPL. You cannot use the SET OMVS or SETOMVS command to change the value. After the value is specified in BPXPRMxx, you can use one of the following methods to change this string:

- The system is re-IPLed with a new BPXPRMxx RUNOPTS string.
- The user or installation sets \_CEE\_RUNOPTS in /etc/rc or /etc/init.config.
- A program or shell script sets \_CEE\_RUNOPTS.

If you do not specify a value for RUNOPTS, the RUNOPTS string or \_CEE\_RUNOPTS environment variable is not provided.

By default, the TSO/E OMVS command uses the specified options as the Language Environment runtime options.

The setting of RUNOPTS does not affect BPXBATCH jobs.

Specifying the RUNOPTS parameter causes the kernel to set the \_CEE\_RUNOPTS environment variable when starting /etc/init, or when the TSO/E OMVS command is entered. This environment variable is normally propagated to subsequent processes (such as /etc/init to /bin/sh to /etc/rc to /bin/inetd to /bin/rlogind to /bin/sh for shell users).

To do this, make sure that any other steps in the flow (such as export statements in /etc/rc) do not overwrite the value of \_CEE\_RUNOPTS. If more runtime options are needed, they should be concatenated to the old value of \_CEE\_RUNOPTS.

The value is from 1 to 250 characters. There is no default; a RUNOPTS string or \_CEE\_RUNOPTS environment variable is not provided.

#### Restrictions:

- The string must be enclosed in parentheses and quotation marks ("").
- An empty string ( ' ') is not valid.
- Although all characters are allowed, nulls, slashes (/), unbalanced SO/SI, and unbalanced parentheses and quotation marks cause unpredictable problems in areas such as the TSO/E OMVS command.

For more information about specifying RUNOPTS strings, see [Customizing the BPXPRMxx member of SYS1.PARMLIB in z/OS UNIX System Services Planning](#).

**ROOT FILESYSTEM('fsname') DDNAME(ddname) TYPE(type\_name) MODE(access) PARM('parameter') SETUID|NOSETUID SECURITY|NOSECURITY AUTOMOVE|NOAUTOMOVE SYSNAME(sysname) TAG(NOTEXT|TEXT,ccsid) MKDIR('pathname')**

Specifies a file system that z/OS UNIX is to logically mount as the root file system. It is optional. If it is not specified, a TFS file system is mounted as the root.

To change the value of the ROOT statement without having to re-IPL, use the TSO/E MOUNT and UNMOUNT commands.

The root file system can be unmounted using the TSO/E UNMOUNT command or ISHELL. Ensure that you specify the IMMEDIATE option.

The ROOT statement does not support the SYSNAME() keyword.

The parameters are as follows:

#### **DDNAME(ddname)**

The ddname on the JCL DD statement that defines the root file system. To use the DDNAME parameter, put a DD statement for the HFS data set containing the root file system in the z/OS UNIX cataloged procedure.

Either FILESYSTEM or DDNAME is required; do not specify both. The ddname is 1 to 8 characters; the system converts the ddname to uppercase.

**zFS restriction:** zFS does not support DDNAME; the FILESYSTEM keyword must be used.

#### **FILESYSTEM('fsname')**

The name of the root file system. The name must be unique in the system.

You can specify the following types of the file system:

- zFS for a z/OS File System (zFS).
- NFS for accessing remote files.
- TFS for a temporary file system (TFS).

Either FILESYSTEM or DDNAME is required; do not specify both. The name is 1 - 44 characters; the characters can be in uppercase, lowercase, or both. The name must be enclosed in single quotation marks. An HFS data set name must conform to the rules of MVS data set names.

### **MKDIR('pathname')**

Specifies the name of a directory that the system will create dynamically after the file system is successfully mounted. This allows the system to create mount points that can be referenced by subsequent MOUNT statements. MKDIR is an optional keyword.

You can specify more than one MKDIR keyword on each ROOT statement. The directories are created in the order they are listed.

You must specify a relative path name; the path name cannot start with a slash (/). Enclose the path name in single quotation marks.

The path name is relative to the file system mount point specified on the MOUNTPPOINT keyword.

The path name can contain intermediate directories, but these intermediate directories must exist in the file system hierarchy. If these intermediate directories do not exist, you can use additional MKDIR keywords to create the necessary intermediate directories.

The directory to be created must reside in a file system that was mounted as RDWR. The permission bits for the created directory is 755. The UID and GID is inherited from this directory's parent. These attributes are overlaid when this directory is used as a mount point.

Do not use the MKDIR keyword for file systems that mount asynchronously, such as the NFS file system. When a file system is mounted asynchronously, message BPXF025I is issued to the system log. Also, do not use MKDIR with the SYSNAME keyword, when SYSNAME identifies a remote system to perform the mount. The results are unpredictable.

A failure to create a directory does not cause a failure of the mount. A message is written to the system log when a problem occurs when the directory is created. If the directory exists, no message is written.

**Restriction:** MKDIR works only on systems that are at z/OS Version 1 Release 5 level or later. If you are using MKDIR in a sysplex that shares a common BPXPRMxx member, make sure that all systems are at least at the z/OS V1R5 level.

### **MODE(access)**

Specifies access to the root file system by all users. With READ, users can only read the root file system. With RDWR, users can use and write in the root file system.

RDWR is the default.

### **PARM('parameter')**

Provides a parameter to be passed directly to the file system type. The parameter format and content are specified by the file system type.

PARM is an optional parameter. The parameter is up to 500 characters long; the characters can be in uppercase, lowercase, or both. The parameter must be enclosed in single quotation marks.

If the physical file system specified does not expect a PARM operand, it ignores all PARM operands. Refer to the documentation for the specific physical file system for valid entry point names.

### **SCEXITTABLE('sc\_exittable')**

Specifies the path name of a z/OS UNIX file. This file is intended to contain a list of z/OS UNIX syscall stubs that a user wants to enable syscall exits for. The stub names must be in all caps. If a null path name is specified, SC\_EXITTABLE is reset to null.

You can change the SC\_EXITTABLE path name dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that will be used for IPLs.

Changes to the SC\_EXITTABLE file are not applied immediately. If a change needs to be activated sooner, use the SETOMVS or SET OMVS command to apply the change immediately.

#### **SERV\_LINKLIB('dsname','volser')**

Specifies the target service library where the z/OS UNIX modules that are normally loaded from SYS1.LINKLIB into the private area of the OMVS address space are located.

If a null *dsname* is specified, SERV\_LPALIB is reset to null. It does not matter what is specified for *volser* if *dsname* is null.

*dsname* is a 1-to-44 character value that represents a valid MVS load library data set name. The alphabetic characters in the load library name must be uppercase. *volser* is a 1-to-6 character value that represents a valid volume serial number for the volume that contains the specified MVS load library. The alphabetic characters in the volume serial number must be uppercase.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that will be used for future IPLs.

#### **SERV\_LPALIB('dsname','volser')**

Specifies the target service library where the z/OS UNIX modules that are normally built into LPA are located.

*dsname* is a 1-to-44 character value that represents a valid MVS load library data set name. The alphabetic characters in the load library name must be uppercase. *volser* is a 1-to-6 character value that represents a valid volume serial number for the volume that contains the specified MVS load library. The alphabetic characters in the volume serial number must be uppercase.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that will be used for future IPLs.

If a null *dsname* is specified, SERV\_LNKLIB is reset to null. It does not matter what is specified for *volser* if *dsname* is null.

### **SECURITY|NOSECURITY**

#### **SECURITY**

Security checks are performed. SECURITY is the default.

#### **NOSECURITY**

Security checks are not performed.

### **SETUID|NOSETUID**

#### **SETUID**

Specifies that the `setuid()` and `setgid()` mode bit on an executable file will be supported.

#### **NOSETUID**

Specifies that the `setuid()` and `setgid()` mode bit on an executable file will not be supported. The UID or GID will not be changed when the program is executed and the APF and program control extended attributes are not honored. The entire file system is uncontrolled.

SETUID is the default.

### **SHRLIBMAXPAGES(*shrlibmaxpages*)**

If you specify the SHRLIBMAXPAGES parameter, it is accepted but will not have any impact on the system. The value that you specify will never be reached, because user-shared library objects are no longer supported. This parameter is intended to control the maximum number of pages that can be allocated in the system to contain user shared library modules.

*shrlibmaxpages* is a decimal value between 1 and 16777216 that specifies a number of 4 K pages. The default is 4096.

### **SHRLIBRGNSIZE(*shrlibrgnsize*)**

Specifies the maximum size of the shared library region for address spaces that load system shared library modules. For these address spaces, the size that is specified is allocated from

high private storage and is used for the loading of system shared library modules. This storage is not allocated in an address space until it loads a system shared library module. This parameter applies to modules loaded from system shared libraries, which allocate storage on megabyte boundaries.

*shrlibrgnsize* is a decimal value between 16777216 (16 megabytes) and 1610612736 (1.5 gigabytes). The specified value (if within the range) is rounded up to a megabyte boundary. The default is 67108864.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

Because the shared library region is allocated in megabytes, the value for SHRLIBRGNSIZE must be evenly divisible by 1048576. Otherwise, the D OMVS,L command might show values in the Current Usage and Highwater Usage columns that are larger than the value in the System Limit column.

### **SMFUPDATE(ON|OFF)**

SMFUPDATE(ON) allows users with UPDATE authority to the BPX.SMF.type.subtype FACILITY class to invoke `smf_record()` without requiring a clean program-controlled environment.

If SMFUPDATE(ON) is not specified in the active BPXPRMxx member, users of `smf_record()` that are permitted to the BPX.SMF.type.subtype FACILITY class with any access authority will require a clean program-controlled environment.

OFF is the default.

### **STARTUP\_EXEC**

STARTUP\_EXEC names a REXX exec that does application environment initialization for z/OS UNIX. This statement is optional; if it is specified, the BPXOINIT process will not run `/etc/init`. The startup exec is typically used by an installation that does not have a file system, but is using a TFS for a file system. It can be used to populate the TFS with any directories and files that are needed. It is specified as:

```
STARTUP_EXEC('Dcname(Memname)',SysoutClass)
```

where:

- Dcname is a 1-to-44-character valid data set name.
- Memname is a 1-to-8-character valid REXX exec member.
- SysoutClass is 1 character and is alphanumeric and specifies the sysout class that the REXX exec will run under. Specifying SysoutClass is optional.

To change the value of STARTUP\_EXEC, edit the BPXPRMxx member and then reIPL. You cannot use the SET OMVS or SETOMVS command to change the value.

STARTUP\_EXEC does not have a default value.

### **STARTUP\_PROC**

This statement specifies a 1-to-8-character name of a started JCL procedure that initializes the kernel. The name specified in this statement must exist on the system before IPL or errors will occur.

Using a started procedure other than OMVS is strongly discouraged. If you want to change the value of STARTUP\_PROC, you must edit the BPXPRMxx member and then re-IPL. You cannot use the SET OMVS or SETOMVS command to change the value.

If you decide to use a started procedure other than OMVS:

- The replacement started procedure must also be a single job step procedure that invokes the BPXINIT program (EXEC PGM=BPXINIT). If it invokes any other program, the OMVS initialization will fail.

- Change the procedure name in the RACF started procedures table or the definitions in the STARTED Class. For more information, see [Preparing for RACF in z/OS UNIX System Services Planning](#).

**Note:** Renaming OMVS to another value might affect the setup of other products such as TCP/IP.

The default is STARTUP\_PROC(OMVS).

## STEPLIBLIST

Specifies the path name of the file in the file system that contains the list of MVS data sets to be used as step libraries for programs that have the set-user-id and set-group-id bit set on.

For planning information, see [STEPLIBLIST](#) in *z/OS UNIX System Services Planning*.

## SUBFILESYSTYPE NAME(*transport\_name*) TYPE(*type\_name*) ENTRYPOINT(*entry\_name*) PARM('parameter') DEFAULT

Specifies an AF\_INET or AF\_INET6 physical file system that is to run underneath the CINET socket file system. The TYPE() value is usually CINET and matches the TYPE operand on a previous FILESSTYPE and NETWORK statement. In the case of TCP/IP, the NAME() value is the *procname*. The system attaches the EZBPFINI load module during initialization, and this file system should be used as the default INET physical file system.

The SUBFILESYSTYPE statement is associated with its corresponding FILESSTYPE and NETWORK statements by matching the value that is specified in the TYPE operand.

The value that is specified on all of the TYPE operands must match, but can be any 1- to 8-character value. The value that is specified on the NAME parameter on the SUBFILESYSTYPE statement is the name to be used by the physical file system when it is initialized. The first character of the NAME parameter must be non-numeric.

For SecureWay Communications Server, the SUBFILESYSTYPE statement must match the TCPIPJOBNAME of that stack. For more information about defining file systems, see [Customizing the BPXPRMxx member of SYS1.PARMLIB](#) in *z/OS UNIX System Services Planning*.

New SUBFILESYSTYPE statements can be added dynamically. However, you cannot dynamically change or delete a value. For more information, see [Dynamically adding FILESSTYPE statements](#) in *BPXPRMxx* in *z/OS UNIX System Services Planning*.

The parameters are as follows:

### DEFAULT

Identifies this file system as the default CINET file system. DEFAULT is an optional parameter. If it is not specified, the file system that is specified in the first SUBFILESYSTYPE statement found in the parmlib member is designated as the default.

### ENTRYPOINT(*entry\_name*)

Specifies the name of the load module that contains the entry point into the file system type. ENTRYPOINT is a required parameter. The name is 1 to 8 characters; the system converts the name to uppercase.

### NAME(*transport\_name*)

Specifies the name that identifies this file system to the CINET physical file system.

NAME is a required parameter. The name is 1 to 8 characters with the first character non-numeric; the system converts the name to uppercase. The value that is specified by the NAME parameter on the SUBFILESYSTYPE statement is the name that the physical file system uses to identify itself when it is initialized. For example, for TCP/IP, this is the starting procedure name.

### PARM('parameter')

Provides a parameter to be passed to the transport driver. The parameter format and content are specified by the file system that is receiving the data.

PARM is an optional parameter. The parameter is up to 1024 characters long; the characters can be in uppercase, lowercase, or both. If the characters are not all in uppercase, the parameter must be enclosed in single quotation marks.

If the physical file system specified does not expect a PARM operand, it ignores all PARM operands. Refer to the documentation for the specific physical file system for valid entry point names.

### **TYPE(*type\_name*)**

Specifies the name of the CINET file system type that is identified in a FILESYSTYPE statement. The TYPE(*type\_name*) parameter must be the same name that was used for the TYPE(*type\_name*) parameter on the FILESYSTYPE statement for the CINET physical file system. TYPE is a required parameter. The name is 1 to 8 characters; the system converts the name to uppercase.

For more information, see [SUBFILESYSTYPE](#) in *z/OS UNIX System Services Planning*.

### **SUPERUSER(*superuser*)**

The name of the superuser, which must conform to the restrictions for the z/OS user ID. The user name must also be defined to RACF (or another security product) and must have a z/OS UNIX user ID (UID) of 0. For example, in RACF, specify OMVS(UID(0)) on the ADDUSER command.

When a daemon issues a `setuid()` to set a UID to 0 and the user ID is not known, `setuid()` uses the user ID from the SUPERUSER statement.

Never permit the user ID BPXROOT to the BPX.DAEMON profile. The BPX.DAEMON profile is described in [BPX.DAEMON](#) in *z/OS UNIX System Services Planning*. This warning applies even if you use a name other than BPXROOT.

The USS\_SUPERUSER health check verifies that the SUPERUSER option contains a user ID that is defined to the security product and has an OMVS segment with a UID of 0. For more information about the health check, see [USS\\_SUPERUSER](#) in *IBM Health Checker for z/OS User's Guide*.

*superuser* is a 1 - 8 character value. The default is BPXROOT.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

### **SWA(ABOVE|BELOW)**

Specifies whether SWA control blocks should be allocated above or below the 16-megabyte line. The SWA parameter only affects the OMVS address space and its SWA blocks. It has no impact on the colony address spaces.

#### **ABOVE**

All SWA control blocks are allocated above the 16-megabyte line.

#### **BELOW**

All SWA control blocks are allocated below the 16-megabyte line.

BELOW is the default.

### **SYSCALL\_COUNTS(YES|NO)**

Specifies that syscall counts are to be accumulated in internal kernel data areas so that the RMF data gatherer can record the information.

#### **NO**

The counts for syscall and CPU time are not accumulated.

#### **YES**

The path length for the most frequently used z/OS UNIX system calls is increased by more than 150 instructions, which makes the reporting of CPU time for z/OS UNIX more accurate. This is reflected in the output from the BPX1TIM, BPX1GPS, BPX1GTH, and BPX1RMG services and from BPXESMF.

If you switch between YES and NO for actively running processes, the accumulated data is inaccurate.

The SMF30OST field of the SMF type 30 record can be seen as a negative number when the CPU time used to compute the time value is less than the previous CPU time and in some cases can even appear as zero (for example, when SYSCALL\_COUNTS is set to NO after having been YES for an earlier part of the run.) In addition, if SYSCALL\_COUNTS=YES, the SMF30OST value

is calculated from OCVTSYSTIME (accumulated syscall time for all syscalls issued in the system) rather than from OASBSYSCALLCOUNT (syscalls for the current process).

NO is the default.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

### **SYSPLEX(YES|NO)**

For z/OS UNIX, the SYSPLEX statement specifies whether a system is to join the SYSBPX XCF group to share resources across the sysplex.

#### **NO**

The system does not participate in a shared file system. If the SYSPLEX statement is not provided, the default is SYSPLEX(NO)

#### **YES**

The system participates in a shared file system.

NO is the default.

For more information about shared file systems, see [Sharing file systems in a sysplex in z/OS UNIX System Services Planning](#). It contains information about parameters specific to the shared file system: SYSPLEX, VERSION, AUTOMOVE, NOAUTOMOVE, and SYSNAME.

You cannot adjust the SYSPLEX field dynamically. There is no SETOMVS, SET OMVS, or SETOMVS RESET=(xx) capability. To change the value of SYSPLEX, you must re-IPL the system.

### **TAG (NOTEXT|TEXT,ccsid)**

Specifies whether implicit file tags are assigned to untagged files in the mounted file system. File tagging controls whether a file's data can be converted during file reading and writing. "Implicit" in this case means that the tag is not permanently stored with the file. Instead, the tag is associated with the file during reading and writing, or when stat() type functions are issued. Either TEXT, or NOTEXT, and ccsid must be specified when TAG is specified.

#### **ccsid**

Names the coded character set identifier to be implicitly set for the untagged file. ccsid is specified as a decimal value from 0 to 65536. However, when TEXT is specified, the values of 0 and 65536 are not valid because those values imply no conversion. Other than this, the value is not checked as being valid and the corresponding code page is not checked as being installed.

#### **NOTEXT**

None of the files in the file system is automatically converted during file reading and writing.

#### **TEXT**

Each untagged file is implicitly marked as containing pure text data that can be converted.

For example:

- TAG(TEXT,819) identifies text files that contain ASCII (ISO-8859-1) data.
- TAG(TEXT,1047) identifies text files that contain EBCDIC ((ISO-1047) data.
- TAG(NOTEXT,65536) tags files as containing binary or unknown data.
- TAG(NOTEXT,0) is the equivalent of not specifying the TAG parameter.
- TAG(NOTEXT,273) tags file with the German code set (ISO-273) but is not eligible for automatic conversion.

The default is NOTEXT.

### **TYPE(type\_name)**

Specifies the name of a file system type that is identified in a FILESYSTYPE statement. The TYPE(type\_name) parameter must be the same as the TYPE(type\_name) parameter on a FILESYSTYPE statement.



TYPE is a required parameter. The name is 1 - 8 characters; the system converts the name to uppercase.

### **TTYGROUP(*group\_name*)**

Specifies the z/OS UNIX group name that is given to subsidiary pseudoterminals (ptys) and OCS remote terminals (rtys). This group name must be defined to the security product and have a unique group ID (GID). No users should be connected to this group.

The *group\_name* is used by certain `setgid()` programs, such as `talk` and `write`, when writing to another user's pty or RTTY.

*group\_name* is a 1 to 8-character value. TTY is the default.

You can change the value dynamically by using the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that will be used for future IPLs.

### **USERIDALIASTABLE('/etc/*tablename*')**

Specifies the path name of a z/OS UNIX file. This file is intended to contain a list of z/OS UNIX user IDs and group names with their corresponding alias names. The alias names can contain any characters in the portable file name character set.

You can change USERIDALIASTABLE dynamically with the SETOMVS or SET OMVS command. To make a permanent change, edit the BPXPRMxx member that is used for IPLs.

Once a user is logged into the system, changing the user ID or group name alias table does not change the alias name immediately. If a change needs to be activated sooner, you can use the SETOMVS or SET OMVS command to change the table more quickly.

For planning information, see [USERIDALIASTABLE](#) in *z/OS UNIX System Services Planning*.

### **UMASK(*umask*)**

Specifies a default umask value for all z/OS UNIX users. Use this setting to better control the files and directories that users on your system can access. Existing facilities that set the umask value will continue to override the system default.

For example, the z/OS UNIX shell, `/bin/sh`, first issues a `umask` call (BPX1UMK) to initially establish the process umask to 000 to override the umask that is specified in BPXPRMxx. The shell then processes the `/etc/profile` file. If a `umask` command is specified, the specified value becomes the process umask value. If `/etc/profile` does not contain a `umask` command, the shell will keep the established umask of 000 as the process umask value.

Changing the default umask value might have unexpected results on your applications. A umask value that is consistent with the umask value that is set in `/etc/profile` might be appropriate.

*umask* is a 3-to-4 digit octal number that specifies the permission settings of files or directories that are created by users or processes that are not to be allowed.

*umask* can also be set to NONE to indicate that no system default umask was specified. NONE provides the capability to remove a prior umask specification for new processes. UMASK(NONE) differs from UMASK(000) in that specifying UMASK(NONE) causes `0extUmaskConf` to be reset, which indicates to applications such as Language Environment that no system umask value is in effect. For more information about how Language Environment handles umask processing, see [umask\(\) - Set and retrieve file creation mask in z/OS XL C/C++ Runtime Library Reference](#).

In addition, if a umask value is not specified in BPXPRMxx, the default is NONE, which indicates that no umask default is in effect.

Specify the value by ORing together the following bits:

#### **4000**

Set-user-ID bit.

#### **2000**

Set-group-ID bit.

#### **1000**

Sticky bit.

**0400**

User read.

**0200**

User write.

**0100**

User execute.

**0040**

Group read.

**0020**

Group write.

**0010**

Group execute.

**0004**

Other read.

**0002**

Other write.

**0001**

Other execute.

For example, UMASK(007) will give no access to other.

**VERSION('version'[UNMOUNT|NOUNMOUNT])**

The VERSION statement applies only to systems that are exploiting shared file systems. VERSION allows multiple releases and service levels of the binaries to coexist and participate in a shared file system. A directory with the value *version* specified on VERSION is dynamically created at system initialization under the sysplex root that is used as a mount point for the version file system. However, this directory is only dynamically created if the sysplex root file system is mounted read/write.

Specify UNMOUNT to turn on the version auto-unmount option, which will cause the VERSION\_AUTO\_UNMOUNT attribute to be set for the version file system if it is mounted on this system. If unspecified, NOUNMOUNT is the default at system initialization. If the version string 'version' is '/' (slash), the version auto-unmount option is set to NOUNMOUNT regardless of what is specified.

**Note:** *version* is a case-sensitive character string no greater than 8 characters in length that indicates a specific instance of the version file system. The most appropriate values for *version* are the name of the target zone, &SYSR1, or another qualifier meaningful to the system programmer. For example, if the system is at V2R9, you can specify REL9 for VERSION.

When SYSPLEX(YES) is specified, you must also specify the VERSION parameter.

The VERSION value is substituted in the content of symbolic links that contain \$VERSION. For scenarios that describe the use of the version file system, see [Sharing file systems in a sysplex in z/OS UNIX System Services Planning](#).

If you are testing or changing to a new maintenance level, dynamically change the VERSION value by using the SETOMVS command.

```
SETOMVS VERSION='string'
```

You can also dynamically turn on or off the VERSION\_AUTO\_UNMOUNT attribute by using the SETOMVS command.

```
SETOMVS VERSION=('string',UNMOUNT|NOUNMOUNT)
```

Using the SETOMVS command:

- If 'string' is specified but not UNMOUNT or NOUNMOUNT, then the current version auto-unmount option is used.

- You can specify \* instead of 'string' in order to change only the version auto-unmount option.

You can also change the settings of this parameter by using SET OMVS=(xx) and SETOMVS RESET=(xx) parmlib specifications.

**Restriction:** Do not change VERSION dynamically if you have any users that are logged on or running applications because replacing the system files for these users might be disruptive.



## Chapter 14. CEAPRMxx (common event adapter parameters)

Use the CEAPRMxx parmlib member to customize common event adapter (CEA) values. CEA provides the ability to deliver z/OS events to C-language clients, such as the z/OS CIM server. CEA also provides instrumentation services used by the IBMzOS\_Incident CIM provider. The CEA address space is started automatically during z/OS initialization.

### Syntax rules for CEAPRMxx

Follow the rules in “General syntax rules for the creation of members” on page 7. The following rules also apply to the creation of CEAPRMxx parmlib members:

- If a statement that has a default is omitted, the default is used.
- Enter data only in columns 1 - 71. The system ignores data in columns 72 - 80.
- You can enter one or more statements on a line, or use several lines for one statement.
- Use blanks as delimiters. The system interprets multiple blanks as a single blank. You can use blanks between parameters and values. For example, both of the following parameter specifications are equally valid:

```
SNAPSHOT (Y)
SNAPSHOT(Y)
```

- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.
- Enter values in uppercase, lowercase, or mixed case. The system converts input to uppercase, except for values that are enclosed in single quotation marks, which are processed without altering the case.
- Enclose values in single quotation marks, using the following rules
  - Two single quotation marks next to each other on the same line are processed as a single quotation mark. For example, the system interprets John ' 's file as John's file.
  - If you enter a single quotation mark in column 71, and another in column 1 of the next line, the system does not treat these two quotation marks as one single quotation mark, as above. Instead, the system interprets this input as quotation marks from two separate strings or as an error.
- When you specify multiple CEAPRMxx parmlib members using concatenation, the system will apply the values in the order in which they are specified. That means that when there are duplicate parameters specified, the last value specified is the one that the system applies.
- When CEA is restarted, it attempts to determine and use parmlib options that were in effect when it terminated. If it fails, the CEA IPL parmlib concatenation is used.

**Note:** When you specify CEA=(xx) in IEASYSxx, do not specify a suffix of NO.

### Syntax format of CEAPRMxx

```
SNAPSHOT ({Y | N})
HLQLONG(CEA)
HLQ(CEA)
BRANCH(branchoffice),COUNTRYCODE(countrycode)
DUMPCAPTURETIME(
  SLIP(OPERLOG(hh:mm:ss) LOGREC(hh:mm:ss) LOGRECSUMMARY(hh:mm:ss))
  DUMP(OPERLOG(hh:mm:ss) LOGREC(hh:mm:ss) LOGRECSUMMARY(hh:mm:ss))
  ABEND(OPERLOG(hh:mm:ss) LOGREC(hh:mm:ss) LOGRECSUMMARY(hh:mm:ss))
)
STORAGE({STORCLAS(stgclass)|VOLSER(volume[,volume[,volume[...]]])})
TSOASMGR(MAXSESSIONS(n) MAXSESSPERUSER(n) RECONSESSIONS(n) RECONTIME(hh:mm:ss))
```

## IBM-supplied defaults for CEAPRMxx

The default CEAPRM00 parmlib member provided in SYS1.PARMLIB contains the following line:

```
SNAPSHOT(N)
```

This value must be set to Y when the CIM provider for IBMzOS\_Incident is set up.

## Statements and parameters for CEAPRMxx

### BRANCH(*branchoffice*),COUNTRYCODE(*countrycode*)

Specifies the branch and country code for use in sending data to the IBM Support Center.

- BRANCH (*branchoffice*) specifies the branch office, typically a three character value.
- COUNTRYCODE (*countrycode*) specifies the country code, typically a three character value.

There are no defaults for these values.

### DUMPCAPTURETIME

Specifies the amount of diagnostic data to be captured for different types of dumps. This statement contains one or more of the following operands:

#### ABEND

Specifies the amount of diagnostic data to be captured with system ABEND dumps, measured in time (hours, minutes). The default amounts are 30 minutes of Operlog, one hour of Logrec detail and a 4-hour Logrec summary report.

This statement contains the following operands:

#### LOGREC

Specifies the amount of LOGREC data to be captured with the dump type. The maximum value of LOGREC is 24 hours.

#### LOGRECSUMMARY

Specifies the amount of LOGRECSUMMARY data to be captured with the dump type. The maximum value of LOGRECSUMMARY is 4 hours.

The amount of data captured depends on how the LOGREC information is configured on your system. If the LOGREC information is written to a logstream, the value is rounded to the nearest 1-hour interval. If the LOGREC information is written to a logger data set, the value closely approximates the capture time for the request and is not rounded.

#### OPERLOG

Specifies the amount of OPERLOG data to be captured with the dump type. The maximum value of OPERLOG is 24 hours.

### DUMP

Specifies the amount of diagnostic data to be captured with DUMP command dumps, measured in time (hours, minutes). The default amounts are 30 minutes of Operlog, one hour of Logrec detail and a 4-hour Logrec summary report.

This statement contains the following operands:

#### LOGREC

Specifies the amount of LOGREC data to be captured with the dump type. The maximum value of LOGREC is 24 hours.

#### LOGRECSUMMARY

Specifies the amount of LOGRECSUMMARY data to be captured with the dump type. The maximum value of LOGRECSUMMARY is 4 hours.

The amount of data captured depends on how the LOGREC information is configured on your system. If the LOGREC information is written to a logstream, the value is rounded to the

nearest 1-hour interval. If the LOGREC information is written to a logger data set, the value closely approximates the capture time for the request and is not rounded.

### **OPERLOG**

Specifies the amount of OPERLOG data to be captured with the dump type. The maximum value of OPERLOG is 24 hours.

### **SLIP**

Specifies the amount of diagnostic data to be captured with SLIP dumps, measured in time (hours, minutes). The default amounts are 30 minutes of Operlog, one hour of Logrec detail and a 4-hour Logrec summary report.

This statement contains the following operands:

### **LOGREC**

Specifies the amount of LOGREC data to be captured with the dump type. The maximum value of LOGREC is 24 hours.

### **LOGRECSUMMARY**

Specifies the amount of LOGRECSUMMARY data to be captured with the dump type. The maximum value of LOGRECSUMMARY is 4 hours.

The amount of data captured depends on how the LOGREC information is configured on your system. If the LOGREC information is written to a logstream, the value is rounded to the nearest 1-hour interval. If the LOGREC information is written to a logger data set, the value closely approximates the capture time for the request and is not rounded.

### **OPERLOG**

Specifies the amount of OPERLOG data to be captured with the dump type. The maximum value of OPERLOG is 24 hours.

## **HLQ(CEA)**

Specifies the high-level qualifier for all log snapshot data sets that are created when SNAPSHOT(Y) is specified. These data sets are of snapshot log streams, prepared data sets used for service, and other associated diagnostic information.

You can adjust this to a different 1- to 4-character qualifier of your own choice. The first character cannot be a number. This value will default to CEA.

If both the HLQLONG and HLQ statements are specified, processing will be done according to the following rules:

- All new diagnostic information will be constructed with the HLQLONG high-level qualifier.
- When searching for specific diagnostic information, the search will first be performed with the HLQLONG value as the high-level qualifier. If no search results are found, a second search will be performed using the HLQ value as the high-level qualifier. If both searches yield no results, the information does not exist.

## **HLQLONG(CEA)**

Specifies the high-level qualifier for all log snapshot data sets that are created when SNAPSHOT(Y) is specified. These data sets are of snapshot log streams, prepared data sets used for service, and other associated diagnostic information.

You can adjust this to a different 1- to 8-character qualifier of your own choice. The first character cannot be a number. This value will default to CEA.

If both the HLQLONG and HLQ statements are specified, processing will be done according to the following rules:

- All new diagnostic information will be constructed with the HLQLONG high-level qualifier.
- When searching for specific diagnostic information, the search will first be performed with the HLQLONG value as the high-level qualifier. If no search results are found, a second search will be

performed using the HLQ value as the high-level qualifier. If both searches yield no results, the information does not exist.

**Note:** You are not required to migrate to the longer high-level qualifier. To continue to use your existing configuration, do not specify the HLQLONG statement.

### SNAPSHOT({Y | N})

Specifies whether or not you want CEA to preserve snapshots of log information about incidents.

- If Y, every time an SVC Dump is taken, CEA will capture the specified amount of operlog, logrec detail, and logrec summary information for review by the IBM Support Center, if necessary. N is the default. Y is the recommended setting when using the CIM IBMzOS\_Incident support. The default amounts are 30 minutes of Operlog, one hour of Logrec detail and a 4-hour Logrec summary report. (The System Logger needs to be set up before OPERLOG or LOGREC snapshots can be taken.)
- If N, the log data will not be captured and will not be available for review by the IBM Support Center.

### STORAGE

Specifies the settings for the system to use when allocating incident data sets. This statement contains only one of the following operands:

#### STORCLAS(stgclass)

Specifies the SMS class you request the system to use for allocation of incident data sets. *stgclass* is the one- to eight-character name of the SMS storage class that you request to add.

#### VOLSER(volume[,volume[,volume[...]]])

Specifies the non-SMS-managed direct access volumes to use for automatic allocation of various incident related data sets. Allocation assigns space from the first volume in the list until that volume is full, and then uses the next volume.

*volume* is the 1-6 character volume serial identifier of the direct access volume that you want to add to the system's list of resources for automatic allocation. You can specify one to eight direct access volume serial identifiers. Separate the volume serial identifiers with commas.

**Note:** The storage specified is used to indicate where various data sets are to be allocated during processing. Storage is used for logrec snapshot reports, prepared data sets for the dumps, the logrec reports, the operlogs, and table information.

### TSOASMGR

Specifies the settings to use for the CEA TSO/E address space manager. For information about the CEA TSO/E address space manager, see [z/OS MVS Programming: Callable Services for High-Level Languages](#).

This statement contains one or more of the following operands:

#### MAXSESSIONS(nnnn)

Specifies the maximum number of concurrent TSO/E address spaces the CEA TSO/E address space manager can create. *nnnn* is an integer from 0 to 2000. By default, the maximum is 50.

A value of zero disables this function. A nonzero value for *nnnn* allows the CEA TSO/E address space manager to create and manage the specified number of concurrent TSO/E address spaces. Use the F CEA,CEA=xx system command to dynamically increase this value. If you try to dynamically decrease this value, an error will occur. The increase will take effect when the CEA address space is restarted.

You can also increase or decrease this value by editing the MAXSESSIONS statement in the CEAPRMxx parmlib member when you IPL the system.

**Note:** The CEA TSO/E address space manager creates a z/OS UNIX message queue for each TSO/E address space it starts. Ensure that the value specified for MAXSESSIONS does not exceed the number of allowable system-wide message queues specified for the IPCMSGNIDS statement in the BPXPRMxx parmlib member.



**MAXSESSPERUSER(nn)**

Specifies the maximum number of concurrent TSO/E address spaces the CEA TSO/E address space manager can create for a single user. *nn* is an integer from 1 to 99. By default, the maximum is 10. If the value specified for MAXSESSPERUSER is greater than the value specified for MAXSESSIONS, no limit will be imposed for a single user.

Use the F CEA,CEA=xx system command to dynamically increase this value. If you try to dynamically decrease this value, an error will occur. The increase will take effect when the CEA address space is restarted.

You can also increase or decrease this value by editing the MAXSESSPERUSER statement in the CEAPRMxx parmlib member when you IPL the system.

**RECONSESSIONS(n)**

Specifies the maximum number of TSO/E address spaces that the CEA TSO/E address space manager can place in a dormant state (the user has requested to log off but the session is not ended) for a single user. *n* is an integer from 0 to 3. A value of 0 disables this function and is the default.

A nonzero value for *n* allows the specified number of TSO/E address spaces to be considered ended and available to be reconnected for that user. This value can be changed by the following system command:

```
F CEA,CEA=xx
```

**Note:** CEA enforces the RECONSESSIONS and RECONTIME values when creating or ending a TSO/E address space or when reaching a system monitor interval of ten (10) minutes; therefore, an expired TSO/E address space can be visible on the system for as much as ten (10) minutes after the RECONTIME interval has expired, but will not be used for reconnection.

**RECONTIME(hh:mm:ss)**

Specifies the amount of time that a TSO/E address space will remain dormant (the user has requested to log off but the session is not ended) in the format *hh:mm:ss*, where *hh* is hours, *mm* is minutes, and *ss* is seconds. A value of 00:00:00 disables this function and is the default.

A value of 00:00:01 or greater specifies the amount of time an address space remains a candidate for reconnection before it is ended. The maximum value is 23:59:59. This value can be changed by the following system command:

```
F CEA,CEA=xx
```

**Note:** CEA enforces the RECONSESSIONS and RECONTIME values when creating or ending a TSO/E address space or when reaching a system monitor interval of ten (10) minutes; therefore, an expired TSO/E address space can be visible on the system for as much as ten (10) minutes after the RECONTIME interval has expired, but will not be used for reconnection.

## Examples of CEAPRMxx parmlib member

---

**Example 1**

```
SNAPSHOT(Y)
HLQ(CEA)
BRANCH(379) COUNTRYCODE(000)
DUMPCAPTURETIME(
  SLIP(OPERLOG(01:00:00) LOGREC(01:00:00) LOGRECSUMMARY(01:00:00))
  DUMP(OPERLOG(01:00:00) LOGREC(01:00:00) LOGRECSUMMARY(01:00:00))
  ABEND(OPERLOG(01:00:00) LOGREC(01:00:00) LOGRECSUMMARY(01:00:00))
)
STORAGE(STORCLAS(STCLAS01))
TSOASMGR(MAXSESSIONS(50) RECONSESSIONS(0) RECONTIME(00:00:00))
```

## Example 2

```
SNAPSHOT(Y)
HLQ(CEA)
BRANCH(180) COUNTRYCODE(000)
DUMPCAPTURETIME(
  SLIP(OPERLOG(01:00:00) LOGREC(01:00:00) LOGRECSUMMARY(01:00:00))
  DUMP(OPERLOG(00:10:00) LOGREC(00:10:00) LOGRECSUMMARY(00:10:00))
  ABEND(OPERLOG(02:00:00) LOGREC(02:00:00) LOGRECSUMMARY(02:00:00))
)
STORAGE(VOLSER(VOL101,VOL102,VOL103))
TSOASMGR(MAXSESSIONS(1000) MAXSESSPERUSER(5) RECONSESSIONS(0) RECONTIME(00:00:00))
```

## Chapter 15. CEEPRMxx (runtime option parameters)

Use the CEEPRMxx parmlib member to provide default Language Environment runtime options for a system. The member is identified during IPL by a CEE=(xx,yy,...) statement, either in the IEASYSxx data set or in the IPL parameter.

You can change the member after IPL with the use of the SET CEE=xx command. Use the SETCEE command to change individual options. Display the current options settings with the D CEE command.

The options set in the CEEPRMxx parmlib member override the IBM-supplied default runtime options. When multiple members are concatenated, the individual Language Environment runtime options are merged, with the last parmlib member taking precedence. During Language Environment initialization, runtime options are merged from all sources in a specific order of precedence. For more information about the order of precedence, see [Order of precedence in z/OS Language Environment Programming Guide](#). For 64-bit addressing mode, see [Order of precedence for 64-bit virtual addressing mode in z/OS Language Environment Programming Guide for 64-bit Virtual Addressing Mode](#).

The runtime options report at the conclusion of a program identifies options that are merged from the parmlib, those set on the console by SETCEE, and all other sources.

For more information about the runtime options that are valid in the CEEPRMxx parmlib member, see [Runtime options in z/OS Language Environment Customization](#).

### Parameter in IEASYSxx (or supplied by the operator)

```
CEE=(xx,yy,...,L)
```

The two character identifier (xx) is appended to CEE to identify the CEEPRMxx member of SYS1.PARMLIB. If you specify the L option in the syntax of the CEEPRMxx member, or in reply to the 'SPECIFY SYSTEM PARAMETERS' message, the system writes all statements read from the CEEPRMxx member to the operator's console.

### Syntax rules for CEEPRMxx

The following rules apply to the creation of CEEPRMxx:

- More than one option may be specified on a line and an option may be continued on multiple lines.
- Use blanks or commas as delimiters. Multiple blanks are interpreted as a single blank. Blanks are allowed between parameters and values. Commas are allowed between options. Commas are required between suboptions and before an OVR or NONOVR attribute.

**Restriction:** Blanks are not allowed within the required =( delimiter or (( delimiter for runtime options that specify an OVR or NONOVR attribute.

- Enter values in uppercase, lowercase, or mixed case. The system converts the input to uppercase, except for values enclosed in single quotation marks, which are processed without changing the case.
- The options for each group are saved independently so that CEEDOPT can specify NATLANG(ENU) while CEECOPT can specify NATLANG(JPN).
- Comments may appear in columns 1-71 and must begin with “/\*” and end with “\*/”. Nested comments are not allowed.

## Syntax format of CEEPRMxx

```
CEEEOPT(rtopt[=]((subopts),{OVR|NONOVR})[,rtopt[=]((subopts),{OVR|NONOVR})]...)
CEEDOPT(rtopt[=]((subopts),{OVR|NONOVR})[,rtopt[=]((subopts),{OVR|NONOVR})]...)
CELQDOPT(rtopt[=]((subopts),{OVR|NONOVR})[,rtopt[=]((subopts),{OVR|NONOVR})]...)
CEEROPT(ALL|COMPAT)
CELQROPT(ALL|NONE)
CEENXSTG(OFF|ON)
```

To specify runtime options without the OVR or NONOVR attribute, use the following syntax:

```
CEEEOPT(rtopt(subopts)[,rtopt(subopts)]...)
CEEDOPT(rtopt(subopts)[,rtopt(subopts)]...)
CELQDOPT(rtopt(subopts)[,rtopt(subopts)]...)
```

You can override runtime options that are specified with this format.

## IBM-supplied default for CEEPRMxx

None.

## Statements and parameters for CEEPRMxx

To specify system-level default runtime options, use the following group options:

### CEEEOPT

Specifies runtime options for CICS environments.

### CEEDOPT

Specifies runtime options for non-CICS environments (except AMODE 64 environments).

### CELQDOPT

Specifies runtime options for AMODE 64 environments.

To specify individual runtime options within one of the valid group options:

### *rtopt*

#### *subopts*

Specifies the valid suboptions for a particular runtime option.

#### **NONOVR**

Indicates that the option cannot be overridden.

#### **OVR**

Indicates that the option can be overridden.



**CAUTION:** Runtime options are intended to allow programs, both yours and programs that are supplied by software vendors, to configure how they want to run with Language Environment. Marking runtime options as NONOVR might cripple the capabilities of these programs, prevent them from being tuned properly, inhibit their ability to perform First Failure Data Capture, and prevent them from running. With very few exceptions, IBM strongly discourages customers from marking any runtime option as NONOVR.

Some runtime options use the *rtopt*|*Nortopt* format without suboptions to turn the option on or off, for example, DEBUG|NODEBUG. To use the override attributes with this type of option, it must be specified in the corresponding *rtopt*=(ON | OFF),OVR | NONOVR format. For example, to turn off the DEBUG option, specify DEBUG=((OFF),OVR).

Once a runtime option is specified as non-overrideable with the NONOVR attribute in a CEEPRMxx parmlib member or a SETCEE command, it cannot later be overridden within the same parmlib member or with a SETCEE command.

To remove a non-overrideable setting from a runtime option, use the SETCEE CLEAR operator command or another parmlib member.

For more information about individual runtime options, see *z/OS Language Environment Customization*.

To control Language Environment processing, use the following keywords:

**CEENXSTG**

Indicates whether non-executable memory is enabled.

**OFF**

Non-executable memory is not enabled.

**ON**

Non-executable memory is enabled. It is the default.

**CEEROPT**

Indicates whether region-specific runtime options should be used in a non-CICS or non-LRR environment. The value can be either ALL or COMPAT.

ALL

Attempts a load and use of CEEROPT in all AMODE 31 environments.

**COMPAT**

Attempts a load and use of CEEROPT only in CICS or LRR environments.

**CELOROPT**

Indicates whether region-specific runtime options should be used in AMODE 64. The value can be either ALL or NONE.

ALL

Attempts a load and use of CELOROPT in all AMODE 64 environments.

**NONE**

Does not attempt a load or use of CELROPT in AMODE 64 environments.

## Example of CEEPRMxx parmlib member

The following figure shows the IBM-supplied version of the CEEPRM00 member, with all valid options within comments. You must remove the comment characters from the options that you want to use.

```

/*****
/* CEEPRM00 - Sample Language Environment parmlib member for
/*      run-time options and keywords.
/*
/*
/* LICENSED MATERIALS - PROPERTY OF IBM
/*
/*
/* 5655-Z0S
/*
/*
/* COPYRIGHT IBM CORP. 2005, 2025
/*
/*
/* US GOVERNMENT USERS RESTRICTED RIGHTS - USE,
/* DUPLICATION OR DISCLOSURE RESTRICTED BY GSA ADP
/* SCHEDULE CONTRACT WITH IBM CORP.
/*
/*
/* STATUS = HLE77F0
/*
/*
/*
/* This sample parmlib member contains the IBM-supplied default
/* run-time options that are valid at the system level. The defaults
/* can be overridden using the options groups CEEDOPT, CEECOPT, and
/* CELQDOPT.
/*
/*
/* This sample also contains the default values for the CEEROPT,
/* CELQROPT and CEENXSTG keywords.
/*
/*
/*
/* Syntax for options:
/*
/*      group_name( option_1, option_2,
/*                  option_3, option_4 )
/*
/*      Where:
/*

```

```

/*      group_name is CEEDOPT, CEECOPT or CELQDOPT.                */
/*      option_x is any option valid at the system level.          */
/*      */
/*      */
/*      Syntax for keywords:                                        */
/*      */
/*      CEEROPT( value ) - Where value is ALL or COMPAT            */
/*      CELQROPT( value ) - Where value is ALL or NONE             */
/*      CEENXSTG( value ) - Where value is ON or OFF               */
/*      */
/*      All valid options and keywords are listed but commented out. */
/*      To include an option you must edit this file (or a copy) and */
/*      remove the comment delimiters around the options to be used. */
/*      It is not necessary to uncomment all options.              */
/*      */
/*      Notes:                                                      */
/*      */
/*      * Comments and blank lines are allowed for readability.    */
/*      */
/*      * Individual options must be separated by a comma or a blank */
/*      */
/*      * There can be more than one option on a line.              */
/*      */
/*      * Mixed case is allowed.                                     */
/*      */
/*      * Individual options can be specified as overrideable (OVR) or */
/*      nonoverrideable (NONOVR).                                    */
/*      */
/*      */
/*****

/*****
/* 31 bit non-CICS option group                                     */
/*****
/*CEEDOPT(
/*      ABPERC=((NONE),OVR),
/*      ABTERMENC=((ABEND),OVR),
/*      AIXBLD=((OFF),OVR),
/*      ALL31=((ON),OVR),
/*      ANYHEAP=((16K,8K,ANYWHERE,FREE),OVR),
/*      BELOWHEAP=((8K,4K,FREE),OVR),
/*      CBLOPTS=((ON),OVR),
/*      CBLPSHPOP=((ON),OVR),
/*      CBLQDA=((OFF),OVR),
/*      CEEDUMP=((60,SYSOUT=*,FREE=END,SPIN=UNALLOC),OVR),
/*      CHECK=((ON),OVR),
/*      COUNTRY=((US),OVR),
/*      DEBUG=((OFF),OVR),
/*      DEPTHCONDLMT=((10),OVR),
/*      DYNDUMP=((*USERID,NODYNAMIC,TDUMP),OVR),
/*      ENVAR=(('),OVR),
/*      ERRCOUNT=((0),OVR),
/*      ERRUNIT=((6),OVR),
/*      FILEHIST=((ON),OVR),
/*      FILETAG=((NOAUTOCVT,NOAUTOTAG),OVR),
/*      HEAP=((32K,32K,ANYWHERE,KEEP,8K,4K),OVR),
/*      HEAPCHK=((OFF,1,0,0,0,1024,0,1024,0),OVR),
/*      HEAPPOLS=((OFF,8,10,32,10,128,10,256,10,1024,10,2048,
/*      10,0,10,0,10,0,10,0,10,0,10,0,10,0,10),OVR),
/*      INFMSGFILTER=((OFF,,,),OVR),
/*      INQPCOPN=((ON),OVR),
/*      INTERRUPT=((OFF),OVR),
/*      LIBSTACK=((4K,4K,FREE),OVR),
/*      MSGFILE=((SYSOUT,FBA,121,0,NOENQ),OVR),
/*      MSGQ=((15),OVR),
/*      NATLANG=((ENU),OVR),
/*      NOAUTOTASK=(OVR),
/*      NOTEST=((ALL,*,PROMPT,INSPREF),OVR),
/*      NOUSRHDLR=((),OVR),
/*      OCSTATUS=((ON),OVR),
/*      PC=((OFF),OVR),
/*      PLITASKCOUNT=((20),OVR),
/*      POSIX=((OFF),OVR),
/*      PROFILE=((OFF,''),OVR),
/*      PRTUNIT=((6),OVR),
/*      PUNUNIT=((7),OVR),
/*      RDRUNIT=((5),OVR),
/*      RECPAD=((OFF),OVR),
/*      RPTOPTS=((OFF),OVR),
/*      RPTSTG=((OFF),OVR),

```

```

/*      RTEREUS=((OFF),OVR), */
/*      SIMVRD=((OFF),OVR), */
/*      STACK=((128K,128K,ANYWHERE,KEEP,512K,128K),OVR), */
/*      STORAGE=((NONE,NONE,NONE,0K),OVR), */
/*      TERMTHDACT=((TRACE,96),OVR), */
/*      THREADHEAP=((4K,4K,ANYWHERE,KEEP),OVR), */
/*      THREADSTACK=((OFF,4K,4K,ANYWHERE,KEEP,128K,128K),OVR), */
/*      TRACE=((OFF,4K,DUMP,LE=0),OVR), */
/*      TRAP=((ON,SPIE),OVR), */
/*      UPSI=((00000000),OVR), */
/*      VCTRSVE=((OFF),OVR), */
/*      XUFLOW=((AUTO),OVR) */
/*      ) */

/*****
/* 31 bit CICS option group
/* The following options are ignored in CICS:
/* - ABPERC - OCSTATUS
/* - AIXBLD - PC
/* - AUTOTASK - PLITASKCOUNT
/* - CBLOPTS - POSIX
/* - CBLQDA - PRTUNIT
/* - DYNDUMP - PUNUNIT
/* - ERRUNIT - RDRUNIT
/* - FILEHIST - RECPAD
/* - FILETAG - RTEREUS
/* - INQPCOPN - SIMVRD
/* - INTERRUPT - THREADHEAP
/* - MSGFILE - THREADSTACK
/* - MSGQ - VCTRSVE
/*
/*****
/*CEECOPT(
/*      ABTERMENC=((ABEND),OVR),
/*      ALL31=((ON),OVR),
/*      ANYHEAP=((4K,4080,ANYWHERE,FREE),OVR),
/*      BELOWHEAP=((4K,4080,FREE),OVR),
/*      CBLPSHPOP=((ON),OVR),
/*      CEEDUMP=((60,SYSOUT=*,FREE=END,SPIN=UNALLOC),OVR),
/*      CHECK=((ON),OVR),
/*      COUNTRY=((US),OVR),
/*      DEBUG=((OFF),OVR),
/*      DEPTHCONDLMT=((10),OVR),
/*      ENVAR=('',OVR),
/*      ERRCOUNT=((0),OVR),
/*      HEAP=((4K,4080,ANYWHERE,KEEP,4K,4080),OVR),
/*      HEAPCHK=((OFF,1,0,0,0,1024,0,1024,0),OVR),
/*      HEAPPOLLS=((OFF,8,10,32,10,128,10,256,10,1024,10,2048,
/*      10,0,10,0,10,0,10,0,10,0,10,0,10),OVR),
/*      INFOMSGFILTER=((OFF,,,),OVR),
/*      LIBSTACK=((32,4080,FREE),OVR),
/*      NATLANG=((ENU),OVR),
/*      NOTEST=((ALL,*,PROMPT,INSPREF),OVR),
/*      NOUSRHDLR=(),OVR),
/*      PROFILE=((OFF, ''),OVR),
/*      RPTOPTS=((OFF),OVR),
/*      RPTSTG=((OFF),OVR),
/*      STACK=((4K,4080,ANYWHERE,KEEP,4K,4080),OVR),
/*      STORAGE=((NONE,NONE,NONE,0K),OVR),
/*      TERMTHDACT=((TRACE,CESE,96),OVR),
/*      TRACE=((OFF,4K,DUMP,LE=0),OVR),
/*      TRAP=((ON,SPIE),OVR),
/*      UPSI=((00000000),OVR),
/*      XUFLOW=((AUTO),OVR)
/*      )

/*****
/* 64 bit options group
/*****
/*CELQDOPT(
/*      CEEDUMP=((60,SYSOUT=*,FREE=END,SPIN=UNALLOC),OVR),
/*      DYNDUMP=((*USERID,NODYNAMIC,TDUMP),OVR),
/*      ENVAR=('',OVR),
/*      FILETAG=((NOAUTOCVT,NOAUTOTAG),OVR),
/*      HEAPCHK=((OFF,1,0,0,0,1024,0,1024,0),OVR),
/*      HEAPPOLLS=((OFF,8,10,32,10,128,10,256,10,1024,10,2048,
/*      10,0,10,0,10,0,10,0,10,0,10,0,10),OVR),
/*      HEAPPOLLS64=((OFF,8,4000,32,2000,128,700,256,350,
/*      1024,100,2048,50,3072,50,4096,50,8192,25,16384,10,
/*      32768,5,65536,5),OVR),
/*      HEAP64=((1M,1M,KEEP,32K,KEEP,4K,4K,FREE),OVR),
/*      INFOMSGFILTER=((OFF,,,),OVR),

```

```

/*      IOHEAP64=((1M,1M,FREE,12K,8K,FREE,4K,4K,FREE),OVR),      */
/*      LIBHEAP64=((1M,1M,FREE,16K,8K,FREE,8K,4K,FREE),OVR),      */
/*      NATLANG=((ENU),OVR),      */
/*      NOTEST=((ALL,*,PROMPT,INSPREF),OVR),      */
/*      POSIX=((OFF),OVR),      */
/*      PROFILE=((OFF,''),OVR),      */
/*      RPTOPTS=((OFF),OVR),      */
/*      RPTSTG=((OFF),OVR),      */
/*      STACK64=((1M,1M,128M),OVR),      */
/*      STORAGE=((NONE,NONE,NONE,),OVR),      */
/*      THREADSTACK64=((OFF,1M,1M,128M),OVR),      */
/*      TERMTHDACT=((TRACE,,96),OVR),      */
/*      TRACE=((OFF,,DUMP,LE=0),OVR),      */
/*      TRAP=((ON,SPIE),OVR)      */
/*      )      */

/*****
/* Keywords      */
/*****
/*CEEROPT( COMPAT )      */
/*CELQROPT( NONE )      */
/*CEENXSTG( ON )      */

```



## Chapter 16. CLOCKxx (time of day parameters)

CLOCKxx performs the following functions:

- Prompts the operator to initialize the time of day (TOD) clock during system initialization.
- Specifies the difference between the local time and Coordinated Universal Time (UTC).
- Controls the utilization of the IBM Sysplex Timer (9037), which is an external time reference (ETR). Having all systems in your complex attached and synchronized to a Sysplex Timer ensures accurate sequencing and serialization of events.
- Provides the means of specifying that the Server time Protocol (STP) architecture is to be used in the sysplex. STP defines the method by which multiple servers maintain time synchronization.
- Allows an installation to set an acceptable time deviation for the TOD clock from an external time source. When the specified ACCURACY bounds are exceeded, an error message is issued so the problem can be corrected. See the section on setting the accuracy monitor service for the TOD clock in *z/OS MVS Planning: Operations* for more information.
- Along with the ACCURACY keyword, specify the ACCMONINTV keyword to set a user-defined timing interval when the TOD clock accuracy monitor service is to be processed.

The CLOCKxx member for a system that is a member of a multisystem sysplex must contain a specification of ETRMODE YES, STPMODE YES, or both. The system then uses the Sysplex Timer or STP to synchronize itself with the other members of the sysplex. The system uses a synchronized time stamp to provide appropriate sequencing and serialization of events within the sysplex.

**Note:** If all MVS images in the sysplex will run in LPARs or under VM on a single physical processor, you can specify SIMETRID instead of ETRMODE YES or STPMODE YES.

For more information about CLOCKxx and the Sysplex Timer, see *z/OS MVS Setting Up a Sysplex*.

### Parameter in IEASYSxx (or supplied by the operator)

```
CLOCK= {aa
        { (aa,bb,...L) }
```

The two character identifier (aa, bb, and so forth) is appended to CLOCK to identify the CLOCKxx member of SYS1.PARMLIB. If you specify the L option in the syntax of the CLOCKxx member, or in reply to the 'SPECIFY SYSTEM PARAMETERS' message, the system writes all statements read from the CLOCKxx member to the operator's console.

### Syntax rules for CLOCKxx

The following rules apply to the creation of CLOCKxx:

1. Use columns 1 through 71. Do not use columns 72-80 for data; these columns are ignored.
2. Comments may appear in columns 1-80 and must begin with “/\*” and end with “\*/”
3. At least one blank has to follow the statement types.
4. The following combinations of parameters are not valid and will be rejected:
  - ETRMODE NO and ETRZONE YES
  - STPMODE NO and STPZONE YES
5. In STP mode, TIMEDELTA is the replacement value to be used instead of ETRDELTA, although the system will continue to accept ETRDELTA.

## Syntax format of CLOCKxx

```

OPERATOR  {PROMPT  }
          {NOPROMPT}

TIMEZONE  d.hh.mm.ss

ACCURACY  mmmm

ACCMONINTV {mmss}
           {mss}

ETRMODE   {YES}
          {NO }

ETRDELTA  nn

ETRZONE   {YES}
          {NO }

SIMETRID  nn

STPMODE   {YES}
          {NO }

TIMEDELTA nn

STPZONE   {YES}
          {NO }

```

## IBM-supplied default for CLOCKxx

The IBM-supplied default parmlib member of SYS1.PARMLIB is CLOCK00, which contains the following:

```

OPERATOR  NOPROMPT
TIMEZONE  W.00.00.00
STPMODE   YES
STPZONE   YES
TIMEDELTA 10
ACCURACY  0

```

## Statements and parameters for CLOCKxx

### ACCURACY *mmmmm*

Specifies an acceptable time deviation for the TOD clock from an external time source in milliseconds, with valid values between 0 and 60000 milliseconds (60 seconds).

When the ACCURACY keyword is specified, the system will also monitor the TOD clock accuracy by issuing message IEA049I to the hardcopy log. Message IEA049I will display the time discrepancy for the TOD clock from an external time source (ETS).

The ACCURACY function will be processed every 60 minutes unless the ACCMONINTV keyword is specified with a user-defined timing interval.

Please refer to message IEA049I for additional details on setting the user-defined time interval.

**Default:** 0, which indicates that the time accuracy check function is not enabled. If the difference between the TOD clock and the external time source time exceeds the ACCURACY value, message IEA032E is issued.

### ACCMONINTV *mmss* | *mss*

Sets a timing interval when the ACCURACY function is to be processed. The ACCMONINTV keyword requires the ACCURACY keyword to be specified and have a nonzero value.

#### *mmss*

Minutes (*mm*) and Seconds (*ss*) in decimal format. Minutes must be between 00 and 60. Seconds must be between 00 and 59.

**mss**

Minutes (*m*) and Seconds (*ss*) in decimal format. Minutes must be between 0 and 9. Seconds must be between 00 and 59.

**Notes:**

- The Seconds (*ss*) value must always be 2 digits. The Minutes (*m* or *mm*) value can be either 1 or 2 digits.
- Specifying ACCMONINTV 000 or 0000 is not valid.

**Default:** 6000 (60 minutes)

**ETRDELTA nn**

Indicates the greatest difference, after IPL, between the system's TOD and the Sysplex Timer TOD by which the system will adjust its TOD, when necessary, to match the Sysplex Timer TOD.

If the difference between the system's TOD and the Sysplex Timer's TOD exceeds the ETRDELTA, one of the following results occur:

1. If the system is part of a multisystem sysplex, the system is terminated with wait state 0A2.
2. If the system is not part of a multisystem sysplex, processing continues, but the Sysplex Timer is not used for the remainder of that IPL.

If you select a value of 0 seconds for ETRDELTA, no deviation between the processor TOD clock and the 9037 Sysplex Timer clock can be corrected by z/OS, so no TOD adjustment is possible. When a sync check is recognized in the ETRDELTA 0 case, one of the two preceding actions will result. IBM suggests that the default of 10 seconds be selected.

**Value range:** 0 - 99 seconds

**Default:** 10 seconds

**ETRMODE {YES|NO}**

Specifies whether MVS is using a Sysplex Timer. You must code ETRMODE YES if this system is a member of a multisystem sysplex. To set ETRMODE to YES, the sysplex must be attached to an operational Sysplex Timer.

**Note:** If all MVS images in the sysplex will run in LPARs or under VM on a single physical processor, you can specify SIMETRID instead of ETRMODE YES.

**NO**

Specifies that MVS is not to use the Sysplex Timer.

**Note:**

1. If PR/SM\* is active, the TOD clocks initially are synchronized to the Sysplex Timer.
2. Specifying NO overrides both the external time reference (ETR) and the simulated sysplex timer (SIMETR).
3. Configurations that support ETRMODE NO are XCF-local mode and Monoplex mode.

**YES**

Specifies that MVS is to use the Sysplex Timer, if available. If you specify ETRMODE YES and an operational Sysplex Timer is not available, the operator is prompted to set the TOD clock during system initialization.

**Default:** NO

**ETRZONE {YES|NO}**

Specifies whether the system is to get the time zone constant from the Sysplex Timer. The time zone constant specifies the difference between the local time and the Coordinated Universal Time (UTC).

**NO**

Specifies that the system is to use the time zone constant specified on the TIMEZONE parameter.

**YES**

Specifies that the system is to use the Sysplex Timer to set the time zone constant. If you specify ETRZONE YES and an operational Sysplex Timer is not available, the system uses the time zone constant specified on the TIMEZONE parameter.

**Default:** The default is YES when ETRMODE is set to YES. NO when ETRMODE is set to NO.

**OPERATOR {PROMPT|NOPROMPT}**

Specifies whether the operator is to be prompted to set the TOD clock during system initialization.

**NOPROMPT**

Specifies that the system is not to prompt the operator during TOD initialization unless the clock is not set.

**PROMPT**

Specifies that the system is to prompt the operator during TOD initialization.

**Note:**

1. If ETRMODE YES or STPMODE YES is specified, the system ignores the OPERATOR parameter.
2. OPERATOR PROMPT and SIMETRID are mutually exclusive keywords. Specify either OPERATOR PROMPT or SIMETRID, but not both. If both are specified, the system rejects the CLOCKxx member during system initialization, and issues a message to prompt the operator for one of the following reasons:
  - A valid CLOCKxx member or
  - EOB (by pressing the enter button on the console).

Otherwise, the operator must reIPL the system.
3. Systems running as Sysplex Test Datesource LPARs must use SIMETRID and therefore must specify OPERATOR NOPROMPT.

**Default:** NOPROMPT

**SIMETRID nn**

Specifies the simulated Sysplex Timer identifier. SIMETRID allows MVS images running on the same central electronics complex (CEC), in native mode in LPARs, or as z/VM guests to participate in a multi-system sysplex when no real sysplex timer is available. In these environments, the MVS TOD clocks are synchronized by PR/SM or the z/VM host. If a real sysplex timer is available when MVS is not being run as a VM guest, IBM suggests that you use it instead of SIMETRID.

Do not use SIMETRID on MVS images that are running on different CECs. Instead, use a real sysplex timer and specify ETRMODE YES. If the installation is using a real sysplex timer, the operational requirements determine whether you specify YES or NO for ETRZONE. Do not specify SIMETRID if you plan to IPL MVS native (for example, not in an LPAR and not under VM), even if you do not plan to have more than one MVS image in the sysplex. SIMETRID is only available when MVS runs in an LPAR, or under z/VM.

Each image that participating in the same sysplex and using simulated ETR for time synchronization must specify the same Sysplex Timer identifier (*nn*).

After the logical TOD clock is set in a partition by an IPL, the LPAR must be reactivated to reset the time again.

**Note:** OPERATOR PROMPT and SIMETRID are mutually exclusive keywords. Specify either OPERATOR PROMPT or SIMETRID, but not both. If both are specified, the system rejects the CLOCKxx member during system initialization, and issues a message to prompt the operator for one of the following situations:

- A valid CLOCKxx member, or
- EOB (by pressing the enter button on the console).

Otherwise, the operator must reIPL the system.

**Value range:** A two-digit hexadecimal number (X'00-1F').

**Default:** None. This value is optional. If specified, ETRZONE, ETRMODE, STPZONE, and STPMODE are ignored and the timezone constant that is specified by TIMEZONE is used.

### STPMODE {YES|NO}

Specifies whether MVS is using STP timing mode. If you specify STPMODE YES and STP is not available, the operator is prompted to set the TOD clock during system initialization.

#### NO

Specifies that MVS is not to use STP timing mode. Either ETR or local MVS timing mode is used depending on the value of the ETRMODE keyword and whether the ETR is usable or not.

#### YES

Specifies that MVS is to use STP timing mode if STP is active.

**Default:** YES

#### Notes:

1. If the z/OS system image is running on a server that is in ETR timing mode, and both STPMODE and ETRMODE were specified as YES, z/OS uses ETRMODE YES.
2. If the z/OS system image is running on a server that is in STP timing mode, and both STPMODE and ETRMODE were specified as YES, z/OS uses STPMODE YES.
3. If the z/OS system image is running on a server that is in LOCAL timing mode, explicitly code STPMODE NO if you want to avoid messages IEA888A and IEA381I during system initialization.

If either ETRMODE YES or STPMODE YES (default) is specified, z/OS issues IEA888A to prompt the operator to set the TOD clock during system initialization. That message is issued regardless of whether OPERATOR PROMPT or NOPROMT is specified.

In addition, if ETRMODE YES is specified, the following message is issued:

```
IEA261I NO ETR PORTS ARE USABLE. CPC CONTINUES TO RUN IN LOCAL MODE.
```

If ETRMODE NO and STPMODE YES (default) are specified, the following message is issued:

```
IEA381I THE STP FACILITY IS NOT USABLE. SYSTEM CONTINUES IN LOCAL  
TIMING MODE.
```

### STPZONE {YES|NO}

Specifies whether the system is to get the time zone constant from STP. The time zone constant specifies the difference between the local time and the Coordinated Universal Time (UTC).

#### NO

Specifies that the system is to use the time zone constant specified on the TIMEZONE parameter.

#### YES

Specifies that the system is to use STP to set the time zone constant. If you specify STPZONE YES and STP is not enabled, the system uses the time zone constant specified on the TIMEZONE parameter.

**Default:** The default is YES when STPMODE is set to YES. The default is NO when STPMODE is set to NO.

### TIMEDELTA nn

Indicates the greatest difference, after IPL, between the system's TOD and the STP Stratum 1 Server's time value, by which the system will adjust its TOD, when necessary, to match the Stratum 1 Server's TOD.

If the difference between the system's TOD and the Stratum 1 Server's TOD exceeds the TIMEDELTA, one of the following results occurs:

1. If the system is part of a multisystem sysplex, the system is terminated with wait state 0A2.
2. If the system is not part of a multisystem sysplex, processing continues, but STP is not used for the remainder of that IPL.

If you select a value of 0 seconds for TIMEDELTA, no deviation between the processor TOD clock and the Stratum 1 Server's TOD can be corrected by z/OS, so no TOD adjustment is possible. When a synch check is recognized in the TIMEDELTA 0 case, one of the two preceding actions will result. IBM suggests that the default of 10 seconds be selected.

**Value range:** 0 to 99 seconds.

**Default:** 10 seconds

### **TIMEZONE d.hh.mm.ss**

Specifies the difference between the local time and the Coordinated Universal Time (UTC). If ETRMODE YES and ETRZONE YES are specified (and an operational Sysplex Timer is available), the system ignores the TIMEZONE parameter.

**d**

Specifies the direction from UTC.

**Value range:** E for east of UTC or W for west of UTC

**Default:** W

### **hh.mm.ss**

Specifies the number of hours (*hh*) minutes (*mm*) and seconds (*ss*) that the local time differs from the UTC.

**Value range:** The value for *hh* must be between 00 and 15. The value for *mm* and *ss* must be between 00 and 59. *mm.ss* values are optional.

In addition, the combined *hh.mm.ss* value must be within the range (00:00:00 - 15:00:00). This means that a value like 15.59.59 is not valid because it is outside the range, even though the *hh* portion is between 00 and 15 and the *mm* and *ss* portions are between 00 and 59. If the *mm* portion or *ss* portion or both are omitted, a default value of 00 is applied to the omitted portion, and appears in message IEA598I at IPL time.

For example, if CLOCKxx contains TIMEZONE W.15, then at IPL time, message IEA598I would indicate:

```
IEA598I TIME ZONE = W.15.00.00
```

**Default:** 00.00.00

**Note:** Some applications have a requirement to run with local time equal to UTC. When Server Time Protocol (STP) is implemented, this requirement can be satisfied by setting an LPAR time offset equal to the local time of day offset and a time zone of zero in the CLOCKxx parmlib member.

## Chapter 17. CNGRPxx (specify console groups)

Use the CNGRPxx parmlib member to define console groups. You can specify HMCS, MCS, SMCS, and extended MCS consoles as members of these groups.

HMCS, MCS, and SMCS consoles are defined to your system through the CONSOLxx parmlib member, which is described in Chapter 23, “CONSOLxx (console configuration definition),” on page 201. For information about defining extended MCS consoles to your system, see *z/OS MVS Planning: Operations*.

You can use console groups in the following situations:

- To specify the order in which consoles are to receive synchronous messages. You specify this group on the DEFAULT statement in the CONSOLxx parmlib member.
- To identify the consoles that must be inactive for the system to place the system console into problem determination state. You specify this group in the AUTOACT keyword on the CONSOLE statement for the system console.

### Console groups in a sysplex

When a system joins a sysplex, the system inherits any console group definitions that are currently defined in the sysplex; its own console group definitions in the INIT statement on CONSOLxx are ignored. If there are no console groups defined when a system joins the sysplex, the joining system's definitions will be in effect for the entire sysplex. After the system is up, any system in the sysplex can issue the SET CNGRP command to add or change the console group definitions. The change lasts for the duration of the IPL.

### Selecting a CNGRPxx member

You can select a CNGRPxx member in the following ways:

- Specify the CNGRP keyword on the INIT statement of the CONSOLxx Parmlib member. For more information, see Chapter 23, “CONSOLxx (console configuration definition),” on page 201.
- Issue the SET CNGRP command either through the COMMNDxx Parmlib member or after initialization. You can have up to 38 CNGRPxx members active at a time. For more information about the SET CNGRP command, see *z/OS MVS System Commands*.

If you define the same console group in separate CNGRPxx members, and those members are activated, the system will use the first specification of the console group.

### Syntax rules for CNGRPxx

The following syntax rules apply to CNGRPxx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- A comma must be used to separate multiple keyword values within a list.
- Comments may appear in columns 1-71 and must begin with "/"\* and end with "\*/".
- No more than 226 lines per CNGRPxx member, including comments, will be processed by the SET CNGRP command.

### Syntax format of CNGRPxx

```
GROUP      NAME(group name)
           MEMBERS(console name[,console name,...])
```

## IBM-supplied default for CNGRPxx

---

None.

## Statement and parameters for CNGRPxx

---

### GROUP

Identifies the beginning of a console group definition. Each group definition consists of one NAME keyword and one MEMBERS keyword. You can specify more than one GROUP statement in one CNGRPxx parmlib member.

### MEMBERS(*console name* [, *console name*,...])

Specifies the ordered list of console names that belong to the specified group. Depending on whether a console is an HMCS, MCS, SMCS, or an extended MCS console, define its name through either:

- The CONSOLE statement of the CONSOLxx parmlib member for HMCS, MCS, and SMCS consoles
- Security Server or TSO/E for extended MCS consoles.

**Value range:** *console name* is 2 - 8 characters. The first character of *console name* must begin with the letters A through Z or with a #, \$, or @. The remaining characters can be A through Z, 0 through 9, or #, \$, or @.

The following reserved console name has a special meaning when used as part of a console group:

| Console name | Meaning  |
|--------------|--|
| *SYSCON*     | When used in a group that is specified on the SYNCHDEST keyword on the DEFAULT statement in CONSOLxx, this routes a synchronous message to the system console. |

### NAME(*group name*)

Specifies the name of the console group. Use this name in the CONSOLxx parmlib member for one of the following reasons:

- On the DEFAULT statement to specify the order in which consoles are to receive synchronous messages.
- On the CONSOLE statement in the AUTOACT keyword to indicate the automatic activate group for the system console.

**Value range:** 1 - 8 alphanumeric or special (#, @, or \$) characters.

**Default:** None. There is no default.



## Chapter 18. CNLcccxx (time and date format for translated messages)

Use the CNLcccxx member of parmlib to specify how translated messages are to be displayed at your installation. CNLcccxx, which is called the message configuration member, allows you to specify the time and date format for translated messages, using the MONTH, DAY, DATE, and TIME statements, as follows:

- Use the required MONTH statement to specify the month names that are to appear in your translated messages. MONTH1 specifies the month name for January, MONTH2 for February, and so on.
- Use the required DAY statement to specify the names of the days of the week that are to appear in your translated messages. DAY1 specifies the name for Sunday, DAY2 for Monday, and so on.
- Use the required DEFAULTS statement to define the default date and time formats for a language.
- Use the optional DATE statement to specify the format for the date. Examples of different date formats are:

```
1/14/2000
14-1-2000
14 January 2000
```

- Use the optional TIME statement to specify the format for the time. Examples of different time formats include:

```
11:46:12 PM
46 MINUTES PAST 11
23:46:12
```

You need one message configuration member for each language your installation supports. Each message configuration member is named CNLcccxx, where ccc is the appropriate language code (see [Table 54 on page 640](#) for a table of valid language codes) and xx identifies the member.

The message configuration member for a specific language is specified on the CONFIG keyword of the LANGUAGE statement in the MMSLSTxx parmlib member. For more information, see [Chapter 75, “MMSLSTxx \(MVS message service list\),” on page 639](#).

IBM provides you with message configuration members for English and Japanese in SYS1.PARMLIB (named CNLENU00 and CNLJPN00, respectively).

### Restrictions for CNLcccxx

Observe the following restrictions when using CNLcccxx:

- Only one CNLcccxx member can be active at one time.
- The system uses the IBM-supplied CNLENU00 member for message processing. You can add definitions to the CNLENU00 member, but do not delete the IBM-supplied definitions. Doing so can cause misformatted text to appear in system messages.

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Selecting a CNLcccxx member

The SET MMS command allows you to modify the MMS parameters that are currently in effect for your system, including the currently active CNLcccxx member. By selecting a MMSLSTxx member that specifies a different CNLcccxx member, you cause the system to refresh the current CNLcccxx settings. The new

MMS and CNLcccxx settings take effect immediately (that is, without requiring a reIPL of the system). For more information about the SET MMS command, see [z/OS MVS System Commands](#).

## Syntax rules for CNLcccxx

The following syntax rules apply to the creation of CNLcccxx:

- Use columns 1 through 71 for data. Columns 72 - 80 are ignored.
- Specify at least one delimiter (space or comma) between a statement and a keyword. Delimiters are not required between keywords.
- Comments may appear in columns 1-71 and must begin with `/*` and end with `*/`. Comments can span more than one line.
- The beginning and ending double byte character set (DBCS) delimiters are called *shift-out* and *shift-in* characters. In examples, the convention `<d1d2>` is used to represent DBCS strings enclosed in their shift-out and shift-in characters, where d1 and d2 each represent a DBCS character, `<` represents X'0E'(shift-in), and `>` represents X'0F'(shift-out).
- The following statements are **required**:

```
MONTH
DAY
DEFAULTS
```

- The following statements are **optional**:

```
DATE
TIME
```

When optional DATE and TIME statements are not specified, the system uses the default date and time from the DEFAULTS statement.

## Syntax format of CNLcccxx

|          |   |
|----------|---|
| MONTH    | MONTH1(monthname)<br>MONTH2(monthname)<br>MONTH3(monthname)<br>MONTH4(monthname)<br>MONTH5(monthname)<br>MONTH6(monthname)<br>MONTH7(monthname)<br>MONTH8(monthname)<br>MONTH9(monthname)<br>MONTH10(monthname)<br>MONTH11(monthname)<br>MONTH12(monthname) |
| DAY      | DAY1(dayname)<br>DAY2(dayname)<br>DAY3(dayname)<br>DAY4(dayname)<br>DAY5(dayname)<br>DAY6(dayname)<br>DAY7(dayname)   |
| DATE     | ID(DATEnnnnnn)<br>FORMAT(datestring)  |
| TIME     | ID(TIMEnnnnnn)<br>FORMAT(timestring)  |
| DEFAULTS | DEFAULTDATE(datestring)<br>DEFAULTTIME(timestring)  |

## Syntax example of CNLcccxx

Figure 8 on page 181 shows an example message configuration member for Italian.

```

MONTH MONTH1(GENNAIO) MONTH2(FEBRAIO) MONTH3(MARZO) MONTH4(APRILE)
MONTH5(MAGGIO) MONTH6(GIUGNO) MONTH7(LUGLIO) MONTH8(AGOSTO)
MONTH9(SETTEMBRE) MONTH10(OTTOBRE) MONTH11(NOVEMBRE)
MONTH12(DICEMBRE)
DAY DAY1(DOMENICA) DAY2(LUNEDI) DAY3(MARTEDI) DAY4(MERCOLEDI)
DAY5(GIOVEDI) DAY6(VENERDI) DAY7(SABATO)
DATE ID(DATE1) FORMAT(&mm/&dd/&yy)
DATE ID(DATESHORT) FORMAT(&dd-&mm-&yy)
DATE ID(DATELONG) FORMAT('&dd &mt &yr')
TIME ID(TIME1) FORMAT(&hh:&mm:&ss)
TIME ID(TIME2) FORMAT(&hh-&mm)
TIME ID(TIMESHORT) FORMAT(&hh-&mm-&ss&12)
TIME ID(TIMELONG) FORMAT('&mm MINUTES PAST &hh')
DEFAULTS DEFAULTDATE(&mm/&dd/&yy) DEFAULTTIME(&hh:&mm:&ss)

```

Figure 8. Example: CNLcccxx message configuration member for Italian

## Statements and parameters for CNLcccxx

### DATE

Specifies the format for displaying dates in message texts.

#### ID(DATExxxxxx)

Specifies the format identifier where xxxxxx is 1 - 6 alphanumeric characters. The format identifiers are case-sensitive and each identifier must be unique.

#### FORMAT(datestring)

Specifies the format of the date in the translated message text. The following keywords can appear in the string:

##### &dd

Include the numerical day of the month in the text (01-31).

##### &dj

Include the numerical day of the year in the text (001-366).

##### &dz

Include the numerical day of the month in the text but suppress leading zeros (1-31).

##### &mm

Include the numerical month of the year in the text (01-12).

##### &mt

Include the name of the month in the text as specified on the MONTH statement.

##### &mz

Include the numerical month of the year in the text but suppress leading zeros (1-12).

##### &yr

Include all four digits of the year in the text.

##### &yy

Include the last two digits of the year in the text.

You can use any characters to delimit the keywords.

For example, given the date April 12, 2001, the date formats and their results follow:

```

DATE ID(DATE1) FORMAT(&mm/&dd/&yr)      (4/12/2001)
DATE ID(DATESHORT) FORMAT(&dd-&mm-&yr)   (12-4-2001)
DATE ID(DATELONG) FORMAT('&dd &mt &yr') (12 April 2001)

```

### DAY

Specifies the string to be substituted in translated messages for the corresponding day of the week. For example,

```
DAY DAY1(SONNTAG)
```

For the German language, specifies that the string “SONNTAG” is printed in messages that are translated to German where the US English message contains the day name “Sunday”.

**DAY1(*dayname*) - DAY7(*dayname*)**

Specifies the string to be substituted in translated messages for the days of Sunday through Saturday.

**DEFAULTS**

Defines the default date and time formats for the language.

**DEFAULTDATE(*datestring*)**

Specifies the date format to use when no DATE statements are specified. To code *datestring*, follow the format that is shown for the FORMAT keyword of the DATE statement.

**DEFAULTTIME(*timestring*)**

Specifies the time format to use when no TIME statements are specified. To code *timestring*, follow the format that is shown for the FORMAT keyword of the TIME statement.

**MONTH**

Specifies the string to be substituted in translated messages for the corresponding month of the year. For example,

```
MONTH MONTH1(JANVIER)
```

For the French language, specifies that the string “JANVIER” is printed in messages that are translated to French where the US English message contains the month name “January”.

**MONTH1(*monthname*) - MONTH12(*monthname*)**

Specifies the string to be substituted in translated messages for the months of January through December.

**TIME**

Specifies the format for displaying time in message texts.

**ID(TIMExxxxxx)**

Specifies the format identifier where xxxxxx is 1 - 6 alphanumeric characters. The format identifiers are case-sensitive and each identifier must be unique.

**FORMAT(*timestring*)**

Specifies the format of the time in the translated message text. The following keywords can appear in the string:

**&h0**

Include the numerical hour (in the range 00-23) in the text but suppress leading zeros.

**&h4**

Include the numerical hour (in the range 00-23) in the text.

**&hh**

Include the numerical hour (in the range 00-11) in the text.

**&hz**

Include the numerical hour (in the range 00-11) in the text but suppress leading zeros.

**&ap**

Specifies an am/pm indicator.

**&dn**

Include the number of decimal places, where *n* is a number from 1 - 6.

**&mm**

Include the position of the minutes in the text.

**&ss**

Include the position of the seconds in the text.

You can use any characters to delimit the keywords.

For example, given the time 11:46:12.1234 P.M., the date formats, and their results follow:

```
TIME ID(TIME1) FORMAT(&h4:&mm:&ss)          23:46:12
TIME ID(TIME2) FORMAT(&h0-&mm)              23-46
TIME ID(TIME3) FORMAT(&hh-&mm-&ss.&d3)       11-46-12.123
TIME ID(TIMESHORT) FORMAT('&hh:&mm:&ss &ap') 11:46:12 PM
TIME ID(TIMELONG) FORMAT('&mm MINUTES PAST &hh') 46 MINUTES PAST 11
```



## Chapter 19. COFDLFxx (hiperbatch parameters)

The COFDLFxx parmlib member provides the name of the DLF installation exit and sets limits on the amount of storage that the system can use for Hiperbatch. To activate DLF, the CLASS statement describing the group of shared objects must be present in the active COFDLFxx parmlib member (the member named on the START command for DLF). Only one COFDLFxx member can be active at a time. On the CLASS statement, you must supply the maximum amount of storage that your installation can use for DLF objects (MAXEXPB).

Although only one COFDLFxx member can be active at a time, you can create several members with different limit values for the storage definition parameters, MAXEXPB and PCTRETB, then use the MODIFY system command to change the active parmlib member.

You can monitor the effectiveness of the values you specify for MAXEXPB and PCTRETB through the MODIFY DLF command with the STATUS operand. If the resulting display shows that the percentage of storage in use is consistently low, you might want to switch to a COFDLFxx parmlib member that has lower limits set for MAXEXPB and PCTRETB.

IBM supplies a default DLF parmlib member (COFDLF00) that contains a default CLASS statement. You will probably want to tailor this CLASS statement to meet your installation's needs.

You cannot replace a DLF installation exit while DLF is active. The exit requested that when DLF is started remains in effect for the duration of the DLF address space. To replace the exit, you must stop DLF, replace the exit (or change the parmlib CONEXIT parameter to specify a different exit), and then start DLF again.

### Parameter in IEASYSxx (or issued by the operator)

None.

### Syntax rules for COFDLFxx

The following syntax rules apply to COFDLFxx:

- The content of the member is one CLASS statement.
- The CLASS statement begins with the statement identifier "CLASS" and ends with the end of file (EOF). No explicit continuation syntax is required.
- Commas and blanks in any combination constitute a delimiter.
- Delimiters or comments can precede the statement identifier.
- Delimiters are not required between parameters with values; the right parenthesis after the specified parameter value is sufficient.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/". Comments are allowed between parameters.
- If the class statement contains duplicates of the following parameters, the system uses the first valid occurrence and issues a message that a duplicate parameter was specified:
  - MAXEXPB
  - PCTRETB
  - CONEXIT

## Syntax format of COFDLFxx

```
CLASS      MAXEXPB(megabytes)
           [PCTRETB(percent)]
           [CONEXIT(exit-name)]
```

## Starting DLF

Issue the following command to start DLF:

```
START DLF, SUB=MSTR, NN=xx
```

The two alphanumeric characters (xx) are added to COFDLF to form the name of the COFDLFxx member. If you do not code NN=xx, the system defaults to COFDLF00. Note that DLF will not start unless SUB=MSTR is specified on the START command. SUB=MSTR means that DLF can continue to run across a JES restart.

## Statements and parameters for COFDLFxx

### CLASS

The CLASS statement indicates the start of the parameters that define the DLF objects.

#### CONEXIT(routine-name)

CONEXIT specifies the name of the installation exit routine for DLF. This routine must be reentrant and reside in an authorized library in the LNKLIST concatenation. For details, see [z/OS MVS Installation Exits](#).

#### MAXEXPB(nnnn)

MAXEXPB is a required parameter that allows you to specify, in megabytes, the maximum amount of storage that the system is to use for Hiperbatch. The value for *nnnn* must be a decimal number from 0 through 9999. You can specify up to 4 digits, including leading zeros. The maximum value that you can specify is the maximum amount of storage that is available on your system.

**Value range:** 0 - 9999 megabytes

#### PCTRETB(nnn)

PCTRETB is an optional parameter that allows you to specify the percentage of the storage amount (defined by MAXEXPB) that DLF is to use for retained DLF objects. Retained DLF objects are used when the output of one job step is passed to another job or job step. The value for *nnn* must be a decimal number from 0 through 100. You can specify up to 3 digits, including leading zeros. If the value for *nnn* is either not in the range or is not specified, the system uses 0.

**Value range:** 0 - 100

**Default:** 0



## Chapter 20. COFVLFxx (virtual lookaside facility parameters)

The virtual lookaside facility (VLF) enables an authorized program to store named objects in virtual storage managed by VLF and to retrieve these objects by name on behalf of users in multiple address spaces. VLF is designed primarily to improve performance by retrieving frequently used objects from virtual storage rather than performing repetitive I/O operations from DASD.

Certain IBM products or components such as LLA, TSO/E, CAS, and RACF use VLF as an alternate way to access data. Since VLF uses virtual storage for its data space there are performance considerations each installation must weigh when planning for the resources required by VLF.

For a description of VLF, see [\*z/OS MVS Programming: Authorized Assembler Services Guide\*](#).

A VLF class is a group of related objects made available to users of an application or component. To get the most benefit from using VLF, consider its use for objects that are:

- Used frequently
- Changed infrequently
- Used by multiple end users concurrently.

To activate a class of VLF objects, VLF requires that a CLASS statement describing that group of objects be present in the active COFVLFxx parmlib member (the member named on the START command used for VLF).

For example, library lookaside (LLA) uses the class of VLF objects named CSVLLA. If the CLASS statement for CSVLLA is not included in the active COFVLFxx parmlib member, LLA cannot use VLF, and many of the performance and operational benefits of LLA will not be available.

IBM supplies a default VLF parmlib member (COFVLF00) that contains CLASS statements for the VLF classes used by IBM-supplied products. You might need to tailor some of these CLASS statements to meet your installation's needs. In addition, your installation can write applications that use VLF, and you must include the CLASS statements for those applications.

There are three items VLF requires for each VLF class used. They are:

1. The name of the class, specified on the required NAME parameter.

IBM supplies the names of the classes it uses. These names start with the letters A-I.

2. The maximum amount of virtual storage that your installation wants VLF to use for the objects in the class.

Unless you supply this value on the optional MAXVIRT parameter of the CLASS statement, VLF will use a default value. Generally, the information about the IBM product that uses the VLF class provides some guidance about how to determine an appropriate value for MAXVIRT.

For any given class, the goal is usually to provide an amount of virtual storage large enough to hold a working set of objects—those objects that are used frequently enough to justify keeping them in virtual storage to avoid DASD retrieval.

When you specify the MAXVIRT value, ensure that it is large enough to hold most or all of the frequently-used objects in a VLF class. An excessively small value tends to cause thrashing of the data in that VLF class, while an excessively large MAXVIRT value tends to increase the consumption of auxiliary storage because infrequently-used data is paged out, rather than discarded. Specifying MAXVIRT allows you to limit the maximum amount of auxiliary storage that could be used to back the VLF virtual storage that is holding the objects in the class.

The MAXVIRT value does not represent the *exact* amount of virtual storage that can be used to store objects. A small percentage of the storage (about 10 percent) is used for control information, and, in most cases, VLF begins to "trim" (discard) least recently used objects when the amount of

virtual storage used for the class approaches 90 percent of the MAXVIRT value. Therefore, allow some excess.

3. A list of the major names that represent the eligible sources of data for objects in the VLF class.

How you specify the major names depends on whether the VLF class is a PDS class or a non-PDS class.

For a PDS class, each major name identifies a unique partitioned data set and consists of a PDS name concatenated to the volume serial number. For a PDS class, use the EDSN and VOL parameters on the CLASS statement to define the major names.

For a non-PDS class, the major name does not correspond to a partitioned data set. To specify the eligible major names for the class, use the EMAJ parameter on the CLASS statement. For an IBM-supplied class, use the product information to determine if anything other than the name(s) specified in the IBM-supplied default COFVLFxx member are eligible.

In addition to the class and major name, VLF also needs a minor name to identify a unique data object, but the minor names do not come from the COFVLFxx parmlib member.

In using the VLF naming structure, consider the TSO/E use of VLF to manage objects in the IKJEXEC class.

- Each TSO user can have a SYSPROC DDNAME with a different concatenation. When TSO/E identifies the user to VLF, it specifies DDNAME(SYSPROC). VLF then determines the major names (volume serial number and PDS name combinations) that make up the individual major name search order for that user. VLF returns a unique user token (UTOKEN) for that user.
- When that user requests a specific object (such as a CLIST named COPY) from the IKJEXEC class, the user token implicitly specifies the major name search order. When VLF returns the COPY object to the user, the object represents the first object with that minor name to be found in the major name search order for that user.

COFVLFxx parmlib members can be concatenated. When they are concatenated, a class definition can span parmlib members.

## Collecting VLF statistics

---

SMF record type 41 record, subtype 3, allows you to capture SMF data related to the usage of VLF. If you request subtype 3, the system writes this record every 15 minutes. For more information about the type of data SMF provides, see *z/OS MVS System Management Facilities (SMF)*.

## Parameter in IEASYSxx (or issued by the operator)

---

None.

## Syntax rules for COFVLFxx

---

The following syntax rules apply to COFVLFxx:

- The content of the member is one or more CLASS statements.
- A CLASS statement begins with the statement identifier “CLASS” and ends with the end of file (EOF) or when another class statement identifier is found. No explicit continuation syntax is required.
- Commas and blanks in any combination constitute a delimiter.
- Delimiters or comments can precede the statement identifier.
- Delimiters are not required between parameters with values; the right parenthesis after the specified parameter value is sufficient.
- Enter data only in columns 1 - 71. The system ignores data in columns 72 - 80.
- Comments begin with /\* and end with \*/. Comments are allowed between parameters.
- If a class statement contains duplicates of the following parameters, the system uses the first valid occurrence and issues a message that a duplicate parameter was specified:

- NAME
- MAXVIRT(nnn)
- multiple VOL parameters for one EDSN parameter.
- COFVLFxx parmlib members can be concatenated. When they are concatenated, a class definition can span parmlib members.

For more general syntax rules, see “General syntax rules for the creation of members” on page 7.

## Syntax format of COFVLFxx

```
CLASS      NAME(classname)
           {EDSN(dsn1) [VOL(vol)] EDSN(dsn2)...}
           {EMAJ(majname1) EMAJ(majname2)...}
           [MAXVIRT(nnn)]
           [ALERTAGE(alert_age)]
```

## Starting VLF

Issue the following command to start VLF:

```
START VLF, SUB=MSTR, NN=xx
```

The two alphanumeric characters (xx) are added to COFVLF to form the name of the COFVLFxx member. If you do not code NN=xx, the system defaults to COFVLF00.

Note that VLF will not start unless SUB=MSTR is specified on the START command. SUB=MSTR means that VLF can continue to run across a JES restart. It is recommended that you arrange for the VLF start command to be issued automatically during the IPL process. If VLF is stopped and restarted during the life of an MVS IPL, any request by an application to retrieve or create a VLF object with a user token obtained prior to the restart causes VLF to pass a return code of X'10' back to the application and continue processing. The application should detect the return code and obtain a new token. For more information about using VLF macros, see *z/OS MVS Programming: Authorized Assembler Services Guide*.

COFVLFxx parmlib members can be concatenated. When they are concatenated, a class definition can span parmlib members.

## Statements and parameters for COFVLFxx

### CLASS

Each group of objects that VLF processes must have a CLASS statement defining it. The CLASS statement indicates that the following parameters define that particular group of objects to VLF.

#### ALERTAGE(*alert\_age*)

ALERTAGE specifies the age, in seconds, for objects in the specified class. The IBM Health Checker for z/OS check IBMVLF, VLF\_MAXVIRT uses the ALERTAGE to determine whether objects are being trimmed too rapidly to meet the installation's usage goals for VLF. You can specify an ALERTAGE in the range from 0 (which indicates that the check will find no exceptions for this class) to 99999999.

The default value is ALERTAGE(60).

The higher the ALERTAGE value you specify, the more likely it is that the VLF\_MAXVIRT check will issue an exception message. See the check description for [VLF\\_MAXVIRT](#) in *IBM Health Checker for z/OS User's Guide* for more information.

#### EDSN(*dsn*) [VOL(*vol*)]

For a PDS class, EDSN(*dsn*) identifies a partitioned data set name whose members are eligible to be the source for VLF objects in the class. The *dsn* can be 1 to 44 alphanumeric characters, including @, #, \$, and periods (.).

You do not need to specify the volume if the cataloged data set is the desired one. If the data set is not cataloged, or if you have multiple data sets with the same name on different volumes, you must specify VOL(*vol*). Without the volume serial number, an uncataloged data set is not included in the eligible data set name list. The system issues an informational message to the operator identifying any data sets where the system cannot find the catalog entry to extract the volume.

The *vol* can be any combination of alphanumeric characters, including @, #, and \$, or a dash (-).

Multiple occurrences of the same data set name with different volumes is acceptable. However, if duplicate entries of the same data set name and the same volume occur, the system issues an informational message and ignores the redundant information.

Do not use the EDSN parameter and the EMAJ parameter on the same CLASS statement.

#### **EMAJ(*majname*)**

EMAJ identifies an eligible major name (*majname*) for a non-PDS class, a class that does not have major names and minor names that are related to partitioned data sets and their members. The *majname* can be 1 to 64 alphanumeric characters except comma (,), blank, or right parenthesis ( ) ; for example EMAJ(LLA).

Do not use the EMAJ parameter and the EDSN parameter on the same CLASS statement.

#### **MAXVIRT(*nnnnnn*)**

MAXVIRT(*nnnnnn*) is an optional parameter that allows you to specify, in 4 K blocks, the maximum amount of virtual storage that VLF can use to store objects for the class.

The value for *n* must be a decimal number from 256 through 524288. You can specify up to six digits, including leading zeros. The maximum value is the maximum data space size. If the system cannot obtain the amount of storage that is specified on MAXVIRT, it obtains as much as possible.

VLF trims least frequently used objects when the amount of storage that is used for a class approaches 90 percent of its MAXVIRT value. For example, if the MAXVIRT value of a class is 1024, VLF begins trimming when the objects of the class exceed 921 4-K blocks of storage. By way of trimming, VLF keeps the most frequently used objects in storage. Small amounts of trimming should be considered normal. A continuous large amount of trimming might indicate that VLF effectiveness is constrained. In this case, it might be advisable to address the trimming. To lessen the chance of trimming, specify a large enough value for MAXVIRT. Specifying a MAXVIRT value that is too large can, in some cases, cause high CPU utilization in VLF. The IGGCAS class for CATALOG is one class where caution should be paid to avoid over specifying MAXVIRT.

**Note:** Subtype 3 of SMF record type 41 can be used to examine any trimming that might be occurring.

If the value for *n* is not in the valid range, the system uses 16 megabytes (4096 4 K blocks.)

**Default:** MAXVIRT(4096)

#### **NAME(*classname*)**

NAME(*classname*) specifies the name of the VLF class. The *classname* can be one to seven alphanumeric characters including @, #, and \$. IBM-supplied VLF class names begin with the letters A through I, for example, NAME(CSVLLA). See the COFVLFxx member of SYS1.SAMPLIB for the IBM-supplied VLF class names. Installation-supplied class names must begin with the letters J-Z or @, #, or \$.

NAME(*classname*) is required on the CLASS statement.

## Chapter 21. COMMNDxx (commands automatically issued at initialization)

COMMNDxx is an optional, installation-created list of automatic commands the system internally issues as part of system initialization. COMMNDxx is useful for automatic entry of commands that are frequently issued at system initialization.

You cannot use this member to issue JES commands, because JES is not started when the system issues the COMMNDxx commands.

**Note:** Some commands should not be issued frequently in large numbers. For example, issuing a large number of VARY device commands could cause your system to go into a 07E wait state. While a 07E wait state may not be seen, IPL performance may be affected when a large number of VARY device commands need to be processed from a COMMNDxx member. See [z/OS MVS System Commands](#) for possible restrictions on other commands.

System trace is activated during the IPL. You can deactivate system trace or change trace options by using the TRACE operator command or by selecting a COMMNDxx parmlib member that contains the options you want. (For information about the TRACE command, see [z/OS MVS System Commands](#).)

**Note:** Do not use COMMNDxx to enter SLIP commands. Instead, use the IEASLPxx parmlib member, with the SET SLIP=xx command specified in COMMNDxx to identify the IEASLPxx member to be used.

Some console-oriented commands affect the operation of a console. You can issue a console-oriented command directly from a console or you can place the command in a COMMNDxx member. If you place a console-oriented command (other than CONTROL M) in COMMNDxx and you do not specify a routing location operand, the system does not execute the command and might not generate an error message. The CONTROL M command does not support routing location operands, but it is valid in COMMNDxx.

When you specify the routing location operands, do so only as described in [z/OS MVS System Commands](#).

If you do not include CMD=xx in the system parameter list (IEASYSxx), or if the operator does not specify CMD=xx, the system searches for the COMMND00 member by default. The COMMND00 member, if it exists, is read if CMD=xx is not included in the system parameter list (IEASYSxx) or is not specified by the operator. If the system cannot locate either the specified COMMNDxx member or COMMND00 during initialization, processing continues without automatic commands.

### Parameter in IEASYSxx (or issued by the operator)

```
CMD= {aa }
      {(aa,bb...)}

```

The two-character identifier (aa,bb,etc.) is appended to COMMND to identify the COMMNDxx member(s) of parmlib. Multiple members can be specified.

**Note:**

1. Commands issued from COMMNDxx do not show on the console. Therefore, the results of these commands may appear on the console without the operator's seeing the command.
2. Commands are issued in the order that they appear in COMMNDxx, but they are executed as follows:
  - Immediate commands, such as DISPLAY T, are executed sequentially as they are issued from COMMNDxx.
  - Execution of task-creating commands, such as DISPLAY A, is deferred until system initialization is complete. Then, factors such as multitasking, multiprocessing, and competition for resources influence the order in which these commands are executed. Thus, COMMNDxx should *not* be used

to issue task-creating commands that must be executed in a specific order, because the execution order of these commands can vary.

3. A command placed in COMMNDxx must look exactly as it does if entered from the console. For example, to place the command SE 'TSO IS UP', CN=CONS1 in COMMNDxx, specify the following:

```
COM='SE 'TSO IS UP',CN=CONS1'
```

## Support for system symbols

System commands in COMMNDxx can specify system symbols. System symbols can represent any type of variable text in system commands, with the exception of command prefixes and names.

Figure 9 on page 192 is an example of a COMMNDxx member that includes system symbols. See Figure 5 on page 45 for a sample IEASYMxx member that defines the system symbols in this COMMNDxx member.

```
COM='S VTAM,,,(LIST=&NODE);'
COM='S NETVIEW,SUB=MSTR,CAT=&CATALOG;,SYS=&SYSNAME;'
COM='S APPC,SUB=MSTR,APPC=02'
COM='S ICR&SYSNAME;.SYSLOG'
COM='SET DAE=01'
COM='SET DAE=&DAE;'
COM='SETXCF START,POLICY,TYPE=CFRM,POLNAME=&POLNAME;'
```

*Figure 9. Example: COMMNDxx parmlib member*

Be aware that the system does not process system symbols in COMMNDxx during parmlib processing. Instead, the system processes the system symbols in the same way that it processes system symbols in commands that are entered on a console. When a command flows through two or more systems in a sysplex, the target system processes the system symbols in the command text, with a few exceptions. See the section on sharing system commands in *z/OS MVS Planning: Operations* for details about how the system processes system symbols in commands that flow through two or more systems.

## Syntax rules for COMMNDxx

The following rules apply to the creation of COMMNDxx:

- Enter only one command per line. To do so, specify the COM=keyword, followed by the command enclosed in single quotation marks.
- Do not specify continuation on any line.
- Lines that begin with an asterisk in column 1 are comments.
- Do not use COMMNDxx to enter MONITOR commands. Instead, use the SETCON MONITOR command to enable or disable Monitor messages.

## IBM-supplied default for COMMNDxx

None.

## Statements and parameters for COMMNDxx

### COM='command'

The specified command is issued by the system during initialization.

**Default:** No commands are issued.

## Chapter 22. CONFIGxx (standard configuration list)

CONFIGxx is a list of control statements that an installation can use to define a standard configuration of system elements. The system elements include the processors, storage, channel paths, devices, PCIE function identifiers (PFIDs), and volumes. You can use the configuration defined in CONFIGxx in two ways:

1. To compare the differences between the current configuration and the standard configuration as defined in a CONFIGxx member. When the operator issues the DISPLAY command with the M=CONFIG(xx) option, the system displays any differences.
2. To reconfigure some of the system elements. The operator can issue the CONFIG command with the MEMBER option.

### Comparing the current and standard configurations

In response to the DISPLAY M=CONFIG(xx) command, the system compares the contents of the CONFIGxx member to the existing configuration. It then displays the differences to the operator. The operator can then resolve these differences by using the CONFIG command.

### Matching configurations

If the existing configuration matches the one specified in CONFIGxx, the following message (IEE097I) is sent to the target console:

```
NO DEVIATION FROM REQUESTED CONFIGURATION
```

### Nonmatching configurations

If the existing configuration does not match the one specified in CONFIGxx, the following message (IEE097I) is sent to the target console:

|        |         |        |
|--------|---------|--------|
| syselm | DESIRED | ACTUAL |
| aaa    | bbb     | ccc    |

- syselm is the system element (CHP, CPU, DEVICE, ESTOR, STORAGE, SWITCH, VOLUME, PFID, or PAV).
- aaa is the address of the system element.
- bbb is the status specified in CONFIGxx.
- ccc is the existing status.

### Examples of CONFIGxx parmlib member

If CPU 0 is actually offline, but is specified as online in CONFIGxx, the message is:

|     |         |         |
|-----|---------|---------|
| CPU | DESIRED | ACTUAL  |
| 00  | ONLINE  | OFFLINE |

If CPU 0 is actually online and a standard (general purpose) processor, but is specified as offline and a zIIP processor in CONFIGxx, the message is:

|     |                 |                    |
|-----|-----------------|--------------------|
| CPU | DESIRED         | ACTUAL             |
| 00  | OFFLINE<br>zIIP | ONLINE<br>STANDARD |

### Error in CONFIGxx statement

If a statement in CONFIGxx is incorrect, the following message (IEE097I) is sent to the target console:

```
INVALID aaa SPECIFIED BEGINNING xxx
```

- aaa is either
  - REQUEST TYPE if the statement is not recognized or
  - OPERAND if there is an error in specifying an operand.
- xxx is the first sixteen characters of the invalid CONFIGxx statement.

## Reconfiguring system elements

---

The CONFIG command with the MEMBER option enables the operator to reconfigure the system according to the options in the specified CONFIGxx member. This reconfiguration is effective until the operator issues a different CONFIGxx MEMBER command or until the operator IPLs the system. With this command, the operator can reconfigure or verify the configuration of available channel paths, processors, storage elements, PCIE function identifiers (PFIDs), and switches. These are defined by the CHP, CPU, STOR(E=id), ESTOR(E=id), PFID, and SWITCH statements in CONFIGxx. Other statements found in CONFIGxx, such as DEV, VOL, ESTOR(ddddM-ddddM), and PAV, cannot be used for reconfiguration; they can be used only for verification.

The SWITCH record allows verification or reconfiguration of ports on a specified switch device in regard to the dynamic channel path management function. The DCM parameter verifies the enabled status or enables the specified port or port range. The NODCM parameter verifies the disabled status or disables the specified port or port range.

See *z/OS MVS System Commands* for more information about the DISPLAY and CONFIG commands.

**Note:** If you specify ONLINE and OFFLINE in the same CONFIGxx member, the ONLINE options are processed before the OFFLINE options. The system processes statements that include the ONLINE option in the following order:

1. STOR
2. CPU
3. CHP
4. PFID

The system processes statements that include the OFFLINE option in the following order:

1. PFID
2. CHP
3. CPU
4. STOR

## Parameter in IEASYSxx:

---

None.

## Syntax rules for CONFIGxx

---

Use the general syntax rules listed in the introduction to this chapter with the following exceptions:

- Continuation statements are not permitted.
- Comment statements are permitted and are indicated by an asterisk in column one.

## IBM-supplied default for CONFIGxx

---

None.



## Statements and parameters for CONFIGxx

### CHP

Specifies the configuration of the channel paths. The syntax is as follows:

```
CHP {xx} [,ONLINE] [,STATIC]
    {(xx-xx)} [,MANAGED]
    {(ALL,id)} [{,OFFLINE},{,UNCOND}]
    {(list)} [{,FORCE}]
```

- xx is one or two hexadecimal digits that identify the channel path identifiers and indicate the different combinations of channel paths.
- ALL, id specifies all channel paths on the side that is identified by the side identifier (id), which can be either 0 or 1. Use CHP ALL,id only when your system is able to be partitioned.
- list can be any combination of the elements (except ALL,id) separated by a comma. The list must be enclosed in parentheses.
- STATIC indicates that the channel path was statically defined to control units in the channel subsystem. (Used for verification only.)
- MANAGED indicates that the channel path was defined to be managed among control units in the channel subsystem. (Used for verification only.)
- OFFLINE, FORCE



**CAUTION:** FORCE is a very powerful option. See the CONFIG command in [z/OS MVS System Commands](#).

**Example:** This example specifies that channel paths 0, 3, 4, 5, 10, 12, 13, 14, and 15 are to be either verified or reconfigured as online, depending on the command issued.

```
CHP (0,3-5,10,12-15)
```

For information about generating CONFIGxx statements through the z/OS Hardware Configuration Definition (HCD), see [z/OS HCD User's Guide](#).

### CORE

Specifies the configuration for a core. The syntax is as follows:

```
{CORE} {(x[,x[,x]...])} [{,ONLINE},{,OFFLINE}] [,OFFLINE] [{,STANDARD | ,ZAAP | ,ZIIP | ,ANY}]
```

- x is a hexadecimal value that specifies the address of the core.
- STANDARD indicates that the core specified to be brought online or offline is expected to be a standard (general purpose) core.
- ZAAP indicates that the core specified to be brought online or offline is expected to be an IBM zEnterprise® Application Assist Processor (zAAP) core.
- ZIIP indicates that the core specified to be brought online or offline is expected to be an IBM z Integrated Information Processor (zIIP) core.
- ANY indicates that the core specified to be brought online or offline can be any type of core.

#### Note:

1. ANY is the default if no core type is specified.
2. If the processor that is being configured does not match the core type that was specified, the command is rejected, and the system issues message IEE241I with 'PROCESSOR TYPE MISMATCH'.
3. The CORE parameter is rejected when LOADxx PROCVIEW CPU is in effect. See the LOADxx PROCVIEW CPU parameter in [“Statements and parameters for LOADxx”](#) on page 618.

**CPU or CPUAD**

Specifies the configuration for the processors. The statement can be specified as CPU or CPUAD. The syntax is as follows:

```
{CPU } { (x) } [, ONLINE [, { STANDARD | ZAAP | ZIIP | ANY } ] ]
{CPUAD} { (x,x[,x]...) } [, OFFLINE [, { STANDARD | ZAAP | ZIIP | ANY } ] ]
{CPUAD|CPU} { (x,[x[,x]...]) } [{ ONLINE|OFFLINE } [, { STANDARD | ZAAP | ZIIP | ANY } ] ]
```

- *x* is a hexadecimal value that specifies the address of the processor.
- STANDARD indicates that the processor specified to be brought online or offline is expected to be a standard (general purpose) processor.
- ZAAP indicates that the processor specified to be brought online or offline is expected to be an IBM zEnterprise Application Assist Processor (zAAP).
- ZIIP indicates that the processor specified to be brought online or offline is expected to be an IBM z Integrated Information Processor (zIIP).
- ANY indicates that the processor specified to be brought online or offline can be any type of processor.

**Note:**

1. ANY is the default if no processor type is specified.
2. If the processor being configured does not match the processor type that is specified, the command is rejected, and the system issues message IEE241I with PROCESSOR TYPE MISMATCH.
3. The CPU/CPUAD parameter is rejected when LOADxx PROCVIEW CORE is in effect. For more information, see the LOADxx PROCVIEW CPU parameter in [“Statements and parameters for LOADxx”](#) on page 618.
4. With LOADxx PROCVIEW CORE,CPU\_OK, CPU is accepted and treated as an alias for CORE. For more information, see the LOADxx PROCVIEW CPU parameter in [“Statements and parameters for LOADxx”](#) on page 618.

**Example:** Depending on the command that is issued, this example specifies that the processor addressed by 2 is to be either verified as online or reconfigured online.

```
CPU (2),ONLINE
```

**DEV or DEVICE**

Specifies the configuration for devices. The syntax is as follows:

```
{DEV } { dev } [,xx ] [,ONLINE ]
{DEVICE} { dev-dev } [, (list) ] [,OFFLINE ]
{ (list) } [, * ]
```

- *dev* specifies the device number and reflects the different combinations of devices. Each *dev* is 1 to 4 hexadecimal digits, optionally preceded by a slash (/).
- *list* can be any combination of the elements that are separated by a comma. The list must be enclosed in parentheses.
- *xx* specifies the channel paths to be used to access the devices.
- \* is used to verify that at least one channel path is online and can access the devices, regardless of which channel path it is.

The system displays a deviation message (IEE097I) for any of the following conditions:

- If channel paths are specified and all of the specified channel paths to the devices are not online or offline.
- If \* is specified and there is no channel path online to access the devices.

- If channel paths are not specified and \* is not specified and all of the channel paths to the devices are not online or offline.

### Examples:

- To cause the system to verify that the devices with device numbers 334 and 33A can be accessed through channel path 12, code:

```
DEV (334,33A),12,ONLINE
```

- To cause the system to verify that the devices with device numbers 340 through 34F can be accessed by all of their associated channel paths, code:

```
DEV 340-34F,ONLINE
```

- To cause the system to verify that devices 100 and 2000 through 21F0 can each be accessed by channel paths 01, 11, and 21, code:

```
DEV (100,2000-21F0),(01,11,21)
```

**Example:** This example assumes the default of ONLINE.

- To cause the system to verify that devices A451, A453, and A455 can be accessed by at least one channel path, code:

```
DEV (A451,A453,A455),*,ONLINE
```

The \* indicates that it is unimportant which channel paths are used to access the devices.

For information about generating CONFIGxx statements through the z/OS Hardware Configuration Definition (HCD), see [z/OS HCD User's Guide](#).

## ESTOR

Specifies the configuration for elements of expanded storage. The syntax is as follows:

```
ESTOR { (E=id) } [ ,ONLINE ]
      { (ddddM-ddddM) } [ ,OFFLINE ]
```

- *id* is the identifier of a storage element. The identifier can be one to four hexadecimal digits from X'0000' to X'FFFF'.
- *dddd* is one to four decimal digits that must be a multiple of 4, followed by an M (megabytes), and cannot exceed a value of 4095. These values are the starting and ending addresses of the section of storage to be verified. You can specify only one range. The starting and ending address must not be the same.

### Note:

1. A CONFIGxx parmlib member that contains the ESTOR(ddddM-ddddM) can be used only as the target of a DISPLAY M=CONFIG command. It cannot be used to reconfigure storage.
2. ESTOR is not supported in the z/Architecture environment. Its specification is tolerated by CONFIGxx and ignored during IPL.

**Example:** This example indicates that a section of expanded storage, whose identifier is X'03' is to be either verified or reconfigured as online.

```
ESTOR(E=03),ONLINE
```

**Example:** This example indicates that a section of expanded storage (location 0 through location 67,108,864) is to be verified as online.

```
ESTOR (0M-64M),ONLINE
```

**PFID**

Specifies the configuration of the PCIE function identifiers (PFIDs). The syntax is as follows:

```
PFID { (xxxx) } [, ONLINE | ON ]
     { (aaaa-bbbb) } [, { OFFLINE | OFF } [, FORCE ] ]
     { (list) }
```

- xxxx is a single PFID. The PFID may have a hexadecimal value from 0 to X'FFFF'.
- aaaa-bbbb is a range of PFIDs. The starting and ending PFIDs may have values from 0 to X'FFFF'. The maximum number of PFIDs that may be specified on a single PFID range is 256.
- list is one or more single PFIDs, ranges of PFIDs, or a combination of single PFIDs and ranges of PFIDs.
- ONLINE or ON brings the specified PFID or PFIDs online.
- OFFLINE or OFF takes the specified PFID or PFIDs offline.
- OFFLINE, FORCE



**CAUTION:** FORCE is a very powerful option. See the CONFIG command in [z/OS MVS System Commands](#).

For information about generating CONFIGxx statements through the z/OS Hardware Configuration Definition (HCD), see [z/OS HCD User's Guide](#).

**STOR or STORAGE**

Specifies the configuration for sections of storage. Multiple ranges can be specified. The statement can be specified as STOR or STORAGE. The syntax is as follows:

```
{ STOR } { ddddddK-dddddddK } [, ONLINE ]
{ STORAGE } { xxxxxxxxxxxxxxxx-xxxxxxxxxxxxxxxx } [, OFFLINE]
            { ddddX-ddddX }
            { (E=id) }
            { (list) }
```

- dddddd is one to seven decimal digits, followed by a K, which are the starting and ending addresses of the section, and cannot exceed a value of 4194303. Each address represents a multiple of 1024 bytes. If necessary, the system rounds the low address down to the next lower 4 K boundary. (This rounding is done to begin and end a section of storage on a 4 K boundary.) The system does not reconfigure a section of storage (in response to a CONFIG command) when the section is specified in this manner.
- xxxxxxxxxxxxxxxx is one to sixteen hexadecimal digits that address the first and last bytes of the section. If necessary, the system rounds the low address down to the next lower 4 K boundary. (This rounding is done to begin and end a section of storage on a 4 K boundary.) The system does not reconfigure a section of storage (in response to a CONFIG command) when the section is specified in this manner.

**Note:** You can insert underscores in hexadecimal specifications to make them easier to read. Underscores are ignored during processing, and do not count towards the number of digits that are used for the address.

- dddd is one to five decimal digits, followed by a multiplier, which are starting and ending addresses of the section, and cannot exceed a value of 16383. The valid multipliers are:

**M**

Megabytes (2\*\*20 bytes)

**G**

Gigabytes (2\*\*30 bytes)

**T**

Terabytes (2\*\*40 bytes)

**P**

Petabytes (2\*\*50 bytes)

The starting and ending addresses must not be the same.

**Note:** You can also specify the addresses in explicit hexadecimal notation (X'xxxxx') followed by a multiplier.

- E=id specifies a storage element that is identified by the storage element identifier (ID), which is one hexadecimal digit.
- list can be any combination of the elements (except E=id) separated by a comma. The list must be enclosed in parentheses.

**Example:** This example indicates that a section of storage (location 8,388,608 through location 33,554,431) is to be verified as online.

```
STOR 8192K-32768K,ONLINE
```

**SWITCH**

Specifies the configuration of the switch ports for Dynamic Channel Path Management. If no SWITCH statement is specified for a switch port, then no verification occurs. The specification is routed to all systems in the logical partition cluster to ensure that all systems run with the same configuration of managed channel paths. The syntax is as follows:

```
SWITCH    { (ssss[,pp[-pp]]) }, DCM | ,NODCM
          { ALL }
```

- ssss is the device number of the switch device to be verified.
- pp[-pp] is the port number or port number list.
- ALL specifies all switch devices.
- DCM specifies that Dynamic Channel Path Management is allowed for the subject port.
- NODCM specifies that Dynamic Channel Path Management is not allowed for the subject port.

For information about generating CONFIGxx statements through the z/OS Hardware Configuration Definition (HCD), see [z/OS HCD User's Guide](#).

**VOL or VOLUME**

Specifies the configuration for DASD volumes. The statement can be specified as VOL or VOLUME. The device number on which a volume should be mounted can optionally be specified. The syntax is as follows:

```
{VOL      } {v      }
{VOLUME  } {v=dev  }
{list    }
```

- v is the volume name.
- dev is the device number and is 1 to 4 hexadecimal digits, optionally preceded by a slash (/). Any digit can be replaced with an X to indicate that the value of that digit is not important. The X and the hexadecimal numbers A, B, C, D, E, and F must be in uppercase.
- list can be any combination of the elements separated by a comma.

**Example:** This example specifies that PAGE1 and P00045 are to be verified as mounted. Mount P00045 on a device with a device number in the range 305 through 3F5.

```
VOL PAGE1,P00045=3X5
```

**PAV**

Specifying the Parallel Access Volumes (PAV) statement causes the display of a list of all unbound PAV-alias devices. No parameters are specified with the PAV statement. The syntax is as follows:

PAV

**HPAV**

Specifying the HPAV statement causes a list of unusable and temporarily unavailable HyperPAV aliases, if any, to be displayed by the DISPLAY MATRIX CONFIG command. No parameters are specified with the HPAV statement. The syntax is as follows:

HPAV

## Chapter 23. CONSOLxx (console configuration definition)

CONSOLxx is an installation-created member of parmlib in which you can define a console configuration to meet the particular needs of your installation.

In CONSOLxx, you define multiple console support (MCS), SNA multiple console support (SMCS) consoles, and Hardware Management Console multiple console support (HMCS) consoles. You define the specific characteristics of MCS, SMCS, HMCS, subsystem consoles, and the system console. You might need to have PF keys on one console issue one group of system commands while on another console you need the PF keys set to issue a different set of commands. You might need to have particular messages routed to one console, and you might want those messages deleted in a certain way. You might need a cluster of consoles to serve different functions for a subsystem. One console in the cluster might display, in a particular format, only the messages that are associated with a particular group of routing codes. Through CONSOLxx, you can specify the configuration and have the system automatically initialize the consoles.

**Note:** In a sysplex environment, up to 250 MCS, SMCS, HMCS, and subsystem consoles can be defined per z/OS image with a limit of 99 active MCS, SMCS, HMCS, and subsystem consoles per z/OS image.

Through CONSOLxx, you can specify initialization values for all console configurations. For example, you can define the characteristics of the hardcopy message set and set routing codes for messages that do not have routing information. You can specify the parmlib member that contains tracing options for the operations services (OPS) component.

You also can specify the operator logon requirements for the consoles at your installation (except the system console). Setting operator logon requirements depends on the security policy in effect at your installation. For information about how operator logon requirements relate to securing access to system commands, and examples of defining consoles through CONSOLxx, see [z/OS MVS Planning: Operations](#).

You can use some operator commands to dynamically change the console attributes. The changes that are made by such commands are only effective when the console is active. The CONSOLxx values will be used the next time the console is activated. For the most part, operator commands cannot change the attributes of an inactive console. See [“Related commands” on page 202](#) for more information.

SET CON= can be used to dynamically add a console definition and to dynamically change console settings and attributes.

**Note:** MCS consoles are locally attached to the system through control devices that do not support Systems Network Architecture (SNA) protocols. SMCS consoles use z/OS Communications Server to communicate with the system and might be remotely attached to the system. SMCS consoles are only available for use when the z/OS Communications Server is active. HMCS consoles are on the Hardware Management Console Integrated 3270 Console window.

**Important:** If automation is used to remotely IPL z/OS, the HMCS console (the "Integrated 3270 Console" that is located on the Hardware Management Console) must be disconnected from the z/OS partition that is to be IPLed before the IPL is initiated. Failure to do so will prevent automation from receiving messages that are issued during the IPL and prevent automation from taking any appropriate action.

### Using CONSOLxx in a sysplex

Take into account the following considerations when you are using CONSOLxx in a sysplex:

- When two or more systems in a sysplex require a CONSOLxx member, you can do one of the following actions:
  - Code a separate CONSOLxx member for each system in the sysplex (the least efficient method).

- Code a single CONSOLxx member for all systems in your sysplex. Specify parameters with sysplex scope to be used by all systems in the sysplex. Consider using system symbols to represent unique values in the member.
- CONSOLxx parameters with sysplex scope are valid only for the first system that enters a sysplex. Because these parameters are ignored by systems that later join a sysplex, you do not need to set them up to specify unique values for different systems in a multisystem environment. For a complete list of parameters in CONSOLxx that have sysplex scope, refer to *z/OS MVS Planning: Operations*.

If different systems require unique values on parameters that do not have sysplex scope, you can use system symbols to represent those unique values in a shared CONSOLxx member. When each system processes CONSOLxx, it replaces the system symbols with the values it has defined to them. See Chapter 2, “Sharing parmlib definitions,” on page 31.

- A named console can be defined on multiple systems, but can only be active on one system at one time.
- The system uses default values for the CONSOLxx statements INIT, HARDCOPY, and DEFAULT if you do not code them. If the default values for these statements are acceptable to your installation, do not code them for the systems in your multisystem environment.
- The console attributes specified in CONSOLxx are used whenever the console is activated. If the VARY command changes the attributes of an active console, those changes remain until the console is deactivated. The CONSOLxx values will then be used the next time that the console is activated. For the most part, the VARY command cannot change the attributes of an inactive console.
- For a complete list of the CONSOLxx values that can be changed by operator command, the sysplex or system scope of the values, and whether these values are restored to CONSOLxx parmlib member settings or IBM defaults by a single system IPL or by reinitialization of the sysplex, see the topic “Summary of CONSOLxx and Commands to Change Values” in *z/OS MVS Planning: Operations*.

## Related members of parmlib

---

CONSOLxx provides a way to centralize the definitions of the console configuration for your installation. Within CONSOLxx, you specify:

- MPFLSTxx parmlib members for message processing control.
- The MMSLSTxx parmlib member to display translated U.S. English messages into another language that your installation has provided.
- The PFKTABxx parmlib member to define any PFK tables you require.
- The CNGRPxx parmlib member to define SYNCHDEST and AUTOACT groups.
- The MSGFLDxx parmlib member to define your installation policy for controlling message flooding situations.

Specifying MPFLSTxx members, the MMSLSTxx member, and the PFKTABxx member within the CONSOLxx member makes it easier to maintain these related members of parmlib rather than setting them after IPL with the SET operator command. See Chapter 76, “MPFLSTxx (message processing facility list),” on page 643, Chapter 75, “MMSLSTxx (MVS message service list),” on page 639, and Chapter 80, “PFKTABxx (program function key table definition),” on page 681. See Chapter 17, “CNGRPxx (specify console groups),” on page 177 for information about specifying CNGRPxx.

CONSOLxx is closely related to the Add Device panel of hardware configuration definition (HCD). The device number you specify in CONSOLxx must match the device number on the panel. See *z/OS HCD User's Guide*.

See also “Parameter in IEASYSxx (or supplied by the operator)” on page 205

## Related commands

---

Through the CONTROL, SET, and VARY commands, you can change some of the characteristics that are specified in CONSOLxx.



The changes can only persist while the console is active. When the console is activated, the attributes of the console are always obtained from CONSOLxx for MCS, SMCS, HMCS, or subsystem consoles.

If the console is inactive, the request to change the console attribute is rejected, with a few exceptions. See the specific command description in [z/OS MVS System Commands](#) for more details.

When system S1 is IPLed into a sysplex, the console CONS1 is defined in the CONSOLxx member with AUTH(INFO). The operator enters a VARY CN(CONS1),AUTH=SYS to give the console a higher authority. System S1 is then removed from the sysplex. When S1 is IPLed and the CONSOLxx member is processed, CONS1 will again have INFO authority.

For more information, see [z/OS MVS System Commands](#).

CONSOLxx contains four optional statement types:

- CONSOLE, which is optional if processor supports the system console. If not, a CONSOLE statement is required for the first system in a sysplex.
- INIT
- HARDCOPY
- DEFAULT

## CONSOLE statement

---

The CONSOLE statement lets you define each console by device number on the CONSOLE statement.

Within a sysplex, different MCS consoles on different systems might have the same device number. Each console must be defined by a unique name that identifies it to the sysplex. The console name you define on the CONSOLE statement is used to identify a given console in system commands (MGCRE), write-to-operator (WTO), write-to-operator-with-reply (WTOR), and installation exits.

All consoles, except for the system console, require a console name to be specified. If no name is specified, the console definition is rejected. For the system console, if a name is not specified, a name is generated by the system.

A console that is defined to more than one system can be active on only one system in the sysplex at a time. If different attributes for the same console are defined in separate CONSOLxx members activated on different systems, the console can have different attributes when activated on different systems.

Besides defining the console by device number, you can also specify initial values for the console's attributes with the CONSOLE statement.

You must have a CONSOLE statement for each device that you want to use as a console. Use the Add Device panel in hardware configuration definition (HCD) to specify the device number and the unit type for MCS consoles only. SMCS consoles require the terminals to be defined for use via z/OS Communications Server. For more information about defining devices for use by z/OS Communications Server, see [z/OS Communications Server: SNA Resource Definition Reference](#). The entries on the panel must match the CONSOLE statement. A CONSOLxx member can include multiple CONSOLE statements; one for each console in the configuration. For more information about the Add Device Panel for HCD, see [z/OS HCD User's Guide](#).

A system command (SETCON DELETE,CN=) and a sample service (IEARELCN) allow you to remove the definition of an MCS, SMCS, HMCS, or subsystem console from a system or sysplex. Before you can delete the definition, the console needs to be inactive.

The IEARELCN service is available as a sample job in the samplib member. For information about the console service, see [z/OS MVS Planning: Operations](#).

## INIT statement

---

You can take the following steps using the INIT statement:

- Specify the limits for WTL, WTO, and WTOR buffers.

- Specify one or more MPFLSTxx members to use with this CONSOLxx member.
- Specify the PFKTABxx member to use with this CONSOLxx member.
- Specify the MMSLSTxx member to use with this CONSOLxx member.
- Specify the CNGRPxx member to set up console groups.
- Specify the Parmlib member that contains component trace options for the operations services (OPS) component.
- Activate the action message retention facility.
- Activate the WTO installation exit IEAVMXIT.
- Specify the MONITOR command to display mount messages.
- Specify an MVS command delimiter so an operator can issue multiple commands.
- Specify the maximum number of seconds the ROUTE \*ALL or ROUTE *systemgroupname* command waits before aggregating responses.
- Specify the z/OS Communication Server APPLID that SMCS is to use on this system.
- Specify the z/OS Communication Server Generic Resource name that SMCS is to use in this sysplex.
- Specify the MSGFLDxx parmlib member to define your installation policy for controlling message flooding situations.

The INIT statement is optional. If you do code an INIT statement, you can code only one in a CONSOLxx member. See [“Syntax and parameters for an INIT statement” on page 222.](#)

## HARDCOPY statement

---

You can take the following steps using the HARDCOPY statement:

- Specify whether the hardcopy medium active at initialization is SYSLOG, OPERLOG or both
- Specify the routing codes for messages to be included in the hardcopy message set
- Specify the kinds of messages (commands, responses or status display) to be included in the hardcopy message set
- Specify whether hardcopy records should have a 4-digit year

The HARDCOPY statement is optional. If you do not specify HARDCOPY, the system uses SYSLOG as the hardcopy medium. You can have only one HARDCOPY statement in a CONSOLxx member. See [“Syntax and parameters for the HARDCOPY statement” on page 220.](#)

For more information about the hardcopy message set, see [z/OS MVS Planning: Operations.](#)

## DEFAULT statement

---

You can take the following steps on the DEFAULT statement:

- Define the default routing codes for unsolicited WTO and WTOR messages that have no routing codes, no descriptor codes, and no console ids assigned.
- Define whether operators must log on to the system before issuing commands from MCS, SMCS, or HMCS consoles.
- Specify whether you want hold mode for consoles.
- Specify the maximum value of a reply ID in the sysplex.
- Define a console group to receive synchronous WTO or WTOR messages that the system issues.

The DEFAULT statement is optional. If you specify DEFAULT, you can have only one DEFAULT statement in a CONSOLxx member. See [“Syntax and parameters for the DEFAULT statement” on page 218.](#)

If you do not code the DEFAULT statement, the system assigns routing codes 1 through 16 to messages that have no other routing attributes, and MCS and HMCS consoles do not require LOGON. SMCS consoles will require logon.

## Parameter in IEASYSxx (or supplied by the operator)

```
CON= {aa}
      {(aa[,L][,NOJES3])}
      {NONE}
      {(NONE[,L][,NOJES3])}
      {NOJES3}
```

The two alphanumeric characters (aa) are appended to CONSOL to form the name of the CONSOLxx member of Parmlib. If you specify the L option in IEASYSxx, or in reply to the 'SPECIFY SYSTEM PARAMETERS' message, the system lists (displays) on the operator's console, all of the statements that are in the CONSOLxx member. If CON=NONE is specified, the system is initialized with the IBM defaults for the values in CONSOLxx.

Specify the NOJES3 option if JES3 is installed on your system, but is not to be used. For systems that have both JES2 and JES3 installed, but run only JES2, the NOJES3 option allows you to omit the comma separating the REPLY ID from the command text when using short form replies to responding to system requests.

## Syntax rules for CONSOLxx

Use the general syntax rules listed in [“General syntax rules for the creation of members”](#) on page 7 with the following exceptions:

- You can define up to 251 consoles (including the system console) within a CONSOLxx member. The maximum number of consoles per system in the sysplex is 250 and 99 of which can be concurrently active, plus one system console for each system.
- Data must be contained in columns 1-71; the system ignores columns 72-80.
- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.
- You do not need to code delimiters between parameters; you can use either blanks or commas between parameters.
- One or more blanks can precede or follow the statement types (CONSOLE or INIT, for example).
- At least one blank must immediately follow the statement types (INIT, DEFAULT, HARDCOPY, and CONSOLE).
- Parameter values must be set off by parentheses. If you code multiple values on certain keywords, separate the values with a comma. Some keywords will allow you to separate multiple values with a blank. See the keyword documentation for specific syntax.
- Do not use blanks in the middle of a keyword, in the middle of a value, or between the parameter and the left parentheses before the value.
- A statement type must be the first data item on a record.
- You can code comments before any statement type.
- A statement type continues to the next statement type in the member or until the end of the member.
- System symbolics can be used anywhere within the CONSOLxx member.
- For the CONSOLE statement, use the following rules:
  - On each CONSOLE statement, DEVNUM is required and must be the first parameter.
  - Any values that you specify for the NAME parameter on the CONSOLE statement must be unique across the sysplex.
  - Do not use a name on the NAME parameter that might be confused with a device number. For example, the console name BEAD is not recommended, since it might be confused with device number X'BEAD'.

## IBM-supplied default for CONSOLxx

---

None. You can create a CONSOLxx member by modifying the IBM-provided sample member IEACONXX in SYS1.SAMPLIB. If no CONSOLxx member is supplied, the system messages go to the system console and the system uses the defaults for the other values in CONSOLxx. For information about when to initialize the system with CON=NONE, see *z/OS MVS Planning: Operations*.

## Statements and parameters for CONSOLxx

---

CONSOLxx includes the following statements:

- [“Syntax and parameters for the CONSOLE statement” on page 206](#)
- [“Syntax and parameters for the DEFAULT statement” on page 218](#)
- [“Syntax and parameters for the HARDCOPY statement” on page 220](#)
- [“Syntax and parameters for an INIT statement” on page 222](#)

### Syntax and parameters for the CONSOLE statement

The syntax of the CONSOLE statement is as follows:

```

CONSOLE  DEVNUM  {(devnum)
                  {(SUBSYSTEM)
                  {(SYSCONS)
                  {(SMCS)
                  {(HMCS)      }
                  }

UNIT      {(unitttype)}
          {(PRT)         }

NAME      (conname)

AUTH      {(MASTER)
          {(INFO)
          {( [SYS] [, IO] [, CONS])
          {(ALL)         }

USE        {(FC)
          {(MS)
          {(SD)         }

ROUTCODE   {(ALL)
          {(NONE)
          {(nnn [, nnn- nnn] [, nnn] . . . )}

LEVEL      {(ALL)
          {( [ALL] [, NB])
          {( [R] [, I] [, CE] [, E] [, IN] [, NB])}

CON        {(Y)
          {(N)         }

SEG(nn)

DEL        {(Y)
          {(R)
          {(RD)
          {(N)
          {(W)         }

RNUM       {(nn)
          {(5)         }

RTME       {(nnn)
          {(2)         }

MFORM      {(M)
          {( [J] [, S] [, T] [, X])}

AREA       {(nn [, nn] . . . )}
          {(NONE)         }

PFKTAB(tablname)

MONITOR({JOBNAMES[-T]}{, SESS[-T]}{, STATUS})

MSCOPE     {( [sysname|*] [, sysname|*] . . . )}
          {( *ALL)         }

CMDSYS     {(sysname)
          {( * )         }

RBUF       {(nn)
          {(15)         }

```

```

AUTOACT    (groupname)

SYSTEM     (sysname)

LU         (nnnnnnnn)

LOGON      {(REQUIRED)
          {(OPTIONAL)
          {(AUTO)
          {(DEFAULT)   }

INTIDS{(Y) | (N)}

UNKNIDS{(Y) | (N)}

ALLOWCMD{(Y) | (N)}
SUPSBY{(Y) | (N)}
TIMEOUT(nn)

```

**ALLOWCMD(Y)|(N)**

Specifies when the system console is able to issue commands. ALLOWCMD is only valid when DEVNUM is SYSCONS. If there are no entries with DEVNUM(SYSCONS), the system uses the default ALLOWCMD(N) as part of the IBM-defined console attributes.

**(N)**

The system console is restricted from issuing commands until it enters PD mode. This is the default value.

**(Y)**

The system console is permitted to issue commands even if it is not running in problem determination (PD) mode.

**AREA**

Specifies the size of the out-of-line display area on the display console. *nn* is a decimal specifying the number of lines in one display area. The first number defines the bottom area of the screen. Subsequent numbers define areas working toward the top of the screen. The minimum number of lines in an area is 4. The maximum number of areas is 11. The sum of the lines in all of the areas must not exceed the screen size. No individual area can be larger than 99. You can separate multiple values with a blank or a comma.

```
AREA      { (nn [, nn] . . . ) }
           { (NONE) }
```

**Restriction:** AREA is not valid when UNIT is PRT, or DEVNUM is SYSCONS.

**Default:** For screen sizes and maximum and default values for AREA, see [Table 20 on page 227](#).

**AUTH**

Specifies the group of operator commands that can be entered from the console. IBM strongly suggests using a security product, such as RACF, to control commands instead of using AUTH, especially with SMCS. For more information about SMCS and console security see [z/OS MVS Planning: Operations](#).

**Restriction:** AUTH is not valid with UNIT(PRT).

You can separate multiple values with a blank or a comma.

```
AUTH      { (MASTER) }
           { (INFO) }
           { ([SYS] [, IO] [, CONS]) }
           { (ALL) }
```

From a console with master authority, you can enter all MVS operator commands. The corresponding authority levels for JES3 are:

- CONS: JES3 authority level=10
- I/O: JES3 authority level=10
- INFO: JES3 authority level=0
- MASTER: JES3 authority level=15
- SYS: JES3 authority level=5

**ALL**

Information, system control, I/O control, and console control commands can be entered from this console.

**INFO**

Any informational commands can be entered from this console.

**MASTER**

Indicates that this is a console with master-level authority.

**[SYS][,IO][,CONS]****CONS**

Specifies that console control commands and informational commands can be entered from this console.

**IO**

Specifies that I/O control commands and informational commands can be entered from this console.

**SYS**

Specifies that system control commands and informational commands can be entered from this console.

For information about which commands can be entered from a console with a specific authority level, see [z/OS MVS Planning: Operations](#).

**Default:** INFO is the default for all consoles except the system console, which is forced to be AUTH(MASTER).

**AUTOACT (groupname)**

Specifies the "automatic activate group" for the system console. It is only valid when DEVNUM(SYSCONS) is specified. If AUTOACT is specified, *groupname* is the name of a console group, as defined in CNGRPxx.

**Value range:** 1 to 8 alphanumeric or national (#, @, \$) characters.

While the AUTOACT group is defined and not suspended:

- The system console is automatically placed into PD mode when all of the consoles in AUTOACT are inactive.
- The system console is automatically removed from PD mode when any console in the AUTOACT group becomes active.

To suspend AUTOACT processing, issue a VARY CN(\*),ACTIVATE or DEACTIVATE command from the system console. This manual intervention overrides automatic processing until the opposite command is issued.

**CMDSYS**

Indicates the system (in the sysplex) where commands entered on this console are to be sent for processing. An asterisk (\*) indicates that commands that are entered on this console are to be processed on the system where this console is defined.

```
CMDSYS      { (sysname) }
            { (*) }
```

A value of \* is recommended for SMCS consoles because the console is not tied to a system and the use of z/OS Communication Server Generic Resources might place the console on different systems at different times.

**Default:** (\*) An asterisk within parentheses.

**CON**

Indicates whether the console is to function in conversational or nonconversational mode.

```
CON         { (Y) }
            { (N) }
```

**N**

nonconversational mode; all messages that are selected for deletion are automatically deleted.

**Y**

Conversational mode; on this console you must verify all messages that are selected for message deletion with the cursor, or selector pen or through the CONTROL command.

**Restriction:** CON is not valid when UNIT is PRT, or DEVNUM is SYSCONS.

**Default:** N

## DEL

Specifies the message deletion mode of the console.

```
DEL      { (Y) }
          { (R) }
          { (RD) }
          { (W) }
          { (N) }
```

### N

Automatic message deletion is not in effect. Messages must be deleted manually.

### R

Specifies roll mode. In roll mode, the system deletes a specified number of messages from the screen when an interval elapses. Deletion occurs only if the screen is full and messages are waiting to be displayed.

### RD

Specifies roll mode except for messages awaiting actions (WTOs, system failure messages (descriptor code 1), immediate action messages (descriptor code 2), and critical eventual action messages (descriptor code 11)). These messages roll to the top of the screen and remain there until deleted.

### W

Specifies wrap mode. In wrap mode, after the screen is filled with messages, new messages overlay the old messages beginning at the top of the screen. A separator line appears and follows the most recent message on the screen. No messages are retained on the screen once overlaid by the separator line. The areas that were defined by the AREA keyword exist, but are unavailable until the console is put into a non-wrap mode.

### Y

All messages that are selected for deletion are deleted when the screen becomes full.

**Restriction:** DEL is not valid when UNIT is PRT or DEVNUM is SYSCONS.

**Default:** RD

## CONSOLE

CONSOLE indicates the beginning of a statement that defines the characteristics of a console.

```
DEVNUM   { (devnum) }
          { (SUBSYSTEM) }
          { (SYSCONS) }
          { (SMCS) }
          { (HMCS) }
```

### DEVNUM

Specifies the type of console. DEVNUM is required and must be the first keyword on the CONSOLE statement.

#### *devnum*

*devnum* must be the same as the number that was specified for the device on the Add Device panel in HCD.

**Note:** The system pins UCBs for console devices defined in CONSOLxx at IPL time, and the UCBs are only unpinned when a console definition is removed using the console removal definition service, which can be invoked using the IEARELCN sample program that resides in SYS1.SAMPLIB. To get a console device with HCD, an IPL is required, unless the console definition is deleted using the SETCON DELETE, CN= command or using IEARELCN.

**Value range:** 1 to 4 hexadecimal digits, optionally preceded by a slash (/).

### HMCS

For an HMCS console, DEVNUM(HMCS) must be specified. DEVNUM(HMCS) is mutually exclusive with the UNIT and SYSTEM keywords.



## SMCS

For an SMCS console, DEVNUM(SMCS) must be specified. DEVNUM(SMCS) is mutually exclusive with the UNIT and SYSTEM keywords.

## SUBSYSTEM

Indicates that this console is reserved for subsystem use. The only keywords that are valid with the DEVNUM(SUBSYSTEM) setting are AUTH and NAME. A subsystem console can have MASTER authority, but it cannot be assigned at IPL. If this subsystem console has been specified with AUTH(Master) at IPL, the default value of the AUTH parameter is set to AUTH(ALL). Otherwise, the default is set to AUTH(INFO).

## SYSCONS

Indicates that this console is the system console that is attached to this processor. The use of the SYSCONS keyword is optional. The first time that you put the system console into problem determination (PD) mode (by issuing VARY CN(\*),ACTIVATE from the system console), its attributes are taken from the CONSOLE statement with DEVNUM(SYSCONS). If there is no such statement, a default set of attributes is used (see “System Console Defaults” below). The system console's attributes can be changed with the VARY CN command.

The SYSCONS is an extended MCS console. See [z/OS MVS Planning: Operations](#) for more information.

If AMRF(N) on the INIT statement is specified, then the DOM attribute for the SYSCONS extended MCS console is set to DOM(ALL) instead of DOM(NORMAL). If AMRF(Y) on the INIT statement is specified or defaulted, then the DOM attribute for the SYSCONS extended MCS console is set to DOM(NORMAL). For more information about the DOM attribute for extended MCS consoles, see [z/OS MVS Planning: Operations](#).

If your MVS system is running as a guest on the z/VM\* system, and the VM system is at release level 1.1.1 or later, VM simulates the system console hardware regardless of the processor type.

**System console defaults:** The system console receives the normal default values for the keywords that are valid with DEVNUM (SYSCONS), except for the following keywords:

- NAME. The system generates a name for the system console. (For more information, see the description of the NAME keyword.)
- AUTH. The system console is always forced to have MASTER authority.
- MSCOPE. The system console default is MSCOPE(\*).
- LEVEL. The system console default is ALL,NB.

**Note:** The only keywords that are valid with DEVNUM(SYSCONS) are NAME, ROUTCODE, LEVEL, MONITOR, MSCOPE, AUTOACT, CMDSYS, INTIDS, UNKNIDS, and ALLOWCMD. All others are ignored.

For more information about using SMCS, devices or emulators that can be used with SMCS, and HMCS, see [z/OS MVS Planning: Operations](#).

```
LOGON { (REQUIRED) }
      { (OPTIONAL) }
      { (AUTO) }
      { (DEFAULT) }
```

You can use this optional parameter to override the LOGON value that is specified on the DEFAULT statement (if any). The system treats the system console as LOGON(OPTIONAL) no matter what LOGON value is specified on the DEFAULT statement.

IBM suggests that SMCS consoles be LOGON(REQUIRED), either by the system-wide specification on the DEFAULT statement or by the individual CONSOLE statement.

If a TIMEOUT value is specified for the console and an operator has logged on with a user ID, the system automatically logs the user ID off after the number of minutes specified in TIMEOUT has occurred without any console input activity. An example of console input activity is pressing an attention-generating key such as Enter, PFK, PA1, or PA2.

(REQUIRED) specifies that an operator must log on to a console before issuing commands from that console. For MCS consoles, commands can be issued without the operator logging on under the following condition:

- When issuing commands from a console with master authority before a security product is active.

If an operator is not logged on to the console, the system rejects commands that are issued from that console.

(OPTIONAL) specifies that the operators can optionally log on to the console.

**Note:** If an operator has not logged on to the console, commands are passed to the security product indicating an operator ID of \*BYPASS\* .

(AUTO) specifies this console is automatically logged on when the console is activated. The user ID is the console name. If a TIMEOUT value is specified for this console, it is ignored when the user ID matches the console name.

(DEFAULT) specifies that this console uses the LOGON specification on the DEFAULT statement.

**Default:** DEFAULT, unless the console is an SMCS console that does not specify the LU keyword, in which case the default is REQUIRED.

**INTIDS**

This optional keyword indicates whether the specified console receives messages that are directed to console ID zero.

(N)

The specified console is not to receive these messages.

(Y)

The specified console is to receive these messages.

**Default:** N

**LEVEL**

LEVEL specifies the message levels for the console.

|       |                                     |   |
|-------|-------------------------------------|---|
| LEVEL | { (ALL)                             | } |
|       | { ([ALL] [, NB])                    | } |
|       | { ([R] [, I] [, CE] [, E] [, IN]) } | } |

**ALL**

Indicates that the console is to receive all messages.

**CE**

This console is to receive critical eventual action messages.

**E**

This console is to receive eventual action messages.

**I**

This console is to receive immediate action messages.

**IN**

This console is to receive informational messages.

**NB**

This console is to receive no broadcast messages.

**R**

This console is to receive the messages that require an operator reply.

To receive all message levels but broadcast messages, specify the following; you can separate multiple values with a space or a comma.

|       |                   |
|-------|-------------------|
| LEVEL | (R, I, CE, E, IN) |
|-------|-------------------|

**Default:** (except for the system console, which defaults to LEVEL(ALL,NB)).

**LU (nnnnnnnn)**

This keyword defines the logical unit that can only use this console. The LU keyword is optional, but is only be specified with DEVNUM(SMCS). If LU is specified, the console can only be activated at that LU, and no other console can be activated with that LU. For more information, see [z/OS MVS Planning: Operations](#).

**Value range:** *nnnnnnnn* is a character value from 1 to 8 characters. The first character of *nnnnnnnn* must begin with the letters A through Z or with a #,@,\$; the remaining characters can be A through Z, 0 through 9, or #,@, or \$.

**MFORM**

MFORM specifies the display format of the messages.

```
MFORM      { (M)
             { ([J] [,S] [,T] [,X]) }
```

M indicates that the system is to display the message text only. The message display does not include timestamp, job ID, or job name information, or the system name. M is the default.

J specifies that the display is to include the job ID or name.

S specifies that the display is to include the name of the system originating the message.

T specifies that the display is to include a timestamp.

X specifies that the system suppress the job name and system name for JES3 messages that are issued from the global processor.

**Notes:**

1. The MFORM keyword is ignored if specified with DEVNUM(SYSCONS).
2. You can separate multiple values with a blank or a comma.

**Default:** M**MONITOR({JOBNAMES[-T]}X,SESS[-T]}X,STATUS)}**

MONITOR is an optional keyword that allows you to have the system report on selected events. You can specify one or more parameter options for MONITOR; you can separate multiple values with a blank or a comma:

```
MONITOR(JOBNAMES-T, SESS-T, STATUS)
```

**JOBNAMES**

specifies that the system is to display the names of jobs when they start and end. The system also displays input/output device allocation at the start of a job step and includes the job name in a diagnostic message if the job ends abnormally.

**SESS**

Specifies that the system is to display the user ID for each TSO/E session when the session starts and ends. The system also includes the user ID in a diagnostic message if a session ends abnormally.

**-T**

Specifies that the system is to display the time with the job name or the user ID. Code -T with the JOBNAMES or the SESS parameter. The time is displayed in hh:mm:ss format. When specified, -T is activated for all consoles that have MONITOR turned on.

**STATUS**

Specifies that the system is to display the names and volume serial numbers of data sets having dispositions of KEEP, CATLG, or UNCATLG whenever these data sets are freed.

**Default:** If you do not specify the MONITOR keyword (and a valid parameter or combination of parameters), the system does not monitor any job names, TSO/E users, or data sets.

**MSCOPE**

Allows you to specify those systems in the sysplex from which this console is to receive messages that are not explicitly routed to this console. An asterisk (\*) indicates the system on which this CONSOLE statement is defined. You can separate multiple values with a blank or a comma.

```
MSCOPE      { (sysname | *[, sysname] . . . ) }
            { (*ALL) }
```

\*ALL indicates that unsolicited messages from all systems in the sysplex are to be received by this console.

**Default:** \*ALL is the default for all consoles except the system console, which defaults to \*.

**NAME(*conname*)**

Specifies the console name that uniquely identifies the console. The console name is required on all consoles except for the system console. Any values you specify for the NAME parameter (names identifying the console) must be unique across the sysplex.



**Attention:** If you do not specify NAME for a console, the console definition is rejected with an error message. The only exception to this rule is the system console.

**Value range:** *conname* is from 2 to 8 characters. The first character of *conname* must begin with the letters A through Z or with a #, \$, or @; the remaining characters can be A through Z, 0 through 9, or #, \$, or @.

To make the same console available to different systems in a sysplex, you must specify the same value for the NAME parameter on the CONSOLE statement in each system's CONSOLxx parmlib member.

Do not specify a console name that could be confused with a device number. For example, do not use a console name like BEAD, since it can be confused with device number x'BEAD'.

Do not use HC, INSTREAM, INTERNAL, SYSIOSRS, UNKNOWN, OPERLOG, SYSLOG, LOGON, or LOGOFF for *conname*; these names are reserved for the system.

**Naming the system console:** IBM strongly suggests that you specify a name for the system console in CONSOLxx. Select a unique name for the system console that cannot be confused with a valid device number.

**Default:** If your operator specifies CON=NONE, or if you do not name the system console in CONSOLxx, MVS tries to use the name of the system to which the console is attached as the name of the system console, as long as that name is unique and cannot be confused with a device number that the system can use. If you do not name the system console in CONSOLxx, use a system name that cannot be confused with a device number that the system can use.

If you specify a system name that the system can interpret as a valid device number, the system does not use SYSNAME as the name of the system console. If the system cannot use SYSNAME for the system console name, or if the system console name is not unique, the name of the system console is SYSCNxxx, where xxx is a three-character suffix generated by the system.

If you try to define a console whose name is the same as an existing console, the system rejects the definition.

**PFKTAB (*tablename*)**

PFKTAB specifies the name of the table that defines the Program Function Key (PFK) definitions.

***tablename***

The 1-8 alphanumeric name for the table. It must be the same as one defined in a PFKTABxx parmlib member. The PFKTABxx member must be active, that is, identified in the PFK parameter on the INIT statement in CONSOLxx.

For more information about PFK tables, see [Chapter 80, “PFKTABxx \(program function key table definition\),” on page 681.](#)

**Note:** PFKTAB is not valid when UNIT is PRT or DEVNUM is SYSCONS.

**Default:** If you do not specify a valid PFK table, the system uses the IBM-supplied default PFK definitions that are described in *z/OS MVS System Commands*.

### RBUF(nn)

Specifies the number of previously entered commands that can be retrieved on this console by pressing the PA1 key. Set RBUF to a value greater than 1 to allow the operator to retrieve multiple commands, without having to retype each command. For example, to allow the operator to retrieve the last five commands that are entered on this console, specify RBUF(5).

Commands are retrieved as they were entered on the console. That is, commands entered with delimiters (or “stacked commands”) are treated as a single command. For example, when RBUF(2) is specified, and the previously entered commands were:

```
'D T' followed by 'D C;D R;K E,D'
```

- Pressing the PA1 key once retrieves: 'D C;D R;K E,D'
- Pressing the PA1 key a second time retrieves: 'D T'

Commands that are entered through PF keys cannot be retrieved, unless the keys are in conversational mode (CON=Y).

Any commands entered through PF keys are retrieved only in case of RBUF(1), even if the keys are in non-conversational mode (CON=N).

**Value range:** *nn* is a decimal value from 1 to 15. If you specify a value that is not between 1 to 15, an error message is issued and the console defaults to RBUF(15).

**Default:** 15 (The last 15 commands entered can be retrieved).

### RNUM(nn)

RNUM specifies the maximum number of lines included in one message roll.

**Value range:** *nn* is a decimal value. The minimum is 1; the maximum is 99 or the number of lines in the message area, whichever is smaller.

**Note:** RNUM is not valid when UNIT is PRT or DEVNUM is SYSCONS.

**Default:** The default value for all unit types is 5 lines or the number of lines in the message area, whichever is smaller.

### ROUTCODE

Specifies the routing codes that are assigned to the console.

```
ROUTCODE { (ALL) }
          { (NONE) }
          { (nnn[, nnn-nnn] [, nnn] . . .) }
```

**Value range:** ALL specifies all routing codes, 1 through 128. *nnn* specifies a decimal value from 1 through 128. *nnn-nnn* specifies a range of decimal value with the lower value first. You can separate multiple values with a space or a comma.

Do not assign routing code 11 to a console, because it is meant for programmer information rather than operator information.

**Default:** NONE is the default for all consoles.

### RTME (seconds)

Specifies the number of seconds between message rolls or wraps.

**Value range:** *nnn* is an integer value from 1 to 999 or the fractions 1/2 or 1/4 (for example, RTME(1/2)).

1. RTME is not valid when UNIT is PRT or DEVNUM is SYSCONS.
2. Do not use the values 1/2 or 1/4 for a 3290 device.

**Default:** The default value for all unit types is 2 seconds.

**SEG(nn)**

SEG specifies the number of lines in the message area that can be deleted when the CONTROL E, SEG command is entered.

**Value range:** *nn* is a decimal value. The minimum is 1; the maximum is 99 or the number of lines in the message area, whichever is smaller.

**Restriction:** SEG is not valid when UNIT is PRT, or DEVNUM is SYSCONS.

**Default:** Default values for SEG are shown in [Table 20 on page 227](#).

**SUPSBY**

SUPSBY indicates whether the console supports standby mode or not. It is valid only with DEVNUM(*devnum*) *USE(FC)*.

**(N)**

The console does not support standby mode. For HMCS console definition, SUPSBY does not need to be specified as 'Y' is the default and cannot be changed. If 'Y' is specified, message IEA195I will be issued as the keyword will be ignored.

**(Y)**

The console supports standby mode.

**Note:** DEVNUM(HMCS) consoles are SUPSBY(Y) and cannot be changed.

**Default:** N

**SYSTEM (sysname)**

Specifies the system you expect the console to be attached to and activated on.

The SYSTEM keyword is mutually exclusive with DEVNUM(SMCS) and DEVNUM(HMCS).

**Default:** None.

**Note:** It is possible that a device is not ready (not turned on) when the system (or sysplex) is being initialized. The device might even be attached to another system as the sysplex is initialized (for example, during an error recovery situation). When you decide to use the device, first turn it on or reattach it to the proper system, then issue a VARY CN,ONLINE command for the console.

This parameter is primarily used for consoles which are physically attached to multiple systems and managed by a physical switch. In this case, the SYSTEM parameter determines which system should attempt to activate the console. You cannot define multiple CONSOLE statements with the same DEVNUM and specify a different SYSTEM on each statement. Only the first statement is processed, and an error message is issued if additional statements exist.

**TIMEOUT(nn)**

TIMEOUT specifies the length of time before users are automatically logged off from a console due to inactivity.

**Value range:** *nn* can be any value between 1 (meaning the user is automatically logged off after 1+ minutes of inactivity) to 99 (meaning the user is logged off after 99+ minutes of inactivity), or 0 (meaning the user is never automatically logged off due to inactivity). Actual logging off occurs between  $nn \leq \text{inactivity} < nn+1$  minutes.

**Default:** The default value is 0, which indicates that users are not automatically logged off after any period of inactivity.

**UNIT**

UNIT specifies the unit type of the console. The unit type must be a valid console device that is listed here. See [Table 19 on page 226](#) for the devices that can be used as MCS consoles.

|      |               |
|------|---------------|
| UNIT | { (3270-X) }  |
|      | { (3277-2) }  |
|      | { (3278-2) }  |
|      | { (3278-2A) } |
|      | { (3278-3) }  |
|      | { (3278-4) }  |
|      | { (3279-2A) } |

```
{(3279-2B)}
{(3279-2C)}
{(3279-3A)}
{(3279-3B)}
{(PRT) }
```

**PRT**

Specifies that the console is a printer. The Add Device panel in HCD must specify a valid device type that can be defined as a printer.

**Default:** If you do not code the UNIT keyword, the system uses the information entered through HCD for the device number to determine the unit type. If the HCD information indicates that it is a display device, the system defaults the UNIT value to 3270-X.

**Note:**

1. Specify 3270-X for devices that meet the following criteria:
  - The device supports the 3270 data stream and Read Partition Query (such as a 3471 or 3472 IBM InfoWindow terminal).
  - The device is attached to a control unit that supports Read Partition Query (should Read Partition Query fail, MCS attempts to bring the device online with 3277-2 display attributes).
2. This keyword is mutually exclusive with DEVNUM(SMCS) and DEVNUM(HMCS). SMCS and HMCS always determines the type of device that is being used.

**UNKNIDS**

This optional keyword indicates whether the specified console receives messages that are directed to "unknown" console IDs. Messages that are issued to a now unresolvable 1-byte console ID are delivered to consoles receiving UNKNIDS.

**(N)**

The specified console is not to receive these messages. This is the default value.

**(Y)**

The specified console is to receive these messages.

**USE {(FC) | (MS) | (SD)}**

USE specifies how the display console is used.

**(FC)**

Defines a full-capability console able to enter commands and receive status displays and messages. If the console is a display device, specify USE(FC).

**(MS)**

Defines a message stream console. If the console is a printer, specify USE(MS).

**(SD)**

Defines a status display console.

**Notes:**

1. The USE keyword is ignored if specified with DEVNUM(SYSCONS).
2. SMCS and HMCS do not support USE(MS) or USE(SD) consoles. Only USE(FC) is accepted for an SCMS or HMCS console.

**Default:** If you do not specify USE, FC is the default if the console is a display device and MS is the default if the console is a printer.

## Syntax and parameters for the DEFAULT statement

```

DEFAULT      ROUTCODE  { (ALL) }
                  { (NONE) }
                  { (nnn[,nnn-nnn] [,nnn] . . . ) }

              LOGON     { (REQUIRED) }
                  { (OPTIONAL) }
                  { (AUTO) }

              HOLDMODE  { (YES) }
                  { (NO) }

              RMAX       { (nnnn) }
                  { (99) }

              SYNCHDEST (groupname)

```

### DEFAULT

Defines the system defaults used by the Communications Task.

```

ROUTCODE      { (ALL) }
               { (NONE) }
               { (nnn[,nnn-nnn] [,nnn] . . . ) }

```

### LOGON

Use LOGON to define whether operators must issue LOGON and LOGOFF commands on MCS, SMCS, and HMCS consoles. This definition only applies to consoles that do not specify LOGON on the CONSOLE statement, or specify LOGON(DEFAULT) on the CONSOLE statement. (For information about securing access to system commands, see *z/OS MVS Planning: Operations*.) The system console is always treated as LOGON(OPTIONAL), no matter which value is specified on the DEFAULT statement.

```

LOGON         { (REQUIRED) }
               { (OPTIONAL) }
               { (AUTO) }

```

### REQUIRED

Specifies that an operator must log on to an MCS, SMCS, or HMCS console before issuing commands from that console except when issuing commands from the master authority console before a security product is active.

### OPTIONAL

Specifies that the operators can optionally log on to the MCS, SMCS, or HMCS consoles.

**Note:** If an operator has not logged on to the console, commands are passed to the security product indicating an operator ID of \*BYPASS\*.

### AUTO

Specifies that consoles are automatically logged on when the consoles are activated. The user ID is the console name. If a TIMEOUT value is specified for a console, it is ignored when the user ID matches the console name.

IBM suggests that SMCS consoles be LOGON(REQUIRED), either by the system-wide DEFAULT or by the individual CONSOLE statement.

If a TIMEOUT value is specified for the console and an operator has logged on with a user ID, the system automatically logs the user ID off after the number of minutes specified in TIMEOUT has occurred without any console input activity. An example of console input activity is pressing an attention-generating key such as Enter, PFK, PA1, or PA2.

If an operator is not logged on to the console, the system rejects commands that are issued from that console.

**Default:** OPTIONAL

### ROUTCODE

Specifies one or more default routing codes for messages that do not have any routing information.



**nnn**

A decimal number from 1 to 128. You can specify a range of routing codes by coding an ascending range of numbers. Separate multiple values with a blank or a comma.

**ALL**

Specifies that 1 through 128 are to be assigned.

**NONE**

Specifies that routing codes are not assigned.

**Default:** If you do not code ROUTCODE, the default is routing codes 1 through 16.

|                 |                  |
|-----------------|------------------|
| <b>HOLDMODE</b> | <b>{ (YES) }</b> |
|                 | <b>{ (NO) }</b>  |

Specifies whether you want hold mode for the console when the console is roll, roll-deletable, hold mode, or wrap mode. Specifying HOLDMODE(YES) allows an operator to press the ENTER key to suspend or hold messages on the console screen. An operator can enter and exit hold mode by pressing the ENTER key with no input.

**Default:** NO

|             |                   |
|-------------|-------------------|
| <b>RMAX</b> | <b>{ (nnnn) }</b> |
|             | <b>{ (99) }</b>   |

Specifies the maximum value of a reply ID in the sysplex. RMAX also determines the size of the reply ID displayed in the message text. For example, specifying an RMAX value of 9999 results in all messages having a four-character reply ID.

**Value range:** 99 - 9999

**Note:** The value that you specify for RMAX can affect the size of the XCF couple data set. For more information, see [z/OS MVS Setting Up a Sysplex](#).

MVS issues message IEA403I when forcing the RMAX value to 99.

**Default:** 99

**SYNCHDEST(groupname)**

Indicates that synchronous messages (those messages issued using WTO and WTOR macros with SYNCH=YES) should be sent to the first available MCS or HMCS console in the group specified. The console must be attached to this member of the sysplex and must be active when the message is issued. Synchronous messages cannot be sent to another member of the sysplex.

**Note:** When a synchronous message is issued, it is extremely important to respond promptly. The synchronous message is issued as a synchronous WTOR, which prevents the system from updating its status on the sysplex couple data set. This, in turn, could lead to Sysplex Failure Management (SFM) deciding that the system is not responding normally, and removing it from the sysplex.

Consoles in this console group must be MCS consoles, the system console, or HMCS consoles. SMCS consoles cannot display synchronous messages. The SYNCHDEST console group can include other types of consoles, such as SMCS consoles or extended MCS consoles, but the system skips these types of consoles when processing synchronous messages. See [Chapter 17, “CNGRPxx \(specify console groups\),” on page 177](#) for information about specifying console groups.

**Note:** 1 - 8 alphanumeric or special (#,@,\$) characters. The reserved console name has special meanings when used as part of this console group:

| Console name | Meaning   |
|--------------|---|
| *SYSCON*     | When used in a group that is specified on the SYNCHDEST keyword, this routes a synchronous message to the system console. |

**Default:** The SYNCHDEST keyword is optional. If you do not specify a SYNCHDEST value, the system routes synchronous messages to the system console.

## Syntax and parameters for the HARDCOPY statement

```

HARDCOPY  DEVNUM  { (SYSLOG)           }
              { (OPERLOG)           }
              { (SYSLOG,OPERLOG) }

              ROUTCODE { (ALL)           }
                      { (NONE)          }
                      { (nn[,nnn-nnn][,nnn]...) }

              CMDLEVEL { (NOCMDS) }
                      { (INCMDS) }
                      { (STCMDS) }
                      { (CMDS)  }

              HCFORMAT { (CENTURY) }
                      { (YEAR  ) }

```

### HARDCOPY

HARDCOPY identifies the hardcopy medium, defines the hardcopy message set, defines routing codes for included messages, specifies the kind of messages that are included in the hardcopy data set, or specifies whether hardcopy records should have a 4-digit year, depending on the options specified.

```

DEVNUM      { (SYSLOG)           }
            { (OPERLOG)           }
            { (SYSLOG,OPERLOG) }

```

DEVNUM specifies the output device.

SYSLOG indicates that the system log is to be the hardcopy medium.

OPERLOG indicates that the operations log is activated and receives the hardcopy message set. You can specify OPERLOG alone or with SYSLOG. When you specify OPERLOG with SYSLOG, both OPERLOG and SYSLOG receives the hardcopy message set.

You can specify both subparameters in either order; (OPERLOG,SYSLOG) is equivalent to (SYSLOG,OPERLOG).

**Default:** The system defaults to SYSLOG as the hardcopy medium in any of the following cases:

- You do not code a HARDCOPY statement.
- You specify OPERLOG alone but the operations log is unusable.

```

ROUTCODE    { (ALL)           }
            { (NONE)          }
            { (nnn[,nnn-nnn][nnn]...) }

```

ROUTCODE specifies the routing codes the system is to use to select messages for the hardcopy message set. At system initialization, processing of the HARDCOPY statement sets up a minimum set of routing codes (1,2,3,4,7,8,10, and 42), in addition to any others specified for the hardcopy message set.

ALL indicates that all routing codes (1-128) are used to select messages for the hardcopy message set.

NONE indicates that no routing codes are used to select messages for the hardcopy message set. It contains the minimum set established at initialization.

*nnn* is a decimal number 1 - 128. You can specify a range of routing codes by coding an ascending range of numbers. You can separate multiple values with a blank or a comma.

**Default:** ALL

```

CMDLEVEL    { (NOCMDS) }
            { (INCMDS) }
            { (STCMDS) }
            { (CMDS)  }

```

CMDLEVEL specifies the types of commands and command responses that are to be included in the hardcopy message set.

NOCMDS specifies that the system is not to include operator or system commands or their responses in the hardcopy message set unless they meet other criteria, such as routing codes. The system ignores this option and assumes CMDS, unless all of the following conditions are met:

- The system is a member in a sysplex.
- Only one console is active on the system and the console is a non-display console, such as a printer.

INCMDS specifies that the system is to include operator and system commands and their responses, excluding any status displays, in the hardcopy message set.

STCMDS or CMDS specifies that the system is to include operator and system commands, their responses, and static status displays in the hardcopy message set. STCMDS and CMDS are equivalent.

**Default:** CMDS

### **HCFORMAT{(CENTURY|YEAR)}**

Specifies the format of the Julian date as it is to appear in the SYSLOG and Master Trace hardcopy records, where:

#### **CENTURY**

Indicates that the Julian date is to use the format *yyyyddd*, showing a 4-digit year and 3-digit day.

**Note:** If you are using CENTURY, examine programs that use SYSLOG to ensure that they can handle the new 4-digit year format.

#### **YEAR**

Indicates that the Julian date is to use the format *yyddd*, showing a 2-digit year and 3-digit day.

**Default:** YEAR

## Syntax and parameters for an INIT statement

```

INIT      MLIM  { (nnnn) }
           { (1500) }

           LOGLIM { (nnnnnn) }
                 { (1000 ) }

           RLIM  (nnnn)

           AMRF  { (Y) }
                 { (N) }

           UEXIT { (Y) }
                 { (N) }

           MPF   { (NO
                 { (xx[,xx,...]) } }

           MMS   { (NO) }
                 { (xx) }

           PFK   { (NONE) }
                 { (xx) }

           CNGRP { (xx[,xx,...]) }
                 { (NO ) }

           MONITOR([SPACE][,DSNAME])

           CMDELIM { (c) }
                  { (X'hh' ) }

           CTRACE { (CTnOPSxx) }
                  { (CTIOPS00) }

           ROUTTIME { (nnn) }
                   { (30 ) }

           APPLID  (nnnnnnnnn)

           GENERIC (nnnnnnnnn)

           MSGFLD  (xx[, (wɪd)])

```

### INIT

Specifies that the communications task initialization values follow.

#### LOGLIM (nnnnnn)

LOGLIM specifies the maximum number of buffers that the system can use for SYSLOG. Each buffer is 156 bytes, and is obtained from the extended common service area (ECSA).

**Value range:** *nnnnnn* is a decimal value from 1000 - 999999.

**Default:** 1000 (meaning 1000 buffers).

#### Notes:

1. Ensure that there is storage in extended CSA available for the LOGLIM value specified. Otherwise, an error results.
2. JES3 systems that use DLOG require a higher default for the LOGLIM parameter to prevent SYSLOG buffer shortages. IBM suggests setting the LOGLIM value based on the JES3 configuration at your installation at least equal to:

```
LOGLIM = (4000 + (2000 x the-number-of-JES3-locals))
```

#### MLIM (nnnn)

MLIM specifies the maximum number of buffers that the system can use to process write-to-operator (WTO) messages. Each buffer is 384 bytes, and is obtained from private storage (subpool 229) in the CONSOLE address space.

**Value range:** *nnnn* is a decimal value from 20 - 9999.

**Default:** 1500 (meaning 1500 buffers).

**RLIM (nnnn)**

RLIM specifies the maximum number of buffers that the system can use to process write-to-operator-with-reply (WTOR) messages. Each buffer is 104 bytes, and is obtained from the extended common service area (ECSA).

**Value range:** *nnn* is a decimal value from 5 to 9999. It is suggested that you specify a value higher than 99.

**Default:** The default is 10 (meaning 10 buffers), unless you have set the PLEXCFG= parameter of the IEASYSxx parmlib member to a value other than XCFLOCAL or MONOPLEX. Here, the default is equal to the value of the RMAX parameter on the DEFAULT statement of the CONSOLxx parmlib member of the first system that joined the sysplex.

For more information, see [the PLEXCFG parameter](#).

**AMRF (Y) | (N)**

AMRF specifies whether the action message retention facility is to be active.

**Notes:**

1. If AMRF(N) is specified, then the DOM attribute for the SYSCONS extended MCS console is set to DOM(ALL).
2. If AMRF(Y) is specified or defaulted, then the DOM attribute for the SYSCONS extended MCS console is set to DOM(NORMAL).
3. If AMRF is not active, then non-SYSCONS extended EMCS consoles will not receive DOMs.

For more information about the DOM attribute for extended MCS consoles, see [z/OS MVS Planning: Operations](#).

**Value Range:** Y indicates that AMRF is to be active, and N indicates that it is not to be active.

**Default:** Y (AMRF is active).

**UEXIT {(Y)} | {(N)}**

UEXIT specifies whether the WTO/WTOR installation exit IEAVMXIT is to be active. A default IEAVMXIT is no longer shipped in SYS1.LINKLIB.

**Value range:** Y indicates that IEAVMXIT is to be active and N indicates that it is not to be active.

**Default:** Y (IEAVMXIT is activated if it exists).

**MPF {(NO)} | {(xx[,xx,...])}**

MPF indicates whether the message processing facility is to be active.

**Value range:** *xx* must be two alphanumeric characters indicating the MPFLSTxx member to use. You can specify one or more MPFLSTxx parmlib members. Multiple members are concatenated.

**Default:** NO (the message processing facility is not active)

**MMS {(NO)} | (xx)}**

MMS indicates whether the MVS message service is to be active.

**Value range:** *xx* must be two alphanumeric characters indicating the MMSLSTxx parmlib member to use.

**Default:** NO (the MVS message service is not active)

**PFK {(NONE)} | {(xx)}**

PFK specifies the PFKTABxx member in parmlib that contains any PFK tables for your consoles.

xx must be two alphanumeric characters, matching the suffix of the PFKTABxx member to be used.

NONE indicates that no PFK tables are defined; the system is to use the IBM-supplied default PFK definitions that are described in *z/OS MVS System Commands*.

**Default:** NONE

**CNGRP {(xx[,xx,...])} | {(NO)}**

CNGRP indicates whether the system or sysplex is to activate console group definitions.

**Value range:** xx must be two alphanumeric characters indicating the CNGRPxx parmlib member to use. You can specify a maximum of 38 two-character suffixes.

**Default:** NO is the default; no active console group definitions are to be activated from the system or sysplex.

**MONITOR ([SPACE],[DSNAME])**

MONITOR specifies whether the system is to add status information to mount messages displayed on consoles.

SPACE indicates that, in mount messages, the system is to display the available space on the direct access volume.

DSNAME indicates that, in mount messages, the system is to display the name of the first non-temporary data set allocated on the volume to which a message refers.

**Default:** There is no default value for this keyword. That is, if you do not specify a value for MONITOR on the INIT statement, neither the data set name nor the available space is displayed in MOUNT messages.

**Note:** If a data set has a disposition of delete, its name does not appear in the mount messages.

**CMDDDELIM {(c)} | {(X'hh')}**

CMDDDELIM specifies an MCS, SMCS, and HMCS command delimiter that the installation chooses. CMDDDELIM allows the operator to enter multiple commands on the console at one time. Each command that is separated by the delimiter is processed separately. Do not use the command delimiter within a quoted string. If you do, the system considers the delimiter as part of the text and it will not process the delimiter. The order in which the system processes the commands may be different from the order in which the operator entered them. PF keys continue to use a semicolon (;) as the delimiter.

The command delimiter is only honored when it is entered from an MCS, SMCS, or HMCS console. It is not honored when entered from a Subsystem (SS) console. If a command is entered from an extended MCS console, such as a TSO CONSOLE, SDSF LOG, or ULOG functions, the recognition of the command delimiter depends on the interface reading the command.

Choose the command delimiter carefully because the delimiter character affects MVS command processing. For example:

- Do not use % or ? as a command delimiter if the SLIP command is to be used with indirect addressing.
- Do not use ; as a command delimiter if the online test executive program (OLTEP) is to be used.
- Do not use & as a command delimiter if the installation uses system symbols.
- Use of &' as a command delimiter causes the DUMPDS NAME function to fail if the command is issued from an MCS, SMCS, or HMCS console.

- Use of : as a command delimiter causes the SETIOS TIME function to fail if the command is issued from an MCS, SMCS, or HMCS console.

The command delimiter can be specified in EBCDIC (c) or in hexadecimal (X'hh') format. Valid values are:

| EBCDIC | Hexadecimal |
|--------|-------------|
| <      | 4C          |
| >      | 6E          |
| &      | 50          |
| ;      | 5E          |
| %      | 6C          |
| ?      | 6F          |
| :      | 7A          |
| "      | 7F          |

CTIOPS00

**Default:** There is no default value for this keyword. If you do not specify a value for CMDDELIM, your operators cannot enter more than one command at a time.

### CTTRACE (member-name)

Specifies the member of Parmlib that contains the tracing options for the operations services (OPS) component.

**Value range:** The 8-character member name must be in the format CTnOPSxx.

**n**

An alphanumeric character that specifies the source of the member. IBM-supplied members use I.

**xx**

Any two characters to identify the member.

**Default:** CTIOPS00

For more information about specifying options for the operations services component trace, see [z/OS MVS Diagnosis: Tools and Service Aids](#). For information about specifying the component trace member of parmli see [Chapter 26, "CTnccccxx \(component trace parameters\)," on page 249](#).

### ROUTTIME (nnn)

In a sysplex, ROUTTIME specifies the maximum number of seconds the ROUTE \*ALL, ROUTE \*OTHER, or ROUTE *systemgroupname* command waits for responses from each system to the command being routed before aggregating responses. The value specified for ROUTTIME in the INIT statement of the first system in the sysplex applies to all systems that join the sysplex, unless you change the value with a CONTROL M command.

**Value range:** nnn is a decimal value between 0 and 999. If the value is zero, MVS does not aggregate command responses, but sends separate responses for each command back to the originator of the ROUTE command.

**Default:** 30

### APPLID (nnnnnnnn)

Specifies the z/OS Communications Server APPLID that SMCS is to use on this system. Each system must have a unique APPLID. If an APPLID is not specified, SMCS will not be available for the life of the system.

**Value range:** *nnnnnnnn* is a character value from 1 to 8 characters. The first character of *nnnnnnnn* must begin with the letters A through Z or with a #,@,\$; the remaining characters can be A through Z, 0 through 9, or #,@, or \$.

#### **GENERIC (nnnnnnnn)**

Specifies the z/OS Communications Server Generic Resource name that SMCS is to use in this sysplex. The first system that IPLs into the sysplex that specifies GENERIC sets the GENERIC for the life of the sysplex unless modified by the CONTROL M command.

This keyword is optional, but if it is specified, APPLID must also be specified.

**Value range:** *nnnnnnnn* is a character value from 1 to 8 characters. The first character of *nnnnnnnn* must begin with the letters A through Z or with a #,@,\$; the remaining characters can be A through Z, 0 through 9, or #,@, or \$.

**Note:** The following rules must be true for GENERIC to work:

- z/OS Communications Server must be an APPN node.
- The system must be in a sysplex. It is not valid for a monoplex or a single system.
- A Coupling Facility must be available.
- The z/OS Communications Server ISTGENERIC structure must be defined in the Coupling Facility policy.
- z/OS Communications Server must be able to communicate with the Coupling Facility.

#### **MSGFLD (xx[, (wrd)])**

Specifies the MSGFLDxx parmlib member to be used and whether Message Flood Automation is to be automatically enabled when the parmlib member is loaded during system initialization.

##### **xx**

Either the word NONE or a two-character MSGFLDxx parmlib member suffix composed of the alphanumeric characters 0-9 and A-Z and the national characters @, # and \$. Specifying the word NONE indicates that no MSGFLDxx parmlib member is to be loaded. If NONE is specified, the built-in policy is used if ON is specified for *wrd*.

##### **wrd**

Either the word ON or OFF. If ON is specified, Message Flood Automation policy is automatically enabled. If OFF is specified, Message Flood Automation policy is not automatically enabled. Specification of ON or OFF is optional.

**Default:** OFF

## Devices used as MCS consoles

Table 19 on page 226 summarizes the devices that can be used as MCS consoles

| Table 19. Devices used as MCS consoles |                      |                     |              |             |
|--|----------------------|---------------------|--------------|-------------|
| Device                                 | Input/Output Devices | Output Only Devices | Specified As | Description |
| 1403                                   |                      | X                   |              | Printer     |
| 3203-5                                 |                      | X                   |              | Printer     |
| 3211                                   |                      | X                   |              | Printer     |
| 3284-1                                 |                      | X                   |              | Printer     |
| 3284-2                                 |                      | X                   |              | Printer     |
| 3286-1                                 |                      | X                   |              | Printer     |
| 3286-2                                 |                      | X                   |              | Printer     |
| 3277-2                                 | X                    | X                   |              | Display     |



Table 19. Devices used as MCS consoles (continued)

| Device   | Input/Output Devices | Output Only Devices | Specified As | Description |
|----------|----------------------|---------------------|--------------|-------------|
| 3278-2   | X                    | X                   |              | Display     |
| 3278-2A  | X                    | X                   |              | Display     |
| 3278-3   | X                    | X                   |              | Display     |
| 3278-4   | X                    | X                   |              | Display     |
| 3278-5   | X                    | X                   | 3270-X       | Display     |
| 3279-2A  | X                    | X                   |              | Display     |
| 3279-2B  | X                    | X                   |              | Display     |
| 3279-2C  | X                    | X                   |              | Display     |
| 3279-3A  | X                    | X                   |              | Display     |
| 3279-3B  | X                    | X                   |              | Display     |
| 3279-2X  | X                    | X                   | 3270-X       | Display     |
| 3279-3X  | X                    | X                   | 3270-X       | Display     |
| 3279-S2B | X                    | X                   | 3270-X       | Display     |
| 3279-S3G | X                    | X                   | 3270-X       | Display     |
| 3290     | X                    | X                   | 3270-X       | Display     |

## Maximum and default specifications for AREA and SEG

Table 20 on page 227 lists the maximum and default specifications for AREA and SEG.

Table 20. Maximum and default specifications for AREA and SEG

| Unit     | Full capability AREA size |         | Status display AREA size |         | Screen size | SEG default |
|----------|---------------------------|---------|--------------------------|---------|-------------|-------------|
|          | Max                       | Default | Max                      | Default |             |             |
| 3270-X   | See note “2” on page 228  |         |                          |         |             |             |
| 3277-2   | 19                        | 14      | 23                       | 11,12   | 24x80       | 9           |
| 3278-2   | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |
| 3278-2A  | 16                        | 14      | 20                       | 10,10   | 20x80       | 8           |
| 3278-3   | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3278-4   | 39                        | 14      | 43                       | 21,22   | 43x80       | 19          |
| 3278-5   | 24                        | 14      | 27                       | 13,14   | 27x132      | 12          |
| 3279-2A  | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |
| 3279-2B  | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |
| 3279-2C  | 16                        | 14      | 20                       | 10,10   | 20x80       | 8           |
| 3279-2X  | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |
| 3279-3A  | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3279-3B  | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3279-3X  | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3279-S2B | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |

Table 20. Maximum and default specifications for AREA and SEG (continued)

| Unit     | Full capability AREA size |         | Status display AREA size |         | Screen size | SEG default |
|----------|---------------------------|---------|--------------------------|---------|-------------|-------------|
|          | Max                       | Default | Max                      | Default |             |             |
| 3279-S3G | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3290     | 20                        | 14      | 24                       | 12,12   | 24x80       | 10          |
| 3290     | 24                        | 14      | 27                       | 13,14   | 27x132      | 12          |
| 3290     | 27                        | 14      | 31                       | 15,16   | 31x80       | 13          |
| 3290     | 28                        | 14      | 31                       | 15,16   | 31x160      | 14          |
| 3290     | 28                        | 14      | 32                       | 16,16   | 32x80       | 14          |
| 3290     | 39                        | 14      | 43                       | 21,22   | 43x80       | 19          |
| 3290     | 46                        | 14      | 50                       | 25,25   | 50x106      | 23          |
| 3290     | 58                        | 14      | 62                       | 31,31   | 62x80       | 29          |
| 3290     | 59                        | 14      | 62                       | 31,31   | 62x160      | 28          |
| SMCS     | See note “1” on page 228  |         |                          |         |             |             |
| HMCS     | 39                        | 14      | N/A                      | N/A     | 43x80       | 19          |

**Notes on :**

1. SMCS screen size requires a minimum screen size of 24 rows x 80 columns to display the SMCS Console Selection Screen. SMCS consoles that do not have a predefined LU should be at least 24x80.
2. 3270-X and SMCS values are calculated dynamically as follows:

**Full Capability AREA Size****Max**

#rows - #rows of entry area

**Default**

14 or the Max Area, whichever is smaller.

**Status Display AREA Size****Max**

#rows

**Default**

2 areas, each is #rows/2. (For odd screen sizes, the B area is one row larger so that it takes up the entire screen.)

**Screen Size**

See SMCS Screen Size Note

**SEG Default**

(#rows - (3 or 4))/2, where 3 or 4 depends on the number of lines in the entry area.

**Message Stream**

#rows - 1

## Chapter 24. COUPLExx (cross-system coupling facility (XCF) parameters)

The cross-system coupling facility (XCF) provides the MVS coupling services that allow authorized programs on MVS systems in a multisystem environment to communicate (send and receive data) with programs on the same MVS system or other MVS systems. The cross-system extended services (XES) allow authorized programs on MVS to use a coupling facility to share data with other programs on the same MVS system or other MVS systems. The eventual goal for the coupling services provided by XCF and XES is to allow an installation to view multiple MVS systems as one MVS system.

For more information about using XCF, see *z/OS MVS Setting Up a Sysplex*.

You must specify a COUPLExx parmlib member for each system in the sysplex. Use the COUPLExx member of SYS1.PARMLIB to specify the following installation values for this system in your sysplex:

- The sysplex name
- The names of the sysplex couple data sets
- The names of other types of couple data sets
- The failure detection interval
- The operator notification interval
- The cleanup interval
- The default message buffer space
- The default message size for a signalling path
- The transport classes
- The outbound signalling paths
- The inbound signalling paths
- The default retry limit
- The local message buffer space
- XCF CTRACE parmlib member
- XES CTRACE parmlib member
- CPUID toleration indicator for VM guest systems
- Initial status of optional XCF/XES functions
- Thresholds for converting synchronous coupling facility (CF) requests to run asynchronously

### Parameter in IEASYSxx (or supplied by the operator)

```
COUPLE=xx
```

The two-character identifier (xx) is appended to COUPLE to identify the COUPLExx member of parmlib.

### Syntax rules for COUPLExx

The following syntax rules apply to COUPLExx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- At least one delimiter (space or comma) is required between a statement and keyword. Delimiters are not required between keywords.

- Use at least one delimiter to separate multiple keyword values within parentheses.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/"

## Syntax format of COUPLExx

```
[COUPLE      SYSPLEX(sysplex-name)]
[CFRMPOL(CFRMPOLNAME)]
[CFRMOWNEDCFPROMPT(NO|YES)]
[CFRMTAKEOVERCF(NO|PROMPT)]
[PCOUPLE(primary-dsname[,primary-volume]) ]
[ACOUPLE(alternate-dsname[,alternate-volume]) ]
[INTERVAL(time-interval) ]
[OPNOTIFY(time-interval) ]
[CLEANUP(cleanup-interval) ]
[MAXMSG(default maxmsg) ]
[RETRY(default retry-limit) ]
[CLASSLEN(default class-length) ]
[CTRACE(parmlib-member) ]
[VMCPUIDTOLERATION(NO|YES) ]
[FUNCTIONS {ENABLE(function[,function ...]) }
           {DISABLE(function[,function ...]) } ]
[CLASSDEF
[  CLASS(class-name)
[  CLASSLEN(class-length) ]
[  MAXMSG(max-messages) ]
[  GROUP(group-name[,group-name]...) ]
[PATHIN
[  {DEVICE(device-number[,device-number]...) }
[  {STRNAME(strname[,strname]...) }
[  MAXMSG(max-messages) ]
[  RETRY(retry-limit) ]
[PATHOUT
[  {DEVICE(device-number[,device-number]...) }
[  {STRNAME(strname[,strname]...) }
[  MAXMSG(max-messages) ]
[  RETRY(retry-limit) ]
[  CLASS(class-name) ]
[LOCALMSG
[  MAXMSG(max-messages)
[  CLASS(class-name) ]
[DATA
[  TYPE(name[,name]...)
[  PCOUPLE(primary-dsname[,primary-volume])
[  ACOUPLE(alternate-dsname[,alternate-volume]) ]
[SYNCA
[  SIMPLEX(nnnnn|DEFAULT)
[  DUPLEX(nnnnn|DEFAULT)
[  LOCKDUPLEX(nnnnn|DEFAULT)
[  LOCKSIMPLEX(nnnnn|DEFAULT)
```

## IBM-supplied default for COUPLExx

The default parmlib member, COUPLE00, contains the following information, which brings a system up in XCF-local mode because the member does not include the PCOUPLE statement.

```
COUPLE SYSPLEX(LOCAL)
```

## Statements and parameters for COUPLExx

### COUPLE

Describes the sysplex (systems complex) in which the system participates.

### ACOUPLE(alternate-dsname[,alternate-volume])

Specifies the name of the alternate sysplex couple data set and, optionally, the volume on which that data set resides. XCF maintains information about the sysplex in both the primary and alternate data sets concurrently. XCF automatically switches to the alternate couple data set when the primary couple data set fails. You cannot specify the ACOUPLE parameter without a PCOUPLE parameter.

**Value range:** The *alternate-dsname* must be a valid data set name of up to 44 characters. Valid characters are alphanumeric (A-Z and 0-9) and national (@,#,\$) characters and periods (.).

The *alternate-volume* is the 1 to 6 character name of a mounted and ready DASD volume. Valid characters are alphanumeric and national characters. If the volume is not specified, the data set must be cataloged in the master catalog.

**Default:** None. If you omit the ACOUPLE keyword, XCF is started with only the XCF primary couple data set specified on the PCOUPLE parameter (if it was specified).

### CFRMOWNEDCFPROMPT(NO|YES)

For IPL of a sysplex, allows the installation to request operator prompting to control usage of coupling facilities previously owned by the same sysplex.

When a coupling facility (CF) is first made available to a sysplex, ownership is established by setting the coupling facility authority data with the ownership information (sysplex name, date, and time of day) and saving the ownership information in the CFRM active policy that is maintained in the CFRM couple data set. A zero value for coupling facility authority data indicates that the coupling facility is not owned and not in use by any sysplex. After a sysplex has established ownership of a coupling facility and the coupling facility remains defined in the CFRM active policy, the sysplex will reestablish ownership without operator prompting when a system gains connectivity after a total loss of connectivity to the coupling facility from all systems in the sysplex.

Operator prompting is accomplished by issuing two message sets, both of which require a YES response to allow the sysplex to use the coupling facility. The message sets are as follows:

1. IXC500I to describe the coupling facility and IXC501A to reply to use the coupling facility.
2. IXC559I to further warn about sysplex usage and IXC560A to confirm usage by the sysplex.

The rules for operator prompting are as follows:

1. CF is not owned (zero value for authority data). The CF cannot be in use by any sysplex so CFRM proceeds to gain ownership of the CF without operator prompting.
2. CF is owned (nonzero value for authority data) and the value matches the ownership information in the CFRM active policy (current sysplex name and stored date and time of day). It is assumed that the CF was last used by the same sysplex so CFRM proceeds to gain ownership of the CF without operator prompting.

**Note:** Specifying or defaulting to NO for CFRMOWNEDCFPROMPT causes the ownership information in the CFRM active policy to remain unchanged when the CFRM couple data set is first used by the sysplex. The saved ownership information can match the nonzero coupling facility authority data.

3. CF is owned (nonzero value for authority data) and the value does not match the ownership information in the CFRM active policy (current sysplex name and stored date and time of day). CFRM may prompt the operator (see CFRMTAKEOVERCF) and will only gain ownership if the operator responds YES to allow sysplex usage of the coupling facility.

Specifying YES for CFRMOWNEDCFPROMPT causes the ownership information in the CFRM active policy to be updated (by clearing the sysplex name portion of the ownership information) when the CFRM couple data set is first used by the sysplex. The updated ownership information will not match the nonzero coupling facility authority data.

**Value range:** One of the following options:

#### NO

Specifies that coupling facilities previously owned by the same sysplex can be used by the sysplex without prompting the operator. The CFRM active policy coupling facility ownership information that is saved when CFRM last gained ownership of coupling facilities for a sysplex is not updated when the CFRM couple data set is first used by the sysplex. See rule “2” on [page 231](#).

#### YES

Specifies that coupling facilities previously owned by the same sysplex cannot be used by the sysplex without prompting the operator. The CFRM active policy coupling facility ownership information that is saved when CFRM last gained ownership of coupling facilities for a sysplex

is updated when the CFRM couple data set is first used by the sysplex. See rule “3” on page 231.

**Default:** NO

APAR OA10197 provides the support for CFMOWNEDCFPROMPT. The APAR is available for systems at z/OS Version 1 Release 4 and higher.

### **CFRMTAKEOVERCF(NO|PROMPT)**

Allows the installation to request operator prompting to control usage of coupling facilities that are owned by a different sysplex. In this context, it is assumed that any prior CF authority has been saved in the CFRM couple data set. Thus, when comparing the saved authority to a nonzero CF authority, a mismatch indicates that a different sysplex must have set the CF authority.

See the CFMOWNEDCFPROMPT keyword for a discussion of how coupling facility authority values are stored, compared, and updated.

**Value range:** One of the following options:

#### **NO**

Specifies that coupling facilities owned by a different sysplex cannot be used by the sysplex. When a coupling facility owned by a different sysplex is encountered, CFRM rejects use of the coupling facility.

#### **PROMPT**

Specifies that the operator can decide whether coupling facilities owned by a different sysplex can be used by the sysplex. When a coupling facility owned by a different sysplex is encountered, CFRM prompts the operator and only gains ownership if the operator responds YES to allow sysplex usage of the coupling facility.

**Default:** NO

Support for CFRMTAKEOVERCF was added in z/OS V2R2. Releases earlier than z/OS V2R2 will behave as if CFRMTAKEOVERCF(PROMPT) had been specified.

### **CFRMPOL(CFRMPOLNAME)**

Specifies the name of the CFRM policy that is to be started at IPL-time if there is no other previously activated CFRM policy. If there is a previously activated CFRM policy, the CFRMPOL specification is ignored. The CFRM couple data set that contains the policy must be accessible to all members of the sysplex. See the PCOUPLE and ACOUPLE statements for a description of the couple data sets.

**Value range:** CFRMPOLNAME is a 1-8 character name of a CFRM policy. Valid characters are A-Z and 0-9. The policy name must start with an alphabetic character.

**Default:** None. If you omit the CFRMPOL keyword, and there is no previously-activated CFRM policy, the system does not automatically start a CFRM policy at IPL time.

**Note:** The CFRMPOL keyword is positional and, when being set, needs to be between the SYSPLEX(plex\_name) and the [PCOUPLE(primary-dsname[,primary-volume]), as shown in the syntax format of COUPLExx.

### **CLASSLEN(nnnnn)**

Specifies the system default for message length that the system uses when CLASSLEN is not specified on either:

- The CLASSDEF statement
- The SETXCF START,CLASSDEF command.

**Value range:** 0 - 62464

**Default:** 956 bytes

**CLEANUP(seconds)**

Specifies how many seconds the system waits between notifying members that this system is terminating and loading a non-restartable wait state. This is the amount of time that XCF group members have to perform cleanup processing.

**Value range:** 0 - 86400 (seconds)

**Default:** 15

**CTRACE(parmlib-member)**

Specifies the member of SYS1.PARMLIB that contains component trace options. You can specify either a CTnXCFxx or a CTnXESxx parmlib member, or both (by specifying the CTRACE keyword more than once).

**Value range:** The 8-character member name must be in the format CTnXCFxx or CTnXESxx, where:

**n**

An alphanumeric character to specify the source of the member. IBM-supplied members will use "I".

**xx**

Any two characters.

**Default:** CTIXCF00 and CTIXES00

The contents of CTIXCF00 are:

```
TRACEOPTS ON
```

The contents of CTIXES00 are:

```
TRACEOPTS
ON
```

For more information about specifying options for the XCF component trace, see [z/OS MVS Diagnosis: Tools and Service Aids](#). For information about coding the component trace member of SYS1.PARMLIB, see [Chapter 26, "CTnccccx \(component trace parameters\)," on page 249](#).

**INTERVAL(seconds)**

Specifies the failure detection interval, the amount of elapsed time at which XCF on another system is to initiate system failure processing for this system because XCF on this system has not updated its status within the specified time.

IBM suggests that the default value (the derived spin failure detection interval) be used. If you specify the INTERVAL value explicitly, it should be no more than twice the derived spin failure detection interval based on the following considerations: the user-specified INTERVAL must be greater or equal to the derived spin failure detection interval so that the system can have a chance to recover before XCF initiates system failure processing; however, if the value is too large, it might allow sympathy sickness to spread throughout the sysplex.

**Value range:** 3 - 86400 (seconds)

**Default:** XCF derives the default INTERVAL value from the excessive spin processing parameters in EXSPATxx.

The value is computed as follows:

```
(N+1)*SpinTime + 5
```

where N is the number of excessive spin recovery actions, +1 indicates the implicit SPIN action, and SpinTime is the excessive spin loop timeout interval. The SPINRCVY statement and the SPINTIME keyword in the EXSPATxx parmlib member determine the number of spin actions and the spin loop timeout, respectively. If the excessive spin parameters are not explicitly set on an EXSPATxx parmlib member, the IBM supplied default spin parameters are used: the derived spin failure detection interval can be 45 seconds or 165 seconds depending on the configuration:

- For systems running in a native or basic mode, or in an LPAR with dedicated CPs, the default spin failure detection interval is 45 seconds.
- For systems running on VM or in an LPAR with shared CPs, the default spin failure detection interval is 165 seconds.

The value is derived from the default EXSPATxx settings:

- The default spin loop timeout value varies by configuration: 10 seconds for systems that have dedicated CPs, or 40 seconds for system that have shared CPs or running under VM.
- The default spin recovery actions are ABEND, TERM, and ACR, and the implicit SPIN.

**Note:**

1. If USERINTERVAL is set or defaulted to be disabled on the FUNCTIONS statement, the effective failure detection interval is the greater of the spin failure detection interval derived from the EXSPATxx parameters, and the user specified INTERVAL (if any). If USERINTERVAL is enabled, XCF uses the user-specified INTERVAL as the effective failure detection interval.
2. Changes to EXSPATxx parameters cause new spin failure detection interval to be computed, and then cause the effective failure detection interval to change.

**MAXMSG(nnnnnn)**

Specifies a value XCF uses to determine the allotment of message buffers when the MAXMSG parameter is not specified on any one of following:

- The CLASSDEF statement
- The PATHIN statement
- The SETXCF START,CLASSDEF command
- The SETXCF START,PATHIN command.

For more information about determining message buffer space, see [z/OS MVS Setting Up a Sysplex](#).

**Value range:** 1 - 999999 K-byte blocks of storage

**Default:** 2000

**OPNOTIFY(seconds)**

Specifies the amount of elapsed time (in seconds) at which XCF on another system is to notify the operator (by using message IXC402D) that this system has not updated its status. The OPNOTIFY value can either be specified as an absolute value (in the form of *nnnnn*) or as a relative value (in the form of *+nnnnn*).

- When an absolute value is specified, the OPNOTIFY value must be greater than or equal to the INTERVAL value if INTERVAL is specified. The effective OPNOTIFY value that is used by the system is the greater one of the indicated OPNOTIFY values and the effective failure detection interval.
- When a relative value is specified, the effective OPNOTIFY value that is used by the system is the sum of the effective failure detection interval plus the relative OPNOTIFY value.

**Value range:**

- For absolute value: 3 to 86400 (seconds)
- For relative value: 0 to 86400 (seconds)

**Default:** A relative value of +3 is used. Thus the effective OPNOTIFY value that is used by the system equals three plus the effective failure detection interval.

**PCOUPLE(primary-dsname[,primary-volume])**

Specifies the name of the primary sysplex couple data set and, optionally, the volume on which that data set resides.

**Value range:** The *primary-dsname* must be a valid data set name of up to 44 characters. Valid characters are alphanumeric (A-Z and 0-9) and national (@, #, \$) characters and periods (.).



The *primary-volume* is the 1 to 6 character name of a mounted and ready DASD volume. Valid characters are alphanumeric and national characters. If the volume is not specified, the data set must be cataloged in the master catalog.

**Default:** None. If you omit the PCOUPLE keyword the system comes up in XCF-local mode. Also, the system ignores the PATHIN and PATHOUT statements and the ACOUPLE keyword.

### RETRY(nnn)

Indicates the system default for how much tolerance XCF has for signaling path failures. The lower the value, the sooner XCF stops the signaling path. A higher value indicates that XCF will tolerate more signaling path failures before XCF stops the signaling path. The system uses this value when the RETRY parameter is not on any one of the following:

- The PATHOUT statement
- The PATHIN statement
- The SETXCF START,PATHOUT command
- The SETXCF START,PATHIN command.

**Value range:** 3 - 255

**Default:** 10

### SYSPLEX(sysplex-name)

Specifies the name of the sysplex in which the system participates. The sysplex name is also the substitution text for the &SYSPLEX system symbol. Specify a sysplex name that is different than any of the system names in the sysplex.

The optional SYSPLEX parameter in the LOADxx parmlib member also specifies the sysplex name. LOADxx defines the substitution text for &SYSPLEX early in system initialization so other parmlib members can use it. Therefore, if you plan to use the &SYSPLEX system symbol in parmlib, specify the sysplex name in LOADxx.

When you specify a sysplex name on this parameter, consider the content of LOADxx:

- If the sysplex name is specified in LOADxx, code the &SYSPLEX system symbol on this parameter, as follows:

```
SYSPLEX(&SYSPLEX.)
```

The use of &SYSPLEX ensures that the sysplex name is the *same* in both LOADxx and COUPLExx. Do not code a name that is different from the name specified in LOADxx. If you do, the substitution text for &SYSPLEX changes during system initialization, and might generate unpredictable results. See “[Step 5. Code support for system symbols in LOADxx](#)” on page 46 for details about how to specify the sysplex name in LOADxx.

- If you specify the sysplex name only in COUPLExx, code the name on this parameter. The system does not define the substitution text for &SYSPLEX until late in system initialization. The system will substitute the text LOCAL for &SYSPLEX in all parmlib members that are processed until the COUPLExx parmlib member is completely processed. If you want to resolve the substitution for &SYSPLEX to anything other than LOCAL during the processing of COUPLExx, you need to specify the substitution in LOADxx.

System logger also may use the sysplex name as part of the staging data set name for a DASD-only log stream. The sysplex name that is specified here allows you to use a digit as the first character, but this is not valid in a staging data set name. If you use a digit as the first character in the sysplex name, system logger substitutes 'STG' for the digit and uses part of the system name in the low-level qualifier for the staging data set name. For complete information, see [z/OS MVS Setting Up a Sysplex](#) and look for the topic on naming conventions for the log stream and DASD log data sets.

**Default:** One of the following:

- A 1- through 8-character sysplex name. Valid characters are alphanumeric (A-Z and 0-9) and national (@,#,\$) characters. The name must match the name that is specified on the SYSPLEX parameter of the XCF couple data set format utility.

**Default:** None. A value must be specified for this parameter.

### VMCPUIDTOLERATION(NO|YES)

Controls the verification of CPU identification information that:

- A VM guest system will perform at SCF initialization with respect to any other active systems in the sysplex
- An LPAR system will perform at XCF initialization with respect to any other active z/VM guest systems in the sysplex

when a simulated external time reference identifier (SIMETRID) is being used.

The keyword has no effect if the system is not running as either a z/VM guest or LPAR system. The keyword also has no effect on system operation subsequent to XCF initialization.

**Value range:** One of the following options:

#### NO

Specifies that a z/VM guest system or LPAR system IPLing into a sysplex will verify its CPU identification information against that of other systems in the sysplex. The system will not tolerate disparate CPU identification information with respect to other systems in the sysplex when SIMETRID is being used.

#### YES

Specifies that a z/VM guest system or LPAR system IPLing into a sysplex will not verify its virtual CPU identification information against that of other systems in the sysplex. It will tolerate disparate CPU identification information with respect to the other systems in the sysplex when SIMETRID is being used.

Also, an LPAR system IPLing into a sysplex will not verify its CPU identification information against the virtual CPU information of any z/VM guest systems active in the sysplex. It will tolerate disparate CPU identification information with respect to z/VM guest systems in the sysplex, but not with respect to other LPAR or native systems in the sysplex when SIMETRID is being used.

VMCPUIDTOLERATION(YES) allows z/VM guest systems participating in a sysplex under z/VM to have disparate CPU identification information, which might be useful in using z/VM to simulate a sysplex comprised of systems on different CECs.

When this option is specified, the system has no way to verify that the z/VM guest systems in the sysplex are in fact guests of the same z/VM host system. The installation must ensure that all systems participating in a sysplex are guests of the same z/VM host system, in order to ensure that the simulated Sysplex Timer support (SIMETRID) provides a common time reference.

**Default:** NO

### FUNCTIONS

Specifies the initial enablement state of XCF/XES optional functions on the current system. You can specify either or both of the two subordinate keywords: ENABLE and DISABLE.

#### ENABLE(function[,function ...])

Enables one or more optional functions.

**Value range:** The acceptable function names are described in topic "The FUNCTIONS Statement" in *z/OS MVS Setting Up a Sysplex*.

**Default:** If a given function is not specified on the FUNCTIONS statement, its initial enablement state will be the default state described in topic "The FUNCTIONS Statement" in *z/OS MVS Setting Up a Sysplex*.

#### DISABLE(function[,function ...])

Disables one or more optional functions.

**Value range:** The acceptable function names are described in topic "The FUNCTIONS Statement" in [z/OS MVS Setting Up a Sysplex](#).

**Default:** If a given function is not specified on the FUNCTIONS statement, its initial enablement state will be the default state described in topic "The FUNCTIONS Statement" in [z/OS MVS Setting Up a Sysplex](#).

## CLASSDEF

Each optional CLASSDEF statement defines an XCF transport class (in addition to the DEFAULT transport class) for message traffic. You can define a maximum of 62 different transport classes. If you do not define the DEFAULT transport class, the system creates a default transport class with these characteristics:

- CLASS - The default classname is DEFAULT
- CLASSLEN - The default message length that is specified with the CLASSLEN parameter of the COUPLE statement
- MAXMSG - The amount of message buffer space that is specified with the MAXMSG parameter of the COUPLE statement
- GROUP - Although no groups are explicitly assigned to the default transport class, the DEFAULT transport class handles the messages for any group that is not explicitly assigned to a specific transport class. The collection of these groups is referred to by the pseudo-group name UNDESIG. Groups are explicitly assigned to a transport class by using the GROUP parameter on the CLASSDEF statement or the SETXCF command.

### CLASS(classname)

Indicates the name of the transport class. Each transport class must have a unique class name on a system. You can specify the same class name on other systems in the sysplex for convenience; but there is no relationship between transport classes on different systems. To modify the definition of the default transport class, use the classname of DEFAULT.

**Value range:** 1 to 8 alphanumeric characters (A-Z and 0-9) and national characters (@, #, and \$).

**Default:** None. A value must be specified.

### CLASSLEN(nnnnnn)

Defines the message length (in bytes) for this transport class. Specify a length equal to the length of the longest messages that are most often sent by the groups that are assigned to the transport class. The class length that you specify is the message length for which the signaling class will optimize its processing. The class length establishes the size of the message buffers that the signaling service will provide in the transport class.

**Value range:** 0 - 62464 bytes

**Default:** The value that is specified or defaulted on the CLASSLEN parameter of the COUPLE statement.

### MAXMSG(nnnnnnn)

Specifies the default amount of 1K message buffers allotted for messages that are sent in this transport class. The system uses this value when MAXMSG is not specified on either of the following options:

- The PATHOUT statement
- The SETXCF START,PATHOUT command.

For more information about determining message buffer space, see [z/OS MVS Setting Up a Sysplex](#).

**Value range:** 1 - 999999

**Default:** The value that is specified or defaulted on the MAXMSG parameter on the COUPLE statement.

**GROUP(groupname,groupname ...)**

Specifies one or more groups that are assigned to this transport class. A group is the set of related members that are defined to XCF by a multisystem application in which members of the group can communicate between MVS systems with other members of the same group. A group can be assigned to more than one transport class.

By explicitly assigning a group to a transport class, you give the group preferential access to the signaling resources (signaling paths and message buffer space) of the transport class.

**Value range:** 1 to 8 alphanumeric characters, including @, #, and \$.

**Default:** If the GROUP parameter is omitted, no groups are explicitly assigned to the transport class. In this case, all groups that are not explicitly defined to a transport class (by specifying their groupname on the GROUP parameter on at least one CLASSDEF statement) are implicitly assigned to this transport class. A group that has not been explicitly assigned to any transport class is called an undesignated group. To explicitly assign the collection of undesignated groups to a transport class, use the pseudo-group name UNDESIG. The pseudo-group name UNDESIG then refers to the collective set of groups that are not explicitly defined to a transport class.

**PATHIN**

Describes the XCF signaling paths for inbound message traffic. More than one PATHIN statement can be specified. The PATHIN statement is not required for a single system sysplex.

**DEVICE(devnum[,devnum ...])**

Specifies the device numbers of a signaling path that is used to receive messages that are sent from another system in the sysplex.

**Value range:** *devnum* is 3 or 4 hexadecimal digits.

**Default:** None. Either this parameter or STRNAME must be specified on the PATHIN statement.

**MAXMSG(max-messages)**

Specifies the amount of message buffers space (in 1 K units) that XCF can use to receive messages over each inbound XCF path that is defined on the PATHIN statement.

You can specify MAXMSG with either a DEVICE or STRNAME statement.

**Value range:** 1 - 999999 K byte blocks of storage

**Default:** The value that is specified or defaulted on the MAXMSG parameter of the COUPLE statement.

**RETRY(nnn)**

Specifies how much tolerance XCF has for failures on the inbound paths that are defined on this PATHIN statement. The lower the value, the sooner XCF stops the path. A higher value indicates that XCF will tolerate more path failures before XCF stops the path.

You can specify RETRY with either a DEVICE or STRNAME statement.

**Value range:** 3 - 255

**Default:** The value that is specified or defaulted on the RETRY parameter of the COUPLE statement.

**STRNAME(strname[,strname ...])**

Specifies the name of one or more coupling facility list structures that are to be used to establish XCF signaling paths.

Either the STRNAME keyword or the DEVICE keyword is required. If you specify the STRNAME keyword, you must provide at least one structure name.

**Value range:** The *strname* can be 1 to 16 characters, including alphanumeric characters (A-Z and 0-9), national characters (@,#,\$), and an underscore (\_), where the first character is uppercase alphabetic. XCF signaling structures must begin with the letters IXC.

**Default:** None. Either this parameter or DEVICE must be specified on the PATHIN statement.

**PATHOUT**

Describes the XCF signaling paths for outbound message traffic. More than one PATHOUT statement can be specified. The PATHOUT statement is not required for a single system sysplex.

**CLASS(classname)**

Assigns the outbound XCF paths to a transport class. A corresponding CLASSDEF statement must define this class, unless you specify a *classname* of DEFAULT.

You can specify CLASS with either a DEVICE or STRNAME statement.

**Value range:** 1 to 8 alphanumeric characters, including @, #, and \$.

**Default:** DEFAULT (The classname of the default XCF transport class).

**DEVICE(devnum[,devnum...])**

Specifies the device numbers of a signaling path that is used to send messages to another system in the sysplex.

**Value range:** *devnum* is 3 or 4 hexadecimal digits.

**Default:** None. Either this parameter or STRNAME must be specified on the PATHOUT statement.

**MAXMSG(max-messages)**

Specifies how much buffer space is contributed to the total amount of buffer space XCF can use to send messages over outbound XCF paths defined on the PATHOUT statement. This value represents a portion of the maximum amount of buffer space for the transport class that this path is assigned to.

You can specify MAXMSG with either a DEVICE or STRNAME statement.

**Value range:** 1 - 999999 K byte blocks of storage. You must specify enough buffer space to contain at least one message whose size is equal to the CLASSLEN value on the CLASSDEF statement for the transport class that this path is defined to.

**Default:** The value that is specified or defaulted on the MAXMSG parameter of the CLASSDEF statement for the XCF transport class this path is assigned to.

**RETRY(nnn)**

Specifies how much tolerance XCF has for failures on the outbound paths that are defined on this PATHOUT statement. The lower the value, the sooner XCF stops the path. A higher value indicates that XCF will tolerate more path failures before XCF stops the path.

You can specify RETRY with either a DEVICE or STRNAME statement.

**Value range:** 3 - 255

**Default:** The value that is specified or defaulted on the RETRY parameter of the COUPLE statement.

**STRNAME(strname[,strname...])**

Specifies the name of one or more coupling facility list structures that are to be used to establish XCF signaling paths.

Either the STRNAME keyword or the DEVICE keyword is required. If you specify the STRNAME keyword, you must provide at least one structure name.

**Value range:** The *strname* can be 1 to 16 characters, including alphanumeric characters (A-Z and 0-9), national characters (@, #, \$), and an underscore (\_), where the first character is uppercase alphabetic. XCF signaling structures must begin with the letters IXC.

**Default:** None. Either this parameter or DEVICE must be specified on the PATHOUT statement.

**LOCALMSG**

Specifies resources for local message traffic between members running on the same system. This statement is optional.

**CLASS(classname)**

Assigns the local message buffer space to a transport class. A corresponding CLASSDEF statement must define this class, unless you specify a *classname* of DEFAULT.

**Value range:** 1 to 8 alphanumeric characters, including @, #, and \$.

**Default:** DEFAULT (The classname of the default XCF transport class).

**MAXMSG(nnnnnn)**

Specifies how much additional buffer space XCF can use for local message traffic beyond the defaults that are specified on the COUPLE and CLASSDEF statements. The total amount of buffer space that is used for local messages is this value added to the value specified or defaulted on the MAXMSG parameter on the CLASSDEF statement for the transport class indicated by the CLASS parameter.

**Value range:** 1 - 999999 K byte blocks of storage. You must specify enough buffer space to contain at least one message whose size is equal to the CLASSLEN value on the CLASSDEF statement for this transport class.

**Default:** None. This parameter must be specified.

**DATA**

Defines the use of additional couple data sets. More than one DATA statement is permitted.

**ACOUPLE(alternate-dsname[,alternate-volume])**

Specifies the name of the alternate couple data set to support the service, and optionally, the volume on which the data set resides. The ACOUPLE keyword is optional with a DATA statement. If the volume is specified, the master catalog is not used to locate the couple data set. If the volume is not specified, the data set must be cataloged in the master catalog.

The ACOUPLE specification is ignored if the service is already operational in the sysplex. If the service is already operational, the system uses the couple data sets for the service that are currently in use by the sysplex.

**Value range:** The *alternate-dsname* must be a valid data set name of up to 44 characters. Valid characters are alphanumeric (A-Z and 0-9) and national (@, #, \$) characters and periods (.). The *alternate-volume* is the 1 to 6 character name of a mounted and ready DASD volume. Valid characters are alphanumeric and national characters.

**Default:** None. If the ACOUPLE keyword is omitted, the system is initialized with only the primary couple data set to support the service name on the TYPE keyword.

**PCOUPLE(primary-dsname[,primary-volume])**

Specifies the name of a primary couple data set to support the service, and optionally, the volume on which the data set resides. The PCOUPLE keyword is required with a DATA statement. If the volume is specified, the master catalog is not used to locate the couple data set. If the volume is not specified, the data set must be cataloged in the master catalog.

The PCOUPLE specification is ignored if the service is already operational in the sysplex. If the service is already operational, the system uses the couple data sets for the service that are currently in use by the sysplex.

**Value range:** The *primary-dsname* must be a valid data set name of up to 44 characters. Valid characters are alphanumeric (A-Z and 0-9) and national (@, #, \$) characters and periods (.). The *primary-volume* is the 1 to 6 character name of a mounted and ready DASD volume. Valid characters are alphanumeric and national characters.

**Default:** None.

**TYPE(name,name...)**

Specifies the names of the coupling services that are to use the couple data set. Names of the coupling services include:

- ARM for automatic restart management
- CFRM for coupling facility resource management

- LOGR, LOGRY, and LOGRZ for system logger
- SFM for sysplex failure management
- WLM for workload management
- BPXMCDS for the z/OS UNIX sysplex-wide mount table

## **SYNCASync**

Specifies the thresholds at which the system converts synchronous CF requests to run asynchronously.

Synchronous CF requests spin while waiting for a request to complete at the CF. This activity consumes CPU resources. If the projected synchronous service time exceeds the defined threshold, z/OS converts the request to run asynchronously. A lower threshold causes more requests to run asynchronously, which reduces CPU consumption but also potentially elongates overall service time. A higher threshold causes more requests to execute synchronously, which increases CPU consumption but also potentially improves throughput.

You must specify at least one of the following keywords with SYNCASync:

### **DUPLEX(nnnnn|DEFAULT)**

Specifies, in microseconds, the synchronous or asynchronous conversion threshold for all duplex requests for structures other than lock structures. Specify DEFAULT to use the system determined threshold.

**Value range:** 1 - 10000 microseconds

### **LOCKDUPLEX(nnnnn|DEFAULT)**

Specifies, in microseconds, the synchronous or asynchronous conversion threshold for all duplex requests for lock structures. Specify DEFAULT to use the system determined threshold.

**Value range:** 1 - 10000 microseconds

### **LOCKSIMPLEX(nnnnn|DEFAULT)**

Specifies, in microseconds, the synchronous or asynchronous conversion threshold for all simplex requests for lock structures. Specify DEFAULT to use the system determined threshold.

**Value range:** 1 - 10000 microseconds

### **SIMPLEX(nnnnn|DEFAULT)**

Specifies, in microseconds, the synchronous or asynchronous conversion threshold for all simplex requests for structures other than lock structures. Specify DEFAULT to use the system determined threshold.

**Value range:** 1 - 10000 microseconds





## Chapter 25. CSVLLAxx (library lookaside (LLA) list)

Use the CSVLLAxx member to specify which libraries (in addition to the LNKST concatenation) library lookaside (LLA) is to manage. If you do not supply a CSVLLAxx member by the LLA=xx parameter of the LLA procedure on the first starting of LLA for this IPL, or if you specify a parameter of LLA=NONE, LLA will, by default, manage only the libraries that are accessed through the LNKST concatenation. If you have started LLA successfully with a CSVLLAxx member and then stop LLA, a subsequent start of LLA will use that CSVLLAxx member unless you supply another CSVLLAxx member. If you want to get back to the default settings, specify LLA=NONE.

You can also use CSVLLAxx to specify the following:

- Libraries to be added or removed from LLA management while LLA is active.
- Whether LLA is to hold an enqueue for the libraries it manages.
- Libraries for which LLA is to use the performance-enhancing FREEZE|NOFREEZE option.
- Members of libraries, or whole libraries, to be selectively refreshed in the LLA directory.
- Multiple CSVLLAxx members to be used to control LLA processing. These members can reside in data sets other than SYS1.PARMLIB. Use the PARMSUFFIX(xx) parameter to specify additional data sets. (See *z/OS MVS Initialization and Tuning Guide* for an example.)
- Whether exit routines are to be called during LLA processing.

The operator can change these options dynamically by specifying alternative CSVLLAxx members through the MODIFY LLA,UPDATE=xx command.

You can produce a program object, an executable program unit that can be stored in a partitioned data set extended (PDSE) program library. Program objects resemble load modules in function, but have fewer restrictions and are stored in PDSE libraries instead of PDS libraries. LLA can only manage PDSE libraries containing program objects. LLA manages both load and program libraries.

You can use data set aliases in CSVLLAxx; however, LLA will use the actual data set name to manage the data set. For example, a DISPLAY LLA command will display the actual data set name rather than the alias. The same holds true for any other tooling that references the list of data sets managed by LLA.

For guidance information about specifying values for CSVLLAxx, see *z/OS MVS Initialization and Tuning Guide*.

### Starting LLA

The START LLA,LLA=xx command identifies the CSVLLAxx parmlib member to be used to build the LLA directory. This command is issued by the IBM-supplied IEACMD00 parmlib member during system initialization; the command can also be entered by the operator. For more information about starting LLA, see *z/OS MVS Initialization and Tuning Guide*.

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Syntax rules for CSVLLAxx

The syntax for CSVLLAxx is:

- Data, including comments, must be contained in columns 1-71; the system ignores columns 72-80.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/".
- There is no limit to the number of times a keyword can be specified.
- Commas or blanks in any combination constitute a delimiter.

- Delimiters or comments can precede the keywords.
- Delimiters are not required between keywords with value; the right parenthesis after the specified keyword is sufficient.
- Continuation is indicated by placing a comma followed by at least one blank after the last name on a record. Comments are allowed between keywords or values.
- The LLA command will not be processed if there are any errors in the contents of the CSVLLAxx parmlib member(s).

## Syntax format of CSVLLAxx

```
LIBRARIES(libname1,libname2,...[-LNKLST-],...) MEMBERS(mmb1,mmb2,..)
LNKMEMBERS(mmb1,mmb2,...)
REMOVE(libname1,libname2,...[-LNKLST-],...)
GET_LIB_ENQ(YES|NO)
PARMLIB(dsn) SUFFIX(xx)
FREEZE(libname1,libname2,...[-LNKLST-],...)
NOFREEZE(libname1,libname2,...[-LNKLST-],...)
EXIT1(NO|OFF)
EXIT2(NO|OFF)
PARMSUFFIX(xx)
```

The IBM-supplied default for CSVLLAxx is None.

## Statements and parameters for CSVLLAxx

### EXIT1(ON|OFF)

Specifies whether the system is to add the CSVLLIX1 exit routine to the CSVLLIX1 dynamic exit.

The EXIT1 statement is processed only when LLA starts, otherwise it is ignored unless it is not syntactically correct.

When EXIT1(ON) is specified, or if EXIT1 is not specified, in the CSVLLAxx parmlib member that is used to start LLA, the system attempts to add the CSVLLIX1 exit routine to the CSVLLIX1 dynamic exit when no exit routines are already added by PROGxx or SETPROG processing.

If exit routines are already added by PROGxx or SETPROG processing, or if EXIT1(OFF) is specified, the system does not attempt to add the CSVLLIX1 exit routine. If you require an exit routine to be added, you must explicitly add the exit routine using PROGxx or SETPROG. If one of the already added exit routines is in the active state, LLA calls the CSVLLIX1 exit. To prevent an exit routine being called after it has been added, you can use the dynamic exit facility to change the state of the exit routine to be inactive.

You can use CSVLLIX1 to do the following tasks:

- Monitor and collect fetch statistics
- Control the 2000 fetch default limit
- Cause staging to happen regardless of statistics for all libraries or even just one library

For more information about CSVLLIX1, see [z/OS MVS Installation Exits](#).

**Default:** ON

**EXIT2(ON|OFF)**

Specifies whether the system is to add the CSVLLIX2 exit routine to the CSVLLIX2 dynamic exit. The EXIT2 statement is processed only when LLA starts, otherwise it is ignored unless it is not syntactically correct.

When EXIT2(ON) is specified, or if EXIT2 is not specified, in the CSVLLAxx parmlib member that is used to start LLA, the system attempts to add the CSVLLIX2 exit routine to the CSVLLIX2 dynamic exit when no exit routines are already added by PROGxx or SETPROG processing.

If exit routines are already added by PROGxx or SETPROG processing, or if EXIT2(OFF) is specified, the system does not attempt to add the CSVLLIX2 exit routine. If you require an exit routine to be added, you must explicitly add the exit routine using PROGxx or SETPROG. If one of the already added exit routines is in the active state, LLA calls the CSVLLIX2 exit. To prevent an exit routine being called after it has been added, you can use the dynamic exit facility to change the state of the exit routine to be inactive.

You can use CSVLLIX2 to do the following tasks:

- Analyze fetch statistics that are provided in the LLA module staging parameter list.
- Influence the calculation of the LLA value (which determines whether a module should be staged) by altering the weighting factors.
- Direct that the module must be staged or must not be staged by setting the appropriate return and reason codes.

For more information about CSVLLIX2, see [z/OS MVS Installation Exits](#).

**Default:** ON

**FREEZE|NOFREEZE(libname1,libname2,...[-LNKLST-],.....)**

Specifies for a library whether to have LLA use the directory that it maintains in its own storage (FREEZE) or to use the directory on DASD storage (NOFREEZE). When a LLA library is specified with FREEZE, the installation takes full advantage of LLA's I/O reduction for directory search for the library and for fetching load modules.

References to members in the data sets of the LNKLST concatenation, when referenced via the appropriate LNKLST DCB, are always treated as FREEZE and cannot be changed by this parameter.

References to members in the data sets of the LNKLST concatenation, when referenced outside the LNKLST (that is, through JOBLIB, STEPLIB, or TASKLIB) are processed as individual libraries. This parameter changes how LLA provides the directory for those references.

-LNKLST- can be used to designate a list of data sets for this parameter, which is derived from all active LNKLST sets. When specified, LLA builds this list for you as part of its normal processing. It is a shorthand way to identify all of the data sets in the LNKLST instead of listing each of them using (-LNKLST-, non-LNKLST libname1, non-LNKLST libname2). As an example, specifying FREEZE (-LNKLST-) directs LLA to set each of the data sets in the LNKLST concatenations list in FREEZE mode. (LLA provides directories from the saved information in LLA storage for requests via JOBLIB, STEPLIB, or TASKLIB.) Specifying NOFREEZE (-LNKLST-) directs LLA to manage each of the data sets (in the LNKLST concatenations list) in NOFREEZE mode, whenever the data set is accessed outside of the LNKLST. That is, LLA provides directories by doing I/O to the DASD storage for these data sets specified via JOBLIB, STEPLIB, or TASKLIB. However, references to members via any active LNKLST concatenation are always provided from LLA storage, so NOFREEZE does not affect that request.

You can change the FREEZE|NOFREEZE status of an LLA library at any time by using the MODIFY LLA command.

For more information about using the FREEZE|NOFREEZE option, see [z/OS MVS Initialization and Tuning Guide](#).

By default, LNKLST data sets that are accessed through the LNKLST concatenation are in FREEZE mode and cannot be changed with this parameter. All other libraries (specified by -LNKLST- or individually by library name) are set to NOFREEZE by default. To take full advantage of LLA, it is recommended that all libraries be explicitly specified as FREEZE.

### **GET\_LIB\_ENQ(YES|NO)**

Specifies whether LLA obtains a shared enqueue for the libraries it manages.

If you specify GET\_LIB\_ENQ (YES), which is the default, LLA obtains a shared enqueue for the libraries it manages. The shared enqueue allows your job to read the libraries, but not to move or erase them. To update these libraries, you must first remove them from LLA management (through the REMOVE keyword).

If you specify GET\_LIB\_ENQ(NO), LLA does not obtain an enqueue for libraries it manages.

Your installation's jobs can update, move, or delete libraries while LLA is managing them.

GET\_LIB\_ENQ(NO) is generally not recommended, however, because of the risks it poses to data integrity. IBM suggests that you use GET\_LIB\_ENQ (NO) only when necessary.

The system processes the GET\_LIB\_ENQ keyword only when LLA is started; you cannot set this value while LLA is active. If you attempt to do so (for example, by specifying the GET\_LIB\_ENQ value on an LLA UPDATE command), the system ignores the GET\_LIB\_ENQ value without issuing a corresponding message.

If you specify the GET\_LIB\_ENQ keyword multiple times in a CSVLLAxx member, the system uses only the first occurrence of the keyword and ignores subsequent occurrences without issuing a corresponding message.

**Default:** YES

### **LIBRARIES(libname1,libname2,...[-LNKLST-],...)**

Lists the names of libraries (*libname1,libname2,...*) that are to be added to LLA, if they are not already being managed by LLA, or selectively refreshed, if they are already being managed by LLA.

A library name must be 1 - 44 characters long.

-LNKLST- (the hyphens are coded) can be used to designate the whole LNKLST concatenation. It is a shorthand way to identify all the data sets in the LNKLST instead of listing each of them, that is: (-LNKLST- , non-LNKLST libname1, non-LNKLST libname2). In a Dynamic LNKLST environment, -LNKLST- designates a list of data sets compiled from all active LNKLST sets. When specified and a new LNKLST set is activated by the Dynamic Lnkst function, any data set in the new LNKLST set that is not currently managed is added to LLA's management. If a new LNKLST data set is the target of a prior REMOVE request, it is not dynamically added to LLA.

**Default:** None

### **LNKMEMBERS(mmbr1,mmbr2,mmbr3,...)**

Lists the member names (*mmbr1,mmbr2,mmbr3...*) that are in the LNKLST concatenation and that are to be selectively refreshed. LNKMEMBERS is equivalent to specifying *LIBRARIES(-LNKLST-) MEMBERS(mmbr1,mmbr2,mmbr3...)*.

The member names (*mmbr1,mmbr2,mmbr3...*) must be 1 - 8 characters long.

**Default:** None

### **MEMBERS(mmbr1,mmbr2,...)**

Dynamically refreshes members in the previously named production libraries.

Each MEMBERS statement must be preceded by a LIBRARIES statement that identifies the libraries that contain the new versions of the members.

The member names (*mmbr1,mmbr2...*) must be 1 - 8 characters long.

The LLA directory for each of the listed libraries is updated with the directory entries for the listed members that are found in each of the data sets. That is, LIBRARIES(LIB.1, LIB.2, LIB.3) MEMBERS(A,B,C) result in the LLA directory for LIB.1 being refreshed with directory entries found for members A, B, and C in the DASD directory for LIB.1; the LLA directory for LIB.2 being refreshed with directory entries found for members A, B, and C in the DASD directory for LIB.2, and so forth.

If -LNKLST- is in the LIBRARIES statement list, LLA dynamically refreshes the specified members in the LNKLST. All occurrences of the member name in the LNKLST concatenation are used to refresh

the LLA directory. In a Dynamic LNKST environment, the specified member is refreshed in all active LNKST sets.

**Default:** None

### **PARMLIB(*dsn*)**

#### **SUFFIX(*xx*)**

Specifies an additional CSVLLAxx member to be processed. The system processes this member completely when encountering this statement.

PARMLIB(*dsn*) identifies the data set where the CSVLLAxx member identified by (*xx*) should be found. The PARMLIB keyword allows you to include CSVLLAxx members from data sets other than SYS1.PARMLIB, thereby allowing you to control LLA's specifications without having update access to SYS1.PARMLIB.

**Default:** None. No additional CSVLLAxx members are read.

### **PARMSUFFIX(*xx*)**

Specifies an additional CSVLLAxx member to be processed. The system processes this member completely when encountering this statement.

This statement is similar to the PARMLIB(*dsn*) SUFFIX(*xx*) statement. The difference is that instead of having to specify a data set name, PARMSUFFIX searches the logical parmlib for the CSVLLAxx member.

There is no default value. No additional CSVLLAxx members are read.

### **REMOVE(*libname1,libname2,...*)**

Removes libraries from the list of libraries that are managed by LLA. That is, LLA is no longer used to provide directory entries or staged modules for these libraries.

Specify REMOVE(-LNKST- , . . .) to remove each of the specified LNKST libraries from LLA management. REMOVE(-LNKST- , . . .) does not change the contents of the LNKST concatenation. In a Dynamic LNKST environment, this parameter designates a list of data sets compiled from all active LNKST sets.

Libraries should be removed from LLA management before they are compressed. For LNKST libraries, see [“Removing or compressing a data set in an active LNKST set” on page 692 in Chapter 81, “PROGxx \(authorized program list, exits, LNKST sets and LPA\),” on page 685](#). For non-LNKST libraries, remove them from LLA management, compress the library, and add the library back to LLA management using CSVLLAxx.

**Note:** It is not valid to specify the following:

- A library that is specified on the LIBRARIES statement or on the FREEZE|NOFREEZE option of this member or a member that is concatenated through use of the PARMLIB(*dsn*) SUFFIX(*xx*) statement.
- A data set in the LNKST if -LNKST- is specified on the LIBRARIES statement of this member or a member that is concatenated through use of the PARMLIB(*dsn*) SUFFIX(*xx*) statement.
- You cannot specify a library to be added to LLA management and designate it to be removed in the same operation.

**Note:** When REMOVE is specified for a data set that is in an LNKST, it does change how LLA provides the directory and module for any member on that data set. All data sets in the LNKST concatenation, except those that were the target of a REMOVE statement, continue to get full LLA management. As the LNKST concatenation is searched, I/O is done to DASD storage for members on REMOVED data sets as required. In certain circumstances, this might have a significant performance impact.

**Default:** None



## Chapter 26. CTnccccxx (component trace parameters)

Use the CTnccccxx parmlib member to specify tracing options for a component trace of either an MVS component or an application. The specific tracing options for those MVS components that support component tracing can be found in [z/OS MVS Diagnosis: Tools and Service Aids](#). For tracing options for non-IBM supplied applications, refer to the documentation for those applications.

The CTnccccxx parmlib member is specified as an 8-character member in the following format:

### CT

Indicates that the member contains component trace options

### n

Specifies the source of the member. IBM-supplied members use “I”.

### ccc

Identifies the component being traced.

### xx

Any two alphanumeric characters.

The CTnccccxx parmlib member is specified on:

- The CTRACE macro (with the DEFINE parameter)
- The TRACE CT operator command
- The parmlib member for some IBM-supplied components.

## Tracing of MVS components

The CTnccccxx parmlib member is specified in the PARM parameter of the TRACE CT operator command. See [z/OS MVS System Commands](#) for information about the TRACE CT command.

## Tracing of installation-provided applications

The CTnccccxx parmlib member is specified in the PARM parameter of the CTRACE macro in the application. See [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#) for information about the CTRACE macro.

The CTnccccxx member specified on the CTRACE macro allows an application to establish component tracing options at initialization. A CTnccccxx member can specify options for only one trace; if an application has multiple, concurrent traces, called **sublevel traces**, a CTnccccxx member must be specified for each sublevel trace.

Tracing options specified in the CTnccccxx parmlib member identified by the CTRACE macro can be overridden by a CTnccccxx parmlib member identified on a TRACE CT command. You can use the PARM parameter on a TRACE CT command:

- To specify a CTnccccxx member that contains the desired options. This trace will begin immediately.
- To specify a CTnccccxx member that contains a PRESET parameter to turn on the trace later when the CTRACE macro is invoked.

## Parameter in IEASYSxx (or supplied by the operator)

None.

## Syntax rules for CTnccccxx

The following syntax rules apply to CTnccccxx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- A comma must be used to separate multiple keyword values within a list.
- Comments may appear in columns 1-71 and must begin with "/"\* and end with "\*/".
- The parameters must be in the order shown in the syntax format, to meet the following requirements:
  - The SUB parameter must be followed by a PRESET, ON, OFF, or LIKEHEAD parameter.
  - The SUB parameter must not be before the WTRSTART parameter.

## Syntax examples

The following is an example of a CTncccxx member that could be used on a TRACE CT command to preset multiple sublevel traces.

```
TRACEOPTS
SUB(SUB201)
PRESET(DEFINE)
ON
ASID(000E,0002,0003)
JOBNAME(TEST1,TEST2,TEST3,TEST5,SMF,JES2) BUFSIZE(10K)
OPTIONS('new optionlist to record problem data')

SUB(SUB202)
PRESET(DEFINE)
LIKEHEAD

SUB(TEST5NODE1.TEST5NODE2.ASID(12,22,23))
PRESET(DEFINE)
OFF
```

The following example member turns on a trace that writes the trace data to a data set.

```
TRACEOPTS
WTRSTART(CTWTR)
ON
WTR(CTWTR)
ASID(0001,0002,0003)
JOBNAME(TEST1,TEST2,TEST3,SMF,JES2)
BUFSIZE(10K)
OPTIONS('list of options')
```

The following example member stops an external writer for a trace. Before this member is used, the trace must be turned off with a TRACE CT,OFF operator command or with a CTncccxx member that specifies TRACEOPTS and OFF. Do not turn off the writer in the same parmlib member as you turn off the trace.

```
TRACEOPTS
WTRSTOP(CTWTR)
```

The following CTnXESxx member turns on three sublevel SYSXES traces and starts an external writer for each sublevel trace. The last two sublevel traces will start later, when they are defined.

```
TRACEOPTS
ON
BUFSIZE(4M)

WTRSTART(XWTRGLO)
WTRSTART(XWTRC01)
WTRSTART(XWTRC02)

SUB(GLOBAL)
ON
WTR(XWTRGLO)
OPTIONS('CONNECT,RECOVERY')

SUB(LT01.ASID(18).CONN1)
PRESET(DEFINE)
ON
WTR(XWTRC01)
OPTIONS('GLOBAL,REQUEST')
```



```

SUB(LT01.ASIG(1A).CONN2)
PRESET(DEFINE)
ON
WTR(XWTRC02)

```

## Syntax format of CTnccccxx

```

TRACEOPTS
{ WTRSTART(membername){WRAP } }
{ } {NOWRAP} }

{ SUB(subname) }

{ PRESET{(DEFINE)} }
{ } {(DELETE)} }

{ ON{ASID(asid) } }
{ } {JOBNAME(jobname-list) }
{ } {BUFSIZE(nnnnK|M) }
{ } {OPTIONS(options) }
{ } {WTR{(membername) } }
{ } { } {(DISCONNECT) } }

{ OFF }

{ LIKEHEAD }

TRACEOPTS WTRSTOP(jobname)

```

## IBM-supplied default for CTnccccxx

IBM supplies defaults for specific components that support component tracing. For more information about default CTnccccxx parmlib members, see the following:

- Chapter 13, “BPXPRMxx (z/OS UNIX System Services parameters),” on page 123
- Chapter 24, “COUPLExx (cross-system coupling facility (XCF) parameters),” on page 229
- Chapter 34, “GRSCNFxx (global resource serialization configuration),” on page 319
- Chapter 23, “CONSOLxx (console configuration definition),” on page 201
- [SYSLOGR component trace in z/OS MVS Diagnosis: Tools and Service Aids](#)

## Statements and parameters for CTnccccxx

To determine if the component to be traced allows the following parameters, see component traces in [z/OS MVS Diagnosis: Tools and Service Aids](#).

### TRACEOPTS

Specifies the component tracing options for an MVS component or an application.

### ON

If the component trace is off, the parmlib member turns on the trace. If the component trace is on and can be changed, the parmlib member changes the trace. An installation-supplied application trace can be changed if the CTRACE macro that defined the trace contained a MOD=YES parameter.

When a head trace that was defined with HEADOPTS=YES is turned on, all sublevel traces currently defined as LIKEHEAD are also turned on. An installation-supplied application trace can also have head and sublevel traces, if specified in the CTRACE macro that defined the trace.

When a trace that has sublevel traces is changed, all sublevel traces currently in the LIKEHEAD state will also be changed. Therefore, a change might cascade down a number of levels.

A head trace might have been defined so that it is not allowed to be changed (HEADOPTS=NO on the CTRACE macro). If this is the case, the trace is just a place holder for options for other traces.

**ASID(asid-list)**

Specifies the address space identifiers (ASIDs) of address spaces to be used as a filter for tracing. Events in these ASIDs are to be recorded by the component trace.

**Note:** A list of 0 to 16 hexadecimal ASIDs separated by commas. An empty ASID list, ASID(), turns off filtering by address spaces. In the ASID parameter, list all address spaces to be traced; address spaces specified for previous traces will not be traced unless listed.

**BUFSIZE(nnnnK | nnnnM)**

Specifies the size, in kilobytes (K) or megabytes (M), of the trace buffer you want the system to use.

**Value range:****nnnnK**

The buffer size in kilobytes, where *nnnn* is a decimal number 1 - 9999.

**nnnnM**

The buffer size in megabytes, where *nnnn* is a decimal number 1 - 2047.

When the size is not specified, the system uses the component-defined default or, for some components, the size that is specified in a TRACE CT command.

The size that is specified for an installation-supplied application trace must be within the range that is specified on the CTRACE macro for the trace; see the programmer for the size value.

**JOBNAME(jobname-list)**

Specifies the names of jobs to be used as a filter for tracing. Events in these jobs are to be recorded by the component trace.

**Value range:** A list of 1 to 16 job names that are separated by commas. An empty job list, JOBNAME(), turns off filtering by jobs. In the JOBNAME parameter, list all jobs to be traced; jobs that are specified for previous traces are not traced unless listed.

**OPTIONS(options)**

Specifies component-specific options for tracing.

For the component options that support component tracing, see the topic on [Component trace in z/OS MVS Diagnosis: Tools and Service Aids](#).

**Value range:** A list of component-specific options with each option enclosed in quotation marks and the options that are separated by commas. For example:

```
OPTIONS('optionA','optionB','optionN')
```

The options for some IBM-supplied component traces can be changed while the trace is running; to change the options for others, stop the trace and restart it with the new options. An installation-supplied application trace, defined with MOD=YES in the CTRACE macro, can be changed while running.

The options for a head level defined with HEADOPTS=NO cannot be changed. When a head level that was defined with HEADOPTS=YES is changed, all of the sublevel traces currently in LIKEHEAD status will also be changed. Therefore, a change may cascade down a number of levels.

Omit OPTIONS to allow the component to use its default options.

**WTR(membername|DISCONNECT)**

Connects or disconnects the component trace external writer and the trace. The member name identifies the member that contains the source JCL that invokes the external writer. The *membername* in the WTR parameter must match the *membername* in the WTRSTART parameter.

WTR(DISCONNECT) disconnects the writer and the trace. The component continues tracing and placing the trace records in the address-space buffer, but stops passing trace records to the external writer.

You must also specify a WTRSTART or WTRSTOP parameter to start or stop the writer.

### LIKEHEAD

Specifies that the trace specified in the SUB parameter is to use the options that are defined to that sublevel trace's head level.

If you use the TRACE CT command to change a trace that is ON or OFF to LIKEHEAD, be aware of the following:

- The attributes of the sublevel trace must match the head level trace.
- The sublevel trace inherits the state (ON or OFF) and the options (ASID, JOBNAME, OPTIONS, and BUFSIZE) of the head level.
- The head level must have been defined with HEADOPTS=YES.

Component traces are defined by the IBM-supplied component; for components that use heads and subheads, see information about the component trace in *z/OS MVS Diagnosis: Tools and Service Aids*. Application traces are defined by the application using the CTRACE macro. For more information, see the documentation for the application.

### OFF

The system is to stop tracing for the component. If the component is connected to a component trace external writer, the system forces an implicit disconnect.

Some components do not stop tracing completely but reduce the tracing activity to the minimum required for serviceability data in a dump. An installation-supplied application trace reduces tracing to a minimum if the head level is defined with MINOPS. All sublevel traces with the LIKEHEAD attribute also reduce tracing to the minimum. Component trace writes a message to the operator when tracing is reduced to the minimum.

A head level defined with HEADOPTS=NO cannot be turned off.

When a head level defined with HEADOPTS=YES is turned off, all sublevel traces currently defined as LIKEHEAD are also turned off. An installation-supplied application trace can have head level and sublevel traces, if specified in the CTRACE macro that defined the trace.

### PRESET(DEFINE | DELETE)

#### DEFINE

Specifies that the component trace options established in the CTncccxx member are to be remembered until the component trace is defined. When a CTRACE macro later defines the trace, the preset information is used to set the options.

Use the PRESET parameter to set up the trace options in anticipation of a job entering the system or an address space being run. Later, when the CTRACE macro is invoked in the job or address space, the system overrides the tracing options set up at initialization and instead uses the options in the CTncccxx parmlib member with the PRESET.

The PRESET parameter is valid only in a parmlib member that is specified on the TRACE CT command; the PRESET parameter is ignored if specified from the CTRACE macro.

To use the preset options, a sublevel trace (SUB) can be defined as either ASID or JOBNAME. If there are both ASID and JOBNAME presets, the system uses only the ASID preset.

Once the information established through the preset is used for a trace, the preset no longer exists.

If you specified a valid preset and then a CTRACE macro is issued with a PARM option, the system ignores the information in the parmlib member specified by the CTRACE macro and, instead, uses the preset information. But, if your preset was not valid, the system will issue an

error message and then proceed to process the trace options that are specified on the CTRACE macro. The preset information is then deleted.

You can change the preset options by using the TRACE CT command with the PARM parameter and specifying PRESET(DEFINE) in the parmlib member.

### **DELETE**

Deletes the existing preset.

### **SUB(subname)**

Identifies a sublevel trace for a component or application with multiple traces. The *subname* is defined by the component or installation-supplied application.

If *subname* is a head level, all of the head's sublevel traces that are defined with a LIKEHEAD=YES parameter inherit the options that are specified in this parmlib member. Therefore, the options you specify for a head level can affect many sublevel traces.

If you specified the SUB parameter on the parmlib member to activate these trace options, the operator should not specify the SUB parameter on the TRACE CT command.

SUB(*subname*) cannot be specified in a parmlib member that is activated during system initialization.

The SUB parameter must be followed by a PRESET, ON, OFF, or LIKEHEAD parameter.

**Value range:** Specify the sublevel trace as it was defined through the CTRACE macro as a name, an ASID, or a job name.

**Default:** None

### **WTRSTART(membername){WRAP|NOWRAP}**

Identifies a member containing source JCL for a started task that the system uses to start the component trace external writer and to open the data sets that the writer uses.

You must also specify the WTR parameter.

#### **NOWRAP**

The system stops writing to the data set or sets when the data set or sets are full. If the WTRSTART parameter on the CTnccccxx parmlib member or TRACE CT command specifies NOWRAP, the system uses the primary and secondary extents of the data set or sets.

#### **WRAP**

When the system reaches the end of the data set or group of data sets, it writes over the oldest data at the start of the data set or the start of the first data set. If the WTRSTART parameter specifies WRAP or omits the parameter, the system uses only the primary extent or extents.

**Default:** WRAP

### **WTRSTOP(jobname)**

Identifies the name of the job for a currently running component trace external writer that the system is to stop. The system also closes the data sets the writer used. The *jobname* is either:

- Member name, if the source JCL is a procedure
- Job name, if provided on a JOB statement within the source JCL

You must also specify the WTR parameter. Otherwise, traces connected to the writer remain connected after the system stops it.

## Chapter 27. CUNUNIXx (Unicode Services environment)

CUNUNIXx contains information that Unicode services uses to define or change its environment. Through the use of the different statements, you can modify the environment in the following ways:

- Add, delete, or replace conversion tables, case support, normalize support, collation support and locale support to the Unicode environment.
- Specify the upper storage limit for pages to be used by conversion images.
- Identify the name of the conversion image to be selected.
- Delete an inactive conversion environment.

### Selecting a CUNUNIXx member

Select a CUNUNIXx parmlib member in one of the following ways:

- Specify the UNI keyword in IEASYSxx.
- Issue the SET UNI command after system initialization.

Two alphanumeric characters are appended to CUNUNI to form the name of the CUNUNIXx parmlib member. After initialization, you can issue the SET UNI command to change the CUNUNIXx member; however, this change is temporary. At the next IPL, the system uses the CUNUNIXx member specified in IEASYSxx. For information about IEASYSxx, see [Chapter 56, “IEASYSxx \(system parameter list\),” on page 421](#). For descriptions of the SET command, see [z/OS MVS System Commands](#).

### Parameter in IEASYSxx

```
UNI= {xx}
```

The two-character identifier (xx) is appended to CUNUNI to identify the CUNUNIXx member of SYS1.PARMLIB.

### Syntax rules for CUNUNIXx

These rules apply to the creation of CUNUNIXx:

- Use columns 1–71 to code statements.
- Comments must begin with "/\*" and end with "\*/".
- Comments can span statements.
- The keywords DELETE and IMAGE cannot be specified in the same member.

## Syntax format of CUNUNIxx

```

ADD FROM(xxxxx) TO(yyyyy) [TECHNIQUE|TECH(zzzzzzzz)]
[PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

ADD CASE([LOCAL|SPECIAL|NORMAL]) [UNIVER(univer)] [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

ADD NORMALIZE|NORM([UNI301|UNI320|UNI401|UNI410|UNI600]) [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

ADD COLLATE|COLL([UCAver]) [PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]
[[LOCALE(locale) [DSNAME(dsname)] [VOLUME|VOL(volser)]] |
[COLRULES(colrules) [DSNAME(dsname)] [VOLUME|VOL(volser)]]]

ADD IMAGE=zzzzzzzz [PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

ADD STRPROFILE=NAME [PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

ADD BLDLOCALE|BLDLOC=locname
[, CCSID(nnnnn)] [TECHNIQUE|TECH(zzzzzzzz)] [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

DELETE FROM(xxxxx) TO(yyyyy) [TECHNIQUE|TECH(zzzzzzzz)] FORCE(YES)

DELETE CASE([LOCAL|SPECIAL|NORMAL]) [, UNIVER(univer)] FORCE(YES)

DELETE NORMALIZE|NORM([UNI301|UNI320|UNI401|UNI410|UNI600]) FORCE(YES)

DELETE COLLATE|COLL([UCAver]) [[LOCALE(locale) | [COLRULES(colrules)]] , FORCE(YES)

DELETE STRPROFILE=NAME [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

DELETE BLDLOCALE|BLDLOC=locname [, CCSID(nnnnn)] [TECHNIQUE|TECH(zzzzzzzz)]

REPLACE FROM(xxxxx) TO(yyyyy) [TECHNIQUE|TECH(zzzzzzzz)] [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)] [FREE(NO| (YES, FORCE))]

REPLACE CASE([LOCAL|SPECIAL|NORMAL]) [, UNIVER(univer)] [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)] [FREE(NO| (YES, FORCE))]

REPLACE NORMALIZE|NORM([UNI301|UNI320|UNI401|UNI410|UNI600]) [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)] [FREE(NO| (YES, FORCE))]

REPLACE COLLATE | COLL([UCAver]) [PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]
[[LOCALE(locale) [DSNAME(dsname)] [VOLUME|VOL(volser)]] |
[COLRULES(colrules) [DSNAME(dsname)] [VOLUME|VOL(volser)]]]
[FREE(NO| (YES, FORCE))]

REPLACE STRPROFILE=NAME [PAGEFIX(YES|NO)] [DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

REPLACE BLDLOCALE|BLDLOC=locname [, CCSID(nnnnn)]
[TECHNIQUE|TECH(zzzzzzzz)] [PAGEFIX(YES|NO)]
[DSNAME|DSN(dsname)] [VOLSER|VOL(volser)]

REALSTORAGE([nnnnnn[K|M|G][])[:]]

DELETE INACTIVE[:]]

DELETE ALL, FORCE(YES)

```

## IBM-supplied default for CUNUNIxx

None.

## Statements and parameters for CUNUNIxx

**ADD BLDLOCALE|BLDLOC=locname[,CCSID(nnnnn)][,TECHNIQUE|TECH(zzzzzzzzzz)] [,PAGEFIX(YES|No)][,DSNAME|DSN(dsname)][,VOLSER|VOL(volser)]**

Adds locales to the Unicode environment.

### **locname**

Specifies the locale name to be added. The locale name is case-sensitive and is converted to uppercase unless it is specified inside single quotation marks.

### **nnnnn**

Specifies the CCSID of the locale to be added.

**zzzzzzzz**

Specifies the technique search order for the character conversion table to be added. zzzzzzzz is an eight-character alphanumeric field. The following values are valid:

- R - Roundtrip conversion
- E - Enforced Subset conversion
- C - Customized conversion
- L - Language Environment-behavior conversion
- M - Modified for special use conversion
- 0-9 - User-defined conversions

See *z/OS Unicode Services User's Guide and Reference* for additional information on techniques.

**Note:** You might get different results for different orders of the techniques placed in the zzzzzzzz field.

**dsname**

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must have similar characteristics as the SYS1.SCUNTB1 data set provided. The size of the data set can be unequal.

If no *dsname* is specified, SYS1.SCUNTB1 is used as the default.

**volser**

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from one- to six-characters.

**ADD CASE([LOCAL | SPECIAL | NORMAL])[UNIVER(*univer*)] [PAGEFIX(YES|NO)] [DSNAME | DSN(*dsname*)] [VOLSER | VOL(*volser*)]**

Adds the character case conversion tables to the Unicode environment. Local, Special, and Normal are optional and can be defined in the same statement only once.

**univer**

Specifies the Unicode standard version to be loaded. The following values are valid:

- UNI300
- UNI301
- UNI320
- UNI401
- UNI410
- UNI500
- UNI600

**dsname**

Specifies the name of the data set that contains the specific tables. The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB1. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB1 is used as the default.

**volser**

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**ADD COLLATE | COLL([UCAver])[PAGEFIX(YES|NO)] [DSNAME | DSN(*dsname*)] [VOLSER | VOL(*volser*)] [[LOCALE(*locale*)] [DSNAME(*dsname*)] [VOLUME|VOL(*volser*)] | [COLRULES(*colrules*)] [DSNAME(*dsname*)] [VOLUME|VOL(*volser*)]]]**

Adds the collation tables to the Unicode environment.

**UCAver**

Specifies the Unicode Collation Algorithm (UCA) versions. The following values are valid:

- UCA301
- UCA400R1
- UCA410
- UCA600

***dsname***

Specifies the name of the data set that contains the specific tables. The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB1. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB1 is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

***locale***

Specifies the local member name where collation rules are to be loaded.

***colrules***

Specifies the User Collation Rules (UCR) member name where collation rules are to be loaded.

**ADD FROM(*xxxxx*) TO(*yyyyy*) [TECHNIQUE | TECH(*zzzzzzzz*)] [PAGEFIX(YES|NO)][DSNAME | DSN(*dsname*)] [VOLSER | VOL(*volser*)]**

Adds specific tables to the Unicode environment.

***xxxxx***

Specifies the source CCSID of the character conversion tables to be added. *xxxxx* is a 1- through 5-character name that identifies the tables.

***yyyyy***

Specifies the target CCSID of the character conversion tables to be added. *yyyyy* is a 1- through 5-character name that identifies the tables.

***zzzzzzzz***

Specifies the technique search order for the character conversion tables to be removed. *zzzzzzzz* is a 1- through 8-character alphanumeric field. The following values are valid:

- R - Roundtrip conversion
- E - Enforced subset conversion
- C - Customized conversion
- L - Language Environment-behavior conversion
- M - Modified for special use conversion
- 0-9 - User-defined conversions

See [z/OS Unicode Services User's Guide and Reference](#) for additional information on techniques.

If no technique search order is specified, the default is RECLM.

**Note:** You might get different results for different orders of the techniques placed in the *zzzzzzzz* field.

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB1. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB1 is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.



**ADD IMAGE=zzzzzzzz[PAGEFIX(YES|NO)][DSNAME | DSN(*dsname*)][VOLSER | VOL(*volser*)]**

Adds an image to the Unicode environment, where the image is a member of the parmlib concatenation. If the image specified already exists in storage, the tables are not added.

**zzzzzzzz**

Specifies the name of the conversion image to be added. The image member specified must be present in SYS1.PARMLIB or in another data set in the logical parmlib concatenation. zzzzzzzz is an eight-character alphanumeric field.

**Value range:** Any valid z/OS member name.

When an image is loaded with the ADD,IMAGE statement, the existing tables in the Unicode environment are not replaced; only those tables that are not currently available in the Unicode environment are loaded from the image.

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBL. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTBL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**ADD NORMALIZE | NORM([*normver*])[PAGEFIX(YES|NO)][DSNAME | DSN(*dsname*)][VOLSER | VOL(*volser*)]**

Adds the normalization tables to the Unicode environment.

***normver***

Specifies the Unicode standard table version to be loaded. The following values are valid:

- UNI301
- UNI320
- UNI401
- UNI410
- UNI600

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBL. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTBL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**ADD STRPROFILE=NAME[,PAGEFIX(YES|NO)][,DSNAME | DSN(*dsname*)] [,VOLSER | VOL(*volser*)]**

Adds the profile to the Unicode environment.

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBL. The size of the data set can be decided according to users' requirements.

If no *dsname* is specified, SYS1.SCUNTBL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**DELETE mode**

Deletes partially or completely the Unicode environment.

**Value range:****ALL**

Delete the whole Unicode environment removing all control structures and tables from the environment. FORCE(YES) is required for this keyword.

**FORCE(YES)**

Specifies that the system will not check whether applications are currently using the tables. The storage that is occupied by the tables is returned to the system.

**INACTIVE**

Delete all the unreferenced control entries within the current Unicode environment and reorganize the Unicode environment to eliminate storage gaps in it. Specify the string literal INACTIVE.

Unreferenced control entries are entities that contain data of the current supported tables and can be obtained while replacing or deleting tables from the Unicode environment.

**DELETE CASE([LOCAL | SPECIAL | NORMAL])[UNIVER(*univer*)] FORCE(YES)**

Removes the character case conversion tables from the Unicode environment. LOCAL, SPECIAL, and NORMAL are optional and can be defined in the same statement only once.

***univer***

Specifies the Unicode standard version to be loaded. Valid values are:

- UNI300
- UNI301
- UNI320
- UNI401
- UNI410
- UNI500
- UNI600

**FORCE(YES)**

Specifies that the system does not check whether applications are currently using the tables. The storage that is occupied by the tables is returned to the system. FORCE(YES) is a required parameter.

**DELETE BLDLOCALE[BLDLOC=*locname*][CCSID(*nnnnn*)][TECHNIQUE|TECH(*zzzzzzzz*)]**

Deletes locales from the Unicode environment.

***locname***

Specifies the locale name to be deleted.

***nnnnn***

Specifies the CCSID of the locale to be deleted.

***zzzzzzzz***

Specifies the technique search order for the character conversion table to be deleted. *zzzzzzzz* is an eight-character alphanumeric field. Possible values are one or more of the following:

- R - Roundtrip conversion
- E - Enforced Subset conversion
- C - Customized conversion
- L - Language Environment-behavior conversion
- M - Modified for special use conversion
- 0-9 - User-defined conversions

See [\*z/OS Unicode Services User's Guide and Reference\*](#) for additional information on techniques.

**Note:** You might get different results for different orders of the techniques placed in the zzzzzzzz field.

### **DELETE COLLATE | COLL([UCAver])[LOCALE(locale)] | [COLRULES(colrules)], FORCE(YES)**

Removes the collation tables to the Unicode environment.

#### ***UCAver***

Specifies the Unicode Collation Algorithm (UCA) versions. The following values are valid:

- UCA301
- UCA400R1
- UCA410
- UCA600

#### ***locale***

Specifies the local member name where collation rules are to be loaded.

#### ***colrules***

Specifies the User Collation Rules (UCR) member name where collation rules are to be loaded.

#### **FORCE(YES)**

Specifies that the system does not check whether applications are currently using the tables. The storage that is occupied by the tables is returned to the system. FORCE(YES) is a required parameter.

### **DELETE FROM(xxxxx) TO(yyyyy) [TECHNIQUE | TECH(zzzzzzzz)] FORCE(YES)**

Remove specific tables from the Unicode environment.

#### ***xxxxx***

Specifies the source CCSID of the character conversion tables to be removed. xxxxx is a 1- through 5-character name that identifies the tables.

#### ***yyyyy***

Specifies the target CCSID of the character conversion tables to be removed. yyyyy is a 1- through 5-character name that identifies the tables.

#### ***zzzzzzzz***

Specifies the technique search order for the character conversion tables to be removed. zzzzzzzz is a 1- through 8-character alphanumeric field. The following values are valid:

- R - Roundtrip conversion
- E - Enforced subset conversion
- C - Customized conversion
- L - Language Environment-behavior conversion
- M - Modified for special use conversion
- 0-9 - User-defined conversions

See [\*z/OS Unicode Services User's Guide and Reference\*](#) for additional information on techniques.

If no technique search order is specified, the default is RECLM.

**Note:** You might get different results for different orders of the techniques placed in the zzzzzzzz field.

#### **FORCE(YES)**

Specifies that the system does not check whether applications are currently using the tables. The storage that is occupied by the tables is returned to the system. FORCE(YES) is a required parameter.

### **DELETE NORMALIZE | NORM([normver]) FORCE(YES)**

Removes the normalization tables from the Unicode environment.

#### ***normver***

Specifies the Unicode standard table version to be deleted. The following values are valid.

- UNI301
- UNI320
- UNI401
- UNI410
- UNI600

**FORCE(YES)**

Specifies that the system does not check whether applications are currently using the tables. The storage that is occupied by the tables is returned to the system. FORCE(YES) is a required parameter.

**DELETE STRPROFILE=NAME[,DSNAME|DSN(dsname)][,VOLSER | VOL(volser)]**

Removes the profile from the Unicode environment.

**dsname**

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB is used as the default.

**volser**

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**REALSTORAGE nnnnnn[K | M | G] [:]**

Defines the upper storage limit, in pages, to be used by the conversion environment. For information about the amount of storage that is required for a conversion environment, see [z/OS Unicode Services User's Guide and Reference](#).

**Value range:** 0 to 524287.

**Example:**

```
REALSTORAGE 0;      /* no explicit limit */
REALSTORAGE 12800; /* 50 MB limit */
```

**Notes:**

1. The request to load a new conversion environment is rejected when the value of the REALSTORAGE keyword is lower than the amount of storage needed.
2. The selection of 0 results in no limit.
3. The REALSTORAGE keyword is an optional parameter.

**REPLACE,BLDLOCALE|BLDLOC=locname[,CCSID(nnnnn)][,TECHNIQUE|TECH(zzzzzzzz)][,PAGEFIX(YES|No)][,DSNAME|DSN(dsname)][,VOLSER|VOL(volser)]**

Replaces locales in the Unicode environment.

**locname**

Specifies the locale name to be replaced.

**nnnnn**

Specifies the CCSID of the locale to be replaced.

**zzzzzzzz**

Specifies the technique search order for the character conversion table to be replaced. zzzzzzzz is an eight-character alphanumeric field. Possible values are one or more of the following:

**R**

Roundtrip conversion

**E**

Enforced subset conversion

**C**

Customized conversion

**L**

Language Element-behavior conversion

**M**

Modified for special use conversion

**0-9**

User-defined conversions

See *z/OS Unicode Services User's Guide and Reference* for additional information on techniques.

**Note:** You may get different results for different orders of the techniques placed in the zzzzzzzz field.

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must have similar characteristics as the SYS1.SCUNTBTL data set provided. The size of the data set can be unequal.

If no *dsname* is specified, SYS1.SCUNTBTL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from one- to six-characters.

**REPLACE CASE([LOCAL | SPECIAL | NORMAL])[UNIVER(*univer*)] [PAGEFIX(YES|NO)] [DSNAME | DSN(*dsname*)] [VOLSER | VOL(*volser*)] [FREE(NO | (YES,FORCE))]**

Replaces the character case conversion tables currently in the Unicode environment. LOCAL, SPECIAL, and NORMAL are optional and can be defined in the same statement only once.

***univer***

Specifies the Unicode standard version to be loaded. These values are possible:

- UNI300
- UNI301
- UNI320
- UNI401
- UNI410
- UNI500
- UNI600

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBTL. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTBTL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**FREE**

Specifies whether the storage associated with the table is to be released.

**NO**

Unicode will not release the storage associated with the table. When FREE is not specified, the default is NO.

**(YES,FORCE)**

Release the storage associated with the table. The system does not check whether applications are currently using the tables.

**REPLACE COLLATE | COLL([UCAver])[PAGEFIX(YES|NO)][DSNAME | DSN(dsname)][VOLSER | VOL(volser)][LOCALE(locale)][DSNAME(dsname)] [VOLUME|VOL(volser)] | [COLRULES(colrules) [DSNAME(dsname)] [VOLUME|VOL(volser)]] [FREE(NO | (YES,FORCE))]**

Replaces the collation tables currently in the Unicode environment.

***UCAver***

Specifies the Unicode Collation Algorithm (UCA) versions. These values are possible:

- UCA301
- UCA400R1
- UCA410
- UCA600

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

***locale***

Specifies the local member name where collation rules are to be loaded.

***colrules***

Specifies the User Collation Rules (UCR) member name where collation rules are to be loaded.

**FREE**

Specifies whether the storage associated with the table is to be released.

**NO**

Unicode will not release the storage that is associated with the table. When FREE is not specified, the default is NO.

**(YES,FORCE)**

Release the storage that is associated with the table. The system does not check whether applications are currently using the tables.

**REPLACE FROM(xxxxx) TO(yyyyy) [TECHNIQUE | TECH(zzzzzzzz)] [PAGEFIX(YES|NO)][DSNAME | DSN(dsname)] [VOLSER | VOL(volser)] [FREE(NO | (YES,FORCE))]**

Replaces specific tables that might be currently in the Unicode environment. If a table to be replaced is not in storage, the system adds the table.

***xxxxx***

Specifies the source CCSID of the character conversion tables to be replaced. xxxxx is a 1- through 5-character name that identifies the tables.

***yyyyy***

Specifies the target CCSID of the character conversion tables to be replaced. yyyyy is a 1- through 5-character name that identifies the tables.

***zzzzzzzz***

Specifies the technique search order for the character conversion tables to be removed. zzzzzzzz is a 1- through 8-character alphanumeric field. Possible values are one or more of the following:

- R - Roundtrip conversion
- E - Enforced subset conversion
- C - Customized conversion
- L - Language Environment-behavior conversion
- M - Modified for special use conversion
- 0-9 - User-defined conversions

See *z/OS Unicode Services User's Guide and Reference* for additional information on techniques.

If no technique search order is specified, the default is RECLM.

**Note:** You may get different results for different orders of the techniques placed in the zzzzzzzz field.

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBL. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTBL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**FREE**

Specifies whether the storage associated with the table is to be released.

**NO**

Unicode will not release the storage that is associated with the table. When FREE is not specified, the default is NO.

**(YES,FORCE)**

Release the storage that is associated with the table. The system does not check whether applications are currently using the tables.

**REPLACE NORMALIZE | NORM([*normver*])[PAGEFIX(YES|NO)][DSNAME | DSN(*dsname*)][VOLSER | VOL(*volser*)][FREE(NO | (YES,FORCE))]**

Replaces the normalization tables currently in the Unicode environment.

***normver***

Specifies the Unicode standard table version to be replaced. These values are possible:

- UNI301
- UNI320
- UNI401
- UNI410
- UNI600

***dsname***

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTBL. The size of the data set can be decided according to users' requirements.

If no *dsname* is specified, SYS1.SCUNTBL is used as the default.

***volser***

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

**FREE**

Specifies whether the storage associated with the table is to be released.

**NO**

Unicode will not release the storage that is associated with the table. When FREE is not specified, the default is NO.

**(YES,FORCE)**

Release the storage that is associated with the table. The system does not check whether applications are currently using the tables.

**REPLACE STRPROFILE=NAME[,PAGEFIX(YES|NO)][,DSNAME|DSN(dsname)] [,VOLSER | VOL(volser )]**

Replaces the current profile in the Unicode environment.

**dsname**

Specifies the name of the data set that contains the specific tables.

The specified *dsname* must contain the same features as the official tables repository, for example, the SYS1.SCUNTB1. The size of the data set can be decided according to users' requirements. If no *dsname* is specified, SYS1.SCUNTB1 is used as the default.

**volser**

Specifies the volume serial number of the device on which the tables are to be loaded. *volser* can be from 1- through 6-characters.

## Samples for parmlib member CUNUNIXx

Figure 10 on page 266 shows how to use the CUNUNI parmlib member to activate a new conversion environment.

```

/*****
/*
/* CUNUNIXX - UNICODE CONVERSION CONTROL PARAMETERS
/*
/*
/*****
/* ESTABLISH A NEW ENVIRONMENT
/*****
/* OPTIONAL KEYWORD REALSTORAGE
/* MAXIMAL USED PAGES OF REAL STORAGE, MIN=0 MAX=524288
/* WHERE 0 MEANS NO EXPLICIT LIMIT (=524288)
/*****
/*
REALSTORAGE 0;
/*
/*****
/* OPTIONAL KEYWORD ADD
/*****
/*
/* ADD SPECIFIC TABLES FOR CHARACTER CONVERSION SERVICE
/*
/*
ADD, FROM=1047 TO=1200, TECH=RECLM
/*
/* ADD CASE CONVERSION SERVICE
/*
/*
ADD CASE
/*
/* ADD COLLATION SERVICE
/*
/*
ADD COLL
/*
/* ADD NORMALIZATION SERVICE
/*
/*
ADD NORM
/*

```

Figure 10. Example: Activate a new conversion environment

Figure 11 on page 266 shows how to delete an inactive conversion environment.

```

/*****
/*
/* CUNUNIYY - UNICODE CONVERSION CONTROL PARAMETERS
/*
/*
/*****
/* delete
/* an unused inactive Unicode conversion environment
/*****
/* REQUIRED EXCLUSIVE KEYWORD
/* - NO OTHER KEYWORDS ARE ALLOWED
/*****
DELETE INACTIVE;

```

Figure 11. Example: Delete an inactive conversion environment



## Chapter 28. DEVSUPxx (device support options)

DEVSUPxx specifies the installation default for device support options. DEVSUPxx is processed during the NIP phase of IPL. After IPL, customers can use system command SET DEVSUP=XX or SET DEVSUP=(XX,YY,ZZ) to activate the DEVSUP changes.

If no installation default is provided through the DEVSUPxx member, and storing data in a compacted format is not explicitly requested on a DD statement, dynamic allocation request, the MOD= parameter on the JES3 \*CALL DJ command, or DCB macro, the system uses the compaction default for the device. For example, the compaction default for a 3480 is NOCOMP. To determine the compaction default for a particular device, see the planning or migration information that accompanies the device.

DEVSUPxx also specifies the installation default for the VOLID facility. The VOLID facility allows tape volumes written in 3480-2 XF (36-track) format and which are mounted on a tape drive not capable of reading this format to be relabeled by the OPEN or EOVL label editor routines. The label editor routines permit the relabel option only when RACF allows the user ALTER authority to the volume. The volume serial number passed to RACF is obtained from the VOLID mark written on the cartridge by the device, and placed in the sense data.

If no installation default for the VOLID facility VOLNSNS, is provided by using the DEVSUPxx member, the system assumes VOLNSNS=NO.

The MEDIAxx parameters of the DEVSUPxx parmlib member allow the customer to specify partitioning category codes. Library partitioning is the ability to partition volumes in an IBM tape library between different z/OS systems (or sysplexes). Partitioning allows each system (or sysplex) to limit its view of library volumes to only those volumes that it owns. This is accomplished when each system that is connected to a library use unique category codes. The DEVSUPxx category codes are read during IPL and the codes are stored into the SSVT (replacing the default category codes).

The IBM Redbooks publication *IBM TotalStorage 3494 Tape Library: A Practical Guide to Tape Drives and Tape Automation* (SG24-4632) lists all default Library Manager volume categories, the platforms on which they are used and their definitions. This book is available at [IBM Redbooks \(www.ibm.com/redbooks\)](http://www.ibm.com/redbooks).

DEVSUPxx also specifies the installation default for creating AL tapes. Use the ALVERSION keyword to specify whether AL tapes are created using the ISO/ANSI/FIPS Version 3 or ISO/ANSI Version 4 label standards. ALVERSION is also used to specify if the specified version level should override (force) the current Version 3 or Version 4 labels of an AL tape. ALVERSION is valid only if the AL tape data set is being opened for output processing to the first file of the first or only volume of the data set. Otherwise, the current AL version level of the tape will not be changed, even if force is specified. The default for ALVERSION is Version 3.

The TAPEAUTHxxx keywords in the DEVSUPxx parmlib member enable options for tape data set security. For more information, see [“Enhanced security for tape data sets” on page 267](#).

Use the DEVSERV QLIB,CATS command, which is documented in [z/OS MVS System Commands](#), to dynamically change the library partitioning category codes without IPL.

The EXPIRATION\_MESSAGE keywords in the DEVSUPxx parmlib member allow you to handle expiration date processing for the opening of any non-VSAM data set on DASD.

In previous releases, a subset of DEVSUPxx keywords was reset to the default values whenever a member was processed, unless the values were explicitly set in the member. This was true for some keywords, but not for all. Starting in z/OS V2R2, the current values of all keywords are preserved when a DEVSUPxx member is processed, unless the member explicitly specifies new values.

### Enhanced security for tape data sets

DFSMS provides additional security functions for tape data sets through the DEVSUPxx parmlib options. DFSMSdfp can now issue RACROUTE in the DATASET class to enable tape data sets to be authorized in

the same way that DASD data sets are authorized, regardless of the RACF SETROPTS in use on the system and regardless of the label types used. To enable all data sets on a tape volume or tape volume set to have the same or similar levels of authorization, DFSMSdftp provides a DEVSUPxx option to request that the users' authorization to a single data set on the volume can also extend to the entire volume. When you open a tape data set, DFSMSdftp can also check your authorization to the first file on the volume. The additional RACROUTE issued by DFSMSdftp depends on the DEVSUPxx keywords and the SETROPTS in use. When you select TAPEAUTHDSN=YES and TAPEAUTHF1=YES, the additional RACROUTE matches that issued for the TAPEAUTHDSN option. When you select TAPEAUTHDSN=NO, SETROPTS TAPEDSN, and TAPEAUTHF1=YES, the additional RACROUTE matches that issued for the SETROPTS TAPEDSN option. When all the data sets on a tape volume have a common or similar authorization requirement, an application program has less chance to gain access to unauthorized data by repositioning the tape to another data set.

The function in DFSMSdftp does not replace all the functional capabilities that the RACF TAPEDSN option, TAPEVOL class, and TVTOC provide. However, together with the functions that DFSMSrmm provides, you do have equivalent capability. The enhanced DFSMSdftp function addresses the authorization requirements for tape data sets and relies on your use of a tape management system such as DFSMSrmm to perform the following operations:

- Verify full 44 character data set names.
- Control the overwriting of existing tape files.
- Handle tape data set retention.
- Control the creation and destruction of tape labels.

When you overwrite an existing tape data set and use a different name, DFSMSdftp does not perform any authorization checking for the overwritten data set. However, when you set the TAPEAUTHF1=YES option, your tape management system can provide the data set name for any of the tape data sets causing additional RACROUTE authorization checks. DFSMSrmm exploits this capability to ensure that when the first file is overwritten, there is an additional RACROUTE issued for the overwritten data set. The tape management system controls how you can overwrite the existing tape data sets. See the DFSMSrmm MASTEROVERWRITE parmlib options for more information. Through your tape management system, you can ensure that DFSMSdftp checks the authorization of any overwritten data sets when the TAPEAUTHF1=YES DEVSUPxx parmlib option is in use.

To help you implement the new tape data set security function of DFSMSdftp, additional options allow access to tape data sets that either RACF does not protect or you are not authorized to access. The TAPEAUTHRC4 and TAPEAUTHRC8 options allow you this control. At CLOSE time, OPEN/EOV tracks the use of these options to change the results of RACF processing through SMF records 14 and 15.

You can now implement tape data set authorization checking whether the data set is on tape or DASD, regardless of tape volume profiles. You can use the following options for tape data set authorization:

- TAPEAUTHDSN keyword to cause RACROUTE to be issued in the DATASET class as if for a DASD data set. TAPEAUTHF1 optionally allows authorization checking for the first data set.
- SETROPTS TAPEDSN to cause RACROUTE to be issued in the DATASET class with DSTYPE=T. This optionally allows the use of TAPEVOL profiles with or without TVTOC, and optionally allows authorization check for the first data set using TAPEAUTHF1.
- Tape volume authorization only through TAPEVOL profiles.

For a complete list of the existing options, see [z/OS Security Server RACF Security Administrator's Guide](#).

## Parameter in IEASYSxx (or issued by the operator)

```
DEVSUP=    {aa }
           {(aa,bb...)}

```

The two alphanumeric characters (*aa*, *bb*, and so forth) are appended to DEVSUP to form the name of the DEVSUPxx member of SYS1.PARMLIB.

## Syntax rules for DEVSUPxx

The following rules apply to the creation of DEVSUPxx. [Figure 12 on page 269](#) shows an example of the syntax:

- Each DEVSUPxx parmlib member can contain any number of keyword entries. These entries are processed left to right, top to bottom.
- Comments can appear in columns 1-80 and must begin with /\*. After finding an opening comment delimiter, the rest of the line is ignored. Therefore, comments may appear as the only entry in a line, or following DEVSUPxx keywords, such as COMPACT and VOLNSNS. Comments cannot span more than one line. Multiple line comments can be included as a series of one-line comments, each starting with the opening comment delimiter.
- One or more blanks can precede or follow the statement types.
- Uppercase or lowercase letters can be used.
- The equal sign = between keywords and their values is mandatory. Intervening blanks are allowed between the keyword and the equal sign, and between the equal sign and the assigned value.
- Multiple lines are allowed, but every keyword entry must be complete on a single line. To specify continuation lines, a comma must be coded following the last entry on the line, without intervening blanks and before any comments on that record.
- Processing of the DEVSUPxx member terminates after the first line without a continuation. Any subsequent keywords or other text will be ignored.

```
COMPACT = YES, VOLNSNS = YES, MEDIA1 = 0011, MEDIA2 = 0012, MEDIA3 = 0013,
MEDIA4 = 0014,
MEDIA5 = 0015,
MEDIA6 = 0016,
MEDIA7 = 0017,
MEDIA8 = 0018,
MEDIA9 = 0019,
MEDIA10 = 001A,
MEDIA11 = 001B,
MEDIA12 = 001C,
MEDIA13 = 001D,
ERROR = 001E,
PRIVATE = 001F,
ALVERSION = FORCE3
```

Figure 12. Example: Syntax for DEVSUPxx

## Syntax format of DEVSUPxx

```
ALVERSION={3|4|FORCE3|FORCE4},
COMPACT={YES|NO},
COPYSDb={YES|SMALL|LARGE|INPUT|NO},
DDRSIZELIM={xxxx|xxxxM|1000M},
{ENABLE | DISABLE} feature,
ENFORCE_DC_MEDIA={ALLMEDIATY|MEDIA5PLUS},
EOSV2 {YES|NO},
ERROR=xxxx,
EXPIRATION_MESSAGE={NEVER|ALWAYS},
FLASHCOPYTOXRC={YES|NO},
GREATER_253={YES|NO},
ICKDSF_NODSEXIST={YES|NO},

ICKDSF_VERIFYOFFLINE={YES|NO},
JES3_ALLOC_ASSIST={YES|NO},
LRECCW_PER_EOSCP=xNN
MEDIAx=xxxx,
MTL_NO_DC_WORM_OK,

MULTINCRFLC={YES|NO},
NON_VSAM_XTIOT={YES|NO},
OCE_ABEND_DESCRIP={YES|NO},
PPRCSYMCONFIG = {YES|NO},
PRIVATE=xxxx,
```

```

REFUCB_FAIL={NONE|VARYOFF_RDEV}
SMF98_DATASET_ACTIVITY={YES|NO},
STAT011_PRESERVE_INDEX={YES|NO},
SUPPR_SMF19_DUMPCOND={YES|NO},
TAPEAUTHDSN = {YES|NO },
TAPEAUTHF1 = {YES|NO },
TAPEAUTHRC4 = {ALLOW|FAIL },
TAPEAUTHRC8 = {FAIL|WARN },
TAPEBLKSZLIM={nnnnn|nnnnnK|nnnnnM|nG},
TAPE_MULTI_VOLUME_ANOMALY={ALLOW|FAIL },
VOLNSNS={YES|NO}

```

## IBM-supplied defaults for DEVSUPxx

---

- DISABLE(AOM4961),
- DISABLE(FLASHCOPYTOGM),
- DISABLE(HPF\_FMTWRITE),
- DISABLE(HPF\_IMBEDDEDLR),
- DISABLE(HPF\_TTEDCW),
- DISABLE(PPRCMT),
- DISABLE(PPRCSUM),
- ENABLE(REFUCB),
- ENABLE(REFVTOC),
- ENABLE(SSR),
- DISABLE(TCTCOMPRESSION),
- DISABLE(VTOCPROT),
- DISABLE(VTOC\_USE\_ZHPF),
- ENABLE(ZERO\_DIR\_PDS),
- ALVERSION=3,
- COMPACT=NO,
- COPYSDS=INPUT,
- DDRSIZELIM=1000M,
- ENFORCE\_DC\_MEDIA=\*,
- EOSV2=NO,
- ERROR=000E,
- EXPIRATION\_MESSAGE=ALWAYS,
- FLASHCOPYTOXRC=NO,
- GREATER\_253=NO,
- ICKDSF\_NODSEXIST=NO,
- ICKDSF\_VERIFYOFFLINE=YES,
- JES3\_ALLOC\_ASSIST=NO,
- LRECCW\_PER\_EOSCP=00,
- MEDIA1=0001,
- MEDIA2=0002,
- MEDIA3=0003,
- MEDIA4=0004,
- MEDIA5=0005,
- MEDIA6=0006,
- MEDIA7=0007,

- MEDIA8=0008,
- MEDIA9=0009,
- MEDIA10=000A,
- MEDIA11=000B,
- MEDIA12=000C,
- MEDIA13=000D,
- MULTINCRFLC=YES,
- NON\_VSAM\_XTIOT=NO,
- PPRCSYCONFIG=NO,
- PRIVATE=000F,
- REFUCB\_FAIL=NONE,
- SMF98\_DATASET\_ACTIVITY=NO,
- STAT011\_PRESERVE\_INDEX=NO,
- SUPPR\_SMF19\_DUMPCOND=NO,
- TAPEAUTHDSN=NO,
- TAPEAUTHF1=NO,
- TAPEAUTHRC4=FAIL,
- TAPEAUTHRC8=FAIL,
- TAPEBLKSZLIM=32760,
- TAPE\_MULTI\_VOLUME\_ANOMALY=ALLOW,
- VOLNSNS=NO,

The values listed for MEDIA1, MEDIA2, MEDIA3, MEDIA4, MEDIA5, MEDIA6, MEDIA7, MEDIA8, MEDIA9, MEDIA10, MEDIA11, MEDIA12, MEDIA13, ERROR, and PRIVATE are IBM defaults. If you use DEVSUPxx to specify these values, they must match the IBM supplied defaults. For example, MEDIA1=0002 is invalid. If you want to specify category 0001, it must be MEDIA1.

## Statements and parameters for DEVSUPxx

---

### ALVERSION=

Specifies whether AL tapes are created that use Version 3 or Version 4 standards. In all cases, the Volume Mount (VOLMT) exit can override the version that is specified by ALVERSION. See [z/OS DFSMS Installation Exits](#) for more information about volume mounts.

**Restriction:** ALVERSION is valid only if the AL tape data set is being opened for output processing to the first file of the first or only volume of the data set.

#### 3

Specifies that new AL labels are written as ISO/ANSI/FIPS Version 3. The Version 3 and 4 labels that are current are preserved.

#### 4

Specifies that new AL labels are written as ISO/ANSI Version 4. The Version 3 and 4 labels that are current are preserved.

### FORCE3

Specifies that all AL labels are forced as ISO/ANSI/FIPS Version 3, including any current version 3 and 4 labels.

### FORCE4

Specifies that all AL labels are forced as ISO/ANSI Version 4, including any current version 3 and 4 labels.

**COMPACT=****NO**

Specifies that data is not to be stored in a compacted format on each 3480, 3490 or 359x tape subsystem, unless overridden by the user. If no installation default is provided through the DEVSUPxx member, and storing data in a compacted format is not explicitly requested on a DD statement, dynamic allocation request, the MOD=parameter on the JES3 \*CALL, DJ command, or DCB macro, then the system uses the compaction default for the device. For example, the compaction default for a 3480 is NOCOMP. To determine the compaction default for a particular device, see the planning or migration documentation that accompanies the device.

**YES**

Specifies that data is to be stored in a compacted format on each 3480, 3490, or 359x tape subsystem, unless overridden by the user.

**COPYSDB=**

Supplies the system-level default for the SDB keyword for IEBGENER. The system uses this value to set a code in the data facilities area (DFA) that any application program can use. See [z/OS DFSMSdfp Advanced Services](#). The keyword is designed for use by assembler language programs that copy data sets.

The meanings for the keyword values are described in [z/OS DFSMSdfp Utilities](#). The default is no code in the DFA, which means that IEBGENER assumes SDB=INPUT.

**Note:** The DFSORT ICEGENER function uses the DFSORT SDB installation value as its default. The IBM-supplied default is SDB=INPUT. See [z/OS DFSORT Installation and Customization](#) for details.

**DDRSIZELIM=**

Specifies the limit on storage usage for Tape DDR swap. The value xxxx is a number from 1 to 1000 and specifies the number of megabytes of main storage that is allowed to be used in a Tape DDR swap. The system stores this value in the data facilities area (DFA), for use by the system and by application programs. Tape DDR swap checks this value to make sure that the total amount of storage that is required in swap processing does not exceed the specified limit. If it does, DDR terminates the swap and prints an error message. The default value for this parameter is 1000 megabytes if there is a DEVSUPxx parmlib member found and either DDSIZELIM is not specified or it is specified with no value. If there is no DEVSUPxx parmlib member found at IPL time, DDSIZELIM is set to 0 MB.

**{ENABLE | DISABLE}(feature)**

Enables or disables a particular feature, where *feature* can be any one of the following choices:

**{HPF\_FMTWRITE|HPF\_IMBEDDEDLR|HPF\_TTEDCW}**

Enables or disables a zHPF feature. Use the option to disable a zHPF feature only at the direction of the system programmer or IBM service support.

**DISABLE(HPF\_FMTWRITE)**

Disable the zHPF Format Writes support.

**ENABLE(HPF\_FMTWRITE)**

Enable the zHPF Format Writes support.

**DISABLE(HPF\_IMBEDDEDLR)**

Disable the zHPF Embedded Locate Record support.

**ENABLE(HPF\_IMBEDDEDLR)**

Enable the zHPF Embedded Locate Record support.

**DISABLE(HPF\_TTEDCW)**

Disable the zHPF TCA Extension support.

**ENABLE(HPF\_TTEDCW)**

Enable the zHPF TCA Extension support.

**Default:** ENABLE(HPF\_FMTWRITE|HPF\_IMBEDDEDLR|HPF\_TTEDCW)

**TCTCOMPRESSION**

Enables or disables the transparent cloud tiering compression feature.

**ENABLE(TCTCOMPRESSION)**

Enables the transparent cloud tiering compression feature.

**DISABLE(TCTCOMPRESSION)**

Disables the transparent cloud tiering compression feature.

**Default:** DISABLE(TCTCOMPRESSION)

**AOM496I**

Enables or disables the issuing of the AOM496I status message on the console for transparent cloud tiering operations.

**ENABLE(AOM496I)**

When the AOM496I feature is enabled, the AOM496I status message for transparent cloud tiering operations is issued to the console.

**DISABLE(AOM496I)**

When the AOM496I feature is disabled, the AOM496I status message for transparent cloud tiering operation is not issued to the console.

**Default:** DISABLE(AOM496I)

**PPRCMT**

Enables or disables the Multi-Target PPRC support.

**DISABLE(PPRCMT)**

When the PPRCMT feature is disabled, functionality is in single target mode.

**ENABLE(PPRCMT)**

When the PPRCMT feature is enabled, support is available to allow a device to be the primary of more than one PPRC pair.

**Default:** DISABLE(PPRCMT)

**PPRCSUM**

Enables or disables the PPRCSUM feature of the Device Manager.

- If the PPRCSUM feature is enabled or disabled after IPL, one device in every control unit must be varied online to activate the feature.
- If Cascaded Incremental Resynchronization (CIR) is enabled in a cascaded PPRC relationship with PPRCSUM feature enabled, PPRCMT feature must also be enabled.

**DISABLE(PPRCSUM)**

When the PPRCSUM feature is disabled, PPRC suspends notification for individual devices is displayed in message IEA494I.

**ENABLE(PPRCSUM)**

Enables the PPRCSUM feature of the Device Manager. Message IEA075I is used instead of IEA494I to report devices that transition to PPRC suspended state. The PPRCSUM feature significantly reduces the volume of messages that are written to the console when devices in a PPRC relationship are suspended. If you enable PPRCSUM, the system issues an IEA075I message every five seconds or when the last device in the control unit was suspended to summarize the PPRC state for all devices in the control unit. This continues until all PPRC state transitions have completed.

If GDPS or other PPRC monitoring software is active, make sure that the appropriate version of this software is installed before you enable PPRCSUM.

**Default:** DISABLE(PPRCSUM)

**Restriction:** PPRCSUM is not supported for an MVS guest running under VM.

**REFUCB**

Enables or disables the automatic REFUCB function of the Device Manager:

**DISABLE(REFUCB)**

The system does not refresh the UCB when a DSS COPY, RESTORE, or ICKDSF FLASHCPY, INIT, or REFORMAT operation has changed either the volume serial number (VOLSER) or the volume table of contents (VTOC) location.

**ENABLE(REFUCB)**

The system automatically updates the UCB when the device support software detects that a DSS COPY, RESTORE, or ICKDSF FLASHCPY, INIT, or REFORMAT operation has changed either the VOLSER or VTOC location. The DEVMAN REFUCB service is invoked on each system in the sysplex that has REFUCB enabled.

- If the device is ONLINE, REFUCB issues a VARY ONLINE, UNCONDITIONAL command, which updates both the VOLSER or VTOC location in the UCB.
- If the device is OFFLINE, no action is taken.

**Default:** ENABLE(REFUCB)

**REFUCB\_FAIL = {NONE|VARYOFF\_RODEV}**

Specifies action to be taken when a failure occurs when refreshing the UCB.

**NONE**

If REFUCB\_FAIL=NONE is specified in the DEVSUP member, message IEA253I is displayed and no action is taken if the REFUCB failed to update the UCB. IEA253I DEVSUP REFUCB\_FAIL=NONE ACTION IS SET

**VARYOFF\_RODEV**

If REFUCB\_FAIL=VARYOFF\_RODEV is specified, message IEA253I message is displayed and the device is varied offline by REFUCB issuing the VARY OFFLINE command to the device. If the device cannot be varied offline, it is changed to a read-only volume.

**Default:** NONE.

**REFVTOC**

Enables or disables the automatic REFVTOC function of the Device Manager:

**DISABLE(REFVTOC)**

When the REFVTOC feature is disabled and the system detects a volume expansion, the system issues message IEA019I, but the VTOC is not rebuilt. An ICKDSF Batch job must be submitted to rebuild the VTOC before the newly added space on the volume can be used.

**ENABLE(REFVTOC)**

When the REFVTOC feature is enabled and the system detects a volume expansion, the system issues message IEA019I. If the volume is online, the Device Manager causes the volume VTOC to be rebuilt. This allows the newly added space on the volume to be used by the system.

**Default:** ENABLE(REFVTOC)

**SMF98\_DATASET\_ACTIVITY**

Enables or disables the generation of SMF type 98 subtype 5, 6, 7 and 8 records.

**YES**

Allows the generation of SMF type 98 subtype 5, 6, 7 and 8 records.

**Note:** Generating SMF type 98 subtypes 5-8 also requires that the Workload Interaction Correlator feature be enabled and SMF configured to collect SMF type 98 subtypes 5-8. For more information, see [Data Set Activity](#) in *z/OS DFSMS Using Data Sets*.

**NO**

Suppresses the generation of SMF type 98 subtype 5, 6, 7 and 8 records.

If SMF98\_DATASET\_ACTIVITY=YES is specified, the following message is logged:

```
IEA253I DEVSUP SMF TYPE(98(5:8)) RECORDS ARE GENERATED
```

If SMF98\_DATASET\_ACTIVITY=NO is specified, the following message is logged:



```
IEA253I DEVSUP SMF TYPE(98(5:8)) RECORDS ARE SUPPRESSED
```

If the keyword is not specified, no message is logged.

**Default:** NO.

## SSR

Enables or disables the secondary space reduction support of the Device Manager.

### DISABLE(SSR)

Disables the secondary space reduction support.

### ENABLE(SSR)

Enables the secondary space reduction support.

**Default:** ENABLE(SSR)

## SUPPR\_SMF19\_DUMPCOND=

Enables or disables the secondary space reduction support of the Device Manager.

### YES

Suppresses the generation of SMF type 19 records for the LSPACE command on dump conditioned volumes.

### NO

Allows the generation of SMF type 19 records for the LSPACE command on dump conditioned volumes.

If SUPPR\_SMF19\_DUMPCOND=YES is specified, the following message is logged:

```
IEA253I SMF SUBTYPE 19 RECORDS ARE SUPPRESSED FOR LSPACE ON DUMP CONDITIONED VOLUMES
```

If SUPPR\_SMF19\_DUMPCOND=NO is specified, the following message is logged:

```
IEA253I SMF SUBTYPE 19 RECORDS ARE GENERATED FOR LSPACE ON DUMP CONDITIONED VOLUMES
```

If the keyword is not specified, no message is logged.

**Default:** NO

## TCTCOMPRESSION

Enables or disables the transparent cloud tiering compression feature.

### ENABLE(TCTCOMPRESSION)

Enables the transparent cloud tiering compression feature.

### DISABLE(TCTCOMPRESSION)

Disables the transparent cloud tiering compression feature.

**Default:** DISABLE(TCTCOMPRESSION)

## ZERO\_DIR\_PDS

Enables or fails the allocation of a PDS with zero directory block that is defined in the JCL. If the ZERO\_DIR\_PDS keyword is not specified, no message is logged during IPL.

### ENABLE(ZERO\_DIR\_PDS)

Allow the allocation of PDS with zero directory block that is specified in the JCL explicitly or implicitly.

This option applies only to PDSs, and not to PDSEs.

You might want to allow creation of a PDS with no directory blocks even though you cannot use it as a PDS. You can cause a new data set to be a PDS by either:

- Coding DSORG=PO on the DD statement
- Coding a value for the number of directory blocks with the SPACE keyword on the DD statement even if the value is 0

Since the directory has no directory blocks, it begins with a file mark that serves as an end-of-file marker. If you now read it as a sequential data set, your program will successfully read nothing instead of getting an unpredictable result. This technique used to be a common way to read a sequential data set that had not been written in. If a program writes to this data set with BSAM or QSAM or with EXCP with DSORG=PS coded, then the system converts the data set from being a PDS to being a basic format sequential data set. This technique still works but it no longer is necessary because when you create a sequential data set and the DD statement has DSORG=PS or has no DSORG value or VSAM option, the system writes a file mark at the beginning. This ensures that you can read this null data set without error. The system programmer might disable this function by issuing this command: F DEVMAN,TRAPON(DONOTWRITEEOF).

There is another technique to get this ability of reading before anything is written. You can specify a nonzero secondary space amount with a zero primary space amount. If you specify DISABLE(ZERO\_DIR\_PDS) or F DEVMAN,TRAPON(DONOTWRITEEOF), you might be interfering with someone that is using this function to create a null sequential data set. You can advise that person that it no longer is beneficial to specify a PDS with no directory blocks.

A user might accidentally try to create a PDS with no directory blocks by coding DSORG=PO but forgetting to specify a number of directory blocks. If you specify DISABLE(ZERO\_DIR\_PDS), then it will be good that the system will catch this user error before wasting the user's time in diagnosing this PDS problem.

#### **DISABLE(ZERO\_DIR\_PDS)**

Fail the allocation of PDS with zero directory block that is specified in the JCL explicitly or implicitly.

**Default:** ENABLE(ZERO\_DIR\_PDS)

#### **VTOCPROT**

Enables or disables the VTOCPROT diagnostic function of the Device Manager.

##### **DISABLE(VTOCPROT)**

Disables the VTOCPROT diagnostic function.

##### **ENABLE(VTOCPROT)**

Enables the VTOCPROT diagnostic function. When the VTOCPORT feature is enabled, common channel programs driven by the EXCP driver are examined for format type commands targeting tracks within the VTOC. Only DSCB control blocks are allowed to be formatted to this area. If the format of the Key and Data are not the required size, the function forces a state save, and issues an ABEND xA1C, Reason Code = 7.

**Default:** DISABLE(VTOCPROT)

#### **VTOC\_USE\_ZHPF**

Specifies that you want the system to read or write VTOC DSCB records, using zHPF when it is available. You must have already specified ZHPF=YES on the ZHPF statement in the IECIOSxx parmlib member.

##### **ENABLE(VTOC\_USE\_ZHPF)**

Specifies that you want the system to read or write VTOC DSCB records, using zHPF when it is available and enabled. If you specify ENABLE(VTOC\_USE\_ZHPF) in either DEVSUPxx or by using the MODIFY DEVMAN command, the DFAVTOCHPF bit in the DFA control block is set on.

##### **DISABLE(VTOC\_USE\_ZHPF)**

Specifies that the system should not use zHPF to access the VTOC. If you specify or default to DISABLE(VTOC\_USE\_ZHPF) in either DEVSUPxx or by using the MODIFY DEVMAN command, the DFAVTOCHPF bit in the DFA control block is set off. CVAF will not use zHPF to access the VTOC.

#### **ENFORCE\_DC\_MEDIA**

Specifies whether data class media policies are enforced for stand-alone, non-specific mounts.

#### **ALLMEDIATY**

Enforces data class media policies for all stand-alone, non-specific mounts.

**MEDIA5PLUS**

Enforces data class media policies for all stand-alone, non-specific mounts for any of the 3592 tape cartridge media types.

**EOSV2=****NO**

For a device in PPRC relationship, Erase-On-Scratch issued a one-channel program to erase one track at a time until all tracks are erased.

**YES**

Erase-On-Scratch can erase up to 12,240 tracks in a single channel program, if the PPRC primary and secondary devices are maintained on the same level of microcode fix as shown in the following table.

| Machine type  | Microcode level |
|---------------|-----------------|
| DS8100/DS8300 | 64.36.89.0      |
| DS8700        | 76.31.70.0      |
| DS8800        | 86.31.86.0      |

**Default:** NO

**Note:** There is no IEA253I message logged for this option.

**EASYTIERHINTS=****NO**

Disables the Easy-Tier Copy Temperature function for software-defined storage. This option disables Query/Set Temperature functions that are used to direct data placement in the Disk Controller. NO is the default.

**YES**

Enables the Easy-Tier Copy Temperature function for software-defined storage. This option enables Query/Set Temperature functions that are used to direct data placement in the Disk Controller.

If the Easy-Tier Copy Temperature function for software-defined storage is enabled by setting EASYTIERHINTS=YES in the DEVSUPxx member of SYS1.PARMLIB, an IEA253I message is logged.

```
IEA253I  DEVSUP  EASY-TIER FOR SOFTWARE DEFINED STORAGE
```

If EASYTIERHINTS=NO is specified followed by issuing the SET DEVSUP=xx command to refresh the PARMLIB member, the IEA253I message is not logged.

If the Easy-Tier Copy Temperature function for software-defined storage is enabled by setting EASYTIERHINTS=YES in the DEVSUPxx member of the PARMLIB followed by an IPL of the system, the EASY-TIER FOR SOFTWARE DEFINED STORAGE status will be seen in the output of the F DEVMAN,REPORT console command. Refer to [z/OS MVS System Commands](#) for usage of the F DEVMAN,REPORT console command.

If the Easy-Tier Copy Temperature function for software-defined storage is disabled by issuing SET DEVSUP=XX with EASYTIERHINTS=NO in the PARMLIB member, the EASY-TIER FOR SOFTWARE DEFINED STORAGE status will not be seen in the output of the F DEVMAN,REPORT command.

**EXPIRATION\_MESSAGE=****ALWAYS**

Normal expiration date processing occurs when opening a non-VSAM data set on DASD. ALWAYS allows OPEN to process expiration date processing as it normally does. That is, OPEN issues message IEC507D and the optional associated TSO/E message IEC108I when any attempt is made to open for output a data set on DASD for which the expiration date has not yet occurred.

**Note:** This keyword does not affect data sets on magnetic tape even if you specify NEVER.

**NEVER**

Disables expiration date processing when a non-VSAM data set on DASD is opened. Set the parameter to NEVER if you want OPEN to disable expiration date processing when opening all non-VSAM data sets on DASD for output processing. Specifying NEVER eliminates the message IEC507D and the optional associated message IEC108I for all non-VSAM data sets on DASD. Therefore, any authorized user can open an expiration date protected non-VSAM DASD data set for output without requiring the operator to allow access.

**Default:** ALWAYS

**FLASHCOPYTOGM**

Enables or disables ANTRQST QFRVOLS, or similar APIs, reporting Global Mirror primary volumes as being FLASHCOPY capable.

**ENABLE(FLASHCOPYTOGM)**

For applications using the ANTRQST QFRVOLS, or similar APIs, to determine if Flashcopy can be used, the system will consider it acceptable to return Global Mirror primary volumes as FlashCopy capable.

**DISABLE(FLASHCOPYTOGM)**

For applications using the ANTRQST QFRVOLS, or similar APIs, to determine if FlashCopy can be used, the system will consider it unacceptable to return Global Mirror primary volumes as FlashCopy capable.

**Default:** DISABLE(FLASHCOPYTOGM)

**FLASHCOPYTOXRC****NO**

Disables support for Remote Pair FlashCopy for XRC environments.

**YES**

Enables support for Remote Pair FlashCopy for XRC environments.

At IPL, or when the SET DEVSUP=xx command is issued with FLASHCOPYTOXRC=YES in DEVSUPxx, this message is displayed:

```
IEA253I DEVSUP ALLOW REMOTE PAIR FLASHCOPY TO XRC
```

If FLASHCOPYTOXRC is not specified at all in DEVSUPxx, no messages are issued.

**GREATER\_253=****NO**

Specifies that in a system-managed tape environment, SMS on a scratch allocation request will retain its current tape subsystem (device pool) limit of 253.

**YES**

Specifies that in a system-managed tape environment, SMS on a scratch allocation request can return more than 253 tape subsystems (device pools) to MVS Allocation. Before enabling this support, ensure that all systems in the sysplex can support the increased limit (z/OS V2R2 or later or z/OS V1R13 and V2R1 with SMS APAR OA44354), otherwise jobs could incur abends.

For more information about tape subsystem limitations, see [Tape subsystem limitation](#) in *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries*.

**Default:** NO

**ICKDSF\_NODSEXIST=****NO**

Disables the ICKDSF NODSEXIST parameter as the default for the ICKDSF INIT command. If the NODSEXIST parameter is disabled and the device contains data sets, the ICKDSF INIT command is not terminated because data sets exist.

If ICKDSF NODSEXIST=NO is specified, an IEA253I message is logged at IPL or after a SET DEVSUP=xx command is issued.

**YES**

Enables the ICKDSF NODSEXIST parameter to be the default for the ICKDSF INIT command. If the NODSEXIST parameter is the default and the device contains data sets other than the VTOC index data set or VVDS, the command terminates and message ICK32179I is in the job output. See *Device Support Facilities (ICKDSF) User's Guide and Reference* for more details.

If ICKDSF\_NODSEXIST=YES is specified, an IEA253I message is logged at IPL or after a SET DEVSUP=xx command is issued.

**Default: NO**

**Note:** If an online INIT is attempted on a volume that has been initialized as an SMS-managed volume and data sets other than the VTOC index data set or VVDS exist, the command terminates and message ICK32177I is in the job output. See *Device Support Facilities (ICKDSF) User's Guide and Reference* for more details.

**ICKDSF\_VERIFYOFFLINE=****NO**

Disables the ICKDSF VERIFYOFFLINE parameter as default. If you want to make sure that the device is offline to all host systems, you must specify the VERIFYOFFLINE parameter.

**YES**

Enables the ICKDSF VERIFYOFFLINE parameter to be defaulted if all the following are true:

1. UNIT parameter is specified.
2. Storage control microcode support exists.
3. z/OS software support exists.
4. Device is not a minidisk.

If ICKDSF\_VERIFYOFFLINE=YES is specified, an IEAV253I DEVSUP ENABLED ICKDSF VERIFYOFFLINE PARAMETER DEFAULT message is also logged. If the keyword is not specified, no message is logged.

**Default: YES****JES3\_ALLOC\_ASSIST=****NO**

Specifies that the allocation assistance support (available with the TS7700 Virtualization Engine) is not to be used by JES3. JES3 scratch and specific allocation requests will continue to be directed to the single library image referred to as the composite library with no knowledge of the underlying clusters (distributed libraries).

**YES**

Specifies that the allocation assist support (available with the TS7700 Virtualization Engine) is being enabled for usage with JES3. With this support enabled, scratch allocations can be directed (through TS7700's management class policies) to specific clusters (distributed libraries) and specific allocations are directed to a preferred list of clusters (distributed libraries) returned by the library.

Before enabling this support refer to the setup steps in the "JES3 Considerations" section in *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries*. If you do not perform the setup before enabling this support, jobs might incur abends.

**Default: NO****LRECCW\_PER\_EOSCP=xNN****xNN**

A number from x01 - x030 equivalent to decimal 1 - 48 that indicates how many Locate Record Erase channel command words (CCWs) can be chained per channel program for the Erase-On-Scratch function. Each Locate Record Erase CCW can erase up to 255 tracks.

**Default:** LRECCW\_PER\_EOSCP=x30 or 48

If XRC is active on the device, the number of Logical Record Erase CCW per EOS channel program is fixed at 5 and cannot be changed.

#### **MTL\_NO\_DC\_WORM\_OK**

Specifies that you can use WORM tape in an MTL environment without a Dataclass specification for WORM. After the specification has taken effect, the only way to reverse it is to re-IPL the system without this keyword set.

#### **MULTINCRFLC(NO|YES)**

##### **NO**

Disables the Multiple Incremental FlashCopy or the Change Recording Version 2 function.

##### **YES**

Enables the Multiple Incremental FlashCopy or the Change Recording Version 2 function.

**Default:** YES.

If Multiple Incremental FlashCopy is enabled by installing the enablement OA45412 PTF followed by an IPL of the system, the MULTIPLE INCREMENTAL FLASHCOPY: CHANGE RECORDING V2 status will be seen in the output of the F DEVMAN,REPORT console command. Refer to [z/OS MVS System Commands](#) for information about the F DEVMAN,REPORT console command.

If Multiple Incremental FlashCopy is disabled by issuing SET DEVSUP=XX with MULTINCRFLC=NO in the DEVSUPxx parmlib member, the MULTIPLE INCREMENTAL FLASHCOPY: CHANGE RECORDING V2 status is not in the output of the F DEVMAN,REPORT command.

#### **NON\_VSAM\_XTIOT=**

##### **NO**

Disables support for XTIOT, uncaptured UCB, and DSAB control blocks that reside above the 16-megabyte line for data sets that use BSAM, QSAM, or BPAM. The default value for NON\_VSAM\_XTIOT is NO.

##### **YES**

Enables support for XTIOT, uncaptured UCB, and DSAB control blocks that reside above the 16-megabyte line for data sets that use BSAM, QSAM, or BPAM.

This option controls whether the access method OPEN macro supports these three options of the data set dynamic allocation function. Set NO if you are concerned that some programs, including installed products, might not correctly handle these options. You can set YES if all programs that might process data sets that were dynamically allocated by other programs can handle these options. Setting YES but not using these options has no effect on virtual storage or performance.

#### **OCE\_ABEND\_DESCRIPTION**

This keyword is checked for syntax but otherwise it is obsolete and has no effect. Its original purpose was to specify whether most error messages in the OPEN/CLOSE/EOV component would have additional information to explain the error. For more information about verbose messages, see [“Controlling verbose message production” on page 650](#).

##### **NO**

Specifies that OPEN, EOV, and CLOSE abend messages will not include a descriptive text for the associated numeric abend and numeric return code. To diagnose and respond to the messages, you might have to look up the codes.

##### **YES**

Specifies that abend messages for selected OPEN, EOV, and CLOSE determinant errors include descriptive text for the associated numeric abend code and numeric return code. This option can eliminate the need to look up the meanings of the abend and reason codes that are returned in the messages.

**Default:** NO

**PPRCSYMCONFG=****NO**

Specifies that the PPRC/Metro Mirror HyperSwap configuration is not symmetrical. This indicates that the same volume address is not used to identify primary and secondary volumes in a pair relationship.

**YES**

Specifies that the PPRC/Metro Mirror HyperSwap configuration is symmetrical. This indicates the same volume address is used to identify both primary and secondary volumes in a pair relationship.

**Default: NO**

A symmetrical logical configuration is a duplicate configuration where the Metro Mirror primary and secondary disk subsystems are configured with the same Logical Subsystem number (LSS) and Channel Connection Address (CCA) pairs. That is the PPRC primary and secondary devices have the same LSS and CCA in the local and remote storage controllers. These configurations are believed to be common as most clients configure Metro Mirror primary and secondary disk subsystems identically. An asymmetrical configuration has logical LSS and CCA numbers different between the local and remote sites.

**STAT011\_PRESERVE\_INDEX=****YES**

If CVAF returns a STAT011 error to its caller, the VTOC index is not disabled.

If STAT011\_PRESERVE\_INDEX=YES and RETRY(STAT011) are both specified in the DEVSUPxx member, DADSM allocation performs the following actions without disabling the VTOC index:

1. Detect the failure that is associated with IEC608I message and performs an SVC dump of DADSM with of the following diagnostic codes:

- 0820040B
- 0853040B
- 0854040B
- 0855040B

Those codes occur when the common VTOC access facility (CVAF) sets the status x0B (STAT011) while using an orphan Format-3 DSCB as a free Format-0 DSCB. If this situation is detected, the dump is not issued until later during VTOC validation process.

2. Use the VTOC validation function to determine the status of the orphan Format-3 DSCBs and other VTOC conditions. Examples of VTOC conditions are VTOC NOT CONVERTED, INCORRECT EXTENTS, or DUPLICATE F1 WITH SAME F3. The following message indicates that validation is entered. The validation does not reclaim any orphan Format-3 DSCBs.

```
IEC604I VTOC VALIDATE ENTERED ON DEVICE xxxx,volser ,----,DEVMAN
```

If there are DSCB-related errors, DSCBs, message IEC618\_ is displayed. If there are other VTOC errors, an IEC602I message may be issued. For example:

```
IEC618I ORPHAN FMT-3 DSCB,DEV=uuuu,volser,yy, (DSCBN0=xxxxxxx, DSCB=cccchhhrr)
```

```
IEC618E INCORRECT EXTENTS IN DSCB=cccchhhrr), DSN=Up to 44-byte datasetname
```

```
IEC618E Fn=cccchhhrr IS MULTIPLY POINTED BY MORE THAN ONE Fm DSCB
```

```
IEC618E INCORRECT F3s COUNT IN F9=cccchhhrr), DSN=Up to 44-byte datasetname
```

```
IEC602I VTOC NOT CONVERTED ON uuuu,volser, 0,(EXTENT=CCHHCCHH,DSCB=CCCCHHHRR-CCCCHHHRR)
```

Take a DEVMAN SVC dump of the current indexed VTOC. The dump will be presented as follows:

```
DUMP TITLE=VTOC VALIDATTION,VOLSER=volser, REASON=IEC6xxx,ERROR= errormessage-text. The
REASON=IEC6xxx will be REASON=IEC618I, REASON= IEC618E, or REASON= IEC602I.
```

*errormessage-text* will include one of the following reasons:

- ORPHAN FMT3 CHAIN
- ORPHAN FMT-3 DSCB
- INCORRECT EXTENTS IN DSCB
- ORPHAN F3 W/ INVALID DSCB
- F3/F9 IS MULTIPLY POINTED
- INCORRECT F3s COUNT IN F9
- OTHER VTOC ERRORS

If orphan Format-3 DSCB is the only type of error that is indicated by orphan Format-3 DSCB in message IEC618I, and if RETRY(STAT011) is activated in the system, the system will retry the allocation to use up one or two orphan Format-3 DSCB. The VTOC index is not disabled because STAT011\_PRESERVE\_INDEX=YES was specified. If RETRY(STAT011) is not activated, the system will not retry to use up ORPHAN FMT-3 DSCB. However, the failure will still not disable the VTOC index.

If another VTOC error (as shown in IEC618\_ and IEC602I with a different reason text such as ORPHAN FMT3 CHAIN or INCORRECT EXTENTS IN DSCB), is detected, the VTOC index is not disabled. The failure is issued with CVAF status code STAT011 regardless of whether RETRY(STAT011) is activated.

If the retry does not succeed, the following message is issued to confirm the error:

```
IEC603I VTOC ERRORS MAY EXIST ON uuuu,volser, 8
```

## NO

If CVAF returns a STAT011 error to its caller, the VTOC index may be disabled.

If STAT011\_PRESERVE\_INDEX=NO is activated, DADSM allocation performs the following actions in addition to disabling the VTOC index or converting it to OSVTOC:

- Internally detects the failure associated with IEC608I message followed by an SVC dump of DADSM with diagnostic codes: DIAG=0820040B, 0853040B, 0854040B, or 0855040B. Those codes are occur when CVAF sets status x0B(STAT011) when it uses an orphan Format-3 DSCB as a free Format-0 DSCB. The dump is not being issued until validation processing begins.
- A VTOC validation function determines the status of the orphan Format-3 DSCBs and other VTOC conditions. The following message is displayed to indicate that validation is entered.

```
IEC604I VTOC VALIDATE ENTERED ON DEVICE xxxx,volser,---,DEVMAN
```

- Message IEC618\_ is displayed for any errors about the DSCBs. If there are other VTOC errors, an IEC602I message may be issued. For example:

```
IEC618I ORPHAN FMT-3 DSCB,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx, DSCB=cccchhhrr)
```

```
IEC618E ORPHAN FMT3 CHAIN,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx, DSCB=cccchhhrr)
```

```
IEC618E INCORRECT EXTENTS IN DSCB=cccchhhrr, DSN=Up to 44-byte datasetname
```

```
IEC618E Fn=cccchhhrr IS MULTIPLY POINTED BY MORE THAN ONE Fm DSCB
```

```
IEC618E INCORRECT F3s COUNT IN F9=cccchhhrr, DSN=Up to 44-byte datasetname
```

```
IEC602I VTOC NOT CONVERTED ON uuuu,volser, 0, (EXTENT=CCHHCCHH,DSCB=CCCCHHHRR-CCCCHHHRR)
```



Take a DEVMAN SVC dump of the current indexed VTOC. For example:

```
DUMP TITLE=VTOC VALIDATION,VOLSER=volser, REASON=IEC6xxx,ERROR= errormessage-text
```

REASON=IEC6xxx will be REASON=IEC618I, REASON= IEC618E, or REASON= IEC602I.

The *error-message-text* will be one of the following reasons:

- ORPHAN FMT3 CHAIN
- ORPHAN FMT-3 DSCB
- INCORRECT EXTENTS IN DSCB
- ORPHAN F3 W/ INVALID DSCB
- F3/F9 IS MULTIPLY POINTED
- INCORRECT F3s COUNT IN F9
- OTHER VTOC ERRORS

If orphan Format-3 DSCB is the only type of errors indicated by ORPHAN FMT-3 DSCB in IEC618I, and if RETRY(STAT011) is activated in the system, the system will retry the allocation to use up one or at most two orphan Format-3 DSCB. It will not disable the index if the allocation is successful. If RETRY(STAT011) is not activated, the system will not retry to use up the orphan Format-3 DSCB. However, any VTOC failure will disable the VTOC index because STAT011\_PRESERVE\_INDEX=NO is used.

In addition to detecting the orphan Format-3 DSCBs (only 'ORPHAN FMT3 CHAIN' in IEC618I message) condition, if another VTOC error is detected as shown in IEC618E or IEC602I with a different reason text, the VTOC index will be disabled, and the system will call the CONVERT routine to convert to non-indexed VTOC(aka.OSVTOC).

An IEC608I message with reason code 24 is issued.

```
IEC608I DADSM FUNCTION DISABLED THE VTOC devn,volser, 24, CCHHR
```

Issue an IEC604I message before converting the disabled-index VTOC to non-indexed VTOC(OSVTOC) device.

```
IEC604I VTOC CONVERT ROUTINE ENTERED ON devn,volser, DI-0,DEVMAN
```

The CONVERT(IGG0425P) routine will attempt to reclaim the orphan DSCBs, and fix any space errors if possible.

The system will restart the allocation one more time on the non-indexed VTOC device.

**Tip:** After the disabled indexed VTOC is converted to OSVTOC, performance might be affected by a large VTOC or the increasing number data sets over time. If that is the case, use the ICKDSF program to convert the VTOC back to an indexed VTOC with the ICKDSF BUILDIX command. For example:

```
BUILDIX DDNAME(DDVOL) IX
```

If the keyword is not specified, no message is logged.

**Default:** NO

## RETRY(STAT011)

If the keyword is activated, DADSM allocation will perform the following actions:

1. Detect the failure with the IEC608I message followed by an SVC DADSM dump with diagnostic codes 0820040B, 0853040B, 0854040B, or 0855040B. They are the result of CVF setting status x0B(STAT011).

2. Take a DEVMAN SVC dump of the disabled-index VTOC and issue the IEC608I message with reason code 24.

```
IEC608I DADSM FUNCTION DISABLED THE VTOC devn,volser, 24,CCHHR
```

3. Issue the IEC604I message before converting the disabled-index VTOC to non-indexed VTOC(OSVTOC) device. For example:

```
IEC604I VTOC CONVERT ROUTINE ENTERED ON devn,volser, DI-0,DEVMAN
```

4. Restart the allocation one more time on the non-indexed VTOC device. Notice that the disabled indexed VTOC has been converted to OSVTOC. The performance may affect slightly if the number data sets is increased significantly over time. If that is the case, use ICKDSF program to convert the VTOC back to an indexed VTOC with the ICKDSF BUILDIX command:

```
BUILDIX DDNAME(DDVOL) IX
```

Refer to the STAT011\_PRESERVE\_INDEX keyword to see how the system behaves when the RETRY(STAT011) keyword is used with STAT011\_PRESERVE\_INDEX keyword.

The following two tables provide a summary of how these two keywords are combined together in the system.

Table 21. Without the RETRY(STAT011) DEVSUP keyword

| STAT011_PRESERVE_INDEX=NO   | STAT011_PRESERVE_INDEX=YES  |
|---|---|
| <p>This is existing behavior without this fix. It is also the default behavior similar to prior releases.</p> <ol style="list-style-type: none"> <li>1. Will not detect orphan DSCBs and will not validate VTOC during the time of the failure.</li> <li>2. Takes an SVC dump of the VTOC with the IEC608I message. This is a SVC dump, not a DEVMAN dump like specified in the other quadrants. The SVC dump is accompanied with DIAG=0820040B, 0853040B, 0854040B, or 0855040B. It is the result of CVAf setting status x0B(STAT011) when it uses an orphan Format-3 DSCB as a free Format-0 DSCB.</li> <li>3. The VTOC index is disabled and the job fails.</li> <li>4. The next access or allocation to the VTOC will cause VTOC convert routine to be entered and reclaimed the orphan DSCBs.</li> <li>5. An ICKDSF job must be executed by a system administrator with the option to convert back to indexed VTOC.</li> </ol> | <ol style="list-style-type: none"> <li>1. Detects orphan DSCBs and validates VTOC. This message is issued: <div data-bbox="873 296 1370 352" data-label="Text"> <pre>IEC604I VTOC VALIDATE ENTERED ON DEVICE xxxx,volser,----,DEVMAN</pre> </div> <p>Message IEC618_ is displayed for any errors about the DSCBs. If there are other VTOC errors, the IEC602I message may be issued.</p> <div data-bbox="873 478 1435 531" data-label="Text"> <pre>IEC618I ORPHAN FMT-3 DSCB,DEV=uuuu,volser,yy (DSCBNO=xxxxxxxx,DSCB=ccccchhrr)</pre> </div> <div data-bbox="873 569 1446 621" data-label="Text"> <pre>IEC618E ORPHAN FMT3 CHAIN,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx,DSCB=ccccchhrr)</pre> </div> <div data-bbox="873 659 1446 709" data-label="Text"> <pre>IEC618E INCORRECT EXTENTS IN DSCB=ccccchhrr,DSN=Up to 44-byte datasetname</pre> </div> <div data-bbox="873 747 1435 798" data-label="Text"> <pre>IEC618E Fn=ccccchhrr IS MULTIPLY POINTED BY MORE THAN ONE Fm DSCB</pre> </div> <div data-bbox="873 835 1422 888" data-label="Text"> <pre>IEC618E INCORRECT F3s COUNT IN F9=ccccchhrr,DSN=Up to 44-byte datasetname</pre> </div> <div data-bbox="873 926 1430 978" data-label="Text"> <pre>IEC602I VTOC NOT CONVERTED ON uuuu,volser,0, (EXTENT=CCHCCHH,DSCB=CCCCHHHRR-CCCCHHHRR)</pre> </div> </li> <li>2. Take DEVMAN DUMP:DUMP TITLE=VTOC VALIDATION,VOLSER=volser,REASON=IEC6xxx,ERROR= error-message-text. <p>The IEC6xxI reason will be IEC618I, IEC618E, or IEC602I.</p> <p>The error-message-text will be one of the following reasons:</p> <pre>ORPHAN FMT3 CHAIN ORPHAN FMT-3 DSCB INCORRECT EXTENTS IN DSCB ORPHAN F3 W/ INVALID DSCB F3/F9 IS MULTIPLY SUPPORTED INCORRECT F3s COUNT IN F9 OTHER VTOC ERRORS</pre> </li> <li>3. Will fail because it's not attempting to retry on orphan DSCBs because the keyword RETRY(STAT011) is not used. Since the VTOC index is to be preserved, the VTOC convert routine will not be entered to clean up orphan DSCBs.</li> <li>4. An ICKDSF job needs to be executed by a system administrator with REFVTOC option to clean the orphan DSCBs.</li> </ol> |

Table 22. With the RETRY(STAT011) DEVSUP keyword

| STAT011_PRESERVE_INDEX=NO   | STAT011_PRESERVE_INDEX=YES   |
|---|--|
| <p>1. Detect orphan DSCBs and validate VTOC.</p> <p>Issue these messages:</p> <pre>IEC604I VTOC VALIDATE ENTERED ON DEVICE xxxx,volser,----,DEVMAN</pre> <p>Message IEC618_ is displayed for any errors about the DSCBs. If there are other VTOC errors, the IEC602I message may be issued.</p> <pre>IEC618I ORPHAN FMT-3 DSCB,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx,DSCB=cccchhhrr)</pre> <pre>IEC618E ORPHAN FMT3 CHAIN,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx,DSCB=cccchhhrr)</pre> <pre>IEC618E INCORRECT EXTENTS IN DSCB=cccchhhrr,DSN=Up to 44-byte datasetname</pre> <pre>IEC618E Fn=cccchhhrr IS MULTIPLY POINTED BY MORE THAN ONE Fm DSCB</pre> <pre>IEC618E INCORRECT F3s COUNT IN F9=cccchhhrr,DSN=Up to 44-byte datasetname</pre> <pre>IEC602I VTOC NOT CONVERTED ON uuuu,volser,0, (EXTENT=CCHHCCHH,DSCB=CCCCHHHRR-CCCCHHHRR)</pre> <p>2. Take DEVMAN DUMP: DUMP TITLE=VTOC.</p> <pre>VALIDATION,VOLSER=volser,REASON=IEC6xxx,ERROR =error-message-text</pre> <p>The IEC6xxI reason will be IEC618I, IEC618E, or IEC602I.</p> <p>The <i>error-message-text</i> will be one of the following reasons:</p> <ul style="list-style-type: none"> <li>ORPHAN FMT3 CHAIN</li> <li>ORPHAN FMT-3 DSCB</li> <li>INCORRECT EXTENTS IN DSCB</li> <li>ORPHAN F3 W/ INVALID DSCB</li> <li>F3/F9 IS MULTIPLY SUPPORTED</li> <li>INCORRECT F3s COUNT IN F9</li> <li>OTHER VTOC ERRORS</li> </ul> <p>3. Will retry on the orphan DSCB because the keyword RETRY(STAT011) is used.</p> <p>If orphan Format-3 DSCB is the only type of error indicated by ORPHAN FMT-3 DSCB in IEC618I, the system will retry the allocation to use up one or at most two orphan format-3 DSCBs, and will disable the VTOC index because STAT011_PRESERVE_INDEX=NO. If the retry fails, it will disable index and convert to OSVTOC to retry allocation once more. It will reclaim the orphan DSCBs.</p> | <p>1. Detect orphan DSCBs and validate VTOC. This message is issued:</p> <pre>IEC604I VTOC VALIDATE ENTERED ON DEVICE xxxx,volser,----,DEVMAN</pre> <p>Message IEC618_ is displayed for any errors about the DSCBs. If there are other VTOC errors, the IEC602I message may be issued.</p> <pre>IEC618I ORPHAN FMT-3 DSCB,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx,DSCB=cccchhhrr)</pre> <pre>IEC618E ORPHAN FMT3 CHAIN,DEV=uuuu,volser,yy, (DSCBNO=xxxxxxxx,DSCB=cccchhhrr)</pre> <pre>IEC618E INCORRECT EXTENTS IN DSCB=cccchhhrr,DSN=Up to 44-byte datasetname</pre> <pre>IEC618E Fn=cccchhhrr IS MULTIPLY POINTED BY MORE THAN ONE Fm DSCB</pre> <pre>IEC618E INCORRECT F3s COUNT IN F9=cccchhhrr,DSN=Up to 44-byte datasetname</pre> <pre>IEC602I VTOC NOT CONVERTED ON uuuu,volser,0, (EXTENT=CCHHCCHH,DSCB=CCCCHHHRR-CCCCHHHRR)</pre> <p>2. Take DEVMAN DUMP: DUMP TITLE=VTOC</p> <pre>VALIDATION,VOLSER=volser,REASON=IEC6xxx,ERROR =error-message-text</pre> <p>The <i>error-message-text</i> will be one of the following reasons:</p> <ul style="list-style-type: none"> <li>ORPHAN FMT3 CHAIN</li> <li>ORPHAN FMT-3 DSCB</li> <li>INCORRECT EXTENTS IN DSCB</li> <li>ORPHAN F3 W/ INVALID DSCB</li> <li>F3/F0 IS MULTIPLY POINTED</li> <li>INCORRECT F3s COUNT IN F9</li> <li>OTHER VTOC ERRORS</li> </ul> <p>3. Will retry on the orphan DSCB because the keyword RETRY(STAT011) is used.</p> <p>If orphan Format-3 DSCB is the only type of error indicated by ORPHAN FMT-3 DSCB in IEC618I, and since RETRY(STAT011) is used, the system will retry the allocation to use up one or at most two orphan format-3 DSCB, and will not disable the VTOC index because STAT011_PRESERVE_INDEX=YES. If the retry fails, it will not disable index and will not convert to OSVTOC to retry to reclaim the orphans.</p> <p>4. An ICKDSF job needs to be executed by a system administrator with REFVTOC option to clean the orphan DSCBs.</p> |

**TAPEAUTHDSN=****NO**

Indicates that OPEN processing to issue RACROUTEs based on the options set in RACF such as SETROPTS TAPEDSN and SETROPTS CLASSACT(TAPEVOL).

**YES**

Enables tape authorization checks in the DATASET class but without DSTYPE=T. All tape data set names created are RACF-protected.

DSTYPE=T indicates to RACF that the check is for data set on a tape volume and that special RACF tape data set and a tape volume processing is to be performed. Without DSTYPE=T RACF authorization checking considers only profiles in the DATASET class.

The system uses the data set name that is specified in the allocation or JCL to check your authorization to read or write the specified file.

In addition, the system determines the RACF erase-on-scratch setting from the RACF profile and passes it to your tape management system.

Use this option only when you have a tape management system, such as DFSMSrmm, installed and actively checking that the 44 character data set name that is specified by the user matches the data set name on tape. Without a tape management system, tape data set open processing can only validate the last 17 characters of the data set name against the tape volume labels.

When you request bypass label processing (BLP) and the mounted volume uses standard labels, OPEN issues the authorization check that the user is authorized to use BLP. This processing uses the existing ICHBLP resource in the RACF FACILITY class. When you specify TAPEAUTHDSN=YES only, it replaces the check that RACF makes as part of tape volume authorization checking.

**Default:** NO

**TAPEAUTHF1=****NO**

Disables additional tape authorization checks in the DATASET class for existing files on the same tape volume when any other file on the tape volume is opened. The default value is NO.

**YES**

Enables additional tape authorization checks in the DATASET class for existing files on the same tape volume when any other file on the tape volume is opened. This function depends on the tape management system returning the 44 character data set name and data set sequence number to OPEN/EOV through the IFGTEP during the Volume Mount exit Volume Security function; if no data set name is returned by the tape management system, processing is as if this keyword had not been specified.

Although intended to enable an additional authorization check for the first data set when any other data set on the tape volume is opened, the implementation allows your tape management system to request one or more additional authorization checks when any data set on a tape volume is opened. Each additional data set name and data set sequence number returned results in an additional RACROUTE. Do not use this function unless you have a tape management system and it can return a data set name and data set sequence number. A data set sequence number is the label number that is normally specified in the JCL LABEL keyword and stored in the catalog.

When TAPEAUTHDSN=YES is in use, any additional RACROUTE matches that issued for TAPEAUTHDSN except for the data set name and data set sequence number. Otherwise, TAPEAUTHF1 uses a RACROUTE that matches that used for SETROPTS TAPEDSN. When neither TAPEAUTHDSN nor SETROPTS TAPEDSN is in use, TAPEAUTHF1 support is not provided.

**TAPEAUTHRC4=**

This applies to authorization checks in the DATASET class, and applies only to the results of TAPEAUTHDSN=YES and TAPEAUTHF1=YES processing.

**ALLOW**

Allows accessing of data sets that are not protected by a security profile. RC4 refers to the return code value of 4 returned from SAF as a result of the RACROUTE issued by OPEN/CLOSE/EOV. A return code of 4 in general means that the resource is not protected.

**FAIL**

Denies accessing of data sets that are not protected by a security profile. TAPEAUTHRC4=FAIL and TAPEAUTHDSN=YES together ensure that all tape data set names created including temporary names that are generated by the tape system are RACF-protected.

**Default:** FAIL

Use this keyword to control PROTECTALL processing for tape data sets. This applies to the results of RACROUTE processing when both TAPEAUTHDSN=YES and when TAPEAUTHF1=YES are specified.

**TAPEAUTHRC8=**

Provides a managed and controlled implementation of tape authorization checks in the DATASET class, and applies only to the results of TAPEAUTHDSN=YES and TAPEAUTHF1=YES processing. This keyword is provided as an aid to the implementation of TAPEAUTHDSN and TAPEAUTHF1.

**FAIL**

Denies accessing of data sets that typically cannot be accessed.

**WARN**

Allows accessing of data sets that typically cannot be accessed. RACF issues an ICH408I message to indicate why access is not allowed; however OPEN/EOV allows access.

**Default:** FAIL

**TAPEBLKSZLIM=**

Specifies the default block size limit for the system to use when a user omits the block size limit on a DD statement for a tape data set and the data class does not supply one. The system stores this value in the DFA (data facilities area), for use by the system and by application programs. See [z/OS DFSMSdfp Advanced Services](#). The system uses this value only in cases when all of the following statements are true.

- An application program uses the large block interface (LBI) of BSAM or QSAM to open a tape data set for output without DISP=MOD. Check the information for the program; if its maximum block size is 32760 or less, or it cannot write to tape, the program probably does not use the LBI.
- The BLKSIZE (block size) value is omitted from all sources.
- The DD statement or dynamic allocation equivalent and the data class do not specify a BLKSZLIM value.

**Restriction:** DFSMSdss only supports BLKSZLIM of 65,520 and larger.

An application program that uses EXCP can take this value from the DFA.

If you code K, M, or G at the end of the number, the system multiplies the number by 1024, 1,048,576 or 1,073,741,824 respectively. The minimum values are 32760 when specified in bytes, 32 K when specified in kilobytes, 1 M when specified in megabytes, and 1G when specified in gigabytes. The maximum values are 2147483648, 2097152 K, 2048 M, and 2 G. These maximum block size values are much larger than the system supports for BLKSIZE. However, coding a large value allows the system to choose the largest optimal block size for the device.

The default for this parameter is 32760. Do not code a value that exceeds 32760 in DEVSUPxx if both of the following statements are true:

- Your system has a job that writes on tape using the large block interface and the job does not supply a value for BLKSIZE or BLKSZLIM. Programs that use the large block interface include IEBGENER, ICEGENER, DFSORT, and programs that are compiled with COBOL for OS/390 and VM Version 2 Release 2.
- The tapes with a large block size might be read on a level of MVS that precedes OS/390 Version 2 Release 10 or might be read on another type of system that does not support such large blocks. OS/400® supports large blocks.

**TAPE\_MULTI\_VOLUME\_ANOMALY=**

Specifies how the system handles any multivolume tape label anomaly condition that is not yet resolved after the Label Anomaly exit is called. This keyword is processed at IPL time, but can be changed by the operator using SET DEVSUP=xx.

If the Label Anomaly exit sets return code 12, it is honored and in all cases it fails the request, overriding the DEVSUPxx setting.

#### **ALLOW**

Use this setting to allow applications to process multi-volume tape data sets even when the volume set is incomplete or in the wrong sequence.

#### **FAIL**

Use this setting to prevent applications from processing multi-volume tape data sets when the volume set is incomplete or in the wrong sequence.

**Default:** ALLOW.

When a request is failed, either by the Label Anomaly exit return code 12, or by the FAIL option, the System Completion Codes are: 413-58 (OPEN RDBK), 413-5C (OPEN FIRST), 637-B4 (EOV OUTSEQ), and 637-B8 (EOV LAST).

DFSMSrmm attempts to recover from errors that are noted in the label anomaly exit using the volume sequence information that is recorded in the DFSMSrmm control data set (CDS). Based on information that is returned by DFSMSrmm, OPEN, and EOV processing attempts to resolve the error by updating the volume list in the job file control block (JFCB) and any JFCB extensions.

Tape users can bypass the system multivolume tape label anomaly processing by specifying OPTCD=B in the JCL. For more information about the considerations using OPTCD=B, see the topic [Determining volume switch](#) in these references:

- [z/OS DFSMS Using Magnetic Tapes](#)
- [z/OS MVS JCL User's Guide](#)
- [z/OS MVS JCL Reference](#)

The tape application can optionally recover from a tape label anomaly failure by providing a DCB abend exit for the applications' DCB. When the application DCB abend exit requests recovery, the missing or out of sequence volume condition is ignored.

#### **VOLNSNS=**

##### **NO**

Specifies that tape cartridges written at track capacities that the drive is not capable of reading (for example, a 36-track cartridge on a D/T3480, or a 256-track cartridge on a D/T3590 Model B1x), are not allowed to be relabeled. Attempts to relabel the cartridges are rejected when RACF protection for tape volumes is active. If no installation default for the VOLID facility VOLNSNS is provided by using the DEVSUPxx member, the system assumes VOLNSNS=NO.

##### **YES**

Specifies that tape cartridges written at track capacities that the drive is not capable of reading. For example, it specifies that a 36-track cartridge on a D/T3480 or a 256-track cartridge on a D/T3590 Model B1x is to be relabeled at the device-capable track capacity by the OPEN or EOV label editor routines. This relabel editor option is permitted only if the user is RACF-authorized to the volume. The volume serial number that is passed to RACF is obtained from the VOLID mark that is written on the cartridge by the device and placed in the sense data.

## **Volume partitioning parameters**

Each volume inside an SMS-managed tape library is assigned a 2-byte Library Manager category number that is based on the use attribute of the volume and the media type. The IBM Tape Library Manager category numbers are used by the operating system to group tape volumes together for specific purposes. Currently, DFSMS uses the following fixed set of category numbers:

#### **X'0001'**

All 3490 standard capacity (CST) scratch cartridges.

#### **X'0002'**

All 3490 enhanced capacity (ECST) scratch cartridges.

**X'0003'**

All 3590 high performance scratch cartridges.

**X'0004'**

All 3590 high performance scratch cartridges.

**X'0005'**

3592 Enterprise Tape Cartridge scratch cartridges.

**X'0006'**

3592 Enterprise WORM Tape Cartridge scratch cartridges.

**X'0007'**

3592 Enterprise Economy Tape Cartridge scratch cartridges.

**X'0008'**

3592 Enterprise Economy WORM Tape Cartridge scratch cartridges.

**X'0009'**

3592 Enterprise Extended Tape Cartridge scratch cartridges.

**X'000A'**

3592 Enterprise Extended WORM Tape Cartridge scratch cartridges.

**X'000B'**

3592 Enterprise Advanced Tape Cartridge scratch cartridges.

**X'000C'**

3592 Enterprise Advanced WORM Tape Cartridge scratch cartridges.

**X'000D'**

3592 Enterprise Advanced Economy Tape Cartridge scratch cartridges.

**X'000E'**

The ERROR category. Used for tape volumes for which the system has detected an error. Tape volumes are added to this category to prevent them from being mounted in response to a 'scratch' tape mount.

**X'000F'**

The PRIVATE category.

Library partitioning is the ability to partition volumes in an IBM tape library between different z/OS systems (or sysplexes). Partitioning allows each system (or sysplex) to limit its view of library volumes to only those volumes that it owns. Partitioning is accomplished when each system connected to a library uses unique category codes. DEVSUPxx parameters are used to specify category codes that replace the default system codes.

The following DEVSUPxx parameters are used to specify category codes for library partitioning:

**MEDIA1=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3490 standard capacity (CST) scratch category code.

**MEDIA2=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3490 enhanced capacity (ECST) scratch category code.

**MEDIA3=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3590 high performance cartridge tape scratch category code.

**MEDIA4=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3590 high performance cartridge tape scratch category code.

**MEDIA5=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Tape Cartridge scratch category code.



**MEDIA6=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise WORM Tape Cartridge scratch category code.

**MEDIA7=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Economy Tape Cartridge scratch category code.

**MEDIA8=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Economy WORM Tape Cartridge scratch category code.

**MEDIA9=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Extended Tape Cartridge scratch category code.

**MEDIA10=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Extended WORM Tape Cartridge scratch category code.

**MEDIA11=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Advanced Tape Cartridge scratch category code.

**MEDIA12=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Advanced WORM Tape Cartridge scratch category code.

**MEDIA13=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the 3592 Enterprise Advanced Economy Tape Cartridge scratch category code.

**ERROR=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the error category code.

**PRIVATE=xxxx**

xxxx specifies a 2-byte hexadecimal value to be used as the private category code.

**Note:** xxxx must be a 4-character hexadecimal value within the range 0000-FEFF.



---

## Chapter 29. DFHSSIxx (message-formatting initialization member)

You can use the DFHSSIxx parmlib member to specify message-formatting initialization parameters for the CICS subsystem of the SYS1.PARMLIB library, where xx is the suffix that identifies the SYS1.PARMLIB member used to define the CICS subsystem. For more information about console message handling, see [CICS Transaction Server for z/OS \(www.ibm.com/docs/en/cics-ts\)](http://www.ibm.com/docs/en/cics-ts).



## Chapter 30. DIAGxx (control common storage tracking and GFS trace)

DIAGxx contains statements that control the following functions:

- Common service area (CSA), extended CSA (ECSA), system queue area (SQA), and extended SQA (ESQA) tracking.
- GETMAIN/FREEMAIN/STORAGE (GFS) trace.

To obtain GFS trace data output, GTF must be started for USR F65 records. For more details, see the GFS trace information in *z/OS MVS Diagnosis: Tools and Service Aids*.

- The behavior of GETMAIN (and STORAGE OBTAIN) for CSA allocations (both above and below 64 megabytes).
- Terminating and restarting an initiator address space when its available region size has decreased.
- Preventing the use of user key CSA/ECSA.
- Controlling the behavior of 64-bit storage services: IARCP64 and IARST64.
- Controlling whether some system functions create system trace entries.
- Controlling the behavior of GETMAIN (and STORAGE OBTAIN) for user-region private area subpools (both above and below the line).
- Controlling the use of freemained frames.
- Controlling AutoIPL, which can re-IPL z/OS, take a stand alone dump (SADMP), or take a SADMP and have SADMP re-IPL z/OS when it has finished.
- Controlling address space layout randomization.

See the description of the VERBEXIT VSMDATA subcommand in *z/OS MVS IPCS Commands* for information about:

- How to format the data that the storage tracking function collects from a dump.
- How to identify jobs or address spaces that own CSA, ECSA, SQA, and ESQA storage.

### Specifying the DIAGxx members

The following methods can be used to specify the current DIAGxx members:

- The operator can enter the SET DIAG=xx command at any time after IPL.
- You can specify the DIAG=xx parameter in the IEASYSxx parmlib member during IPL, and then select IEASYSxx in the LOADxx parmlib member or specify SYSP=xx in response to the SPECIFY SYSTEM PARAMETERS system message.
- You can specify DIAG=xx in response to the SPECIFY SYSTEM PARAMETERS system message.

You can specify one or more current DIAGxx parmlib members during IPL. For example, a DIAG=(03,04) system parameter tells the system to use DIAG03 and DIAG04 as current members. The system processes these members in the order they are specified. For all statements other than VSM TRACK, only the last statement for that option is honored. Before changing options with SET DIAG=xx, consider issuing a D DIAG command to see what options are currently in affect. Combine the displayed options with any new request that shares the same option statement.

The VSM TRACK parameter is cumulative. For example, if you specify VSM TRACK SQA(ON) in DIAG03 and VSM TRACK CSA(ON) in DIAG04, the system turns SQA/ESQA tracking on when it processes DIAG03, and turns CSA/ECSA tracking on when it processes DIAG04 (so both are turned on). The VSM TRACE parameter, in contrast, is not. For example, if you specify VSM TRACE GETFREE(ON) SUBPOOL(127) in DIAG03 and VSM TRACE GETFREE(ON) SUBPOOL(0) ASID(1) in DIAG04, the second specification replaces the first, with the result that the system performs a GFS trace for ASID 1 only.

IBM provides the following parmlib members:

**DIAG00**

Sets storage tracking on and GFS trace off. This is the default; if you do not specify a DIAGxx parmlib member during IPL, the system processes the default member DIAG00.

**DIAG01**

Sets storage tracking on but does not change GFS trace settings.

**DIAG02**

Sets storage tracking off but does not change GFS trace settings.

## Parameter in IEASYSxx (or specified by the operator)

---

DIAG=(xx[,yy...])

The two-character identifier *xx* is appended to DIAG to identify the DIAGxx parmlib member. You can also specify multiple DIAGxx members on this parameter. For example, you can specify two active members using the form DIAG=(xx,yy). If you do not specify the DIAG=xx parameter, the system processes the DIAG00 parmlib member.

## Syntax rules for DIAGxx

---

- When creating DIAGxx, enter data only in columns 1 through 71. Do not enter data in columns 72 through 80; the system ignores these columns.
- If the system finds a syntax error in DIAGxx, the system issues an error message, and then attempts to continue processing the next keyword.
- Comments may appear in columns 1-71 and must begin with "/"\* and end with "\*/".

## Syntax format of DIAGxx

```

[ASCBV31([NO|YES]) ]
[ASLR({NO|YES|YES3164|YES64}) ]
[AUTOIPL SADMP(sadmp info) MVS(mvs info) ]
[NUCLABEL {ENABLE|DISABLE}{BLWRST02}] ]
[CBATTR [EXECUTABLE(structure1,structure2,...)] [NONEXECUTABLE(structure1,structure2,...)]] ]
[CBLOC [VIRTUAL24(structure1,structure2,...)] ]
[FF31HIGH(NO) ]
[FF31HIGH(YES) [EXCLUDEJOBLIST([job1[,job2...]])] ]
[FREEMAINEDFRAMES(NO) ]
[FREEMAINEDFRAMES(YES) [EXCLUDEJOBLIST([job1[,job2...]])] ]
[REUSASID(NO|YES) ]
[TRAPS NAME ([trapname1,{trapname2}...]) ]
[VIRTUAL31(structure1,structure2,...)] ]
[REAL31(structure1,structure2,...)] ]
[REAL64(structure1,structure2,...)] ]
[VSM ALLOWEARLYRUCSA(NO|YES) ]
[VSM ALLOWUSERKEYCSA(NO|YES) ]
[VSM BESTFITCSA(NO|YES) ]
[VSM CHECKREGIONLOSS(bbb{K|M}{},aaa{K|M}{}) ]
[VSM NEUTRALZONE(bbb{K|M}{},aaa{K|M}{}) ]
[VSM TRACE ]
[ {GETFREE(ON)|GET(ON|OFF) FREE(ON|OFF) ]
[ [ASID({asid1|asid1-asidx}{[, {asid2|asid2-asidx}]...}) ]
[ [DATA(data1[,data2...]) ]
[ [KEY({key1|key1-keyx}{[, {key2|key2-keyx}]...}) ]
[ [LENGTH({len1|len1-lenx}{[, {len2|len2-lenx}]...}) ]
[ [SUBPOOL({sub1|sub1-subx}{[, {sub2|sub2-subx}]...}) ]
[ [JOBNAME([job1[,job2...]]) ]
[ [ADDRESS([addr1|addr1-addrx][,addr2-|addr2-addrx...]) ]
[ [LOCREAL(loc1[,loc2...]) ]
[ {GETFREE (OFF) ]
[VSM TRACK ]
[ {CSA (ON|OFF) ]
[ {SQA (ON|OFF) ]
[ {CSA (ON|OFF) SQA (ON|OFF) ]
[VSM USEZOSV1R9RULES(NO|YES) ]

```

## IBM-supplied default for DIAGxx

DIAGxx has the following IBM-supplied default parmlib members.

| IBM-supplied default parmlib member | Contents   |
|-------------------------------------|--|
| DIAG00                              | <ul style="list-style-type: none"> <li>VSM TRACE GETFREE (OFF)</li> <li>VSM TRACK CSA(ON) SQA(ON)</li> </ul> |
| DIAG01                              | <ul style="list-style-type: none"> <li>VSM TRACK CSA(ON) SQA(ON)</li> </ul>                                  |
| DIAG02                              | <ul style="list-style-type: none"> <li>VSM TRACK CSA(OFF) SQA(OFF)</li> </ul>                                |

If you do not specify a DIAGxx parmlib member during IPL, the system uses the default member DIAG00, which turns on storage tracking and turns off GFS trace.

If you specify a DIAGxx parmlib member during IPL omitting either the storage tracking or GFS trace statement, the omitted element is turned off.

The system expects a default member to be present. If you do not specify a DIAGxx parmlib member during IPL, and none of DIAG00, DIAG01, or DIAG02 exists, the system uses the following options:

- VSM TRACE GETFREE (OFF)
- VSM TRACK CSA(ON) SQA(ON)

In this case:

- CSA and SQA tracking are active and will remain active until turned off through a SET DIAG=xx command.
- GFS tracing is off.
- The system issues informational message IEA301I to the operator.

## Statements and parameters for DIAGxx

### ASCBV31(NO|YES)

Specifies whether the ASCB is in 31-bit addressable storage when requested by a subsequent **START** command or subsequent use of the **ASCRE** macro.

#### NO

The ASCB is in 24-bit addressable storage.

#### YES

The ASCB is in 31-bit addressable storage.

#### Default: NO

As the address space level 31-bit ASCB controls are on an address space basis, you are ensured that the related primary programs either automatically enable it or provide direction on to enable it by using the related address space start method. However, before using DIAGxx ASCBV31 (YES), ensure that any program that runs in those address spaces or accesses ASCBs of other address spaces supports 31-bit ASCBs. For more information about programs that support 31-bit ASCBs, see [ASCBV31 and REUSASID supported z/OS components in z/OS MVS System Commands](#).

### ADDRESS(addr1|addr1–addrx,[addr2|addr2–addrx]...)

Specifies that the system is to produce trace records only for requested storage of specific addresses. You can specify up to eight storage addresses. Each address must be a hexadecimal number from 0 to 7FFFFFFF. If you do not specify this parameter, the system produces trace records for requested storage of all addresses.

You can specify a specific address, a range of addresses, or any combination of both, as shown in the following examples:

- ADDRESS(0–FFFFFF). The system produces trace records for all addresses less than 16 megabytes.
- ADDRESS(8000,70000000–7FFFFFFF) The system produces trace records for addresses 8000 and 70000000–7FFFFFFF.

If you specify a range of addresses, ensure that the address at the end of the range is greater than or equal to the address of the beginning of the range. A request matches a range if any byte of the request is within the range.

ADDRESS filtering does not apply to a subpool FREEMAIN request, causing a trace record to be produced for the subpool FREEMAIN, as well as an associated "Releasing Subpool" trace record. (For a description of the "Releasing Subpool" trace record, refer to [Formatted GFS Trace Output in z/OS MVS Diagnosis: Tools and Service Aids](#), under GETMAIN, FREEMAIN, STORAGE (GFS) Trace.)

### ASID({asid1|asid1-asidx},{asid2|asid2-asidx}...)

Indicates that the system is to produce trace records only for one or more specified address space identifiers (ASIDs). Each ASID must be a hexadecimal number from 0 to 7FFF. The ASID that the system checks when it determines whether to produce a trace record is as follows:

#### CSA Storage=

If CSA tracking is on, the associated ASID is the one indicated by the OWNER parameter on GETMAIN or STORAGE. If CSA tracking is off (or for a request to release storage, was off when the storage was obtained), the associated ASID is unknown, causing no ASID filtering to be done and a trace record to be produced.

#### Private Storage=

The target address space of the storage.



**SQA Storage =**

If SQA tracking is on, the associated ASID is the one indicated by the OWNER parameter on GETMAIN or STORAGE. If SQA tracking is off (or for a request to release storage, was off when the storage was obtained), the associated ASID is unknown, causing no ASID filtering to be done and a trace record to be produced.

ASID 0 matches common storage requests with OWNER=SYSTEM.

If you omit this parameter, the system produces trace records for all ASIDs. You can specify 1 - 32 ASIDs.

You can specify a specific ASID, a range of ASIDs, or any combination of both, as shown in the following examples:

- ASID(5,6,9) - The system produces trace records for ASIDs 5, 6, and 9.
- ASID(5-7,9,11-13) - The system produces trace records for ASIDs 5, 6, 7, 9, 11, 12, and 13.

If you specify a range of ASIDs, ensure that the ASID at the end of the range is greater than the ASID at the beginning of the range.

**ASLR(NO|YES|YES3164|YES64)**

Indicates whether address spaces on this system are subject to address space layout randomization (ASLR). For information about the implications of enabling ASLR and how to exclude individual jobs from ASLR, see [Address space layout randomization in z/OS MVS Initialization and Tuning Guide](#). The ASLR values are:

**NO**

Indicates that the 24-bit and 31-bit low private area and the 64-bit private area of address spaces are not subject to address space layout randomization.

**YES**

Indicates that the 24-bit and 31-bit low private area and the 64-bit private area of address spaces are subject to address space layout randomization.

**YES3164**

Indicates that only the 31-bit low private area and the 64-bit private area of address spaces are subject to address space layout randomization.

**YES64**

Indicates that only the 64-bit private area of address spaces is subject to address space layout randomization.

**Default:** NO

**AUTOIPL SADMP(sadmp info) MVS(mvs info) [NUCLABEL {ENABLE|DISABLE}(BLWRSTO2)]****(sadmp info)**

Either (device,loadparm) or (NONE).

- For SADMP(device,loadparm), if the system is about to enter a wait state, SADMP is loaded from this volume with this load parameter.
- For SADMP(NONE), if the system is about to enter a wait state, SADMP is not loaded.

**(mvs info)**

Either (device,loadparm,loadtype) or (LAST,loadtype) or (NONE)

**loadtype**

Either CLEAR or NORMAL.

If ,loadtype is not specified, it defaults to ,CLEAR.

**Notes:**

1. SADMP specified with a device and load parameter and MVS specified with NONE causes the AutoIPL function to IPL SADMP only.
2. SADMP specified with NONE and MVS specified with a device and load parameter or with LAST causes the AutoIPL function to re-IPL MVS immediately, with no SADMP taken.

3. SADMP with a device and load parameter and MVS with a device and load parameter or with LAST causes SADMP to be IPLed, followed by MVS.
4. Any valid specification of AUTOIPL causes any prior AutoIPL information to be replaced.
5. SADMP (NONE) and MVS (NONE) both specified effectively deactivates the AutoIPL function.
6. The SADMP *loadparm* value can be specified so that SADMP executes without prompts to the operator. For information on coding the SADMP load parameter, see [Procedure A: Initialize and run stand-alone dump in z/OS MVS Diagnosis: Tools and Service Aids](#).
7. The MVS with LAST parameters do not support HyperSwaps in which the IPL, IODF, and SADMP secondary volumes are not part of an alternate subchannel set (that is, the primary and secondary device pairs do not have identical device numbers and all reside in a single subchannel set). Therefore, if MVS with LAST was specified in that environment and a HyperSwap® swapped different device numberHyperSwap within subchannel set zero and no intervening IPL occurred, the MVS with LAST function will still attempt to use the original IPL, IODF, and SADMP volumes before the swap.
8. *device* is a 4-digit device number that can be prefixed by \*. The asterisk prefix denotes that the device in the currently active subchannel set should be used. If an asterisk does not prefix the device number, the device in subchannel set 0 is used.

This function is intended for HyperSwap environments that use alternate subchannel sets. Environments without HyperSwap or HyperSwap environments that do not use an alternate subchannel set will not benefit from using \*.

9. Only in a HyperSwap environment that uses an alternate subchannel set will the MVS with LAST parameters ensure that AUTOIPL uses the device number from the appropriate subchannel set in the event of a HyperSwap.
  10. AUTOIPL, when requested to IPL an MVS system, will, by default, specify the CLEAR option that can lead to an elongated response time for the function. The request can be made to perform better by specifying the NORMAL suboption for AUTOIPL. The result of requesting this option is that the AUTOIPL initiated IPL will be done using the NORMAL option.
- Note:** This processing might result in the unavailability of reconfigurable storage when the IPL is done so the specification of this option should only be used when necessary.
11. An IPL of MVS or SADMP that is initiated via AUTOIPL will be the same type of IPL (CCW or List-Directed) as the last IPL that was initiated by an operator. If that IPL was List-Directed, the Secure or not Secure setting for AUTOIPL will also be the same as the last IPL that was initiated by an operator.

For more information about AutoIPL, see [Using the automatic IPL function in z/OS MVS Planning: Operations](#).

**CBATTR [EXECUTABLE(structure1,structure2,...)] [NONEXECUTABLE(structure1,structure2,...)]**

**EXECUTABLE**

Provides the names of executable structures.

**NONEXECUTABLE**

Provides the names of nonexecutable structures.

Structure names:

**JCLPARM**

Indicates that the parameter list passed to a program specified on the JCL EXEC statement in register 1 will be executable or nonexecutable. By default, the storage is nonexecutable.

If both lists include JCLPARM, the resulting executability attribute is undefined.

**CBLOC [VIRTUAL24(structure1,structure2,...)] [VIRTUAL31(structure1,structure2,...)]  
[REAL31(structure1,structure2,...)] [REAL64(structure1,structure2,...)]**

**VIRTUAL24**

Provides the names of structures to be located in 24-bit virtual storage.

**VIRTUAL31**

Provides the names of structures to be located in 31-bit virtual storage.

Structure names:

**IHARMPL**

When a task or address space termination resource manager is called, the location of the RMPL and save area (x'248' bytes of private storage) is determined by which list includes IHARMPL. If neither of the lists include IHARMPL, the RMPL and save area are in 24-bit virtual storage. If both lists include IHARMPL, the resulting location is undefined. Using 31-bit virtual storage can reduce 40D-10 abnormal memory terminations which occur due to 24-bit private storage exhaustion. Task and address space termination resource managers are established using the RESMGR macro, or via function routines for SubSystem Interface (SSI) function codes 4 (End of task) or 8 (End of memory). Do not specify IHARMPL in the VIRTUAL31 list if your system uses any old resource managers which run in 24-bit addressing mode.

**IHAXTLST**

When a module is loaded into storage, the location of the extent list is determined by which list includes IHAXTLST. If neither of the lists include IHAXTLST, the extent list is in 24-bit virtual storage. If both lists include IHARMPL, the resulting location is undefined. There is one extent list per loaded program. The size is 16 bytes for a module with one extent, plus 8 bytes per additional extent.

**IEFMASTERSWA**

Specifying IEFMASTERSWA in the CBLOC VIRTUAL31 list in DIAGxx has a similar effect on the Master Scheduler address space's SWA as specifying SWA=ABOVE in the JES2 parameters does for other address spaces, except that Master Scheduler's SWA is in CSA storage, not private storage. This can reduce the amount of 24-bit CSA in use for SWA by around 14K bytes. If neither of the lists include IEFMASTERSWA, the SWA control blocks are in 24-bit CSA storage. If both lists include IEFMASTERSWA, the resulting location is undefined.

**IHAACEE3PTY**

When a 3rd-party ACEE is created by RACROUTE REQUEST=AUTH, the location of the 3rd-party ACEE is determined by which list includes IHAACEE3PTY.

- If neither of the lists include IHAACEE3PTY, the 3rd-party ACEE is in 24-bit virtual storage.
- If the VIRTUAL31 list includes IHAACEE3PTY, the 3rd-party ACEE is in 31-bit virtual storage
- If the VIRTUAL24 list includes IHAACEE3PTY, the 3rd-party ACEE is in 24-bit virtual storage.
- If both lists include IHAACEE3PTY, the resulting location is undefined.

**IHALCCA**

When a CPU is brought online, the location of its LCCA is determined by which list includes IHALCCA. If neither of the lists include IHALCCA, the LCCA is in 31-bit virtual storage. If both lists include IHALCCA, the resulting location is undefined. The LCCA of the IPL CPU is built in 24-bit storage before DIAGxx is processed.

If additional standard CPs are brought online later in the IPL process, the IPL CPU is automatically configured offline and back online, with its LCCA located according to the CBLOC specification.

**IHAPCCA**

When a CPU is brought online, the location of its PCCA is determined by which list includes IHAPCCA. If neither of the lists include IHAPCCA, the PCCA is in 31-bit virtual storage. If both lists include IHAPCCA, the resulting location is undefined. The PCCA of the IPL CPU is built in 24-bit storage before DIAGxx is processed.

If additional standard CPs are brought online later in the IPL process, the IPL CPU is automatically configured offline and back online, with its PCCA located according to the CBLOC specification.

**IHAASVT**

When the system is IPLed, the location of its ASVT is determined by which list includes IHAASVT. If neither of the lists include IHAASVT, the ASVT is in 24-bit virtual storage. If both lists include IHAASVT, the resulting location is undefined.

**CNZSSICB**

When SSI Functions 9, 10, or 14 are called upon, their respective control blocks are created in 31-bit storage.

If neither of the lists include CNZSSICB, the control blocks are created in 24-bit virtual storage. If both lists include CNZSSICB, the resulting location is undefined.

**REAL31**

Provides the names of structures to be backed in 31-bit real storage.

**REAL64**

Provides the names of structures to be backed in 64-bit real storage.

Structure names:

**IHAASCB**

The real storage backing of ASCBs is determined by which list includes IHAASCB. If neither of the lists includes IHAASCB, ASCBs are backed in 64-bit real storage. If both lists include IHAASCB, the real storage backing is undefined.

**IHAWEB**

The real storage backing of WEBs is determined by which list includes IHAWEB. If neither of the lists includes IHAWEB, WEBs are backed in 64-bit real storage. If both lists include IHAWEB, the real storage backing is undefined.

**CSA (ON|OFF)**

The status of the common service area (CSA and ECSA) tracking function. Specifying CSA(ON) might lead to a small performance degradation and an increase in ESQA use. Omitting this parameter leaves the status of CSA/ECSA tracking unchanged.

**DATA(data1[,data2]...)**

Specifies the data items that you want to include in the trace. The data items are listed in the following table.

| <b>Data</b>  | <b>Information included in trace.</b>  |
|--------------|--|
| <b>ALL</b>   | All trace information (BASIC plus REGS). If you omit the DATA keyword, the default is DATA(ALL).                           |
| <b>REGS</b>  | The contents of the caller's registers when the system processed the linkage instruction to GETMAIN, FREEMAIN, or STORAGE. |
| <b>BASIC</b> | All of the trace information except REGS. The BASIC data is included in every trace record.                                |

RETADDR, RETCODE, TYPE, SVCNUM, ADDR, LENGTH, SPKEY, FLAGS, ASID, and TCB are accepted for compatibility with older releases and are ignored.

**FREEMAINEDFRAMES(NO)****FREEMAINEDFRAMES(YES) [EXCLUDEJOBLIST([job1[,job2...]])]**

To enhance performance on IBM z13<sup>®</sup> and later hardware, the system does not free the real frame that is backing a low private virtual page following a FREEMAIN (that is, when the page no longer contains any GETMAIN-assigned storage ranges); however, the system overwrites the contents of the frame to ensure that sensitive information is removed. Such a frame is referred to as a *freemained frame*. Freemained frames do not cause the count of frames that are owned by the address space to be decremented, nor do they cause the count of available frames within the system to be incremented.

**FREEMAINEDFRAMES(NO)**

Disables the freemained frames feature on a system-wide basis. The high freemained frames feature is also disabled when this option is specified.

**FREEMAINEDFRAMES(YES) [EXCLUDEJOBLIST([job1[,job2...]])]**

Enables the freemained frames feature, except for the specified jobs. If the job name of either a START, MOUNT, LOGON, or initiated program matches a value that is specified in the **EXCLUDEJOBLIST** parameter, that job is excluded from the freemained frames feature. Up to

eight job names can be specified and can include the \* and ? wildcard characters, where the \* character is allowed in any position.

When you exclude a job, all existing freemained frames, including high freemained frames, are purged from the associated address space.

Reissuing the SET DIAG command with different **EXCLUDEJOBLIST** values cannot increase the total number of excluded jobs; the last **EXCLUDEJOBLIST** specification overrides any previous specifications.

Disabling this feature for selected jobs cause performance degradation for the entire system, not just for the specified jobs.

**Example:** The following statement disables the freemained frames feature for all initiators under JES2:

```
FREEMAINEDFRAMES(YES) EXCLUDEJOBLIST(INIT)
```

This feature is active by default on z13<sup>®</sup> and later hardware and only applies to region private storage below the 2 GB bar, which is defined as subpools 0-127, 129-132, 240, 244, 250-252.

### **FF31HIGH(NO)**

#### **FF31HIGH(YES) [EXCLUDEJOBLIST([job1[,job2...]])]**

This is automatically set to NO. The FREEMAINEDFRAMES(NO) is specified or changed to NO.

To enhance performance on IBM IBM z14<sup>®</sup> and later hardware, the system might not free the real frame that is backing a high private or LSQA page following a FREEMAIN (that is, when the page no longer contains any high private GETMAIN-assigned storage ranges); the system overwrites the contents of the frame to ensure that sensitive information is removed if the frame's key is not 0-7 or not fetch protected. Such a frame is referred to as a high freemained frame. Like Low Private Freemained frames, High Private Freemained Frames do not cause the count of frames that are owned by the address space to be decremented, nor do they cause the count of available frames within the system to be incremented.

### **FF31HIGH(NO)**

Disables the high freemained frames feature on a system-wide basis.

#### **FF31HIGH(YES) [EXCLUDEJOBLIST([job1[,job2...]])]**

Enables the high freemained frames feature, except for the specified jobs. If the job name of either a START, MOUNT, LOGON, or initiated program matches a value that is specified in the EXCLUDEJOBLIST parameter, that job is excluded from the freemained frames feature. Up to eight job names can be specified and can include the \* and ? wildcard characters, where the \* character is allowed in any position. When you exclude a job, all existing high freemained frames are purged from the associated address space. Reissuing the SET DIAG command with different EXCLUDEJOBLIST values will not increase the total number of excluded jobs; the last EXCLUDEJOBLIST specification overrides any previous specifications. Disabling this feature for selected jobs cause performance degradation for the entire system, not just for the specified jobs.

**Default:** YES

### **GETFREE(ON|OFF)**

Specifies the status of the GFS trace.

#### **JOBNAME(job1[,job2...])**

Specifies that the system is to produce trace records only for one or more specified job names. Each job name must be 1 - 8 alphanumeric or national characters. The wildcard characters ? and \* can be included.

The job name that the system checks when it determines whether to produce a trace record is the job name for the ASID that would be used to match an ASID filter.

### **CSA Storage=**

If CSA tracking is on, the associated JOBNAME is the one indicated by the OWNER parameter on GETMAIN or STORAGE. If CSA tracking is off (or for a request to release storage, was off when the

storage was obtained), the associated JOBNAME is unknown, causing no JOBNAME filtering to be done and a trace record to be produced.

#### **Private Storage=**

The target JOBNAME of the storage.

#### **SQA Storage =**

If SQA tracking is on, the associated JOBNAME is the one indicated by the OWNER parameter on GETMAIN or STORAGE. If SQA tracking is off (or for a request to release storage, was off when the storage was obtained), the associated JOBNAME is unknown, causing no JOBNAME filtering to be done and a trace record to be produced.

#### **KEY({key1|key1-keyx},{key2|key2-keyx}...)**

Specifies the storage keys for which the system is to produce trace records. If you do not specify this parameter, the system produces trace records for all storage keys. You can specify any number of keys or key ranges. Each key must be a decimal number 0 - 15.

If you specify a range of keys, ensure that the key at the end of the range is greater than or equal to the key at the beginning of the range.

You can specify a specific key, a range of keys, or any combination of both, as shown in the following examples:

- KEY(1,2). The system produces trace records for storage keys 1 and 2.
- KEY(1-3,15). The system produces trace records for storage keys 1, 2, 3 and 15.

KEY filtering does not apply to a subpool FREEMAIN request, causing a trace record to be produced for the subpool FREEMAIN, as well as an associated "Releasing Subpool" trace record. (For a description of the "Releasing Subpool" trace record, refer to Formatted GFS Trace Output in [z/OS MVS Diagnosis: Tools and Service Aids](#), under GETMAIN, FREEMAIN, STORAGE (GFS) Trace.)

#### **LENGTH({len1|len1-lenx},{len2|len2-lenx}...)**

Indicates that the system is to produce trace records only for requested storage of specific lengths (in bytes). You can specify up to eight storage lengths. Each length must be a decimal number 1 - 10 digits (the maximum value is 2147483640 bytes). If you do not specify this parameter, the system produces trace records for requested storage of all lengths.

Specify each length as a multiple of 8 bytes. If you do not, the system rounds the value up to the next higher multiple of 8.

You can specify a specific length, a range of lengths, or any combination of both, as shown in the following examples:

- LENGTH(512,1024). The system produces trace records for requested lengths of 512 and 1024 bytes.
- LENGTH(512,520-528,1024-1032). The system produces trace records for requested lengths of 512, 520-528, and 1024 - 1032 bytes.

If you specify a range of lengths, ensure that the length at the end of the range is greater than or equal to the length at the beginning of the range. If the requested storage is of a variable length, the system uses the length of the storage that was obtained.

LENGTH filtering does not apply to a subpool FREEMAIN request, causing a trace record to be produced for the subpool FREEMAIN and an associated "Releasing Subpool" trace record. (For a description of the "Releasing Subpool" trace record, refer to Formatted GFS Trace Output in [z/OS MVS Diagnosis: Tools and Service Aids](#), under GETMAIN, FREEMAIN, STORAGE (GFS) Trace.)

#### **LOCREAL(loc1[,loc2]...)**

Specifies the real storage locations for which trace records should be produced, as specified by the LOC keyword on the GETMAIN or STORAGE macros. For example, LOCREAL(24,31) requests tracing for those storage requests that specified real storage backing below the line (LOC=24 or LOC=(xx,24)) and those storage requests that specified real storage backing in 31-bit storage (LOC=(xx,31)).

LOCREAL(64) traces all storage requests that specify LOC(xx,64) or LOC(xx,PAGEFRAMESIZE1MB).

Valid parameters for LOCREAL are 24, BELOW, 31, ANY, 64, and PAGEFRAME SIZE1MB:

#### **24 | BELOW**

The system produces trace records for requests that specify real storage backing below the line.

#### **31 | ANY**

The system produces trace records for requests that specify real storage backing in 31-bit storage.

#### **64**

The system produces trace records for requests that specify real storage backing in 64-bit storage.

#### **PAGEFRAME SIZE1MB**

The system produces trace records for requests that specify LOC(xx,PAGEFRAME SIZE1MB).

If you do not specify this parameter, trace records are produced for all storage locations.

#### **REUSASID(NO|YES)**

Specifies whether a reusable ASID is assigned when requested by the ASCRE macro or the REUSASID=YES parameter on the START command.

##### **NO**

An ordinary ASID is assigned.

##### **YES**

A reusable UIDASID is assigned.

##### **Default: YES**

The use of reusable ASIDs might result in system OD3 abends, if products or programs have not been upgraded to tolerate reusable ASIDs. For more information about reusable ASIDs, see [z/OS MVS Programming: Extended Addressability Guide](#).

#### **SUBPOOL({sub1|sub1-subx},{sub2|sub2-subx}...)**

Specifies the subpools for which the system is to produce trace records. If you omit this parameter, the system produces trace records for all subpools. You can specify any number of subpools.

You can specify a specific subpool, a range of subpools, or any combination of both, as shown in the following examples:

- SUBPOOL(129,132) - The system produces trace records for subpools 129 and 132.
- SUBPOOL(129-131, 227-229, 252) - The system produces trace records for subpools 129, 130, 131, 227, 228, 229 and 252.

If you specify a range of subpools, ensure that the subpool at the end of the range is greater than or equal to the subpool at the beginning of the range.

#### **SQA (ON|OFF)**

The status of the system queue area (SQA and ESQA) tracking function. Specifying SQA(ON) might lead to a small performance degradation and an increase in ESQA usage. Omitting this parameter leaves the status of SQA/ESQA tracking unchanged.

#### **TRAPS NAME ({trapname1},{trapname2}...)**

Specifies a list of the traps that should be activated. If you issue command SET DIAG=xx and the DIAGxx parmlib member contains a TRAPS NAME statement, the list of TRAPS specified replaces the previous list of activated traps. This deactivates any traps that are not in the new list.

Specifying a null list of trap names deactivates all the TRAPS. If your DIAGxx parmlib member does not contain a TRAPS statement, there is no change to the list of traps that are activated. If you specify multiple parmlib members (DIAG=(03,04)) and both contain TRAPS statements or you code multiple TRAPS statements in a single parmlib member, only the last TRAPS statement is honored.

The following traps are supported:

##### **IarCp64InitFree**

The IARCP64 services initialize storage to contain nonzero values on a REQUEST=FREE.

**Note:** IarCp64InitFree is intended to be used in a test environment to surface programs that reference storage after it has been freed with IARCP64 REQUEST=FREE. Because this will potentially cause more pages to be backed, consume more CPU cycles and possibly cause more page faults, do not activate this option in a production environment.

#### **IarCp64InitGet**

The IARCP64 service is to initialize storage to contain nonzero values on a REQUEST=GET.

**Note:** IarCp64InitGet is intended to be used in a test environment to surface programs that obtain cells from a cell pool with IARCP64, but fail to initialize it before using it. Because this will likely cause more pages to be backed and possibly more page faults, do not activate this option in a production environment.

#### **IarRucsaFlt**

Issues a diagnostic SC0D-05005C00 abend when a fault on user-key CSA storage occurs while IEASYSxx RUCSA is defined and the faulter does not have SAF READ authority to CLASS(FACILITY) PROFILE(IARRSM.RUCSA). The abend is retried and not exposed to the faulter. It can be used to create a system memory dump and LOGREC entry to help identifying software that faults on RUCSA.

#### **IarSt64InitFree**

The IARST64 service is to initialize storage to contain nonzero values on a REQUEST=FREE.

This option is intended to be used in a test environment to surface programs that reference storage after it has been freed with IARST64 REQUEST=FREE. Because this will potentially cause more pages to be backed, consume more CPU cycles and possibly cause more page faults, do not activate this option in a production environment.

#### **IarSt64InitGet**

The IARST64 service is to initialize storage to contain nonzero values on a REQUEST=GET.

This option is intended to be used in a test environment to surface programs that obtain storage with IARST64, but fail to initialize it before using it. Since this will likely cause more pages to be backed and possibly more page faults, activating this option in a production environment should be avoided.

#### **IarSt64Trailer**

The IARST64 REQUEST=GET service is to force trailer processing for storage requests, even if it means to increase the size of the obtained storage cell to make room for the trailer.

This option is intended to be used in a test environment to surface programs that modify storage past the end of the requested storage size. When storage is freed with IARST64 REQUEST=FREE, the service abends the caller if it detects that the trailer has been overlaid. Since this will potentially increase the size of the storage cell, it can reduce the number of cells per extent, which can cause more pages to be backed, consume more CPU cycles and possibly cause more page faults, activating this option in a production environment should be avoided.

#### **IEARISGNLTRACE**

Turns on system tracing of RISGNL.

#### **IEARPSGNLTRACE**

Turns on system tracing of RPSGNL.

#### **IEARTM2NOSNAPTRC**

RTM processing will not capture a systrace snapshot. If a dump is requested, dump processing will request a systrace snapshot to include in the dump.

#### **IEASCHEDULETRACE**

Turns on system tracing of SCHEDULE and IEAMSCHD. Adding tracing of SRB scheduling might cause a small degradation in performance.

#### **IeaSlipConfirm**

Checks to see whether JOBNAME or ASID is specified when MODE=HOME is specified on the SLIP command. If both JOBNAME and ASID parameters were omitted, SLIP issues message IEE088D asking if you would like to continue. This trap is used only for V2R1 systems and is obsolete in



V2R2. In V2R2, SLIP always issues message IEE088D when MODE=HOME is specified without JOBNAME and ASID.

### VSM ALLOWEARLYRUCSA(NO|YES)

#### NO

When restricted use common service area (RUCSA) is defined and VSM ALLOWUSERKEYCSA is NO, the following uses of RUCSA might abend:

- Creating or referencing RUCSA storage within an address space that is started during system IPL before the security product has been initialized.
- Creating RUCSA storage while running under the Master address space
- Creating or referencing RUCSA storage within user exits or started task initialization routines that run before the completion of job selection.

#### YES

When RUCSA is defined, the previously described early usage conditions are permitted. Do not specify VSM ALLOWEARLYRUCSA(YES) if early usage has not been recorded by SMF type 30 records. For more information on determining whether early use conditions exist, see [Restricted use common service area \(RUCSA/extended RUCSA\)](#) in *z/OS MVS Initialization and Tuning Guide*.

SAF READ authority to the IARRSM.RUCSA resource profile in the FACILITY class is still required except for address spaces that are always started early in system IPL, before the security product has completed initialization.

**Default:** NO

### VSM ALLOWUSERKEYCSA(NO)

#### NO

ALLOWUSERKEYCSA(NO) is tolerated but no value other than NO is allowed because user-key CSA storage is not supported outside of a restricted use common service area (RUCSA). When a RUCSA is not defined, prevents user-key CSA from being allocated by failing any attempt to obtain user-key storage from a CSA subpool (through GETMAIN or STORAGE OBTAIN) with an appropriate abend.

When a RUCSA is defined, only users with SAF READ authority to the IARRSM.RUCSA resource in the FACILITY class can use user-key CSA.

For more information about RUCSA, see [Restricted use common service area \(RUCSA/extended RUCSA\)](#) in *z/OS MVS Initialization and Tuning Guide*.

**Default:** NO

### VSM BESTFITCSA(NO|YES)

Indicates how GETMAIN or STORAG|OBTAIN processes requests for (E)CSA storage.

#### NO

Indicates to use a "first fit" algorithm in certain situations such as when you use the STARTBDY and CONTBDY options. It matches the default behavior on all current releases of z/OS. However, in some environments, this option can lead to (E)CSA fragmentation.

#### YES

Indicates to always use a "best fit" algorithm. It minimizes (E)CSA fragmentation to help prevent user and system outages because of requests for (E)CSA storage that the system cannot satisfy.

**Default:** NO, to provide seamless migration. The default value represents the historical behavior; instead, specify YES to always benefit from the "best fit" behavior.

### VSM CHECKREGIONLOSS(*bbb*{K|M},*aaa*{K|M})

Indicates the amount of region size loss that can be tolerated in an initiator address space. The initiator remembers the initial maximum available region size (below and above 16 MB) before it selects its first job. After the termination of each job run in the initiator, if the maximum available region size (below or above 16 MB) has decreased from the initial value by more than the CHECKREGIONLOSS specification, the initiator terminates with message IEF093I or

IEF094A, depending on whether the subsystem automatically restarts the initiator. JES2, JES3, WLM, OMVS, and APPC all automatically restart initiators, so initiator issues IEF093I in most cases. CHECKREGIONLOSS allows the installation to avoid 822 abends in subsequent jobs that are selected by an initiator. The available region size of the initiator has decreased because of storage fragmentation or problems that have caused storage not to be freed.

Because the initiator notifies the owning subsystem that the initiator is being terminated on the job termination SSI call, the CHECKREGIONLOSS detection must be done before some storage that will eventually be freed actually gets freed. The SWA subpool is an example (and for some jobs, a large example) of this. The detection processing recognizes storage that is part of the SWA subpool, and treats it as if it was freed. However, if you are looking at a memory dump of an IEF093I message, you still need to manually ignore the SWA storage.

Some fragmentation (especially above 16 MB) is normal. A job that uses a lot of SWA (or other system control blocks in high extended private) might cause fragmentation because this forces another system control block that persists across jobs to be allocated at a lower address. The VSM cell pool extents (VSMP eye catcher at the beginning of a 4 KB page) are an example of persistent storage. Compression of VSM cell pool extents requires a large amount of CPU time (much more than the CPU time for terminating and restarting an initiator). Recycling of initiators under the control of CHECKREGIONLOSS is the intended mechanism for dealing with fragmentation.

In addition to normal fragmentation, IEF093I might in some cases expose a storage leak problem that can be investigated and fixed. Differentiating between normal fragmentation and a storage leak is a time consuming manual process done by analyzing dumps.

#### Selecting the CHECKREGIONLOSS values:

- Select values small enough to avoid 822 abends for the jobs in your installation that have the largest REGION requirements. That depends on the size of your private area above and below 16 M, and the REGION requirements of your largest jobs.
- Select values large enough so that the frequency of IEF093I messages is not excessive, and so that the frequency of initiator recycling is not a performance issue.

Start with something like:

```
CHECKREGIONLOSS(256K,10M)
```

Decrease the values if you see 822 abends, and increase the values if you frequently see IEF093I messages.

**Note:** This DIAGxx parmlib parameter is enabled after z/OS V2R4.

#### **bbb{K|M}**

Specifies the region size below 16 MB.

**Value range:** 0 - 2046M

A value greater than or equal to 16M effectively disables the feature for below 16M.

#### **aaa{K|M}**

Specifies the region size above 16 MB.

**Value range:** 0 - 2046M

A value greater than or equal to 2032M effectively disables the feature for above 16M.

**Default:** CHECKREGIONLOSS(256K,30M)

#### **VSM NEUTRALZONE (bbb{K|M},aaa{K|M})**

For 24-bit and for 31-bit private virtual storage, there is an area of unallocated storage between the current top of allocated low private and the current bottom of allocated high private/LSQA referred to as the "neutral zone". The NEUTRALZONE DIAGxx parmlib option defines the minimum size of this area.

#### **bbb{K|M}**

Specifies the minimum size of the neutral zone below 16 MB.

**Value range:** 0 - 2046M

A value of 0 effectively disables the function for below 16 MB.

#### **aaa{K|M}**

Specifies the minimum size of the neutral zone above 16 MB.

**Value range:** 0 - 2046M

A value of 0 effectively disables the function for above 16MB.

**Default:** VSM NEUTRALZONE(56K,1M)

#### **Notes:**

1. A request for a low private subpool which would reduce the neutral zone to less than its minimum size will fail.
2. A request for high prIvate/LSQA which would reduce the neutral zone to less than 1/2 of its minimum will cause the job to be cancelled with system completion code 822-04.
3. The goal is to limit low private storage in order to reserve space for high private/LSQA, and to cancel a job which is running out of storage while there is still enough storage available to take a dump and run task level recovery routines such as ESTAE, ESTAEX, ARR, and task termination resource managers. Without taking such action, the address space may be abnormally memtermmed, in which case dumping sometimes cannot be done or is incomplete, and task level recovery is bypassed.
4. Reducing the NEUTRALZONE values makes it less likely that the job will be cancelled, but reduces the effectiveness of the feature in preventing an abnormal memory termination due to an out of storage condition. First consider reducing the size of region before reducing the size of the minimum size of the neutral zone. Decreasing the minimum size of the neutral zone should be only a last resort.
5. Increasing the NEUTRALZONE values increases the likelihood of the job being cancelled, but improves the effectiveness of the feature in preventing an abnormal memory termination due to an out of storage condition.

#### **VSM TRACE**

Indicates that the statement defines a GFS trace of storage that is obtained and released.

#### **VSM TRACK**

Indicates that the system is to process the VSM tracking parameters.

#### **VSM USEZOSV1R9RULES(NO|YES)**

##### **NO**

Specifies GETMAIN and STORAGE OBTAIN behavior for user-region private area subpools that are both below and above the line to be implemented. Thus DQEs can be merged where possible.

##### **YES**

Causes GETMAIN and STORAGE OBTAIN behavior to be unchanged from its historic behavior.

**Default:** The default is YES to provide a seamless migration. However, IBM recommends that you specify USEZOSV1R9RULES(NO) to obtain a performance benefit for applications with long DQE/FQE chains for user-region private area subpools.

### **Examples**

**Example 1:** The following example shows a DIAGxx parmlib member that starts GFS trace for requests to obtain or release virtual storage in subpools 1 through 127 and 229. The GFS trace includes requests for:

- Address spaces 1 and F
- A length of 4096 bytes
- Keys 8, 10, 11, and 12.

GFS trace includes all data in the trace, except for register information.

```
VSM TRACE GETFREE(ON)
          SUBPOOL(1-127,229)
          ASID(1,F)
          LENGTH(4096)
          KEY(8,10-12)
          DATA(RETADDR,RETCODE,TYPE,SVCNUM,
              ADDR,LENGTH,SPKEY,FLAGS,ASID,TCB)
```

**Example 2:** The following example shows a DIAGxx parmlib member that starts GFS trace for requests to obtain or release virtual storage in subpools 129 through 255. The GFS trace includes requests for:

- All address spaces (the ASID keyword is not specified)
- Lengths in the 4096-8192 byte range
- All keys (the KEY keyword is not specified)

GFS trace includes all data in the trace, except for register information.

```
VSM TRACE GETFREE(ON)
          SUBPOOL(129-255)
          LENGTH(4096-8192)
          DATA(RETADDR,RETCODE,TYPE,SVCNUM,
              ADDR,LENGTH,SPKEY,FLAGS,ASID,TCB)
```

**Example 3:** The following example shows a DIAGxx parmlib member that turns CSA/ECSA tracking on and turns SQA/ESQA tracking off:

```
VSM TRACK CSA(ON) SQA(OFF)
```

**Example 4:** The following example shows a DIAGxx parmlib member that controls termination and restarting of initiator address spaces when the amount of region loss exceeds 256 K below 16 M or 10 M above 16 M.

```
CHECKREGIONLOSS(256K,10M)
```

**Example 5:** The following example shows a DIAGxx parmlib member that prevents the use of user key CSA.

```
VSM ALLOWUSERKEYCSA(NO)
```

**Example 6:** The following example shows a DIAGxx parmlib member that enables the reuse of ASID.

```
REUSASID(YES)
```

**Example 7:** The following example shows a DIAGxx parmlib member that specifies that LCCAs and PCCAs must be located above 16 MB.

```
CBLOC VIRTUAL31(IHALCCA,IHAPCCA)
```

**Example 8:** The following example shows a DIAGxx parmlib member that specifies several traps to be activated. All of the diagnostic options that relate to IARCP64 requests are turned on.

```
TRAPS NAME(IARCP64INITGET,IARCP64INITFREE,IARCP64TRAILER)
```

**Example 9:** The following example shows a DIAGxx parmlib member that turns off all traps. This turns off all of the TRAP options.

```
TRAPS NAME()
```

For examples of output from storage tracking, see [z/OS MVS Diagnosis: Tools and Service Aids](#). For information about the location of GFS trace records, see [z/OS MVS Diagnosis: Tools and Service Aids](#).

## Chapter 31. EXITxx (allocation installation exit list)

Use the EXITxx member of SYS1.PARMLIB to specify the following installation exits for the following allocation decisions.

### Volume ENQ

When a job must wait to enqueue on a volume or a series of volumes, code the volume ENQ exit routine to make exceptions, if any, to the installation default policy for certain jobs and/or volumes. See Chapter 4, “ALLOCxx (allocation system defaults),” on page 67 for information about specification of the installation default policy. See [z/OS MVS Installation Exits](#) for information about coding the volume ENQ installation exit.

### Volume Mount

When a job's allocation request requires a volume to be mounted, code the volume mount exit routine to make exceptions, if any, to the installation default policy for certain jobs and/or volumes. See Chapter 4, “ALLOCxx (allocation system defaults),” on page 67 for information about specification of the installation default policy. See [z/OS MVS Installation Exits](#) for information about coding the volume mount installation exit.

### Specific Wait

When a job must wait for a specific volume or device to become available, code the specific waits exit routine to make exceptions (for certain jobs and/or volumes) to the installation default policy. See Chapter 4, “ALLOCxx (allocation system defaults),” on page 67 for information about specification of the installation default policy. See [z/OS MVS Installation Exits](#) for information about coding the specific waits installation exit.

### Allocated/Offline Device

When a job must wait because the device it requested is offline or allocated to another job, code the allocated/offline device exit routine to make exceptions, if any, to the installation default policy for certain jobs and/or devices. See Chapter 4, “ALLOCxx (allocation system defaults),” on page 67 for information about specification of the installation default policy. See [z/OS MVS Installation Exits](#) for information about coding the allocated/offline device installation exit.

**Note:** IBM provides the PROGxx parmlib member as an alternative to EXITxx. PROGxx allows you to specify exits, control their use, and associate one or more exit routines with exits, at IPL or while the system is running. IBM suggests that you use PROGxx to specify exits whether or not you want to take advantage of these functions.

You can convert the format of EXITxx to PROGxx using the IEFEXPR REXX exec provided by IBM. For example, the following statement in EXITxx

```
EXIT EXITNAME(xx)MODNAME(yy)
```

would look like this in PROGxx:

```
EXIT ADD EXITNAME(xx) MODNAME(yy)
```

For information about how to use the IEFEXPR REXX exec to convert the exit definitions in EXITxx to equivalent definitions in PROGxx, see Chapter 43, “IEAAPFxx (authorized program facility list),” on page 361.

For information about how to use PROGxx to define and control the use of exits, see [PROG](#).

## Parameter in IEASYSxx (or issued by the operator)

### EXIT= aa

The two alphanumeric characters, represented by aa are appended to EXIT to identify the EXITxx member of parmlib.

## Syntax rules for EXITxx

---

The following syntax rules apply to EXITxx:

- Use columns 1 through 71. Do not use columns 72 through 80 for data; these columns are ignored.
- At least one delimiter (space or comma) is required between a statement and keyword. Delimiters are not required between keywords.
- Comments may appear in columns 1-71 and must begin with "/\*" and end with "\*/".

## Syntax format of EXITxx

---

```
EXIT  EXITNAME(exitname)
      MODNAME(module name)
```

## IBM-supplied default for EXITxx

---

There is no default EXITxx parmlib member supplied by IBM. A sample parmlib member, EXIT00, is provided in SYS1.SAMPLIB.

## Statements and parameters for EXITxx

---

### EXIT

Specifies installation exit information for a single exit point and exit routine name. You must specify an EXIT statement for each installation exit that you want to get control.

### EXITNAME

This required parameter specifies the name of an installation exit point. The following list contains valid values.

- IEF\_VOLUME\_ENQ for the volume ENQ installation exit
- IEF\_VOLUME\_MNT for the volume mount installation exit
- IEF\_SPEC\_WAIT for the specific waits installation exit
- IEF\_ALLC\_OFFLN for the allocated/offline device installation exit.

See [z/OS MVS Installation Exits](#) for information about the individual exits.

### MODNAME

This required parameter specifies the exit's load module name. The exit routine name can be any 1-8 character string of alphanumeric or special (#, @, or \$) characters. The first character of the routine name cannot be a number.

## Chapter 32. EXSPATxx (excessive spin condition actions)

The EXSPATxx member allows an installation to specify actions to be taken to recover from excessive spin conditions without operator involvement. A system routine might be spinning because it cannot obtain a resource held by another processor. EXSPATxx allows you to specify the action or actions to be taken to end the spin loop if the excessive spin is detected while spinning for one of the following:

- A RISGNL response
- A spin lock to be released
- A successful BIND BREAK completion
- The RESTART resource
- An address space to quiesce
- An INTSECT release
- A CPU in the stopped state.

EXSPATxx does not support actions for spin loops that are caused by SIGP failures.

The IBM-supplied defaults for the system are appropriate in a normal environment. In a test environment, however, you might want to specify particular actions to be taken.

In addition to recovery actions, EXSPATxx allows you to specify a timeout interval. If an excessive spin continues beyond the timeout interval, the system automatically issues a SPIN action before taking any recovery action specified in an EXSPATxx member. If the excessive spin continues until the timeout interval is reached again, then the recovery actions specified in the EXSPATxx member are taken.

For more information about handling excessive spin conditions, see [\*z/OS MVS Setting Up a Sysplex\*](#)

### Parameter in IEASYSxx (or issued by the operator)

There is no IEASYSxx parameter to set EXS=xx. It can be set only by the SET command.

The two alphanumeric characters (xx) indicate the EXSPATxx member that contains the excessive spin recovery actions and the excessive spin loop timeout interval.

### Syntax rules for EXSPATxx

The following syntax rules apply to EXSPATxx:

- SPINRCVY or SPINTIME can start in any column between column 1 and 71.
- SPINRCVY or SPINTIME must be the first entry on a record.
- Comments may appear in columns 1-71 and must begin with "/\*" and end with "\*/".
- Any number of blanks can exist between SPINRCVY and the first action.
- Multiple actions on a SPINRCVY statement must be separated by commas. A blank is not a valid delimiter between two actions.
- SPINRCVY and multiple actions must appear on the same logical record.
- SPINTIME=sss cannot contain blanks.
- The system ignores columns 72 through 80.

### Syntax example of EXSPATxx

An example of the syntax for an EXSPATxx member is:

```
SPINRCVY  action[,action]...
SPINTIME=sss
```

## IBM-supplied default for EXSPATxx

None.

The EXSPATxx member is optional. At initialization time, the IBM-supplied default recovery actions are taken for excessive spin conditions. After initialization, you can issue the SET EXS=xx command to specify the EXSPATxx member. Two alphanumeric characters are appended to EXSPAT to form the name of the EXSPATxx member.

The IBM-supplied default recovery actions for excessive spin conditions are:

```
SPINRCVY ABEND,TERM,ACR (see note 1)
SPINTIME=10 or SPINTIME=40 (see note 2)
```

### Note:

1. Since the system will automatically issue a SPIN action before taking any recovery action specified in an EXSPATxx member, this specification will actually result in actions of SPIN, ABEND, TERM, ACR, which are the same actions that would be taken by the system if SPINRCVY were not specified at all.
2. The default spin loop timeout interval depends on the system configuration. For MVS running in a native or basic mode, or in an LPAR with dedicated CPs, the default is 10 seconds. For MVS running on VM or in an LPAR with shared CPs, the default spin loop timeout interval is 40 seconds.

## Statements and parameters for EXSPATxx

### SPINRCVY

Specifies the actions that the system is to take to end a spin loop that is not caused by a SIGP failure. SPINRCVY must be the first entry on a record defining these actions. At least one action is required on a SPINRCVY statement. You can specify a maximum of eight parameters on a SPINRCVY statement.

### ABEND

The system abnormally ends the current unit of work on the processor that is causing the excessive spin (abend code X'071') and takes a SLIP dump if the installation is running with the IBM-supplied default for IEASLPxx. Recovery routines for the unit of work are allowed to retry.

### ACR

The system invokes alternate CPU recovery (ACR) processing for the processor causing the excessive spin. The processor is taken offline.

### OPER

The system issues message IEE331A and processes the operator's reply. If the message could not be issued, or if the operator does not respond, the processor that is in an excessive spin is put into a restartable wait state (X'09n'). The operator can respond to the message with ABEND, ACR, TERM, SPIN, or U (equivalent to SPIN) to continue.

### SPIN

Specifies that the spinning processor is to continue spinning. An informational message (IEE178I) is displayed.

### TERM

The system abnormally ends the current unit of work on the processor that is causing the excessive spin (abend code X'071') and takes a SLIP dump if the installation is running with the IBM-supplied default for IEASLPxx. Recovery routines for the unit of work are not allowed to retry.

### SPINTIME=sss

Specifies the excessive spin loop timeout interval, where sss is the number of seconds. sss can be one through three digits but must be at least 10 seconds. For MVS running in a native or basic mode, or



in an LPAR with dedicated CPs, the default is 10 seconds. For MVS running on VM or in an LPAR with shared CPs, the default spin loop timeout interval is 40 seconds.

**Default:** 10 seconds or 40 seconds

**Notes:**

1. In a PR/SM environment, system configuration and weighting affect the amount of processing (CPU cycles) that occurs in each partition during the timeout interval.
2. The specified SPINTIME value affects the default value of the INTERVAL parameter in the COUPLExx member of SYS1.PARMLIB. If the excessive spin parameters are not explicitly set in an EXSPATxx parmlib member, the IBM supplied default spin parameters are used: the derived spin failure detection interval can be 45 seconds or 165 seconds depending on the configuration. See the [INTERVAL parameter in the COUPLExx member](#) for more information.
3. For an MVS system that is running in a non-dedicated PR/SM environment or under VM, if you specify non-default values for SPINTIME, consider the following facts:
  - The more processing power (CPU cycles) available to the system, the less time it needs to resolve a spin loop.
  - The less processing power available to the system, the more time it needs to resolve a spin loop.
  - Specifying a SPINTIME that is too low might cause premature excessive spin conditions.

If your system is running in a logical partition that is sharing central processing resources, and you want to use a SPINTIME value of less than the default time (40 seconds), the BLWSPINR member of SYS1.SAMPLIB contains an exec that can help you evaluate your spintime requirements.

## Example of EXSPATxx

If you specify more than one action, the system executes the actions in the order of their specification. For example, if you code

```
SPINRCVY      ABEND,ACR
SPINTIME=30
```

the system allows the excessive spin to continue for about 30 seconds and then issues a SPIN action before your first recovery action, issuing an informational message and allowing the excessive spin to continue for another 30 seconds. The system then issues ABEND 071 to end the unit of work that is causing the spin and takes a SLIP dump if the installation is running with the IBM-supplied default for IEASLPxx. The recovery routines for that unit of work try to recover; if they fail, the spin is allowed to continue for 30 seconds. Finally, the system initiates ACR (alternate CPU recovery) to take the processor that is causing the spin offline.

**Note:** After the processor is taken offline, it can be brought back online by the operator through the CF CPU(x),ONLINE command.



## Chapter 33. FXEPRMxx (IBM Function Registry for z/OS)

FXEPRMxx contains statements that let you control the IBM Function Registry for z/OS, for example statements that affect the enablement state of individual function entries.

### Parameter in IEASYSxx (or issued by the operator)

**FXE = {x1|(x1,...,xn)}**

The two alphanumeric or national characters, represented by x1 and xn, are appended to FXEPRMxx to identify the FXEPRMxx member or members of parmlib for the IBM Function Registry for z/OS.

### Syntax rules for FXEPRMxx

The following syntax rules apply to FXEPRMxx:

- Use columns 1 through 71. Do not use columns 72 through 80 for data; these columns are ignored.
- At least one delimiter (space or comma) is required between a statement and keyword. Delimiters are not required between keywords.
- Comments may appear in columns 1-71 and must begin with "/\*" and end with "\*/".

### Syntax format of FXEPRMxx

```
{VENDORNAME|VENDOR|VN}(vendornam) | {VENDORSLOT|VS}(vendorslot)}
{PRODUCTNAME|PRODUCT|PN}(productname | {PRODUCTSLOT|PS}(productslot)}
[, {PRODUCTID|PID}(productID)]
[, {INSTANCEID|IID}(instanceID)]
{FUNCTIONNAME|FUNCTION|FN}(functionname | {FUNCTIONSLOT|FS}=functionslot)}
[, {FUNCTIONUPDTYPE|FUNCUPDTYPE|FUT}({AUTHONLY|ANYAUTH})]
ENABLED={YES|NO}
```

### IBM-supplied default for FXEPRMxx

There is no default FXEPRMxx parmlib member assumed if you do not specify FXE= in IEASYSxx.

### Statements and parameters for FXEPRMxx

**{VENDORNAME|VENDOR|VN}(vendornam)**

A string identifying the owning vendor area by name, with optional wildcard use:

- You can use an asterisk (\*) to match a sequence of zero, one, or more characters.
- You can use a question mark (?) to match a single arbitrary character.

Any comparisons to actual registry values for matching purposes will be case-insensitive.

**{VENDORSLOT|VS}(vendorslot)**

A number identifying the owning vendor area by the vendor area slot number in the anchor table. Slot numbers start at 1.

**{PRODUCTNAME|PRODUCT|PN}(productname)**

A string identifying the owning product area by name, with optional wildcard use:

- You can use an asterisk (\*) to match a sequence of zero, one, or more characters.
- You can use a question mark (?) to match a single arbitrary character.

Any comparisons to actual registry values for matching purposes will be case-insensitive.

**{PRODUCTSLOT|PS}(productslot)**

A number identifying the owning product area by the product area slot number in the owning vendor area table. Slot numbers start at 1.

**{PRODUCTID|PID}(productID)**

A string qualifying the owning product area further using a product ID.

Note that although this is shown as optional in the command syntax, this parameter is required to successfully match those products in the registry which are set up with a product ID, for example to distinguish different instances or versions of the same product.

You can use wildcards, as follows:

- You can use an asterisk (\*) to match a sequence of zero, one, or more characters.
- You can use a question mark (?) to match a single arbitrary character.

Any comparisons to actual registry values for matching purposes will be case-insensitive.

**{INSTANCEID|IID}(instanceID)**

A string qualifying the owning product area further, using an instance ID.

Note that although this is shown as optional in the command syntax, this parameter is required to successfully match those products in the registry that are set up with an instance ID, for example to distinguish different instances or versions of the same product.

You can use wildcards, as follows:

- You can use an asterisk (\*) to match a sequence of zero, one, or more characters.
- You can use a question mark (?) to match a single arbitrary character.

Any comparisons to actual registry values for matching purposes will be case-insensitive.

**{FUNCTIONNAME|FUNCTION|FN}(functionname)**

A string identifying the function entry by name, with optional wildcard use:

- You can use an asterisk (\*) to match a sequence of zero, one, or more characters.
- You can use a question mark (?) to match a single arbitrary character.

Any comparisons to actual registry values for matching purposes will be case-insensitive.

**{FUNCTIONSLOT|FS}(functionslot)**

A number identifying the owning function entry by the function entry slot number in the owning product area. Slot numbers start at 1.

**{FUNCTIONUPDTYPE|FUNCUPDTYPE|FUT}({AUTHONLY|ANYAUTH})**

Selects the list of function entries in the owning product area, based on authorization:

**AUTHONLY**

Selects the list of function entries, in the owning product area, which can only be updated by authorized code and the SETFXE command. This is the default value.

**ANYAUTH**

Selects the list of function entries, in the owning product area, which can be updated by code of any authorization level (unauthorized code is required to use the FXECNTRL service), or the SETFXE command.

**ENABLED({YES|NO})**

The desired enablement state to be set in the selected function entry.

## Chapter 34. GRSCNFxx (global resource serialization configuration)

The contents of the GRSCNFxx parmlib member are used during system initialization to define the attributes of global resource serialization processing.

A *global resource serialization complex* consists of two or more systems connected by communication links. The systems in the complex use global resource serialization to serialize any shared resources such as controlling access to data sets on shared DASD volumes at the data set level rather than at the volume level. (For more information, see *z/OS MVS Planning: Global Resource Serialization*.)

The majority of GRSCNFxx parameters are specific to defining a global resource serialization ring complex. However, GRSQ is specific to star mode, and the following keywords are relevant for all modes, including GRS=NONE:

- SYNCHRES
- ENQMAXA
- ENQMAXU
- AUTHQLVL
- MONITOR

To define a global resource serialization ring complex, use the GRSCNFxx parmlib member. GRSCNFxx contains a GRSDEF statement for each system. The statement identifies:

- The name of the system in the complex, by means of the MATCHSYS parameter.
- The CTC links assigned to the system, by means of the CTC parameter.
- The minimum amount of time that the RSA-message is to spend in the system, by means of the RESMIL parameter.
- Whether or not the system identified by the MATCHSYS keyword has the automatic restart capability, by means of the RESTART parameter.
- Whether or not the system identified by the MATCHSYS keyword has the capability to automatically rejoin the complex, by means of the REJOIN parameter.
- The maximum amount of time (the tolerance time interval) before global resource serialization will detect a timeout, by means of the TOLINT parameter.
- The method to establish the global resource serialization ring acceleration function, by means of the ACCELSYS parameter.
- The member of parmlib that contains the default global resource serialization component tracing options, by means of the CTRACE parameter.

There are three basic ways to use GRSCNFxx to define your complex:

1. You can create one GRSCNFxx parmlib member that contains GRSDEF statements that define all of the systems in the complex. After creating the member, copy it to the parmlib on each system. As each system is initialized, it reads the GRSCNFxx member, locates its own GRSDEF statement, and uses the information in the statement during initialization.
2. You can create a unique GRSCNFxx member for each system in the complex. The member consists of a GRSDEF statement for that particular system. You place the unique member in parmlib on that particular system, and that system uses the information it contains during initialization.
3. If all systems in the global resource serialization complex will belong to the same sysplex, you can create one GRSCNFxx member that contains a single GRSDEF statement that defines consistent information for all systems. The IBM-supplied default member, GRSCNF00, can be used for this purpose.

Variations or combinations of these methods are, of course, possible. Which ever method you choose, GRSCNFxx provides information about the configuration of the complex that global resource serialization requires during initialization. Other information that global resource serialization requires comes from the following system parameters (in IEASYSxx):

- GRS=
- GRSCNF=
- GRSRNL=
- SYSNAME=

The GRS, GRSCNF, GRSRNL, and SYSNAME parameters can only be specified at IPL time, either in IEASYSxx or by the operator. They all remain in effect for the duration of the IPL. For specific details about how to specify any one of these parameters, see the description of the parameter provided in [Chapter 56, “IEASYSxx \(system parameter list\),” on page 421.](#)

During initialization processing for a system that is to join an existing complex, global resource serialization verifies that the information in GRSCNFxx is consistent with the existing complex. Even if a system is defined in a GRSCNFxx parmlib member and initialized with GRS=JOIN, it cannot join the complex unless either:

- at least one CTC link associated with the system in GRSCNFxx is attached to another active system in the complex, or
- the system is joining a sysplex (see [Chapter 24, “COUPLExx \(cross-system coupling facility \(XCF\) parameters\),” on page 229](#))

## Parameters in IEASYSxx

|              |  |      |
|--------------|--|------|
| GRS=         | { JOIN<br>{ START<br>{ TRYJOIN<br>{ NONE<br>{ STAR | 1-71 |
| GRSCNF=xx    | { xx   | 1-71 |
| GRSRNL=      | { (xx,yy...<br>{ EXCLUDE                           | 1-71 |
| SYSNAME=name |  |      |

## Syntax rules for GRSCNFxx

The following rules apply to the creation of GRSCNFxx:

- Use columns 1 through 71; columns 72 through 80 are ignored.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/". A comment can span lines and can appear anywhere except within a keyword or a specified value.
- Each GRSDEF statement is defined as beginning with the characters “GRSDEF” and ending with the character immediately preceding the next GRSDEF statement.
- The GRSDEF statement format is:

```

GRSDEF      [MATCHSYS      {(name)
              {(*)
              {(1-8 decimal digit)
              {(OFF)
              [CTC (3-4 hexadecimal digit device number)...
              [RESTART      {(YES)
              {(NO)
              [REJOIN       {(YES)
              {(NO)
              [TOLINT (1-8 decimal digit)
              [ACCELSYS (1-2 decimal digit)
              [CTRACE (parmlib member name)
              [SYNCHRES      {(YES)
              {(NO)
              [GRSQ          {(ALL)
              {(CONTENTION)
              {(LOCAL)
              [ENQMAXA(1-8 decimal digit)]
              [ENQMAXU(1-8 decimal digit)]
              [AUTHQLVL(decimal digit 1 or 2)]
              [MONITOR       {(YES)
              {(NO)

```

**Note:**

1. You can put a blank anywhere except within a keyword or a specified value.
2. You can use as many lines as you need for one GRSDEF statement.
3. You can specify multiple parameters on the same line.
4. No delimiters or blanks are needed between parameters. For example, the following GRSDEF statement is valid:

```
GRSDEF MATCHSYS(*) CTC(9A0)CTC(8B0)CTC(7D0)RESMIL(10)
```

5. Duplicate GRSDEF statements cause a syntax error. A syntax error also occurs if you specify more than one GRSDEF statement with MATCHSYS(\*), either explicitly or by default, or more than one GRSDEF statement with the same MATCHSYS name.
6. If this system is not a member of a sysplex, each GRSDEF statement must include at least one CTC parameter. Each GRSDEF statement can include up to a maximum of 64 CTC parameters.

## IBM-supplied default for GRSCNFxx

Default member GRSCNF00 contains:

```

GRSDEF
  RESMIL(10)
  TOLINT(180)
  ACCELSYS(99)

```

## Statements and parameters for GRSCNFxx

### ACCELSYS(num)

Specifies the threshold for global resource serialization ring acceleration and the number of systems that must see a resource request before it is granted. To use ring acceleration, every system must have a link to every other system. Ring acceleration requires a fully connected complex, and it also requires an alternate link for each connection not in the sysplex. When the ACCELSYS keyword is not specified, ring acceleration is turned off. The maximum performance benefit is provided when the ACCELSYS threshold value is 2.

Specifying a different ACCELSYS value for different systems in a complex is allowed, but the complex uses the highest ACCELSYS value specified to determine when to send the shoulder-tap acknowledgment. If the highest value is greater than the number of systems in the ring, the shoulder-tap acknowledgment does not take place. To ensure that shoulder-tap processing occurs, specify ACCELSYS(num) on all systems in the ring, making sure that the value of *num* is less than the number of systems in the ring.

**Value range:** The ACCELSYS threshold value range is 2 - 99.

**Default:** 99

### CTC(device number)

Identifies the device number of a CTC link that is attached to this system that is dedicated to the use of global resource serialization. Only one device number can be specified on each CTC parameter, but up to 64 different CTC parameters can be specified. If this system is a member of a sysplex, it is not necessary to specify the CTC parameter unless this system must have a link to a system outside of the sysplex.

**Value range:** 3 or 4 hexadecimal digits. The device number cannot be preceded by a slash.

**Default:** None

### CTRACE(member-name)

Specifies the member of SYS1.PARMLIB that contains the default global resource serialization component tracing options.

**Value range:** The 8-character member name must be in the format CTnGRSxx, where:

**n**

An alphanumeric character to specify the source of the member. IBM-supplied members use I.

**xx**

Any two characters to identify the member.

**Default:** CTIGRS00

The contents of CTIGRS00 are as follows:

```
TRACEOPTS
  OFF
  OPTIONS('CONTROL','MONITOR')
  BUFSIZE(16M)
```

For more information about specifying options for the global resource serialization component trace, see *z/OS MVS Diagnosis: Tools and Service Aids*. For information about specifying the component trace member of SYS1.PARMLIB, see [Chapter 26, "CTnccccxx \(component trace parameters\)," on page 249](#).

### GRSQ{ (ALL) }

#### { (CONTENTION) }

#### { (LOCAL) }

The GRSQ keyword is only relevant for star mode. It is ignored for ring and none mode. When the SDATA=GRSQ option is specified, the GRSQ keyword collects global resource serialization information during SYSMDUMP and SVC dump processing. ENQ resource information from all systems in the global resource serialization complex is gathered and placed into the dump. This can be time consuming when running in star mode because global resource serialization needs to collect and merge information from all systems in the sysplex. The time it takes increases as more systems are added to the sysplex or the number of concurrent ENQs increase, or both. The GRSQ keyword allows the installation to limit the data collected and therefore lessen the time that is needed to complete the dump.

- GRSQ(CONTENTION) causes GRSQ processing to collect all ENQ resources on the local system, and only collect information about global resources in contention in the rest of the GRS complex.
- GRSQ(LOCAL) causes GRSQ processing to collect all ENQ resources on the local system only. This is not a recommended value and should only be used as a circumvention. The GQSCAN that is issued does not collect data from the other systems.
- GRSQ(ALL) causes GRSQ processing to collect all ENQ resources from all systems in the entire GRS complex. Specifying GRSQ(CONTENTION) adds WAITCNT=1.

**Default:** CONTENTION



**MATCHSYS{(name)}****{{(\*)}}**

Identifies the system that is defined in the GRSDDEF statement. A system that is being initialized compares the value specified on the SYSNAME system parameter to the value specified for MATCHSYS to locate its GRSDDEF statement in GRSCNFxx. Omitting MATCHSYS or specifying MATCHSYS(\*) is regarded as a match unless a GRSDDEF statement exists with an explicit name that matches the SYSNAME value. Including both a GRSDDEF statement with an explicit MATCHSYS name and a GRSDDEF statement with MATCHSYS(\*), either explicitly or by default, thus does not cause a syntax error; the system ignores the GRSDDEF statement with MATCHSYS(\*).

Global resource serialization initialization processing searches the statements in GRSCNFxx until it finds a GRSDDEF statement that matches the SYSNAME value, then uses the information in the statement to continue initialization. It issues an error message if it finds no match.

**Value range:** 1 - 8 alphanumeric characters, including the @, #, and \$ characters.

**Default:** \*

**MONITOR{(YES)|(NO)}**

Indicates whether the system defined in the GRSCNFxx MATCHSYS parameter is to have GRS SMF 87 monitoring activated.

**Default:** NO

**Note:** See *z/OS MVS Planning: Global Resource Serialization* for more information.

**REJOIN{(YES)|(NO)}**

Indicates whether the system defined in the MATCHSYS parameter can automatically rejoin the active ring, after that system was stopped, then started. Specifying REJOIN(YES) eliminates the need for the operator to issue a VARY GRS, RESTART command to have the system join the active ring.

**Note:** If this system is a member of a sysplex, regardless of what you specify, REJOIN is set to REJOIN(YES).

**Default:** YES

**RESMIL(number|OFF)**

Specifies the RSA-message residency time.

A value, if specified, indicates the minimum RSA-message residency time in milliseconds, (that is, the least amount of time that the RSA-message is to spend in this system). The actual amount of time that the RSA-message will spend in this system will vary between the time you specify in milliseconds and a maximum value calculated by global resource serialization. In this way, global resource serialization balances CPU utilization and ENQ response time. If you omit RESMIL, then the default for the RSA-message residency time is 10 milliseconds.

OFF, if specified, indicates that the RSA-message residency time is zero and that global resource serialization does no tuning. Note that RESMIL(OFF) differs from RESMIL(0). When you specify RESMIL(0), the system tunes the residency time in a range with a minimum of zero.

**Value range:** 0 to 999999999 milliseconds

**Default:** 10 milliseconds

**RESTART{(YES)|(NO)}**

Indicates whether the system defined in the GRSCNFxx MATCHSYS parameter can automatically rebuild a disrupted ring. A disrupted ring occurs when the RSA-message stops moving because of a system failure or a link failure.

**Note:** If this system is a member of a sysplex, regardless of what you specify, RESTART is set to RESTART(YES).

**Default:** YES

**TOLINT(num)**

Specifies, in seconds, the maximum tolerance time interval global resource serialization allows the RSA-message to return to that system, before it considers the RSA-message overdue.

When the TOLINT value specified is not valid, then message ISG008E is issued, the TOLINT keyword is ignored, a default of 3 minutes (180 seconds) is used, and the IPL continues.

**Value range:** The TOLINT value specified must be greater than zero (0), and less than 86000 seconds (24 hours).

**Default:** 180 seconds (3 minutes)

### **SYNCHRES{(YES)|(NO)}**

Indicates whether the system defined in the GRSCNFxx MATCHSYS parameter is to have synchronous reserve processing activated.

**Default:** YES

#### **Notes:**

- If SYNCHRES=YES, but GRS cannot complete the I/O to reserve a device, message ISG363I is issued. The request continues as if SYNCHRES=NO.
- A reserve is done synchronously regardless of any SYNCHRES=NO specification if ZHPF is enabled and the device operates I/O in Transport Mode.

### **[ENQMAXA(value)]**

### **[ENQMAXU(value)]**

Identifies the system-wide maximum of concurrent ENQ requests for authorized (ENQMAXA) or unauthorized (ENQMAXU) requesters.

The ENQMAXA range is 250,000 to 99,999,999. The default MAXVALUE is 250,000.

The ENQMAXU range is 16,384 to 99,999,999. The default MAXVALUE is 16,384.

See *z/OS MVS Planning: Global Resource Serialization* for information about how concurrent ENQ request counts are updated.

### **[AUTHQLVL(value)]**

Indicates the authorized qname level. GRS manages a list of authorized qnames for processing ENQ and DEQ names. If an unauthorized requester attempts to issue an ENQ or DEQ for an authorized qname, GRS fails the request. Although authorized requesters are not required to use qnames from the authorized list, IBM strongly suggests that they use these qnames to provide protection against "denial-of-service attacks", where an unauthorized requester might obtain a critical ENQ resource and not release it.

As of z/OS V1R13 IBM recognizes two authorized qname lists. The default list (AUTHQLVL=1) contains the qnames for many IBM products or services that uses them. IBM recognizes a second authorized qname list (AUTHQLVL=2) that includes additional qnames.

For complete information about the contents of these qname lists and ENQ and DEQ processing for authorized qnames, see "Authorized qnames" in *z/OS MVS Planning: Global Resource Serialization*.

Use the SETGRS AUTHQLVL to dynamically change the value of the level from 2 to 1.

Use the DISPLAY command to return information about the AUTHQLVL value in effect.

For command syntax information, see *z/OS MVS System Commands*.

**Value range:** Either 1 or 2.

**Default:** 1

## Chapter 35. GRSMONxx (global resource serialization monitor)

GRSMONxx consists of two lists of filters for the GRS Monitor. When the GRS Monitor is active, meaning that the GRS MONITOR parameter is YES, the system uses these filters to determine whether to monitor ENQ (ENQ, DEQ, ISGENQ, or RESERVE), GQSCAN, or ISGQUERY REQINFO=QSCAN requests. The following filter lists are included:

### INCLUDE list

Specifies criteria to monitor a request.

### EXCLUDE list

Specifies criteria to prevent the monitoring of a request.

The following items summarize filter processing for a given request:

- The lists are searched in the order of the INCLUDE list and then the EXCLUDE list. If an entry is included on both lists, it is processed according to the EXCLUDE list.
- For a filter to match, all of the sub-keywords (except INCLUDE and EXCLUDE) must match. In effect, a filter is a logical 'AND' of all of the sub-keywords.
- If the request matches any filter on the INCLUDE list, then the request is further checked against the EXCLUDE list.
  - If the request matches a filter on the EXCLUDE list, the request is not monitored.
  - If the request does not match any filter on the EXCLUDE list, and monitoring is active, then the request is monitored.
  - If there is no EXCLUDE list, and monitoring is active, then the request is monitored
- If a GRSMONxx parmlib member is applied but it has no INCLUDE list or monitoring is not active, then the request is not monitored.
- If no GRSMONxx parmlib member is applied and monitoring is active, the GRS monitor remains compatible with OA42221 on lower release levels. In this circumstance, global, generic queue scans are monitored. You can detect this condition by issuing `display GRS[, system]` and observing GRSMON: NONE in response message ISG343I.

For more information about using the GRS monitor, see [z/OS MVS Planning: Global Resource Serialization](#).

Use the **SETGRS** command to change the GRSMONxx parmlib member while the system is active. For more information about the **SETGRS** command, see [z/OS MVS System Commands](#).

## Parameters in IEASYSxx

None.

## Syntax rules for GRSMONxx

The following rules apply to the creation of GRSMONxx:

- Use columns 1 through 71; columns 72 through 80 are ignored.

**Note:** If you need to continue to another line when specifying a value, for example the name on the RNAME parameter, then use multiple quoted strings, delimited by commas, as the value for the parameter.

- Comments may appear in columns 1-71 and must begin with `/*` and end with `*/`. A comment can span lines and can appear anywhere except within a keyword or a specified value.

- Each FILTER statement is defined as beginning with the characters "FILTER" and ending with the character immediately preceding the next FILTER statement.
- In a filter statement, you cannot specify a given keyword more than once.
- Each FILTER statement must begin with FILTER, then specify an action and then a type of request, in that order. For example, FILTER INCLUDE ENQ. Additional keywords are required depending on the specified type of request:
  - FILTERs of type ENQ, which includes DEQ and ENQDEQ, also require both QNAME and RNAME. You can specify QNAME and RNAME in any order after the action and type keywords. The rest of the ENQ keywords are optional.
  - FILTERs of type QSCAN do not have any additional required keywords.
- The following actions occur for a GRSMONxx parmlib member that contains no FILTER statements:
  - The GRSMONxx parmlib member is ignored.
  - The system makes no changes to the GRS monitor filters.
  - Message ISG386I is issued to alert operations in case the empty GRSMONxx parmlib member was specified unintentionally.
  - The system still issues message IEE712I, indicating that the SETGRS command was processed successfully.

The following rules apply to the search processing of GRSMONxx filters:

- A request matches on a filter when all of the criteria in the filter is met. The criteria is defined by specifying type applicable keywords on the FILTER statement.
- You can specify wild cards according to the following usage rules:
  - The QNAME, RNAME, and JOBNAME keywords permit the use of the following wild card characters:

**Asterisk (\*)**

Use an asterisk to match 0 to  $n$  characters in a string where the maximum string size is greater than or equal to  $n$ , which is in turn greater than or equal to 1. See the documentation for each parameter for its maximum string size.

**Question mark (?)**

Use a question mark to match one character in a string.

- Filter match processing occurs under the requester's work unit, for example the requester is the invoker of ENQ, when monitoring is active. Consider the following suggestions to help optimize wild card match performance:
  - Specify the wild card at the end of the string, for example RNAME(IBMUSER.\*).
  - Specify a wild card by itself, for example RNAME(\*)
- Specifying "QNAME(\*) RNAME(\*)" without additional filters is not recommended because it potentially leads to the monitoring of every ENQ request on the system. Due to the high volume of these requests during normal activity, they might consume SMF resources and lead to SMF data loss conditions.

## Syntax format of GRSMONxx

```

FILTER {INCLUDE|INCL|EXCLUDE|EXCL} {ENQ|DEQ|ENQDEQ}
      QNAME(qname_name)
      RNAME({rname_name|
        'beginning_of_rname_name',
        'end_of_rname_name'})
      [SCOPE({STEP|SYSTEM|SYSTEMS|ANY})]
      [JOBNAME(jobname_name)]
      [RESERVE({YES|NO|ANY})]
      [AUTHQLVL({2|NONE})]
      [RNLMATCH({YES|NO|ANY})]
      [WAITER({YES|NO|ANY})]
QSCAN
      [GENERIC({YES|NO|ANY})]
      [XSYS({YES|NO|ANY})]

```

## IBM-supplied default for GRSMONxx

IBM does not supply a default parmlib member for GRSMONxx.

**Tip:** See SYS1.SAMPLIB(ISGMON00), which provides examples of FILTER statements and their general capability.

## Statements and parameters for GRSMONxx

### AUTHQLVL( 2 | **NONE** )

Specifies the Qname level that the filter should match.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:**

**2**

Directs the filter to match any ENQ, DEQ, or ISGENQ request that would fail at AUTHQLVL 2, for example when the requester is not authorized and is making use of an authorized Qname. For more information about authorized Qnames, see [z/OS MVS Planning: Global Resource Serialization](#).

**Note:** You can use AUTHQLVL(2) to help migrate to GRS AUTHQLVL(2).

**NONE**

Directs the filter to match any request.

**Default:** NONE.

### ENQ | DEQ | ENQDEQ | QSCAN

Specifies the type of request that the filter should match.

**Value range:**

**DEQ**

Directs the filter to match DEQ or ISGENQ REQUEST=RELEASE requests.

**ENQ**

Directs the filter to match ENQ, RESERVE, or ISGENQ REQUEST=OBTAIN requests.

**ENQDEQ**

Directs the filter to match both ENQ and DEQ requests as previously defined.

**QSCAN**

Directs the filter to match GQSCAN and ISGQUERY REQINFO=QSCAN requests.

### FILTER

Specifies the beginning of a filter statement.

**GENERIC( YES | NO | ANY )**

Specifies whether to match requests that specify a generic or specific QNAME or RNAME.

**Note:** This keyword is applicable to type QSCAN.

**Value range:**

**YES**

Directs the filter to match requests that specify a non-specific QNAME or RNAME.

**NO**

Directs the filter to match requests that specify a specific QNAME or RNAME.

**ANY**

Directs the filter to match any request.

**Default:** ANY.

**INCLUDE | INCL | EXCLUDE | EXCL**

Specifies the monitoring action that the filter should take.

**Value range:**

**INCLUDE | INCL**

Specifies to include matching requests in monitoring.

**EXCLUDE | EXCL**

Specifies to exclude matching requests from monitoring.

**JOBNAME( *jobname\_name* )**

Specifies a string that represents the JOBNAME of the issuer of the ENQ, RESERVE, or ISGENQ macro.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:** A string of characters that adheres to the following rules:

- Contains between 1 and 8 characters
- May contain wild card characters
- May contain quoted strings to specify characters such as blanks

For more information about the syntax, see [“Syntax rules for GRSMONxx” on page 325](#) and [“Syntax format of GRSMONxx” on page 327](#).

**QNAME( *qname\_name* )**

Specifies a string representing a QNAME value on an ENQ, RESERVE, or ISGENQ macro.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:** A string of characters that adheres to the following rules:

- Contains between 1 and 8 characters
- May contain wild card characters
- May contain quoted strings to specify characters such as blanks

For more information about the syntax, see [“Syntax rules for GRSMONxx” on page 325](#) and [“Syntax format of GRSMONxx” on page 327](#).

**RESERVE( YES | NO | ANY )**

Specifies whether to match requests that, after RNL processing, did or did not result in a hardware reserve.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:**

**YES**

Directs the filter to match requests that, after RNL processing, result in a hardware reserve.

**NO**

Directs the filter to match requests that, after RNL processing, did not result in a hardware reserve.

**ANY**

Directs the filter to match any request.

**Default:** ANY.

**RNAME( *rname\_name* | 'beginning\_of\_rname\_name', 'end\_of\_rname\_name' )**

Specifies the RNAME value on an ENQ, RESERVE, or ISGENQ macro.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:** A string of characters that adheres to the following rules:

- Contains between 1 and 255 characters
- May contain wild card characters
- May contain quoted strings to specify characters such as blanks
- May contain multiple strings delimited by commas to specify RNAME values that are longer than one line
- Exactly matched the RNAME on a request, unless wild card characters are used

For more information about the syntax, see [“Syntax rules for GRSMONxx” on page 325](#) and [“Syntax format of GRSMONxx” on page 327](#).

**RNLMATCH( YES | NO | ANY )**

Specifies whether to match requests that match either the System Inclusion RNL, System Exclusion RNL, or the Reserve Conversion RNL.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:**

**YES**

Directs the filter to match requests that match either the System Inclusion RNL, System Exclusion RNL, or the Reserve Conversion.

**NO**

Directs the filter to match requests that do not match any of the RNLs.

**ANY**

Directs the filter to match any request.

For more information about RNLs, see [Chapter 36, “GRSRNLxx \(global resource serialization resource name lists\),” on page 331](#).

**Default:** ANY.

**SCOPE( STEP | SYSTEM | SYSTEMS | ANY )**

Specifies whether to match requests that match ENQ resources with, after RNL processing, specific scope types.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:**

**STEP**

Directs the filter to match requests that match ENQ resources with a scope type of "STEP."

**SYSTEM**

Directs the filter to match requests that match ENQ resources with, after RNL processing, a scope type of "SYSTEM."

**SYSTEMS**

Directs the filter to match requests that match ENQ resources with, after RNL processing, a scope type of "SYSTEMS."

**ANY**

Directs the filter to match any request.

**Default:** ANY.

**WAITER( YES | NO | ANY )**

Specifies whether to match ENQ/ISGENQ REQUEST=OBTAIN requests that encountered non-waitless contention, meaning they were queued to wait for the resource. This includes ECB-type requests.

**Note:** This keyword is applicable to types ENQ, DEQ, and ENQDEQ.

**Value range:**

**YES**

Directs the filter to match requests that encountered non-waitless contention.

**NO**

Directs the filter to match requests that did not encounter non-waitless contention.

**ANY**

Directs the filter to match any request.

**Default:** ANY.

**XSYS( YES | NO | ANY )**

Specifies whether to match requests that require a cross-system search of GRS Queues in the GRS Complex.

**Note:** This keyword is applicable to type QSCAN.

**Value range:**

**YES**

Directs the filter to match requests that require a search of GRS Queues across all systems in the GRS Complex.

**NO**

Directs the filter to match requests that require a search of only the local system GRS Queues.

**ANY**

Directs the filter to match any request.

**Default:** ANY.



## Chapter 36. GRSRNLxx (global resource serialization resource name lists)

GRSRNLxx consists of three resource name lists (RNLs). When a global resource serialization complex is active, the system uses these RNLs to determine how to treat the resources defined in the RNLs.

The RNLs are:

- The SYSTEM inclusion RNL. The system treats each resource named in this RNL as a global resource if an ENQ or a DEQ macro instruction for the resource specifies a scope of SYSTEM.
- The SYSTEMS exclusion RNL. The system treats each resource named in this RNL as a local resource if an ENQ, DEQ, or RESERVE macro instruction for the resource specifies a scope of SYSTEMS.
- The RESERVE conversion RNL. The system suppresses a hardware reserve for each resource named in this RNL if a RESERVE macro instruction requests the use of the resource.

GRS requires that the RNLs on every system in the GRS complex be exactly the same in order to maintain a consistent serialization protocol. IBM suggests avoiding the use of system symbols in GRSRNLxx in order to reduce the risk of an RNL mismatch during IPL which would result in a disabled wait state. An RNL mismatch can occur when such a system symbol changes in value, and the symbol resolves to a different value on the system attempting to join the complex than on the systems which are active in the complex.

**Note:** Specifying RNL=NO on the ENQ macro bypasses all RNL processing. See *z/OS MVS Programming: Assembler Services Guide* for information about the ENQ macro.

Use the SET GRSRNL command to change the RNL list while the system is active. For more information, see *z/OS MVS System Commands*.

See *z/OS MVS Planning: Global Resource Serialization* for detailed information about global resource serialization, RNLs, and the RNL syntax checker. The RNL syntax checker lets you check the syntax of GRSRNL parameters specified on the JCL and resource names specified in GRSRNLxx.

### Parameter in IEASYSxx (or supplied by the operator)

```
GRSRNL= {aa
        {(aa,bb...)}
        {EXCLUDE
        }
```

The two alphanumeric characters, represented by aa (or bb, and so forth), are appended to GRSRNL to form the name of the GRSRNLxx member. If GRSRNL=EXCLUDE is specified, no RNLs are to be used in the complex and all resources are treated as local.

### Support for system symbols

Any static symbols used must be consistent across the GRS complex. If the symbols used in the RNL members resolve to different values, the RNL specifications for each system will differ. GRS requires that the RNL specification used for system initialization matches the current specification for the rest of the complex. If the RNL specifications do not match, GRS puts the initializing system into a non-restartable wait state.

### Syntax rules for GRSRNLxx

The following rules apply to the creation of GRSRNLxx:

- Use columns 1 through 71; columns 72 through 80 are ignored. Note that if you need to continue to another line when specifying a value (such as the name on the RNAME parameter), you must start the continuation in column 1.
- Comments may appear in columns 1-71 and must begin with /\* and end with \*/. A comment can span lines and can appear anywhere except within a keyword or a specified value.
- Each RNLDEF statement is defined as beginning with the characters RNLDEF" and ending with the character immediately preceding the next RNLDEF statement.
- Each RNLDEF statement must contain, in any order, the RNL, TYPE, QNAME, and RNAME parameters. For example:

```
RNLDEF RNL(INCL) TYPE(SPECIFIC) QNAME(SYSDTNM)
      RNAME(SYS1.USR)

RNLDEF RNL(INCL) TYPE(GENERIC) QNAME(SYSDTNM)
      RNAME(SYS1.U)

RNLDEF RNAME(SYS1.U) TYPE(GENERIC) RNL(INCL)
      QNAME(SYSDTNM)
```

Exceptions to this are:

- The RNAME parameter can be omitted if TYPE(GENERIC) is specified for a generic QNAME resource. For example:

```
RNLDEF TYPE(GENERIC) QNAME(X'1A4A783F2B') RNL(EXCL)
```

- A null GRSRNLxx parmlib member is valid. The system does not consider a member in error if it is empty; that is, if it contains neither RNLDEF statements nor comments.
- A specific resource name entry matches a search argument only when they are the same.

A match occurs only when the length of the RNAME value on the RNLDEF statement is the same as the length of the RNAME value that is coded on the ISGENQ, ENQ, or RESERVE macro, and only when the RNAME value on the RNLDEF statement is the same as RNAME value coded on the ISGENQ, ENQ, or RESERVE macro. For example:

Assume that an RNLDEF statement is coded as follows to add an entry in the Systems Exclusion List:

```
RNLDEF RNL(EXCL) TYPE(SPECIFIC) QNAME(MYQNAME) RNAME(ABC)
```

Further assume that an application program is coded to issues an ENQ and defines the length of the RNAME as 44 bytes with blanks filled to the right of 'ABC':

```
ENQ (QAM,RNAM,E,L'RNAM'),MF=(E,XENQ)
.
.
.
RNAM DC CL44'ABC'
```

In this case, the length of the RNAME value on the RNLDEF statement does not match the length of the RNAME value that is coded on ENQ macro. You can correct this by taking one of the following actions:

- Change the RNLDEF statement to specify the correct RNAME length and value:

```
RNLDEF RNL(EXCL)TYPE(SPECIFIC)QNAME(MYQNAME)RNAME(X'C1C2C34040404040...40')
[not all blanks are shown]
```

- Change the RNLDEF statement from a specific to a generic type:

```
RNLDEF RNL(EXCL) TYPE(GENERIC) QNAME(MYQNAME) RNAME(ABC)
```

- Change the RNLDEF statement from a specific to a pattern type using any one of the following variations:

```
RNLDEF RNL(EXCL) TYPE(PATTERN) QNAME(MYQNAME) RNAME(*)
RNLDEF RNL(EXCL) TYPE(PATTERN) QNAME(MYQNAME) RNAME(ABC*)
```

- Change the application program to eliminate the blank fill:

```
ENQ    (QNAME,RNAME,E,L'RNAME),MF=(E,XENQ)
.
.
.
RNAME    DC    CL3'ABC'
```

Change the length of the RNAME, if the length is hardcoded on the ENQ macro.

**Note:**

1. You can put a blank anywhere except within a keyword or a specified value.
2. You can use as many lines as you need for one RNLDEF statement.
3. You can specify multiple parameters on the same line.
4. You do not need to put a blank (or other delimiter) between parameters. For example, the following RNLDEF statement is valid:

```
RNLDEF RNL(EXCL) TYPE(SPECIFIC) QNAME(SYSDSN) RNAME(SYS1.BROADCAST)
```

5. You can use from 1 to 8 characters for the name that you specify on the QNAME parameter. You must enclose the name in parentheses.
6. You can use from 1 to 255 characters for the name that you specify on the RNAME parameter. You must enclose the name in parentheses. Any complete line of blanks (columns 1-71) will be ignored when specifying a value for the RNAME.
7. You can specify the names on the QNAME and RNAME parameters in any of the following formats:
  - If the name contains characters that cannot display, you must use two hexadecimal digits to specify each character of the name. For example:

```
RNLDEF RNL(INCL) TYPE(GENERIC) QNAME(X'18')
      RNAME(X'19')
```

- If the name contains displayable characters that are alphanumeric (A-Z and 0-9), \*, ?, #, @, and \$, or a period (.), enter the name as is. or example:

```
RNLDEF RNL(EXCL) TYPE(GENERIC) QNAME(STW@7)
      RNAME(REW.20)
```

- If the name contains displayable characters other than those already described (including a blank, but excluding a single quotation mark), enclose the name in single quotation marks. For example:

```
RNLDEF RNL(CON) TYPE(SPECIFIC) QNAME('$ ( ) *')
      RNAME('A B')
```

## IBM-supplied default for GRSRNLxx

IBM provides default RNL statements in GRSRNL00 (the default member). See *z/OS MVS Planning: Global Resource Serialization* for the default statements and their meaning.

## Statements and parameters for GRSRNLxx

### QNAME(name)

Specifies the major name of the resource.

### RNAME(name)

Specifies the minor name of the resource.

```
RNL  {(INCL)}
      {(EXCL)}
      {(CON) }
```

Specifies the RNL in which the resource name entry is to be placed.

**CON**

Indicates the RESERVE conversion RNL.

**EXCL**

Indicates the SYSTEMS exclusion RNL.

**INCL**

Indicates the SYSTEM inclusion RNL.

The RNLs on all systems in the complex must be the same. Every RNL on each system must contain the same resource name entries, and that these resource name entries must appear in the same order.

```
TYPE    { (GENERIC) }
        { (SPECIFIC) }
        { (PATTERN) }
```

Specifies the type of resource name entry that is being defined in the RNL.

**GENERIC**

Indicates that this entry may match multiple resources.

- If RNAME is omitted, this entry matches a resource with the specified QNAME and any RNAME.
- If RNAME is provided, this entry matches a resource with the specified QNAME and an RNAME that is either the same as the provided RNAME or begins with the provided RNAME.
- QNAME must match exactly.

There is an equivalent TYPE(PATTERN) RNL definition for a TYPE(GENERIC) RNL definition.

- TYPE(GENERIC) QNAME(q) with RNAME omitted is equivalent to TYPE(PATTERN) QNAME(q) RNAME(\*).
- TYPE(GENERIC) QNAME(q) RNAME(r) is equivalent to TYPE(PATTERN) QNAME(q) RNAME(r\*).

Processing of TYPE(GENERIC) RNL entries is a little faster than processing the equivalent TYPE(PATTERN) RNL entries.

**PATTERN**

Indicates that the resource name in the RNL entry is a pattern that must fit the resource name that is specified on the ENQ request. You can use wildcard characters (\* or ?) in either part of the resource name.

**\***

Allows matching for a substring of any characters for any length, including zero.

**?**

Allows matching for any single character.

For example:

```
RNLDEF RNL (EXCL) TYPE (PATTERN)
QNAME (SYSDSN)
RNAME (SYS1.*.PARMLIB)
```

You can convert all hardware RESERVEs to global ENQ with the following specification:

```
RNLDEF RNL (CON) TYPE (PATTERN)
QNAME (*)
```

**Note:** This is recommended only on systems that are using GRS Star.

**SPECIFIC**

Specify a QNAME (major name) and an RNAME (minor name) for the resource.

## Chapter 37. GTFPARM (generalized trace facility parameters)

GTFPARM provides default or installation-defined trace options to control the generalized trace facility (GTF). The member is read only when the operator (or an automatic command) issues START GTF. GTFPARM is not used during system initialization.

The member name on the START command can be the same as the IBM-supplied cataloged procedure, GTF. The PROC statement of that procedure identifies GTFPARM as the member from which GTF will get its trace parameters. If the installation wants to place the GTFPARM member in a data set other than SYS1.PARMLIB, specify the alternate data set in the SYSLIB DD statement and then specify a member from that PDS using the MEMBER keyword. If the installation wants to substitute another member in place of GTFPARM, the operator may enter the replacement member name on the START command with the MEMBER keyword.

The IBM procedure, GTF, as supplied in SYS1.PROCLIB, contains these statements:

```
//GTFNEW PROC      MEMBER=GTFPARM
//IEFPROC EXEC      PGM=AHLGTF,PARM='MODE=EXT,DEBUG=NO,
                    TIME=YES',TIME=1440,REGION=2880K
//IEFRDOR DD        DSN=SYS1.TRACE,UNIT=SYSDA,
//                  SPACE=(TRK,20),DISP=(NEW,KEEP)
//SYSLIB DD          DSN=SYS1.PARMLIB(&MEMBER),DISP=SHR
```

For further analysis of this procedure and additional information about GTF trace options, see *z/OS MVS Diagnosis: Tools and Service Aids* or the GTF topics in *z/OS MVS Diagnosis: Tools and Service Aids*.

Because default options in GTFPARM specify minimal data for only a limited number of traced events, you may wish to tailor GTF to trace specific events for problem determination purposes through one of the following methods:

- Specify another SYS1.PARMLIB member name, using the MEMBER keyword on the START command.
- Change the trace options in GTFPARM.
- Change the SYSLIB DD statement of the IBM procedure to specify a parmlib member that has the options you want.
- Retain the IBM procedure to handle default options, and write one or more alternate procedures, each specifying a different alternate parmlib member. You could design each member to contain GTF options useful under particular circumstances. Instruct the operator when to issue the START command for each member name.

GTF tries to read parameters from the specified parmlib member. If an error occurs in opening or reading the member, or if GTF detects a syntax error, it writes a diagnostic message to the operator, and requesting that SPECIFY TRACE OPTIONS be used, as if no GTF parmlib member were available. The operator therefore must have a complete list of desired GTF parameters available when he starts GTF.

### Parameter in IEASYSxx (or issued by the operator)

None.

### Syntax rules for GTFPARM

The following rules apply to the creation of a GTF parmlib member:

- Specify the TRACE keyword and its main options only on the first record. Do not place them on subsequent records. For example,

```
Record #1:      TRACE=IOP,SVCP,SSCH
```

This example requests the tracing of specific I/O interrupts, specific SVC interrupts, and all start subchannel and resume subchannel operations.

- The second and subsequent records should contain only “prompting” keywords, such as IO= or SVC=. These keywords provide for detailed operands that indicate which I/O interrupts or which SVC interrupts should be traced. For example, the IOP and SVCP keywords in the Record #1 example (above) must be followed by prompting records that name specific device numbers and specific SVC numbers for which interrupts should be traced. As an example,

Record #2: IO=(191,192,102A),SVC=(1,2,3)

If the specific operands of any prompting keyword are missing, GTF does not prompt the operator. It accepts a general specification. For example, if IOP is specified in Record #1, and Record #2 specifies only SVC=(1,2,3), and no particular device numbers are specified for I/O tracing, GTF assumes that tracing of I/O interrupts is desired for all devices.

When all of the records have been read, GTF issues message AHL103I TRACE OPTIONS SELECTED -- IO,SVC=(1,2,3). The operator can then respond to message AHL125A RESPECIFY TRACE OPTIONS OR REPLY U by either entering all the desired options or accepting the input that was specified in the parmlib member.

- An END keyword or an end-of-file must follow all prompting keywords. If the END keyword is used, it must appear either on the last record supplying prompting keywords or on its own record.
- Lines that begin with an asterisk in column 1 are comments.
- If you need to specify additional operands for the same keyword, restate the keyword and the additional operands in a subsequent prompting record. The previous examples, expanded to include additional SVC numbers and an END keyword, would appear like this:

Record #1: TRACE=IOP,SVCP,SSCH  
 Record #2: IO=(191,192,102A),SVC=(1,2,3)  
 Record #3: SVC=(4,5,6,7,8,9,10),END

- Certain trace options do not work in combination with others. [Table 23 on page 336](#) shows those trace options that should not be specified together. If you specify two or more options from the same horizontal row, GTF uses the option in the lowest numbered column and ignores the other options. For example, if you specify both SYSP and SVC (row C), GTF uses SYSP and ignores SVC.

| Table 23. Combining certain GTFPARM options |      |      |     |       |      |
|---|------|------|-----|-------|------|
|   | 1    | 2    | 3   | 4     | 5    |
| A   | SYSM | SYSP | SYS | SSCHP | SSCH |
| B   | SYSM | SYSP | SYS | IOP   | IO   |
| C   | SYSM | SYSP | SYS | SVCP  | SVC  |
| D   | SYSM | SYSP | SYS | PIP   | PI   |
| E   | SYSM | SYSP | SYS | EXT   |      |
| F   | SYSM | SYSP | SYS | RR    |      |
| G   | SYSM | SYSP | SYS | CSCH  |      |
| H   | SYSM | SYSP | SYS | HSCH  |      |
| I   | SYSM | SYSP | SYS | MSCH  |      |
| J   | SYSM | SYSP | SYS | XSCH  |      |
| K   | URSP | USR  |     |       |      |
| L   | CCWP | CCW  |     |       |      |

## IBM-supplied default for GTFPARM

When GTF is started by specifying the IBM-supplied cataloged procedure, the following options exist in GTFPARM:

```
TRACE=SYSM,USR,TRC,DSP,PCI,SRM
```

These keywords cause the following events to be recorded: SVC interruptions, I/O interruptions, program-controlled I/O (PCI) interruptions, program interruptions, external interruptions, dispatcher executions, start subchannel and resume subchannel operations, clear subchannel operations, halt subchannel operations, modify subchannel operations, entries to the system resource manager, entries to recovery routines, events associated with GTF (TRC), and data passed to GTF via the GTRACE macro (USR). All keywords except USR result in minimal format trace entries. USR entries are the length specified by the user in the GTRACE macro. Such entries may optionally be a maximum of 8192 bytes, excluding the prefix.

**Note:** If you use the default options provided, be aware that some data will be duplicated by the system trace if it is executing concurrently with GTF.

## Statements and parameters for GTFPARM

Only the options that are provided in the IBM default member, GTFPARM, are described. For a complete list and description of GTF options, see *z/OS MVS Diagnosis: Tools and Service Aids*.

### DSP

This parameter requests recording for all dispatchable units of work (SRB, LSR, TCB, and SVC prologue dispatch events). The option is not included in the specification of SYS or SYSM. It must be specified in addition to other parameters. The parameter produces comprehensive format except when SYSM is also specified. With SYSM, data is in minimal format.

### END

This parameter indicates the end of the prompting records. In the parmlib member, an end of file serves the same purpose. Never include the END parameter in the first record (the record that contains the TRACE parameters) because GTF regards such an occurrence as an error.

### PCI

This parameter requests that program-controlled I/O interruptions (PCIs) be recorded in the same format as other requested I/O trace records. If specific device numbers are specified through prompting records, program controlled I/O interruptions are recorded for the specified devices. I/O tracing must be requested because PCI must be specified with a GTF parameter that causes IO, such as SYS or SYSM.

### SRM

This parameter requests a trace entry each time that the system resource manager (SRM) is invoked. The option is not included in the specification of SYS or SYSM. It must be specified in addition to other parameters. Data is in comprehensive format except when SYSM is also specified. Comprehensive format includes the job name.

### SYSM

This parameter requests recording of minimal trace data for all external interruptions (EXT), program interruptions (PI), recovery routines (RR), and supervisor call interruptions (SVC). SYSM causes recording of all I/O interruption (IO), start subchannel and resume subchannel operations (SSCH), clear subchannel operations (CSCH), halt subchannel operations (HSCH), modify subchannel operations (MSCH), and cancel subchannel operations (XSCH). When you specify DSP, RNIO, or SRM, in addition to SYSM, GTF produces minimal trace data for those events.

**Note:** Specification of SYS, SYSM, or SYSP causes GTF to ignore the following trace options if you specify them in any form: CSCH, HSCH, MSCH, SSCH, XSCH, IO, SVC, PI, EXT, RR.

### TRC

This parameter requests that traced events include those related to GTF processing itself. If this parameter is not specified, GTF-related events are excluded from the trace output.

## **GTFPARM**

### **USR**

This parameter requests that user data passed to GTF through the GTRACE macro is recorded with the system data.



## Chapter 38. GTZPRMxx (Generic Tracker parameters)

GTZPRMxx parmlib members contain statements that control the behavior of Generic Tracker. The statements are as follows, in order of importance:

- TRACKING (enable or disable tracking)
- EXCLUDE (add an EXCLUDE statement)
- DEBUG (add a DEBUG statement)
- CLEAR (reset or clear settings, statistics, and data)
- DIAGNOSE (for service and internal analysis)

To specify which list of GTZPRMxx members that the tracking facility should consider, use one of these options:

- The system parameter GTZ on the reply to message IEA101A at IPL time, via `GTZ={xx | (xx, . . . , zz)}`.
- The system parameter GTZ in IEASYSxx, via `GTZ={xx | (xx, . . . , zz)}`.
- The operator command `SET GTZ={xx | (xx, . . . , zz)}`.

Additional references and an overview for the tracking facility can be found in *z/OS MVS Diagnosis: Tools and Service Aids*. The overview also describes how to create GTZPRMxx (Generic Tracker) parmlib members from existing CNIDTRxx (Console Tracker) parmlib members by using the utility program GTZCNIDT.

The syntax of GTZPRMxx parmlib members is a sequence of zero or more statements. The statements have the same syntax and semantics as the corresponding SETGTZ subcommands; you only have to drop the SETGTZ command prefix. Both the SETGTZ command and the parmlib statements support `keyword=value` and `keyword (value)` syntax, but the preferred syntax for each is "keyword=value" for the SETGTZ command and "keyword (value)" for the parmlib syntax.

For more information about the SETGTZ subcommands, see the [SETGTZ command](#) in *z/OS MVS System Commands*.

When multiple statements are specified in a GTZPRMxx parmlib member, the parser attempts to recover from erroneous statements and will try to continue processing any remaining statements.

### Parameters in IEASYSxx (or supplied by the operator)

```
GTZ={xx | (xx, . . . , zz)}
```

The two-character identifier (xx, zz, and so forth) is appended to GTZPRM to identify the GTZPRMxx member of SYS1.PARMLIB. If GTZ= is not provided in IEASYSxx, nor on the reply to message IEA101A at IPL time, no default is chosen.

### Syntax rules for GTZPRMxx

Use the general syntax rules listed in "General syntax rules for the creation of members" on page 7 with the following exceptions and additions for GTZPRMxx:

- Line continuation characters are not needed.
- Statements do not have to be specified in all uppercase.

## Syntax format of GTZPRMxx

```
[PERSIST({OFF|SMF})]

[TRACKING({ON|OFF})]

[CLEAR({TRACKDATA|EXCLUDE|DEBUG|ALL})]

[EXCLUDE(filter)] with filter:
  ALL
  | [ OWNER({owner-filter-text| *})]
  { [ SOURCETYPE(ALL)]
  | [ SOURCETYPE(NOPATH) [ SOURCE({source-filter-text| *})]]
  | [ SOURCETYPE(PATH) [ SOURCEPATH({sourcepath-filter-text| *})]]}]
  [ EVENTDESC({event-description-filter-text| *})]
  [ EVENTDATA({event-data-filter-value| *})]
  [ EVENTJOB({event-job-filter-text| *})]
  [ EVENTASID({event-ASID-filter-value| *})]
  { [ PROGRAMTYPE(ALL)]
  | [ PROGRAMTYPE(NOPATH) [ PROGRAM({program-filter-text| *})]]
  | [ PROGRAMTYPE(PATH) [ PROGRAMPATH({programpath-filter-text| *})]]}]
  [ PROGRAMOFFSET({program-offset-filter-value| *})]
  [ HOMEJOB({home-job-filter-text| *})]
  [ HOMEASID({home-ASID-filter-value| *})]

[DIAGNOSE(ACTION(action) VALUE(value))]

[DEBUG(
ACTION({ABEND|DUMP})
REASON(usrdsn)
LIMIT({actionlimit|NOLIMIT})
filter)]
with filter:
  ALL
  | [ OWNER({owner-filter-text| *})]
  { [ SOURCETYPE(ALL)]
  | [ SOURCETYPE(NOPATH) [ SOURCE({source-filter-text| *})]]
  | [ SOURCETYPE(PATH) [ SOURCEPATH({sourcepath-filter-text| *})]]}]
  [ EVENTDESC({event-description-filter-text| *})]
  [ EVENTDATA({event-data-filter-value| *})]
  [ EVENTJOB({event-job-filter-text| *})]
  [ EVENTASID({event-ASID-filter-value| *})]
  { [ PROGRAMTYPE(ALL)]
  | [ PROGRAMTYPE(NOPATH) [ PROGRAM({program-filter-text| *})]]
  | [ PROGRAMTYPE(PATH) [ PROGRAMPATH({programpath-filter-text| *})]]}]
  [ PROGRAMOFFSET({program-offset-filter-value| *})]
  [ HOMEJOB({home-job-filter-text| *})]
  [ HOMEASID({home-ASID-filter-value| *})]
```

## IBM-supplied default for GTZPRMxx

There is no default GTZPRMxx parmlib member assumed if GTZ= is not specified. You can refer to SYS1.PARMLIB(GTZPRM00) for a working GTZPRMxx parmlib member that contains recommended statements (mainly exclusions in the form of EXCLUDE statements) as known to IBM when a new release becomes available.

To see if there is a more current version of the GTZPRM00 parmlib member, check [z/OS downloads](http://www.ibm.com/systems/z/os/zos/downloads) ([www.ibm.com/systems/z/os/zos/downloads](http://www.ibm.com/systems/z/os/zos/downloads)).

## Statements and parameters for GTZPRMxx

### PERSIST({OFF|SMF})

#### OFF

The tracking facility does not attempt to persist GTZ data. In general, GTZ data is kept in dynamic storage of the GTZ address space. When the system or GTZ is shut down, this data is lost unless it was either extracted or persisted, as follows:

- Extracted by using GTZ tools such as the DISPLAY GTZ operator command, the GTZPRINT tool, the GTZQUERY service, or the GTZLQRY REXX function before the shutdown takes place.
- Persisted in parallel to being stored in dynamic storage. See the SMF statement description.

**SMF**

The tracking facility attempts to persist GTZ data in form of SMF records. There might be other options in effect that can prevent the actual writing of such data. See, for example, the TYPE|NOTYPE options in the SMFPRMxx parmlib member.

The SMF record type for GTZ data is 125, with one subtype of value 1. Subtype 1 records contain persisted TRACKDATA information. Mapping macro GTZZSMF1 describes the fields of these type 125 records. See also the utility programs GTZSMFU2 and GTZSMFU3, which can be used to format these type 125 records in text form.

TRACKDATA that was collected by the tracking facility before SMF persistence was enabled is not recorded in SMF records.

**Default:** None. The Generic Tracker starts with data persistence initially disabled.

**TRACKING({ON|OFF})**

Enables or disables tracking for the Generic Tracker.

**ON**

Enables tracking. The tracking facility honors GTZTRACK service requests and record data as appropriate.

**OFF**

Disables tracking. The tracking facility ignores all GTZTRACK service requests and does not record any data. Tracking data, GTZPRMxx information, or related statistics are not deleted and will continue to be accumulated after a future TRACKING=ON request. To remove data from the facility, use the CLEAR command. To retrieve any data, use the DISPLAY GTZ command, the GTZQUERY service, or the GTZPRINT utility.

**Default:** None. The Generic Tracker starts with TRACKING initially disabled (OFF).

**CLEAR({TRACKDATA|EXCLUDE|DEBUG|ALL})**

Removes and resets assorted tracking facility data, settings, and statistics.

**TRACKDATA**

Removes all tracked instances and related data, such as occurrence counts and time stamps for unique instances from the facility.

**EXCLUDE**

Removes all EXCLUDE statements and related data such as hit statistics for EXCLUDE statements from the facility.

**DEBUG**

Removes all DEBUG statements and related data such as hit statistics for DEBUG from the facility.

**ALL**

Executes all the actions for EXCLUDE, DEBUG, and TRACKDATA. It also resets additional statistics such as the list of suffixes for the GTZPRMxx parmlib members.

**Default:** None.

**EXCLUDE(*filter*)**

Adds an EXCLUDE statement to the tracking facility. The EXCLUDE statement consists of a filter for tracked instances. Any future GTZTRACK request with data that matches the filter are not recorded, and any matching recorded instances that have been tracked are cleared from the facility.

When trackdata comes in, if both an EXCLUDE statement and a DEBUG statement apply, the debug program is triggered and the tracked instance is not recorded.

Duplicate EXCLUDE statements are ignored by the system.

***filter***

Any tracked instance that matches the whole filter (all the filter pieces, OWNER, SOURCE,... match their GTZTRACK-based counterparts) are excluded from being recorded for future GTZTRACK calls, and are cleared from the facility for past GTZTRACK data that was already recorded.

**ALL**

All tracked instances are matched and excluded. ALL is the default.

**OWNER({owner-filter-text|\*})**

To be compared to the OWNER value of a tracked instance as specified on its GTZTRACK request.

**owner-filter-text**

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. The value can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (all character sequences of zero or more characters are matched).

**SOURCETYPE(ALL)**

SOURCETYPE is optional.

**ALL**

Any tracked instances with either a SOURCE or SOURCEPATH value is matched. No further filtering is provided.

**Default:** ALL.

**SOURCETYPE(NOPATH)[SOURCE({source-filter-text|\*})]****NOPATH**

Only tracked instances with a SOURCE are matched. Optionally a specific SOURCE filter value can be specified. Tracked instances with a SOURCEPATH value are not matched.

**SOURCE**

To be compared to the SOURCE value of a tracked instance (as specified on its GTZTRACK request). SOURCE can only be specified for SOURCETYPE=NOPATH.

**source-filter-text**

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. It can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters

**Default:** \* (matches any character sequence of zero or more characters).

**SOURCETYPE(PATH)[SOURCEPATH({sourcepath-filter-text|\*})]**

To be compared to the SOURCEPATH value of a tracked instance (as specified on its GTZTRACK request). SOURCEPATH can only be specified for SOURCETYPE=PATH.

**PATH**

Only tracked instances with a SOURCEPATH are matched. Optionally, a SOURCEPATH filter can be specified. Tracked instances with a SOURCE value are not matched.

**SOURCEPATH****sourcepath-filter-text**

Must be 1-1024 characters and be surrounded by single quotation marks ('). The value is case-sensitive.

No blanks are removed.

The single quotation marks do not count toward the maximum length.

The specified value can contain wildcard characters anywhere in the string. It can also contain any EBCDIC character, but it cannot contain only blanks or X'00'. IBM recommends using printable characters.

**\***

Matches all SOURCEPATH values. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. A single asterisk can be specified without any single quotation marks.

**Default:** \* (matches all sourcepath values).

#### **EVENTDESC({*event-description-filter-text*|\*})**

To be compared to the EVENTDESC value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-description-filter-text***

The value must be 1-64 characters and be surrounded by single quotation marks ('). The single quotation marks do not count toward the maximum length.

The specified value can contain wildcard characters anywhere in the string. A question mark (?) matches a single arbitrary character. The value can also contain any EBCDIC character, but not just blanks or just X'00'. IBM recommends using printable characters.

No blanks are removed.

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters).

#### **EVENTDATA({*event-data-filter-value*|\*})**

To be compared to the EVENTDATA value of a tracked instance as specified on its GTZTRACK request.

##### ***event-data-filter-value***

The EVENTDATA value is interpreted as a 16-byte value. It can be specified in one of the following ways:

- In hexadecimal format as one of X'hh' or 0hhx or 'hh'X or xhh, with *hh* representing 1-32 hexadecimal digits (A-F, a-f, 0-9).
- As a decimal number.

**\***

Matches all of the EVENTDATA values.

**Default:** \* (matches all of the EVENTDATA values).

#### **EVENTJOB({*event-job-filter-text*|\*})**

To be compared to the event address space job name, as derived from the EVENTASID value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-job-filter-text***

The value must be 1-8 characters. It can contain wildcard characters anywhere in the string. A question mark (?) matches a single arbitrary character. It can only contain alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters).

#### **EVENTASID({*event-ASID-filter-value*|\*})**

To be compared to the EVENTASID value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-ASID-filter-value***

The EVENTASID value is interpreted as a 16-bit binary value. It can be specified in hexadecimal format (for example, X'82C1', 082C1x, '82C1'X, or x82C1) or in decimal format (for example, 33473).

**\***

Matches all of the EVENTASID values.

**Default value:** \* (matches all of the EVENTASID values).

### **PROGRAMTYPE(ALL)**

PROGRAMTYPE is optional.

#### **ALL**

Any tracked instances with either a PROGRAM or PROGRAMPATH value is matched. No further filtering is provided.

**Default:** ALL.

### **PROGRAMTYPE(NOPATH)[PROGRAM({*program-filter-text*|\*})]**

#### **NOPATH**

Only tracked instances with a PROGRAM are matched. Optionally a specific PROGRAM filter value can be specified. Tracked instances with a PROGRAMPATH value are not matched.

#### **PROGRAM**

To be compared to the PROGRAM value of a tracked instance (as specified on its GTZTRACK request). PROGRAM can only be specified for PROGRAMTYPE=NOPATH.

#### ***program-filter-text***

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #) or wildcard characters. It can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters

**Default:** \* (matches any character sequence of zero or more characters).

### **PROGRAMTYPE(PATH)[PROGRAMPATH({*programpath-filter-text*|\*})]**

To be compared to the PROGRAMTYPE value of a tracked instance (as specified on its GTZTRACK request). PROGRAMPATH can only be specified for PROGRAMTYPE=PATH.

#### **PATH**

Only tracked instances with a PROGRAMPATH are matched. Optionally, a PROGRAMPATH filter can be specified. Tracked instances with a PROGRAMPATH value are not matched.

#### **PROGRAMPATH**

#### ***programpath-filter-text***

Must be 1-1024 characters and be surrounded by single quotation marks ('). The value is case-sensitive.

No blanks are removed.

The single quotation marks do not count toward the maximum length.

The specified value can contain wildcard characters anywhere in the string. It can also contain any EBCDIC character, but it cannot contain only blanks or X'00'. IBM recommends using printable characters.

**\***

Matches all PROGRAMPATH values. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. A single asterisk can be specified without any single quotation marks.

**Default:** \* (matches all *programpath* values).

### **PROGRAMOFFSET(*programoffset-filter-value*|\*)**

To be compared to the program offset, as derived from the EVENTADDR value of a tracked instance (as specified on its GTZTRACK request).

***programoffset-filter-value***

If PROGRAMOFFSET is specified, the *programoffset* value is interpreted as an 8-byte binary value that can be specified in hexadecimal format (for example, X 'C2', 0C2x, 'C2'X, or xC2) or decimal format (for example, 193).

**\***

Matches all of the the PROGRAMOFFSET values.

**Default:** \* (matches all of the PROGRAMOFFSET values).

**HOMEJOB({*home-job-filter-text*|\*})**

To be compared to the home address space job name as derived from the dispatchable unit under which a tracked instance's GTZTRACK request was executed.

***home-job-filter-text***

Must be 1-8 characters. It can only contain alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. It can contain wildcard characters anywhere in the string. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches all of the the HOMEJOB values.

**Default:** \* (matches all of the HOMEJOB values).

**HOMEASID({*home-ASID-filter-value*|\*})**

To be compared to the ID of the home address space as derived from the dispatchable unit under which a tracked instance's GTZTRACK request was executed.

***home-ASID-filter-value***

16-bit binary value. It can be specified in hexadecimal format (for example, X '82C1', 082C1x, '82C1'X, or x82C1) or in decimal format (for example, 33473).

**\***

Matches all the HOMEASID values.

**Default:** \* (matches all of the HOMESAID values).

**DIAGNOSE(ACTION=*action*,VALUE=*value*)**

Use the DIAGNOSE statement only as directed and when requested by IBM Service personnel to aid in collecting diagnostic information.

**DEBUG(**

**ACTION({*ABEND*|*DUMP*})**

**REASON(*user-reason-code*)**

**LIMIT({*actionlimit*|*NOLIMIT*})**

***filter*)**

**ACTION({*ABEND*|*DUMP*})****ABEND**

For matching GTZTRACK requests, the system triggers a non-percolating ABEND with system completion code X 'E77' and with a reason code as specified by REASON. This action is recommended when a matching track request is made when SLIP processing is available, since SLIP allows a number of actions for when this ABEND is trapped, including creating an SVC dump. For example:

```
SLIP SET,ENABLE,ID=TRAK,COMP=E77,REASON=34,ACTION=SVCD,END
```

If no SLIP is set, an entry in LOGREC is made, but a dump is not taken.

To help identify the occurrence of what is being tracked, the following registers at the time of the abend will contain the information that is shown:

**R2**

The address of the GTZTRACK parameter list. See the program listing of the GTZTRACK invoker for a mapping.

**R3**

The HOME-ASID of the GTZTRACK caller.

**R4**

The eight characters of the HOME-jobname of the GTZTRACK caller.

**R5**

The eight characters of the event-jobname that is associated with the EVENTASID parameter of the GTZTRACK request.

**R6**

The eight characters of the PROGRAM name as derived from the EVENTADDR parameter of the GTZTRACK request, or the address of the derived PROGRAMPATH.

**R7**

The program OFFSET as derived from the EVENTADDR parameter of the GTZTRACK request.

**DUMP**

For matching GTZTRACK requests, the system triggers a percolating ABEND with system completion code X'E77' and with a reason code as specified by REASON. A dump according to the DUMP options of the current job is created. Use this action only when a matching track request is made and SLIP processing is not available yet. Otherwise, ACTION=ABEND is recommended.

See ACTION=ABEND for special register contents that are being set by the system.

**REASON(user-reason-code)**

Specifies which reason code to tag the debug action with.

The reason code must be in the range 0000x - 0FFFx and be specified in hexadecimal format (for example, X'02C1', 02C1x, '02C1'X, or x2C1) or decimal format (for example, 705).

**LIMIT({actionlimit|NOLIMIT})**

Requests that this DEBUG statement should not trigger more than *actionlimit* number of debug actions of the specified kind for all future, matching GTZTRACK requests. The limit must be in the range of 1 - 65535 or NOLIMIT must be used.

After the limit is reached and you want to reset the limit to allow additional debug actions in the future, use the CLEAR DEBUG command and then add any DEBUG statement again. You can combine this in a separate GTZPRMxx parmlib member and use the SET GTZ=xx command to have the tracking facility process these statements.

**Default:** None.

***filter***

Any new tracked instance that matches the whole filter (all the filter pieces, OWNER, SOURCE,... match their GTZTRACK based counterparts) and has not reached its limit will trigger the requested DEBUG action.

**ALL**

All tracked instances are matched and will trigger a DEBUG action if the LIMIT is not exceeded.

**Default:** ALL.

**OWNER({owner-filter-text|\*})**

To be compared to the OWNER value of a tracked instance as specified on its GTZTRACK request.

***owner-filter-text***

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #) or wildcard characters. It can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).



**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters).

### **SOURCETYPE(ALL)**

SOURCETYPE is optional.

#### **ALL**

Any tracked instances with either a SOURCE or SOURCEPATH value is matched. No further filtering is provided. ALL is the default.

### **SOURCETYPE(NOPATH)[SOURCE({*source-filter-text*|\*})]**

#### **NOPATH**

Only tracked instances with a SOURCE are matched. Optionally a specific SOURCE filter value can be specified. Tracked instances with a SOURCEPATH value are not matched.

#### **SOURCE**

To be compared to the SOURCE value of a tracked instance (as specified on its GTZTRACK request). SOURCE can only be specified for SOURCETYPE=NOPATH.

##### ***source-filter-text***

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #) or wildcard characters. It can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters

**Default:** \* (matches any character sequence of zero or more characters)

### **SOURCETYPE(PATH)[SOURCEPATH({*sourcepath-filter-text*|\*})]**

To be compared to the SOURCEPATH value of a tracked instance (as specified on its GTZTRACK request). SOURCEPATH can only be specified for SOURCETYPE=PATH.

#### **PATH**

Only tracked instances with a SOURCEPATH are matched. Optionally, a SOURCEPATH filter can be specified. Tracked instances with a SOURCE value are not matched.

#### **SOURCEPATH**

##### ***sourcepath-filter-text***

Must be 1-1024 characters and be surrounded by single quotation marks ('). The value is case-sensitive.

No blanks are removed.

The single quotation marks do not count toward the maximum length.

The specified value can contain wildcard characters anywhere in the string. It can also contain any EBCDIC character, but it cannot contain only blanks or X'00'. IBM recommends using printable characters.

**\***

Matches all SOURCEPATH values. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. A single asterisk can be specified without any single quotation marks.

**Default:** \* (matches all SOURCEPATH values).

### **EVENTDESC({*event-description-filter-text*|\*})**

To be compared to the EVENTDESC value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-description-filter-text***

The EVENTDESC value must be 1-64 characters and be surrounded by single quotation marks ('). Those single quotation marks do not count toward the maximum length. The value can

contain wildcard characters anywhere in the string. A question mark (?) matches a single arbitrary character. The value can also contain any EBCDIC character, but not just blanks or just X'00'. IBM® recommends using printable characters. No blanks are removed.

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters).

#### **EVENTDATA({*event-data-filter-value*|\*})**

To be compared to the EVENTDATA value of a tracked instance as specified on its GTZTRACK request.

##### ***event-data-filter-value***

The EVENTDATA value is interpreted as a 16-byte value. It can be specified in one of the following ways:

- In hexadecimal format as one of X'hh' or 0hhx or 'hh'X or xhh, with *hh* representing 1-32 hexadecimal digits (A-F, a-f, 0-9).
- As a decimal number.

**\***

Matches all of the EVENTDATA values.

**Default:** \* (matches all of the EVENTDATA values)

#### **EVENTJOB({*event-job-filter-text*|\*})**

To be compared to the event address space job name, as derived from the EVENTASID value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-job-filter-text***

The EVENTJOB value must be 1-8 characters. It can contain wildcard characters anywhere in the string. A question mark (?) matches a single arbitrary character. It can only contain alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters)

#### **EVENTASID({*event-ASID-filter-value*|\*})**

To be compared to the EVENTASID value of a tracked instance (as specified on its GTZTRACK request).

##### ***event-ASID-filter-value***

The EVENTASID value is interpreted as a 16-bit binary value. It can be specified in hexadecimal format (for example, X'82C1', 082C1x, '82C1'X, or x82C1) or in decimal format (for example, 33473).

**\***

Matches all of the EVENTASID values.

**Default value:** \* (matches all of the EVENTASID values).

#### **PROGRAMTYPE(ALL)**

PROGRAMTYPE is optional.

##### **ALL**

Any tracked instances with either a PROGRAM or PROGRAMPATH value is matched. No further filtering is provided.

**Default:** ALL.

**PROGRAMTYPE(NOPATH)[PROGRAM({*program-filter-text*|\*})]****NOPATH**

Only tracked instances with a PROGRAM are matched. Optionally a specific PROGRAM filter value can be specified. Tracked instances with a PROGRAMPATH value are not matched.

**PROGRAM**

To be compared to the PROGRAMTYPE value of a tracked instance (as specified on its GTZTRACK request). PROGRAM can only be specified for PROGRAMTYPE=NOPATH.

***program-filter-text***

The value must be a 1-8 characters string and can contain only alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #) or wildcard characters. It can contain wildcard characters anywhere in the string, and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches any character sequence of zero or more characters.

**Default:** \* (matches any character sequence of zero or more characters).

**PROGRAMTYPE(PATH)[PROGRAMPATH({*programpath-filter-text*|\*})]**

To be compared to the PROGRAMPATH value of a tracked instance (as specified on its GTZTRACK request). PROGRAMPATH can only be specified for PROGRAMTYPE=PATH.

**PATH**

Only tracked instances with a PROGRAMPATH are matched. Optionally, a PROGRAMPATH filter can be specified. Tracked instances with a PROGRAMPATH value are not matched.

**PROGRAMPATH*****programpath-filter-text***

Must be 1-1024 characters and be surrounded by single quotation marks ('). The value is case-sensitive.

No blanks are removed.

The single quotation marks do not count toward the maximum length.

The specified value can contain wildcard characters anywhere in the string. It can also contain any EBCDIC character, but it cannot contain only blanks or X'00'. IBM recommends using printable characters.

**\***

Matches all of the PROGRAMPATH values. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. A single asterisk can be specified without any single quotation marks.

**Default:** \* (matches all of the PROGRAMTYPE values).

**PROGRAMOFFSET(*programoffset-filter-value*|\*)**

To be compared to the program offset, as derived from the EVENTADDR value of a tracked instance (as specified on its GTZTRACK request).

***programoffset-filter-value***

If PROGRAMOFFSET is specified, the *programoffset* value is interpreted as an 8-byte binary value that can be specified in hexadecimal format (for example, X' C2 ', 0C2x, ' C2 'X, or xC2) or in decimal format (for example, 193).

**\***

Matches all the PROGRAMOFFSET values.

**Default:** \* (matches all PROGRAMOFFSET values).

**HOMEJOB({*home-job-filter-text*|\*})**

To be compared to the home address space job name as derived from the dispatchable unit under which a tracked instance's GTZTRACK request was executed.

***home-job-filter-text***

Must be 1-8 characters. It can only contain alphabetic characters (A-Z, a-z), numerics (0-9), national characters (@, \$, #), or wildcard characters. It can contain wildcard characters anywhere in the string. An asterisk (\*) matches any character sequence of zero or more characters and a question mark (?) matches a single arbitrary character. All lowercase characters (a-z) are folded to uppercase (A-Z).

**\***

Matches all of the HOMEJOB values.

**Default:** \* (matches all of the HOMEJOB values).

**HOMEASID({*home-ASID-filter-value*|\*})**

To be compared to the ID of the home address space as derived from the dispatchable unit under which a tracked instance's GTZTRACK request was executed.

***home-ASID-filter-value***

The HOMEASID value is interpreted as a 16-bit binary value. It can be specified in hexadecimal format (for example, X'82C1', 082C1x, '82C1'X, or x82C1) or in decimal format (for example, 33473).

**\***

Matches all of the HOMEASID values.

**Default:** \* (matches all of the HOMEASID values).

---

## Chapter 39. HZSPRMxx (manage IBM Health Checker for z/OS checks)

Use an HZSPRMxx parmlib member to make permanent updates to IBM Health Checker for z/OS checks and their parameters. The policy statements in the HZSPRMxx member or members currently in use for a system make up the IBM Health Checker for z/OS policies. The information in the current IBM Health Checker for z/OS policy is applied to all existing checks and to any new checks you add.

IBM Health Checker for z/OS processes policy information when checks are refreshed, added, or when there is an IPL. Put any check changes you want to make permanent and to have applied to any checks you add in the future in your policy.

For complete information about the HZSPRMxx parmlib member, including syntax and parameters, see [Using HZSPRMxx and MODIFY hzsproc command in \*IBM Health Checker for z/OS User's Guide\*](#).



## Chapter 40. IARPRMxx (Real Storage Manager controls)

IARPRMxx contains statements that control the following functions:

- Dedicated Memory

### Specifying the IARPRMxx members

The following methods can be used to specify the current IARPRMxx members:

- You can specify the RSM=xx parameter in the IEASYSxx parmlib member during IPL. Then, select IEASYSxx in the LOADxx parmlib member or specify SYSP=xx in response to the SPECIFY SYSTEM PARAMETERS system message.
- You can specify RSM=xx in response to the SPECIFY SYSTEM PARAMETERS system message.

You can specify one or more current IARPRMxx parmlib members during IPL. For example, an RSM=(03,04) system parameter tells the system to use IARPRM03 and IARPRM04 as current members. The system processes these members in the order that they are specified. For all statements, only the last statement for that option is recognized.

### Parameter in IEASYSxx (or specified by the operator)

```
RSM=(xx[,yy...])
```

The two-character identifier xx is appended to IARPRM to identify the IARPRMxx parmlib member. You can also specify multiple IARPRMxx members on this parameter. For example, you can specify two active members by using the form RSM=(xx,yy). IARPRMxx parmlib member has no default.

### Syntax rules for IARPRMxx

- When creating IARPRMxx, enter data only in columns 1 - 71. Do not enter data in columns 72 through 80; the system ignores these columns.
- If the system finds a syntax error in IARPRMxx, the system issues an error message, and then attempts to continue processing the next keyword.
- Comments can appear in columns 1-71 and must begin with "/" and end with "/".

### Syntax format of IARPRMxx

```
[DEDICATEDMEMORY(mmG|nnT) ]  
[PROMPT(NO|YES)]
```

### Statements and parameters for IARPRMxx

**DEDICATEDMEMORY(mmG | nnT)**

**DMEM(mmG|nnT)**

Specifies the amount of real memory to be designated as Dedicated Memory where the suffixes G represents Gigabytes and T represents Terabytes. The amount must be a multiple of 2G and the total amount of configured memory on the system must equal a multiple of 2G. The system rounds the specified value up or down to a storage increment multiple. Dedicated Memory is designated from the top of Central Storage, regardless of whether the memory is online. At least 16G of online

non-Dedicated Memory must exist after the Dedicated Memory designation, otherwise the request is rejected. Some amount of Dedicated Memory must be used by the system to manage Dedicated Memory; at least 4G must be requested.

**PROMPT(NO|YES)**

Specifies whether the system should prompt the operator to continue with the IPL after message IAR073I is issued. Message IAR073I describes the system's memory configuration, including the amount of Dedicated Memory. If PROMPT(YES) is specified, the IAR077A message is issued to prompt the operator.

**Default:** PROMPT(NO)

**RESTRICTPFTCADS(NO|YES)**

The PFTCADS space describes how real storage is used. When RESTRICTPFTCADS(NO) is specified or defaulted, applications can access the PFTCADS. When RESTRICTPFTCADS(YES) is specified, only the operating system has access.

**Default:** RESTRICTPFTCADS(NO)

**IARR2V\_REQAUTH(NO|YES)**

IARR2V is a macro service that translates a real storage address to a virtual storage address. When IARR2V\_REQAUTH(NO) is specified or defaulted, unauthorized applications can invoke the service specifying real storage that they do not have access to. When IARR2V\_REQAUTH(YES) is specified, IARR2V invocations will fail for unauthorized (key 8-15 and problem state) applications that do not have access to the real storage to be translated.

**Default:** IARR2V\_REQAUTH(NO)

## Example of IARPRMxx parmlib member

The following configuration specifies 16G of Dedicated Memory. If there is at least 16G of online memory after the 16G of Dedicated Memory is designated, the request should be successful. Message IAR073I is issued, specifying the details of the memory configuration.

```
DMEM(16G)
PROMPT(YES)
```



## Chapter 41. IDAVDTxx (VSAM dynamic trace parameters)

Use the IDAVDTxx parmlib member to enable VSAM record management trace and define the trace parameter for any VSAM data set dynamically when diagnostic data is required.

You can predefine up to the maximum of eight trace entries with different trace parameters. Each trace entry consists of the target data-set name, the target job name, and the usual trace parameters. When the trace entries are defined, you can use the START console command to call IDAVDT to enable VSAM record management trace. After you start IDAVDT, you can interact with IDAVDT by the MODIFY command to perform the following functions:

### ENABLE

Enable a specific trace entry that is stored in the dynamic trace area.

### DISABLE

Disable a specific trace entry that is stored in the dynamic trace area.

### DISPLAY

Display a specific trace entry that is stored in the dynamic trace area.

### INVALIDATE

Invalidate a specific trace entry, or all trace entries that are stored in the dynamic trace area.

### READIN

Parse the trace entries in the specified IDAVDTxx parmlib member and insert it into the dynamic trace save area that is located in common storage.

### VALIDATE

Validate a specific trace entry, or all trace entries that are stored in the dynamic trace area.

## Syntax rules for IDAVDTxx

Follow the rules in “General syntax rules for the creation of members” on page 7. The following rule also applies to the creation of IDAVDTxx parmlib members:

- All text should be in uppercase.

## Syntax format for IDAVDTxx

```
VTRACE      DSNAME(data_set_name)
             JOBNAME(job_name)
             HOOK(hook_id [,hook_id])
             PARM1(trace_parm_1)
             [PARM2(trace_parm_2)]
             [ECODE(ANY|rsncode)]
             [KEYVALUE(target_key_value|x'target_key_hex_value')]
             END
```

## IBM-supplied defaults for IDAVDTxx

The default member is IDAVDT00.

## Statements and parameters for IDAVDTxx

### DSNAME(data\_set\_name)

Specifies which data set the user would like to enable VSAM record management trace.

**ECODE(ANY|*rsncode*)**

Tracing occurs only if an error code is being returned to the caller.

**ANY**

Tracing is performed for any nonzero return code.

***rsncode***

Tracing is performed only if the RPLFDBK code matches the *rsncode*.

**HOOK(*hook\_id* [,*hook\_id*])**

Specifies the list of VSAM predefined Hook points where the trace should execute during VSAM record management processing. This statement consists of 1 to 3 other statements (SLIP, DUMP, or ABEND).

**JOBNAME(*job\_name*)**

Specifies the job where the targeted data set was opened or will be opened.

**KEYVALUE(*target\_key\_value*|*x'target\_key\_hex\_value'*)**

Tracing occurs only if the current processing key matched the *target\_key\_value*. The input value can be either HEX or EBCDIC value.

**PARM1(*trace\_parm\_1*)**

Specifies which control blocks VSAM record management trace should capture.

**PARM2(*trace\_parm\_2*)**

Specifies which control blocks VSAM record management trace should capture when tracing the AIX®.

**VTRACE**

The current entry defines a VSAM record management trace entry.

## Examples of IDAVDTxx parmlib member

---

```
VTRACE          DSNAME(SAMPLE.KSDS.DATA)
                JOBNAME(VRMTRA01)
                HOOK(0,1)
                PARM1(1001010000000)
                KEYVALUE(x'C1C2C3C4C5C6')
                END
```

## Chapter 42. IEAABD00 (ABDUMP written to a SYSABEND data set)

IEAABD00 contains IBM defaults and installation assigned parameters for ABDUMP for use when an ABEND dump is written to a SYSABEND data set.

Specify ABDUMP parameters for a dump to be taken to a SYSABEND data set as follows:

- The dump request parameter list pointed to by the DUMPOPT keyword of the ABEND macro. (An ABEND dump can also be requested through the CALLRTM or SETRP macros. See [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#) or [z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO](#).) You can use the list form of the SNAP macro to build the list. (For details regarding the ABEND and SNAP macros, see [z/OS MVS Programming: Assembler Services Reference ABE-HSP](#).)
- The initial system dump options that are specified in IEAABD00. These options are added to the options on the dump request parameter list.
- The system dump options as altered by the CHNGDUMP command. With the CHNGDUMP command, options can be added to or deleted from the system dump options list. The CHNGDUMP command can also cause the dump request parameters to be ignored. (For a description of the CHNGDUMP command, refer to [z/OS MVS System Commands](#).)

The ABDUMP initialization routine reads IEAABD00 to get ABDUMP parameters. If during initialization, IEAABD00 is invalid or cannot be located, the operator is notified. No prompting occurs. If both valid and invalid options are included in the member, or a syntax error is encountered, a message lists the valid options that were accepted before the error occurred.

### Parameter in IEASYSxx (or specified by the operator)

None.

### Syntax rules for IEAABD00

The following rules apply to the replacement of IEAABD00:

- There are two keywords, SDATA and PDATA. Each keyword is followed by a string of operands that are separated by commas and enclosed in parentheses. A single operand does not need parentheses.

```
SDATA=(SQA,CB,ENQ,TRT)      or  SDATA=ALLSDATA
PDATA=(PSW,REGS,SA,ALLPA,SPLS) or  PDATA=ALLPDATA
```

- Normally both parameters (that is, SDATA=operands and PDATA=operands) can fit on one line. If, however, continuation is needed, use a comma followed by a blank.

```
SDATA=(SQA,CB,ENQ,TRT),
PDATA=(PSW,REGS,
SA,ALLPA,SPLS)
```

- Lines that begin with an asterisk in column 1 are comments.
- Alternatively, to include a comment, place the comment on the same line as the data. Use at least one blank to separate the data from the comment. The following example shows a continuation and the related comments.

```
SDATA=(SQA,CB,    SQA and CB data
ENQ,TRT)         ENQ and trace data
```

## IBM-supplied default for IEAABD00

---

These defaults are in IEAABD00:

```
SDATA=(LSQA,CB,ENQ,TRT,ERR,DM,IO,SUM),
PDATA=(PSW,REGS,SPLS,ALLPA,SA)
```

These options request a dump of the following areas:

- LSQA, including subpools 229, 230, and 249
- Formatted control blocks for the task
- Formatted global resource serialization control blocks for the task
- GTF trace and system trace
- Recovery termination control blocks for the task
- Data management control blocks for the task
- IOS control blocks for the task
- Summary data (see explanation in the SUM parameter section)
- PSW at entry to ABEND
- Contents of general registers at entry to ABEND
- Save area linkage information and a backward trace of save areas
- Modules that are listed on the link pack area queue for the task and the job pack area queue for the task, and active SVC modules that are related to the failing task
- User storage that is allocated for the task.

## Statements and parameters for IEAABD00

---

### **PDATA=**

Request application-related problem program key storage areas.

### **ALLPDATA**

All the following options are automatically specified.

The following parameters request dump of specific PDATA areas, as indicated:

### **ALLPA**

Contents of both the job pack area and the LPA, as they relate to the failing task, plus SVCs related to the failing task.

### **JPA**

Contents of the job pack area (module names and contents) that relate to the failing task.

### **LPA**

Contents of the LPA (module names and contents) related to the failing task. Includes active SVCs related to the failing task.

### **PSW**

Program status word at entry at ABEND.

### **REGS**

Contents of general registers at entry to ABEND.

### **SA or SAH**

SA requests save area linkage information and a backward trace of save areas. This option is automatically selected if ALLPDATA is specified. SAH requests only save area linkage information.

### **SPLS**

User storage subpools (0-127, 129-132, 244, 251, and 252) related to the failing task.

### **SUBTASKS**

Problem data (PDATA) options that are requested for the designated task are also in effect for its subtasks.

**SDATA=**

Request application-related system storage, including key 0 areas, that the application programmer can see.

**ALLSDATA**

Except ALLVNUC and NOSYM, all the following options are automatically specified.

The following parameters request dump of specific SDATA areas, as indicated:

**ALLVNUC**

Entire virtual nucleus. SQA, LSQA, and the PSA are included.

**CB**

Control blocks related to the failing task.

**DM**

Data management control blocks (DEB, DCB, IOB) for the task.

**ENQ**

Global resource serialization control blocks for the task.

**ERR**

Recovery termination control blocks (RTM2WA, registers from the SDWA, SCB, EED) for the task.

**IO**

IOS control blocks (UCB, EXCPD) for the task.

**LSQA**

Local system queue area for the address space. If storage is allocated for subpools 229, 230 and 249, they are dumped for the current task.

**NOSYM**

No symptom dump is to be produced.

**NUC**

Read/write portion of the control program nucleus. SQA, LSQA, and the PSA are included.

**PCDATA**

Program call information for the task that is being dumped.

**SQA**

The system queue area.

**SUM**

Requests that the dump contain summary data, which includes the following data:

- Dump title.
- Abend code and PSW at the time of the error.
- If the PSW at the time of the error points to an active load module: (1) the name and address of the load module, (2) the offset into the load module indicating where the error occurred, and (3) the contents of the load module.
- Control blocks related to the failing task.
- Recovery termination control blocks.
- Save areas.
- Registers at the time of the error.
- Storage summary that consists of 1 K (1024) bytes of storage before and 1 K bytes of storage after the addresses pointed to by the registers and the PSW. The storage is printed only if the user is authorized to obtain it, and, when printed, duplicate addresses are removed.
- System trace table entries for the dumped address space.

**SWA**

Scheduler work area that is used for the failing task.

**TRT**

System trace table and GTF trace, as available.



## Chapter 43. IEAAPFxx (authorized program facility list)

Use the IEAAPFxx member to specify program libraries that are to receive authorized program facility (APF) authorization. List the names (dsnames) of the libraries, along with one of the following to indicate where the library resides:

- The volume serial number of the volume on which the library resides.
- Six asterisks (\*\*\*\*\*) to indicate that the library resides on the current system residence (sysres) volume.
- \*MCAT\* to indicate the library resides on the volume on which the IPL-time master catalog resides.
- Nothing after the library name, to indicate that the storage management subsystem (SMS) manages the library.

If an installation wants IEAAPFxx, it must explicitly create the member. The member IEAAPF00 must be explicitly created by the installation also.

Do not define aliases in the APF list because IBM's data management services (for example, OPEN processing) map an alias to its actual library name and query the APF list by the actual library name. An alias in the APF list does not authorize anything.

You can use IEAAPFxx to create an APF list in a static format. A static list can be updated only at IPL and can contain a maximum of 255 entries (SYS1.LINKLIB, SYS1.SVCLIB, and 253 entries that are specified by your installation).

**Note:** IBM provides the PROGxx parmlib member as an alternative to IEAAPFxx, which allows you to update the APF list dynamically and specify an unlimited number of APF-authorized libraries. IBM suggests that you use PROGxx to specify the APF list (regardless of whether you plan to take advantage of the dynamic update capability). The system processes IEAAPFxx and PROGxx if both parameters are specified. If you decide to use PROGxx only, remove APF=xx system parameters from IEASYSxx and IEASYS00.

For information about how to use the IEAAPFPR REXX exec to convert the APF definitions in IEAAPFxx to equivalent definitions in PROGxx, see [“Specifying the APF list” on page 27](#).

For information about how to use PROGxx to specify the format and contents of the APF list, see [PROG](#).

For more information about using authorized libraries, see [z/OS MVS Programming: Authorized Assembler Services Guide](#).

**Note:**

1. Except for concatenations opened during NIP, any unauthorized library that is concatenated to authorized libraries will cause all of the concatenated libraries to be considered unauthorized.
2. You can specify a maximum of 253 library names in an IEAAPFxx member.
3. Allowing SMS to manage a data set means that the data set might be moved to a different volume during normal SMS processing. To ensure the data set retains APF authorization, specify nothing after the library name, to indicate that the library is managed by SMS.
4. As of MVS 4.3, it is no longer necessary for the data sets in the LPALST to be APF-authorized. However, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library in the LPALST to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

## Parameter in IEASYSxx (or supplied by the operator)

### APF=xx

The two characters (A-Z, 0-9, @, #, or \$), represented by xx, are appended to IEAAPF to identify the IEAAPFxx member. If the APF list is not explicitly defined (via the APF system parameter, the default IEAAPF00 parmlib member, or APF statements within PROGxx via the PROG system parameter), then only SYS1.LINKLIB and SYS1.SVCLIB will be APF-authorized during the IPL.

**Note:** In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) will be treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

## Syntax rules for IEAAPFxx

The following rules apply to the creation of IEAAPFxx:

- Enter data only in columns 1 through 71. Do not enter data in column 72 through 80; the system ignores these columns.
- Place only one library name and corresponding volume serial number on a line (record).
- Duplicate data set names are valid.
- On each record, first enter the library name, then one or more blanks, then one of the following:
  - The volume serial number of the volume on which the library resides.
  - **\*\*\*\*\*** (six asterisks), to indicate that the library resides on the current SYSRES volume.
  - **\*MCAT\***, to indicate that the library resides on the volume that contains the IPL-time master catalog.
  - Nothing, to indicate the library is SMS-managed.
- To continue to another record, place a comma after the volume serial number. Omit this comma on the last record.

```
first record:      SYS1.SUPER.UTILS      614703,
second record:     W12.PAYROLL.LOADLIB    705650
```

- On a line, data entered after the comma is treated as a comment and ignored.
- Data records entered after the last data line are treated as comments and ignored.

```
SYS1.SUPER.UTILS      614703,   Super utilities
SMS.MANAGED.LOADLIB    ,       No vol=>SMS managed
W12.PAYROLL.LOADLIB    705650,   /* Payroll programs */
X11.LOADLIB            345000    /* Last line */
This line and any following lines are ignored.
```

- For an SMS-managed volume, use only standard comments (delimited by /\* and \*/) on the last line.

```
SYS1.SUPER.UTILS      614703,   Super utilities
SMS.MANAGED.LOADLIB1    ,       No vol=>SMS managed
W12.PAYROLL.LOADLIB    705650,   Payroll programs
X11.LOADLIB            345000,   /* X11 programs */
SMS.MANAGED.LOADLIB2    ,       /* Last line */
```



## IBM-supplied default for IEAAPFxx

---

If the APF list is not explicitly defined (via the APF system parameter, the default IEAAPF00 parmlib member, or APF statements within PROGxx via the PROG system parameter), then only SYS1.LINKLIB and SYS1.SVCLIB is APF-authorized during the IPL. Additionally, if the default for the LNKAUTH system parameter is taken (LNKAUTH=LNKLST) or is specified in IEASYSxx or by the operator, libraries in the LNKLST concatenation are also authorized when accessed as part of the LNKLST concatenation.

**Note:**

1. When LNKAUTH=APFTAB is specified, the system considers SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE and SYS1.SIEAMIGE to be APF-authorized when they are accessed as part of the concatenation (even when they are not included in the APF list).
2. In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

## Statements and parameters for IEAAPFxx

---

Not applicable.



## Chapter 44. IEAAPP00 (authorized I/O appendage routines)

IEAAPP00 contains the names of authorized installation-written I/O appendage routines. These appendages, when listed, can be used by any unauthorized user program. Otherwise, only programs authorized under APF or running under system protection key (0-7) may use the EXCP appendages. If your installation does not use EXCP appendages, you need not create IEAAPP00.

If the EXCP caller is not in system protection key or the job step is not authorized, the system verifies that the caller's appendage names are listed. If the names cannot be found, the system issues a 913 ABEND. If, however, the caller is authorized, the system loads the appendages without inspecting the list.

### Syntax rules for IEAAPP00

The following rules apply to the creation of IEAAPP00:

- IEAAPP00 can contain up to five entries, with each entry specifying names of a particular type of appendage. For example:

|        |                              |
|--------|------------------------------|
| SIOAPP | Start I/O                    |
| PCIAPP | Program-Controlled Interrupt |
| EOEAPP | End of extent                |
| ABEAPP | Abnormal end                 |
| CHEAPP | Channel end                  |

You need not necessarily use all five types of entries.

- Each entry consists of an appendage-type name, followed by a list of suffixes of that type, separated by commas. The suffixes can range from WA to Z9. The appendage-type name can start in any column. For example, this entry specifies two Start I/O appendages.

|        |       |
|--------|-------|
| SIOAPP | WA,X4 |
|--------|-------|

- Continuation is indicated by a comma followed by one or more blanks. The next record can start in any column.
- Comments are indicated by an asterisk in the first column or a combination of /\* and \*/ between columns 1 and 71. Comments are allowed at the start of a member or interspersed throughout the member.

Here is an example of a complete IEAAPP00 member. In this example, note that there are no channel-end appendages and none for abnormal end. Routine IGG019X3 is used as both end-of extent and PCI appendage.

|        |                    |
|--------|--------------------|
| SIOAPP | Y1,Y2,             |
| EOEAPP | X1,Z2,X3,X4,X5,X6, |
| PCIAPP | X3                 |

### IBM-supplied default for IEAAPP00

None.

### Statements and parameters for IEAAPP00

Not applicable.



## Chapter 45. IEACMD00 (IBM-supplied commands)

IEACMD00 contains IBM-supplied commands, as follows:

- A CHNGDUMP command to add trace table, LSQA and XES information to SVC dumps.
- A SET command (SET SLIP=00) to indicate that the system is to use the IEASLP00 parmlib member to issue IBM-supplied SLIP commands.
- A SET command (SET DAE=00) to indicate that the system is to use the ADYSET00 parmlib member to start DAE processing.
- A START command (START LLA, SUB=MSTR) to start the library lookaside (LLA) procedure, which resides in SYS1.PROCLIB. The LLA procedure then starts the library lookaside function.
- A START command (START BLSJPRMI, SUB=MSTR) creates IPCS tables which allows SNAP ABDUMP and IPCS to print formatted control blocks in dumps.
- A START command (START IFGEDI, SUB=MSTR) enables enhanced data integrity for physical sequential data sets.

An installation that uses the optional COMMNDxx parmlib member should check for commands in COMMNDxx that conflict with commands in IEACMD00, and resolve any conflicts. It is also recommended that an installation place its commands in the COMMNDxx member, leaving the IEACMD00 member for IBM-supplied commands only.

Place all SLIP commands in IEASLPxx.

### Note:

1. The order in which task-creating commands appear in IEACMD00 does NOT guarantee the order in which they are executed. Thus, IEACMD00 should not be used for commands that must be executed in a specific order. Commands are issued in the order that they appear in IEACMD00, but they are executed as follows:
  - Immediate commands, such as DISPLAY T, are executed sequentially as they are issued from IEACMD00.
  - Execution of task-creating commands, such as DISPLAY A, are deferred until system initialization is complete. Then, factors such as multitasking, multiprocessing, and competition for resources influence the order in which these commands are executed.

Thus, IEACMD00 should *not* be used to issue task-creating commands that must be executed in a specific order, because the execution order of these commands can vary.
2. The SET SLIP=00 command causes the IBM-supplied IEASLP00 parmlib member to execute. As a result, the SLIP commands specified in IEASLP00 are in effect at IPL-time. These commands suppress dumps that are considered to be unnecessary. For more information about IEASLP00, see [Chapter 53, “IEASLPxx \(SLIP commands\),” on page 405](#).
 

To activate an IEASLPxx member instead of the IBM-supplied member (IEASLP00), change the SET SLIP=00 command to SET SLIP=xx (where xx is the two character suffix of the alternate IEASLPxx member to be used).
3. The SET DAE=00 command causes the ADYSET00 parmlib member to execute. As a result, dump analysis and elimination (DAE) processing as specified in ADYSET00 is in effect.
 

To prevent the system from activating DAE automatically, change ADYSET00 to contain DAE=STOP.

For more information about DAE and its parmlib members, see [Chapter 3, “ADYSETxx \(dump suppression\),” on page 61](#).
4. For descriptions of the CHNGDUMP, SET, START, and SLIP commands, see [z/OS MVS System Commands](#).

## Parameter in IEASYSxx (or supplied by the operator)

---

None.

## Syntax rules for IEACMD00

---

The following rules apply to the modification of IEACMD00:

- Enter only one command for each line. To do so, specify the COM= keyword, followed by the command enclosed in single quotation marks.
- Do not specify continuation on any line.
- Lines that begin with an asterisk in column 1 are comments.

## IBM-supplied default for IEACMD00

---

The following commands are placed in IEACMD00 by IBM:

```
COM='CHNGDUMP SET,SDUMP=(LSQA,TRT,XESDATA),ADD'  
COM='SET SLIP=00'  
COM='SET DAE=00'  
COM='START LLA,SUB=MSTR'  
COM='START BLSJPRMI,SUB=MSTR'  
COM='START IFGEDI,SUB=MSTR'
```

## Statements and parameters for IEACMD00

---

Not applicable.

## Chapter 46. IEADMCxx (DUMP command parmlib)

IEADMCxx enables you to supply DUMP command parameters through a parmlib member. IEADMCxx enables the operator to specify the collection of dump data without having to remember and identify all the systems, address spaces and data spaces involved.

This parmlib enables you to specify lengthy DUMP commands without having to reply to multiple writes to operator with reply (WTORs). Any errors in an original specification may be corrected and the DUMP command re-specified.

IEADMCxx is an installation-supplied member of SYS1.PARMLIB that can contain any valid DUMP command. A dump command may span multiple lines and contain system static and (DUMP command SYMDEF defined) symbols and comments.

Dump commands using parmlib members are specified by member suffix using the PARMLIB=keyword. Multiple members may be specified within parentheses separated by commas. A dump command specified using the parmlib keyword are taken immediately without prompting for further parameters through WTOR. Since no WTOR replies are required, the ROUTE command can be used when issuing a DUMP command specifying parmlib members for increased functionality.

**Note:** Do not use the ROUTE command with the DUMP command when specifying parmlib members that use the REMOTE keyword.

### Performance implications

None.

### Syntax rules for IEADMCxx

The following syntax rules apply to IEADMCxx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- Blank lines are permitted.
- Comments can appear in columns 1-71, can span lines, and must begin with /\* and end with \*/.
- Do not use nested comments in this parmlib member.
- A statement can be continued even though there is no explicit continuation character.
- You can use substrings of previously defined system symbols. See [“Step 1. Know the rules for using system symbols in parmlib” on page 47](#) for more information about using substrings.

### Syntax format of IEADMCxx

The syntax of the DUMP command specified within the IEADMCxx members of SYS1.PARMLIB is identical to that specified on the DUMP command through replies. See [z/OS MVS System Commands](#) for more information.

### IBM-supplied default for IEADMCxx

None. However, see [Operator command in an IEADMCxx parmlib member in z/OS MVS Diagnosis: Tools and Service Aids](#) for a list of IBM-supplied SYS1.SAMPLIB members that should be tailored for your installation-specific requirements before being installed as PARMLIB members.

### Statements and parameters for IEADMCxx

#### DUMP

The DUMP command.

```

COMM={ (title) }
      { 'title' }
      { "title" }

TITLE={ (title) }
       { 'title' }
       { "title" }

```

The title (1 - 100 characters) that you assign to the dump. The title is the first record in the dump data set.

**PARMLIB=xx | PARMLIB=(xx[,xx]...)**

The two alphanumeric characters indicating the IEADMCxx member of SYS1.PARMLIB that contains the DUMP command specification.

The syntax of the DUMP command that is specified within the IEADMCxx members of SYS1.PARMLIB is identical to that specified on the DUMP command through replies. See [z/OS MVS System Commands](#) for more information.

**Note:** A DUMP's title is determined as follows:

- Titles that are specified in the DUMP command (for example, DUMP TITLE="DUMP Specified through WTOR") take precedence over titles that are specified within parmlibs.
- When a title is not specified in the DUMP command, the title that is specified within a parmlib takes precedence.

If titles are specified in multiple parmlib members, the first parmlib's title takes precedence. For example, if all of the parmlibs in PARMLIB=(RA,XC,CF) are titled, the dump title is the one specified in the RA parmlib.

- If a title is not specified in the DUMP command or parmlib, the title is as follows: DUMP FOR PARMLIB=(xx,yy,zz), where xx,yy,zz are the parmlibs.

Following are examples of IEADMCxx usage:

1. To request a dump through WTOR, enter:

```
DUMP COMM=(Dump specified via WTOR)
```

or

```
DUMP TITLE=(Dump specified via WTOR)
```

In response to this command, the system issues the following response:

```
* id IEE094D SPECIFY OPERAND(S) FOR DUMP COMMAND
```

Replying to this command determines the contents of the dump.

2. To request a dump of the RACF address space, including all of its private area and a summary dump using a DUMP command parmlib member:

- a. Create member IEADMCRA

```
JOBNAME=RASP,SDATA=(SUM,RGN)
```

- b. Issue the following on the MVS console:

```
DUMP TITLE=(RACF dump),PARMLIB=RA
```

3. To request a dump of the XCF address space, including all of its data spaces on all systems within the sysplex using a DUMP command parmlib member:

- a. Create member IEADMCXC

```
JOBNAME=XCFAS,DSPNAME=('XCFAS'.*),SDATA=COUPLE,
REMOTE=(SYSLIST=*( 'XCFAS' ),DSPNAME,SDATA)
```



- b. Issue the following on the MVS console:

```
DUMP TITLE=(Dump all XCF data),PARMLIB=XC
```

4. To request a dump that includes structure control data for CACHESTRUCTURE, directory information and entry data for storage classes 3-8 and 10 with entry data written with serialization, and directory information for all entries that are grouped by cast-out class using a DUMP command parmlib member:

- a. Create member IEADMCCF

```
STRLIST=(STRNAME=CACHESTRUCTURE,  
ACCESSTIME=NOLIMIT,  
(STGCLASS=(3-8,10),ENTRYDATA=SERIALIZE),(COCLASS=ALL))
```

- b. Issue the following on the MVS console:

```
DUMP TITLE=(CACHESTRUCTURE dump),PARMLIB=CF
```

5. To request a dump of the RACF address space on this system, the XCF address spaces and data spaces on all systems in the sysplex, and the CACHESTRUCTURE structure from the coupling facility, issue the following command on the MVS console:

```
DUMP TITLE=(RACF, XCFASs and CACHESTRUCTURE),PARMLIB=(RA,XC,CF)
```

6. To show the use of variable substitution where &REGIONAM is a new symbol and &SYSCONE is a static symbol:

- a. Where a parmlib member, like IEADMCTC, could contain:

```
TSONAME=(TCPIP&SYSCONE.,CICS&REGIONAM.),SDATA=(SWA,RGN)
```

- b. The DUMP system command includes the SYMDEF for &REGIONAM:

```
DUMP TITLE=(Dump TCPIP and CICS),PARMLIB=TC,  
SYMDEF=&REGIONAM.='TOR7')
```

7. To request the dump of TCP/IP on this system, including only the high virtual CSA that is owned by the ASID and a summary dump, using a DUMP command parmlib member:

- a. Run the following command to create member IEADMCTP:

```
JOBNAME=TCPIP,SDATA=(SUM,HCSABYASID)
```

- b. Run the following command on the MVS console:

```
DUMP TITLE=(TCPIP dump),PARMLIB=TP
```

8. To request that a dump include private storage of XMEMT ASIDs that have an active cross-memory relationship with the originally requested, non-exempt target ASIDs 3B and 41:

- a. Create the member and specify the target XMEMT ASIDs. For example, if you created IEADMCGV.

```
SDATA=(CSA,SQA,LSQA,RGN),XMEMT=YES,ASID=(3B,41)
```

- b. Issue the following console command:

```
DUMP TITLE=(XMEMT dump),PARMLIB=GV
```



## Chapter 47. IEADMP00 (ABDUMP written to a SYSUDUMP data set)

IEADMP00 contains IBM defaults and installation parameters for ABDUMP for use when an ABEND dump is written to a SYSUDUMP data set. ABDUMP parameters for a SYSUDUMP data set may be specified as follows:

- The dump request parameter list pointed to by the DUMPOPT keyword of an ABEND macro. (An ABEND dump can also be requested through the CALLRTM and SETRP macros. For details, see *z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN* and *z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO*.) The list can be built by using the list form of the SNAP macro. (For details, see ABEND and SNAP macros in *z/OS MVS Programming: Assembler Services Reference ABE-HSP*.)
- The initial system dump option specified in IEADMP00. This option is added to the options on the dump request parameter list.
- The system dump options as altered by the CHNGDUMP command. With the CHNGDUMP command, options can be added to or deleted from the system dump options list. The CHNGDUMP command can also cause the dump request parameters to be ignored. (For a description of the CHNGDUMP command, refer to *z/OS MVS System Commands*.)

During IPL an information message will notify the operator if IEADMP00 is invalid or cannot be found. No prompting of the operator will occur. If the member contains both valid and invalid parameters, an information message will indicate the valid options that were accepted before the error occurred.

### Parameter in IEASYSxx (or specified by the operator)

None.

### Syntax rules for IEADMP00

The following rules apply to the replacement of IEADMP00:

- There are two keywords, SDATA and PDATA. Each keyword is followed by a string of operands separated by commas and enclosed in parentheses. A single operand does not need parentheses.

|                                |    |                |
|--------------------------------|----|----------------|
| SDATA=(SQA,CB,ENQ,TRT)         | or | SDATA=ALLSDATA |
| PDATA=(PSW,REGS,SA,ALLPA,SPLS) | or | PDATA=ALLPDATA |

- Normally both parameters (SDATA=operands and PDATA=operands) can fit on one line. If, however, continuation is needed, use a comma followed by a blank.

```
SDATA=(SQA,CB,ENQ,TRT),
PDATA=(PSW,REGS,
SA,ALLPA,SPLS)
```

- Lines that begin with an asterisk in column 1 are comments.
- Alternatively, to include a comment, place the comment on the same line as the data. Use at least one blank to separate the data from the comment. The following example shows a continuation and related comments.

|                |                    |
|----------------|--------------------|
| SDATA=(SQA,CB, | SQA and CB data    |
| ENQ,TRT)       | ENQ and trace data |

## IBM-supplied default for IEADMP00

---

The IBM-supplied default parmlib member is IEADMP00, which contains SDATA=SUM.

## Statements and parameters for IEADMP00

---

### **SDATA=**

Request application-related system storage, including key 0 areas, that the application programmer can see.

### **ALLSDATA**

Except ALLVNUC and NOSYM, all the following options are automatically specified.

The following parameters request dump of specific SDATA areas, as indicated:

### **ALLVNUC**

Entire virtual nucleus. SQA, LSQA, and the PSA are included.

### **CB**

Control blocks related to the failing task.

### **DM**

Data management control blocks (DEB, DCB, IOB) for the task.

### **ENQ**

Global resource serialization control blocks for the task.

### **ERR**

Recovery termination control blocks (RTM2WA, registers from the SDWA, SCB, EED) for the task.

### **IO**

IOS control blocks (UCB, EXCPD) for the task.

### **LSQA**

Local system queue area for the address space. If storage is allocated for subpools 229, 230 and 249, they are dumped for the current task.

### **NOSYM**

No symptom dump is to be produced.

### **NUC**

Read/write portion of the control program nucleus. SQA, LSQA, and the PSA are included.

### **PCDATA**

Program call information for the task being dumped.

### **SUM**

Requests that the dump contain summary data, which includes the following information:

- Dump title.
- Abend code and PSW at the time of the error.
- If the PSW at the time of the error points to an active load module: (1) the name and address of the load module, (2) the offset into the load module indicating where the error occurred, and (3) the contents of the load module.
- Control blocks related to the failing task.
- Recovery termination control blocks.
- Save areas.
- Registers at the time of the error.
- Storage summary consisting of 1 K (1024) bytes of storage before and 1 K bytes of storage after the addresses pointed to by the registers and the PSW. The storage is printed only if the user is authorized to obtain it, and, when printed, duplicate addresses are removed.
- System trace table entries for the dumped address space.

**SQA**

The system queue area.

**SWA**

Scheduler work area that is used for the failing task.

**TRT**

System trace table and GTF trace, as available.

**PDATA=**

Request application-related problem program key storage areas.

**ALLPDATA**

All the following options are automatically specified.

The following parameters request dump of specific PDATA areas, as indicated:

**ALLPA**

Contents of both the job pack area and the LPA, as they relate to the failing task, plus SVCs related to the failing task.

**JPA**

Contents of the job pack area that relate to the failing task. These include module names and contents.

**LPA**

Contents of the LPA related to the failing task. These include module names and contents. Also includes active SVCs related to the failing task.

**PSW**

Program status word at entry to ABEND.

**REGS**

Contents of general registers at entry to ABEND.

**SA or SAH**

SA requests save area linkage information and a backward trace of save areas. This option is automatically selected if ALLPDATA is specified. SAH requests only save area linkage information.

**SPLS**

User storage subpools (0-127, 129-132, 244, 251, and 252) related to the failing task.

**SUBTASKS**

Problem data (PDATA) options that are requested for the designated task will also be in effect for its subtasks.



## Chapter 48. IEADMR00 (ABDUMP written to a SYSMDUMP data set)

IEADMR00 contains IBM defaults and/or installation parameters for ABDUMP, for use when an ABEND dump is written to a SYSMDUMP data set. ABDUMP parameters for a SYSMDUMP data set may be specified as follows:

- The dump request parameter list pointed to by the DUMPOPT keyword of an ABEND macro. (An ABEND dump can also be requested through the CALLRTM and SETRP macros. For details, see *z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN* or *z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO*.) The list can be built by using the list form of the SNAP macro. (For details, see the descriptions of the ABEND and SNAP macros in *z/OS MVS Programming: Assembler Services Reference ABE-HSP*.)
- The initial system dump options specified in IEADMR00. These options are added to the options on the dump request parameter list.
- The system dump options as altered by the CHNGDUMP command. With the CHNGDUMP command, options can be added to or deleted from the system dump options list. The CHNGDUMP command can also cause the dump request parameters to be ignored. (For a description of the CHNGDUMP command, see *z/OS MVS System Commands*.)

During IPL, an informational message will notify the operator if IEADMR00 is invalid or cannot be found. No prompting of the operator will occur. If the member contains both valid and invalid parameters, an informational message will indicate the valid options that were accepted before the error occurred.

### Recommendation for IEADMR00 with z/OS UNIX

The system writes a SYSMDUMP as the core dump of a forked address space that runs a z/OS UNIX process. A core dump is written to a z/OS UNIX file on behalf of the user experiencing the error. To obtain sufficient diagnostic data without consuming excessive storage in the file system, request the following options in IEADMR00:

```
SDATA=(RGN,TRT,SUM)
```

### Parameter in IEASYSxx (or specified by the operator)

None.

### Syntax rules for IEADMR00

The following rule applies to the replacement of IEADMR00:

- There is one keyword, SDATA. The keyword is followed by a string of operands separated by commas and enclosed in parentheses. A single operand does not need parentheses.

```
SDATA=(SQA,TRT)           or           SDATA=ALLSDATA
```

- Lines that begin with an asterisk in column 1 are comments.
- Alternatively, to include a comment, place the comment on the same line as the data. Use at least one blank to separate the data from the comment. The following example shows a continuation and the related comments.

```
SDATA=(SQA,LSQA,  SQA and LSQA data
SWA,TRT)          SWA and trace data
```

## IBM-supplied default for IEADMR00

---

The IBM-supplied default parmlib member is IEADMR00, which contains  
SDATA=(NUC,SQA,LSQA,SWA,TRT,RGN,SUM).

## Statements and parameters for IEADMR00

---

### SDATA=

#### ALLSDATA

Except ALLNUC and NOSYM, all the following options are automatically specified.

The following parameters request dump of specific SDATA areas, as indicated:

#### ALLNUC

Entire control program nucleus. The PSA is included.

#### CSA

Common service area subpools that are not fetch protected.

#### GRSQ

All global resource serialization control blocks and other global resource serialization storage.

#### LPA

Contents of the LPA related to the failing task. These include module names and contents. Also includes SVCs related to the failing task.

#### LSQA

Local system queue area for the address space. If storage is allocated for subpools 229, 230 and 249, they will also be dumped.

#### NOSYM

No symptom dump is to be produced.

#### RGN

Private area for the address space region.

#### NUC

Read/write portion of the control program nucleus. The PSA is included.

#### SQA

The system queue area.

#### SUM

Summary dump information as provided in the SVC dump. (See the description of the SUM parameter for the SDUMP macro in [z/OS MVS Programming: Assembler Services Reference ABE-HSP](#).)

#### SWA

Scheduler work area that is used for the failing task.

#### TRT

System trace table and GTF trace, as available.



## Chapter 49. IEAFIXxx (fixed LPA list)

Use the IEAFIXxx member to specify the names of modules that are to be fixed in storage for the duration of an IPL. (The libraries, which contain the modules, must be cataloged in the system master catalog, unless the VOLUME parameter is specified.) You can use IEAFIXxx to temporarily add or replace SVC or ERP routines that already exist in the pageable LPA (PLPA), or to page fix such routines to improve system performance.

Like the temporary modules chosen through the MLPA option, fixed link pack area (FLPA) modules are not automatically reactivated by a quick start or a warm start IPL. That is, the FLPA can be reestablished only by re-specification of the FIX parameter at the quick start or warm start IPL.

### Note:

1. Any library that includes modules for the FLPA must be a PDS. You cannot use PDSEs in the LPAIST concatenation.
2. As of MVS Version 4.3, it is no longer necessary for the data sets in the LPAIST to be APF-authorized. However, any module in the fixed link pack area will be treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected any data set named in IEAFIXxx to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

Because fixed modules are not paged, you can save I/O time and paging overhead by placing moderately used modules into the FLPA. This can shorten the LPAIST concatenation. When a module is requested, the program manager searches the list of fixed routines before it examines the pageable LPA directory. The price for this performance improvement is the reduction in storage available for paging old jobs and starting new jobs. Remember that pages referenced frequently tend to remain in storage even when they are not fixed.

You can use the FLPA to reduce page-fault overhead at the expense of some storage. This trade-off is desirable with a system that tends to be CPU-bound but has sufficient storage.

You carry out the trade-off by placing moderately used modules into the FLPA (through IEAFIXxx). High usage PLPA modules probably need not be fixed because they are referenced frequently enough to remain in storage. Because less storage will be available for pageable programs, the system will swap out address spaces that would otherwise occupy storage, awaiting CPU availability.

Modules specified in IEAFIXxx are loaded and fixed in the order in which they are specified in the member (to keep search time within reasonable limits, do not allow the FLPA to become excessively large). If the first load module of a type 3 or 4 SVC routine is specified, the SVC table is updated as required.

Modules specified in IEAFIXxx are placed in the FLPA or in the extended FLPA, depending on the RMODE of the modules. Modules with an RMODE of 24 are placed in the FLPA, while those with an RMODE of ANY are placed in the extended FLPA.

The FLPA and the extended FLPA are page-protected by default. A protection exception occurs if there is an attempt to store data into either area.

To override page protection, use the NOPROT option on the FIX system parameter.

**Note:** The FLPA and the extended FLPA are not mapped V=R. Modules in either area cannot be assumed to be backed by contiguous real frames.

## Parameter in IEASYSxx (or specified by the operator)

```
FIX= {aa
      {aa[,L][,NOPROT]}
      {aa,bb,...[,L][,NOPROT]}}
```

The two characters (A-Z, 0-9, @, #, or \$) represented by aa (or bb, etc.), are appended to IEAFIX to form the name of one or more IEAFIXxx members of SYS1.PARMLIB. The system defaults to no FLPA, if you fail to specify the option in one of the following ways:

- FIX keyword included in the IEASYSxx member.
- FIX keyword entered by the operator at IPL.

The LPA modules that are fixed in storage are also page protected, by default. If an attempt is made to store into a page-protected module, a protection exception occurs. However, an installation can use the NOPROT option to override the page protection default. When NOPROT is specified, the LPA modules in the IEAFIXxx parmlib member(s) are not page protected in storage.

If the L option is specified, the system displays the contents of the IEAFIXxx parmlib member(s) at the operator's console as the system processes the member(s).

## Syntax rules for IEAFIXxx

The following rules apply to the creation of IEAFIXxx:

- Each statement must begin with the INCLUDE keyword.
- The library name follows the LIBRARY keyword and is enclosed in parentheses.
- The list of modules follows the MODULES keyword and is enclosed in parentheses. Any number of module names can be specified.

Use major names or alias names, or both. Any alias names by which a module is to be accessed must be included. If an alias name is included and the associated major name is omitted, the system will locate the major name.

- The statement is assumed to be all information from one INCLUDE keyword to the next INCLUDE keyword or until end-of-file.
- Use all columns except 72 through 80.
- Blanks or commas can be used as delimiters. Multiple occurrences of a delimiter are interpreted as a single delimiter.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/". They are allowed anywhere a delimiter is allowed.

## Syntax format of IEAFIXxx

```
INCLUDE    LIBRARY(data-set-name)
           VOLUME(volser)
           MODULES(module-name, module-name,...)
```

## Syntax example of IEAFIXxx

```
INCLUDE    LIBRARY(SYS1.LINKLIB)  MODULES( IKJPARS IKJPARS2 IKJSCAN
                                           IKJEFD00 IKJDAIR)

INCLUDE    LIBRARY(SYS1.SVCLIB)   MODULES(IGC000RC,IGC09302,IGC09303)

INCLUDE    LIBRARY(SYS1.AUTHLIB)  MODULES(IEAV0021,IEAV0032,IEAV0033,
                                           IEAV0041,IEAV0042,IEAV0043,
                                           IEAV0053,IEAV0054)
```

## IBM-supplied default for IEAFIXxx

---

None.

## Statements and parameters for IEAFIXxx

---

### **INCLUDE**

Specifies modules to be loaded as a temporary extension to the existing pageable link pack area (PLPA).

Both LIBRARY and MODULES must be specified. VOLUME is optional.

### **LIBRARY**

Specifies a data set name. The specified library, which must be a PDS, must be cataloged in the system master catalog unless you specify a volser using VOLUME. In this case, the data set must be on the specified volume.

If you specify SYS1.LINKLIB or SYS1.LPALIB, the system uses only those libraries, and not their concatenations.

### **MODULES**

Specifies a list of 1 to 8 character module names.

### **VOLUME**

Allows uncataloged data sets.



## Chapter 50. IEALPAXx (modified LPA list)

Use the IEALPAXx member to specify the reenterable modules that are to be added as a temporary extension to the pageable link pack area (PLPA). (The libraries, which contain the modules, must be cataloged in the system master catalog, unless the VOLUME parameter is specified.) This extension is temporary; the modules will remain in paging data sets and will be listed on the active LPA queue only for the duration of the IPL.

The system will not automatically quick-start or warm-start these modules (that is, reinstate the modules without re-specification of the MLPA parameter). Both the modified LPA (MLPA) and the fixed LPA (FLPA) modules (those named in IEAFIXxx) do not require the system to search the LPA directory when one of the modules is requested. The modified LPA, unlike the fixed LPA, however, contains pageable modules that behave in most respects like PLPA modules.

### Note:

1. A library that includes modules for the MLPA must be a PDS. You cannot use PDSEs in the LPA LST concatenation.
2. The data sets in the LPA LST can be a mixture of APF-authorized and non-APF-authorized data sets. However, any module in the modified link pack area will be treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected any library that contributes modules to the modified link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.
3. If duplicate entries are found for a module or alias name, the first instance is used and subsequent instances are ignored.

You can use IEALPAXx to temporarily add or replace SVC or ERP routines. Another possible application would be the testing of replacement LPA modules that have been altered by PTFs.

LPA modules specified in IEALPAXx are placed in the MLPA or in the extended MLPA, depending on the RMODE of the modules. Modules with an RMODE of 24 are placed in the MLPA, while those with an RMODE of ANY are placed in the extended MLPA. By default, the MLPA and the extended MLPA are page protected, which means that a protection exception will occur if there is an attempt to store data into either area. To override page protection, use the NOPROT option on the MLPA system parameter.

LPA modules that have been replaced through IEALPAXx are not physically removed from the PLPA or from the LPA directory. They are, however, logically replaced because, when one of them is requested, MLPA is searched first and the system does not examine the LPA directory which contains the name of the replaced module.

The system searches the fixed LPA before the modified LPA for a particular module and selects the module from the modified LPA only if the module is not also in the fixed LPA.

If the first load module of a type 3 or 4 SVC routine is added or replaced, the SVC table is updated as required.

## Parameter in IEASYSxx (or supplied by the operator)

```
MLPA= {aa
      {(aa[,L][,NOPROT])
      {(aa,bb,...[,L][,NOPROT])}
```

The two characters (A-Z, 0-9, @, #, or \$) represented by aa (or bb, and so forth), are appended to IEALPA to form the name of the IEALPAXx parmlib members. If the L option is specified, the system displays the contents of the IEALPAXx parmlib members at the operator's console as the system processes the members.

Because the modified LPA is not a permanent addition to the LPA, you should specify MLPA in an alternate system parameter list (IEASYSxx) and not in IEASYS00. Or, you can have the operator enter the parameter from the console.

The LPA modules in the IEALPxx parmlib members are page-protected in storage, by default. If an attempt is made to store into a page-protected module, a protection exception occurs. However, the NOPROT option allows an installation to override the page protection default. When NOPROT is specified, the LPA modules in the IEALPxx parmlib members are not page-protected.

## Syntax rules for IEALPxx

The following rules apply to the creation of IEALPxx:

- Each statement must begin with the INCLUDE keyword.
- The library name follows the LIBRARY keyword and is enclosed in parentheses.
- The list of modules follows the MODULES keyword and is enclosed in parentheses. Any number of module names can be specified.

Use major names or alias names, or both. Any alias names by which a module is to be accessed must be included. If an alias name is included and the associated major name is omitted, the system will locate the major name.

- The statement is assumed to be all information from one INCLUDE keyword to the next INCLUDE keyword or until end-of-file.
- Use all columns except 72 through 80.
- Blanks or commas can be used as delimiter. Multiple occurrences of a delimiter are interpreted as a single delimiter.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/". They are allowed anywhere a delimiter is allowed.

## Syntax format of IEALPxx

```
INCLUDE    LIBRARY(data-set-name) [VOLUME(volser)]
           MODULES(module-name, module-name,...)
```

## Syntax example of IEALPxx

```
INCLUDE    LIBRARY(SYS1.LINKLIB)  MODULES( IKJPARS IKJPARS2 IKJSCAN
                                           IKJEFD00 IKJDAIR)

INCLUDE    LIBRARY(SYS1.SVCLIB)   MODULES(IGC000RC,IGC09302,IGC09303)

INCLUDE    LIBRARY(SYS1.U30LIB)   MODULES(IEAU0021,IEAU3002,IEAU3003)

INCLUDE    LIBRARY(SYS1.AUTHLIB)  MODULES(IEAV0021,IEAV0032,IEAV0033,
                                           IEAV0041,IEAV0042,IEAV0043,
                                           IEAV0053,IEAV0054)

INCLUDE    LIBRARY(MY.U90LIB)     VOLUME(U90PAK) MODULES(MYMOD1,MYMOD2)
```

## IBM-supplied default for IEALPxx

None.

## Statements and parameters for IEALPAxx

---

### **INCLUDE**

Specifies modules to be loaded as a temporary extension to the existing PLPA. Both LIBRARY and MODULES must be specified. VOLUME is optional.

### **LIBRARY**

Specifies a data set name. The specified library, which must be a PDS, must be cataloged in the system master catalog unless you specify a volser using VOLUME in which case the data set must be on the specified volume. (If you specify SYS1.LINKLIB or SYS1.LPALIB, the system uses only those libraries, and not their concatenations.)

### **MODULES**

Specifies a list of 1 to 8 character module names.

### **VOLUME**

Allows uncataloged data sets.





## Chapter 51. IEAOPTxx (OPT parameters)

The OPT parameters allow the installation to change many system resources manager (SRM) constants. The following list categorizes the options as special including, for example, abnormal termination or whether non-enclave transaction work of queue servers and enclave servers is to be managed or not, adjusting options for constants, or options for special assist processors.

The OPT contains several categories of information. The keywords do not have to be grouped by category and can appear in any order. The system ignores both repetition of a keyword and the use of keywords that were used in previous releases and are no longer supported.

### Special options

- [,ABNORMALTERM=*option*]
- [,ABSMSUCAPPING=*option*]
- [,AIMANAGEMENT=YES|NO]
- [,CNTCLIST=*option*]
- [,DVIO=*option*]
- [,FULLPRESYSTEM=YES|NO]
- [,HIPERDISPATCH=YES|NO]
- [,INITIMP=*option*]
- [,MANAGENONENCLAVEWORK=YES|NO]
- [,VARYCPU=*option*]
- [,VARYCPUMIN=*nn*]
- [,STORAGESERVERMGT=YES|NO]
- [,SUPPSAFINFOMSG=YES|NO]

### Adjusting constant options

- Enqueue residence constants
  - [,ERV=xxxxxx]
- SRM invocation interval constant
  - [,RMPTTOM=xxxxxx]
- MPL adjustment constants
  - [,RCCFXET=(xxxxx,yyyyy)|AUTO]
  - [,RCCFXTT=(xxxxx,yyyyy)|AUTO]
- CPU management constants
  - [,BLWLINTHD=*option*]
  - [,BLWLTRPCT=*option*]
  - [,CCCAWMT=xxxxxxx]
  - [,CCCSIGUR=*option*]
  - [,CCIMP=0|1|2]
  - [,CCIMPBOOST=0|1|2]
  - [,TIMESLICES=*option*]
- Pageable storage and real storage constants

- [,IRA405I(n)=xx]
- [,MCCAFCTH=xxxxx,yyyyy]
- [,MCCFXEPR=xxx]
- [,MCCFXTPR=xxx]
- [,STORAGENSWDP=xxx]
- [,STORAGEWTOR=xxx]
- Selective enablement for I/O constants
  - [,CPENABLE=(xxx,yyy) | SYSTEM]
- Routing options
  - [,RTCAPLEADTIME=x]
  - [,RTBELEADTIME=x]
  - [,RTPIFACTOR=xxx]
  - [,WASROUTINGLEVEL=x]
  - [,WLMIRDSTRUC=*option*]
- Resource contention constants
  - [,MAXPROMOTETIME=xxxxx]

### Special assist processor options

- [IIPHONORPRIORITY= YES|NO]
- [PROJECTCPU=YES|NO]
- [MT\_ZIIP\_MODE=1|2]
- [ZIIPAWMT=xxxxx]

## Syntax rules for IEAOPTxx

---

Comments may appear in columns 1-71 and must begin with "/" and end with "\*/".

## IBM-supplied default for IEAOPTxx

---

The IBM-supplied default parmlib member is IEAOPT00 with ERV=500.

## Statements and parameters for IEAOPTxx

---

### **ABNORMALTERM=option**

Specifies whether the abnormal terminations that are reported by the WLM report service IWMRPT for a server are included when computing the weight of the routing service IWM4SRSC that is called for the server. In the syntax, *option* is either YES or NO.

#### **NO**

The abnormal terminations that are reported by the IWMRPT service are not included when computing the weight of the IWM4SRSC routing service.

#### **YES**

The abnormal terminations are included when computing the weight of the IWM4SRSC routing service.

**Default:** YES

### **ABSMSUCAPPING=option**

Specifies whether a defined capacity limit or group capacity limit is to be enforced only while the long term four-hour rolling average consumption is greater than or equal to the defined limit, or if it should always be enforced. In the syntax, *option* is either YES or NO.

**NO**

The defined capacity limit or group capacity limit is enforced only while the long term four-hour rolling average consumption is greater than or equal to the respective limit.

**YES**

The defined capacity limit or group capacity limit is enforced permanently, independently of the long term four-hour rolling average consumption.

**Default:** NO

Absolute MSU capping requires an IBM zEC12 (GA2) CPC, or later, server to become effective.

**AIMANAGEMENT=YES|NO**

Specifies whether WLM is to use artificial intelligence (AI) for WLM-managed batch initiators for all service classes that are enabled for AI.

WLM only uses AI for batch initiator management when all of the following conditions are true:

- The **AIMANAGEMENT** parameter in the active IEAOPTxx member is set to (or defaulted to) YES.
- The AI Framework for IBM z/OS components are configured and started, including the AI model server and the AI Base Component for IBM z/OS.
- The AI model for WLM batch initiator management is trained and deployed, and enabled for specific service classes via the AI Control Interface for IBM z/OS task in z/OSMF.

**BLWLINTHD=option**

Specifies the threshold time interval for which a blocked address space or enclave must wait before being considered for promotion.

If the CPU utilization of a system is at 100%, workloads with low importance (low dispatch priority) might no longer be dispatched. This can lead to problems if the low priority work holds a resource that is required by high priority workloads. Therefore, if an address space or enclave has ready-to-run work units (TCBs or SRBs) but does not get CPU service for the specified time interval because of its low dispatch priority, it is temporarily promoted to a higher dispatch priority. Address spaces that are swapped out are not considered for promotion.

**Value range:** 1–65535 seconds

**Default:** 20 seconds

**BLWLTRPCT=option**

Specifies how much of the CPU capacity is to be used to promote blocked workloads. This parameter does not influence the amount of CPU service that a single blocked address space or enclave is given. Instead, this parameter influences how many different address spaces or enclaves can be promoted at the same point in time. If the value specified with this parameter is not large enough, blocked workloads might need to wait longer than the time interval defined by BLWLINTHD.

**Value range:** 0–200 (up to 20%. 0% indicates blocked workload support is not enabled).

**Default:** 5 (0.5%)

**CCCAWMT=xxxxxxx**

Specifies whether to activate or deactivate Alternate Wait Management (AWM). If AWM is active, SRM and LPAR cooperate to reduce low utilization effects and overhead. In an LPAR, some *n*-way environments with little work appear to require more capacity than expected because of the time spent waking up idle logical and physical processors to compete for individual pieces of work. If AWM is active, SRM and LPAR reduce this unproductive use of processor so that capacity planning is more accurate and CPU overhead is reduced.

**Value range:**

- For HIPERDISPATCH=NO, any value 1–499999 makes AWM active, and any value 500000–1000000 makes AWM inactive. AWM is active or inactive only for general purpose processors (CPs) and zIIPs.
- For HIPERDISPATCH=YES, the valid range is 1600–3200. Any other value is reset to the default value of 3200. AWM is always active and cannot be turned off.

**Default:** AWM is active. For HIPERDISPATCH=NO, the default is 12000 (12 ms). For HIPERDISPATCH=YES, the default is 3200 (3.2 ms).

**Notes:**

1. There can be a significant effect on performance by using large values (such as 490,000) to activate AWM. IBM strongly suggests accepting the default value. Specify a value for CCCAWMT in order to override the default after consulting with the IBM Support Center. Do not specify what is thought to be the default value as a means of disabling any OPT control. Default values sometimes change over time. Always convert a control to a comment (see the following example) if the objective is to use the default value while retaining a reminder of the last value used.

```
/* CCCAWMT=5000000      now a comment - used to turn off AWM    */
```

2. Specify a value greater than or equal to 500000 to deactivate AWM. AWM should be active when IBM z Integrated Information Processors (zIIP) are present and IIPHONORPRIORITY=YES is specified. See the description of the [IIPHONORPRIORITY](#) parameter for more information. You should accomplish this by removing the CCCAWMT parameter (whereby the default is for AWM to be active).

**CCCSIGUR=option**

Specifies the minimum mean-time-to-wait threshold value for heavy CPU users. This constant is used to determine the range of mean-time-to-wait values that are assigned to each of the 10 mean-time-to-wait dispatching priorities. The specified real time value is adjusted by relative processor speed to become SRM time to insure consistent SRM control across various processors.

**Value range:** 0–32767 milliseconds

**Default:** 45

**CCImp=0|1|2**

**CCImpBoost=0|1|2**

Specifies how CPU protection is implicitly assigned to work. **CCImp** applies when no boost is active; **CCImpBoost** applies while the boost is in effect.

**0**

CPU protection is not assigned to any work unless **CPU Critical** has been explicitly assigned for the service class in the active WLM policy.

**1|2**

Specifies the importance level up to which CPU protection is implicitly assigned to the work when **CPU Critical** has not been assigned for the service class in the active WLM policy.

**Default:** CCImp=1 and CCImpBoost=2

**Notes:**

- Implicit CPU protection is only assigned to single-period service classes and the first period of multi-period service classes.
- To complete a **CCImp** change for an active system after the SET OPT command was issued, SRM issues a policy refresh for that active system. Workload management issues the IWM065I message to indicate the policy refresh.
- To complete a **CCImpBoost** change for an active system, SRM does not immediately issue a policy refresh but activates the change only when the next recovery process boost or shutdown boost starts or the VARY WLM command is used to activate a policy.

**Examples:**

- CCImp=0 and CCImpBoost=1 suppresses implicit CPU protection in general but enables implicit CPU protection when a boost is in effect for importance 1 work.
- CCImp=1 and CCImpBoost=1 assigns implicit CPU protection for any importance 1 work.

**CNTCLIST=option**

Specifies if the individual commands in a TSO/E CLIST are treated as separate commands for transaction control.

In the syntax, *option* is either YES or NO.

**NO**

The CLIST is treated as a single transaction.

**YES**

Each command is to be treated as an individual transaction. By specifying CNTCLIST=YES, SRM control of a TSO/E command becomes the same whether the command is executed explicitly or as part of a CLIST.

**Value range:** YES or NO

**Default:** NO

**CPENABLE=(xxx,yyy) | SYSTEM**

Specifies the low (ICCTPILO) and high (ICCTPIHI) threshold values for the percentage of I/O interruptions to be processed through the test pending interrupt (TPI) instruction path in IOS. SRM uses these thresholds to dynamically manage the number of logical processors that are enabled for I/O interruptions. When the measured percentage of I/O interrupts handled using TPI is higher than the range specified, the system enables an additional CP for I/O interrupts. When the measured percentage is lower than the specified range the system disables one of the processors already handling I/O interrupts.

CPENABLE=(0,0) invalidates the thresholds and enables all logical processors in the LPAR for I/O interrupts, which is usually not recommended.

CPENABLE=SYSTEM automatically applies the low and high thresholds recommended by IBM (5 and 15 for LPARs running on IBM z14 and later processors) and removes the need to update the parameter with a hardware migration.

You can find more information about the CPENABLE setting in CPENABLE Recommendations for IBM Z and z/OS ([www.ibm.com/support/pages/node/6353717](http://www.ibm.com/support/pages/node/6353717)) on IBM Techdocs.

**Default:** CPENABLE=SYSTEM

**DVIO=option**

Specifies whether directed VIO is to be active in the system or not.

**NO**

Directed VIO is not to be active in the system; the NONVIO parameter of the IEASYSxx parmlib member is ignored.

**YES**

Directed VIO is to be active in the system; that is, the NONVIO keyword of the IEASYSxx parmlib member is honored.

**Default:** YES

**ERV=xxxxxx**

Specifies the number of CPU service units that an address space or enclave is allowed to absorb when it is possibly causing enqueue contention.

During this “enqueue residency” time, the address space (including the address space that is associated with an enclave) is not considered for swap-out based on recommendation value analysis. The address space or enclave runs with a high enough priority to guarantee the needed CPU time.

ERV is in effect for an address space or enclave that meets one of the following criteria:

- The address space or enclave is enqueued on a system resource that is needed by another address space.

- An authorized program in the address space or enclave obtains control of the resource (even if another address space does not need that resource) as a result of issuing a reserve for a DASD device that is SHARED.

**Note:** SRM determines the execution time equivalent to the specified ERV by multiplying the ERV by the model-dependent time that is needed to accumulate 1 CPU service unit.

**Example:** ERV=2

In the preceding example, if an address space consumes one service unit in 10 milliseconds, it is allowed to execute for 20 milliseconds before it is eligible for swap-out while enqueued on a resource requested by other address spaces.

**Value range:** 0–999999

**Default:** 500

#### **FULLPRESYSTEM=YES|NO**

Specifies the SRM to allow full preemption for the system address spaces.

##### **NO**

SRM turns off full preemption mode for the system address spaces.

##### **YES**

SRM allows full preemption handling for system address spaces. To free up a processor immediately when such an address space becomes ready, the system issues signal processor (SIGP) instructions. The SIGP instructions also run in HiperDispatch mode, so when HIPERDISPATCH=YES and FULLPRESYSTEM=YES, too much LPAR overhead can result. Therefore:

- Use FULLPRESYSTEM=NO when HIPERDISPATCH=YES.
- Use FULLPRESYSTEM=YES when HIPERDISPATCH=NO.

**Default:** The default values are as follows:

- NO when HiperDispatch is in effect.
- YES when HiperDispatch is not in effect.

#### **HIPERDISPATCH=YES|NO**

##### **YES**

Specifies that SRM is to turn on HiperDispatch mode.

##### **NO**

Specifies that SRM is to turn off HiperDispatch mode.

Partitions with greater than 64 logical processors defined at IPL are forced to run with HIPERDISPATCH=YES. After IPL, partitions with greater than 64 logical processors are unable to switch into HIPERDISPATCH=NO. Also, when partitions specify LOADxx PROCVIEW CORE, they are forced to run with HIPERDISPATCH=YES.

**Note:** When HIPERDISPATCH=YES, VARY CPU management is automatically turned off no matter what is specified for VARYCPU.

**Default:** YES

#### **IFAHONORPRIORITY=YES|NO**

This parameter is deprecated and not used by SRM.

#### **IIPHONORPRIORITY=YES|NO**

Specifies whether zIIP processors get help from general purpose processors (CPs) when there is insufficient capacity for the workload demand.

##### **NO**

Specifies that CPs never examine zIIP processor eligible work. General purpose processors also run zIIP processor eligible work if it is necessary to resolve contention for resources with non-zIIP processor eligible work.

**YES**

Specifies that general purpose processors run both zIIP processor eligible and non-zIIP processor eligible work in priority order when the zIIP processors indicate the need for help from general purpose processors. The need for help is determined by the alternate wait management (AWM) function of SRM for both CPs and zIIPs. (See the description of the [CCCAWMT](#) parameter for a description of AWM.) CPs help each other, and CPs can also help zIIPs if YES is in effect, which is the default. Specifying YES does not mean that the priorities are always honored, because the system manages dispatching priorities based on the goals that are provided in the WLM service definition. AWM should not be disabled when IIPHONORPRIORITY=YES is in effect.

If zIIP processors are defined to the LPAR but are not online, the zIIP-eligible work units are processed by CPs in priority order. The system ignores the IIPHONORPRIORITY parameter in this case and handles the work as if it had no eligibility to zIIP processors. The zIIP-eligible processor times are reported in RMF and SMF for planning purposes.

**Recommendation:** Specify or default to IIPHONORPRIORITY=YES.

**Default:** YES

**INITIMP=option**

Specifies the dispatching priority for batch, APPC, and OMVS initiators. The option is specified as one of the following values:

**0**

The initiator dispatching priority is set to 254.

**1,2,or 3**

Defines that the initiator dispatching priority has to be lower than the dispatching priority for CPU critical work with the same or a higher importance level.

If no service class with the CPU critical attribute and a corresponding or higher importance level is defined in the WLM policy, the dispatching priority is calculated in the same way as for parameter INITIMP=E.

**E**

Defines that the initiator dispatching priority is calculated in the same way as the enqueue promotion dispatching priority. The dispatching priority is calculated dynamically to ensure access to the processor. It should not impact high importance work; however, there is no guarantee that CPU critical work always has a higher dispatching priority.

An INTIMP value affects only the system on which it was set.

**Example:** INITIMP=2

With INITIMP=2, if there are service classes with an importance of 2 and the CPU critical attribute, the dispatching priority of initiator address spaces is always lower than the dispatching priority of the work running in those service classes. Because CPU critical work with a higher importance level always has a higher dispatching priority, the dispatching priority of the initiator is also lower than any CPU critical work with an importance of 1.

With INITIMP=2 and CPU critical work with an importance of 1 and 3, the initiator always has a lower dispatching priority than the work running in the service class with the CPU critical attribute and an importance of 1 but not for the work running in the CPU critical service class with an importance of 3.

With INITIMP=2 and no service classes with the CPU critical attribute and an importance of 1 or 2, the initiator dispatching priority is set to the enqueue promotion dispatching priority which is dynamically calculated. The initiators do not run at a dispatching priority of 254 as that is only the case if you do not specify the INITIMP parameter or if you have set it to 0.

**Default:** 0

**IRA405I(n)=xx**

Specifies the percentage of the fixed storage that causes the system to issue message IRA405I. Specify a value for *n* to indicate the storage area, where *n* can be:

**0**

Real storage area below 16 M.

**1**

Real storage area between 16 M and 2 G.

**2**

Total real storage.

And xx is the percentage value (without the percent symbol - %) of the fixed storage, as shown in the following example:

```
IRA405I(1)=60
```

When each value of the *n* is specified, the value ranges and the default values for the IRA405I parameter can be:

**IRA405I(0)****Value range:** 0–100**Default value:** 70**IRA405I(1)****Value range:** 0–100**Default:** 50**IRA405I(2)****Value range:** 0–100**Default:** 50

**Note:** Applications like Db2®, zCX, and some other applications fix the majority of frames. It is normal on systems where such applications are active that message IRA405I occurs when the default value was not changed. If you run such applications on your system, you should change the IRA405I(2) OPT parameter to a higher value.

**MANAGENONENCLAVEWORK=option**

Specifies whether non-enclave transaction work of queue servers and enclave servers is to be managed or not, where *option* is YES or NO.

**NO**

Indicates that you expect no work consuming significant CPU service to be running in the address space outside of an enclave. The CPU consumption of work running outside of enclaves is not included when workload management assesses the impact of CPU adjustments for the enclave work.

**YES**

Indicates that SRM is to manage the non-enclave transaction work towards the first service class period of the address space performance goal. Based on this expanded performance management, be sure to verify the performance goals for the service class of the address spaces that process the enclave work. For a detailed description, see the section on performance management of address spaces with enclaves in [z/OS MVS Programming: Workload Management Services](#).

This performance management is available for z/OS V1R12 and later releases.

**Notes:**

- To complete a MANAGENONENCLAVEWORK status change from YES to NO or NO to YES for an active system, SRM issues a policy refresh for that active system. Workload management indicates the policy refresh for this status change with message IWM065I.
- The non-enclave work of an address space is not performance managed if the service class of the address space is a system-provided service class other than SYSOTHER. This condition exists even if the OPT parameter ManageNonEnclaveWork=YES was specified.



**Default:** NO

**Example:** MANAGENONENCLAVEWORK=YES

In the example, SRM is to manage the non-enclave work of enclave servers and queue servers.

#### **MAXPROMOTETIME=xxxx**

Specifies the time during which a resource holder is allowed to run promoted when it is possibly causing a resource contention. A resource holder is either an address space or enclave. During this resource contention residency time, the resource holder runs with the highest priority of all resource waiters to guarantee the needed importance. Also, during this interval, the address space (including the address space that is associated with an enclave) is not considered for swap-out based on recommendation value analysis. If MAXPROMOTETIME=0 is specified, SRM does not promote any resource holder.

MAXPROMOTETIME is in effect if the resource manager has notified the address space or enclave under contention by using the WLM IWMCNTN notification service. See *z/OS MVS Programming: Workload Management Services* for a description of the WLM IWMCNTN service.

The value that is specified for MAXPROMOTETIME is multiplied by 10. This is the time span in seconds during which the address space or enclave under contention is allowed to run promoted.

**Example:** MAXPROMOTETIME=12

With MAXPROMOTETIME=12, SRM allows an address space or enclave to run  $12 \times 10$  seconds (=2 minutes) promoted. When the time is exceeded, the promotion is canceled.

**Value range:** 0–1000

**Default:** 6

#### **MCCAFCTH=(lowvalue,okvalue)**

Specifies the low and the OK threshold values for storage. The *lowvalue* indicates the number of frames on the available frame queue when stealing begins. The *okvalue* indicates the number of frames on the available frame queue when stealing ends. SRM automatically adjusts the actual threshold values based on measurements of storage usage, but threshold values should never fall below the values that are specified in MCCAFCTH. You do not have to specify an MCCAFCTH value.

If the *lowvalue* or *okvalue* is below the default value, the default value is enforced.

**Value range:** *lowvalue*=1–32767 frames

**Default:** The maximum of 400 and 0.2% of the pageable storage in the system

**Value range:** *okvalue*=1–65535 frames

**Default:** The maximum of 800 and 0.4% of the pageable storage in the system

#### **MCCFXEPR=xxx**

Specifies the percentage of storage that is fixed within the first 16 megabytes. SRM uses this threshold to determine when a shortage of pageable storage exists because there are too many fixed pages.

**Value range:** 0–100 percent

**Default:** 92 percent

#### **MCCFXTPR=xxx**

Specifies the percentage of online storage that might be fixed. SRM uses this threshold to determine when a shortage of pageable storage exists.

**Note:** SRM uses the lesser of the values, (MCCFXTPR  $\times$  amount of online storage) and (MCCFXEPR  $\times$  amount of storage that is fixed within the first 16 megabytes) to set the threshold frame count so that it can detect a shortage of pageable storage that is caused by too much page fixing. In this way, SRM can detect a shortage of pageable storage that is caused by too much page fixing before or at the same time as a shortage caused by too much paging.

**Value range:** 0–100 percent

**Default value:** On small systems (less than 320 GB), the target is 80 percent. On large systems (more than 320 GB), the target is total storage minus 64 GB.

**Note:** If  $100\% - \text{MCCFXTPR} \times \text{the total amount of online frames}$  is greater than 64 gigabytes, the MCCFXTPR keyword is not used in determining the threshold at which a shortage of pageable storage exists.

Instead, on systems with more than 320 gigabytes of storage, a pageable storage shortage is detected when less than 64 gigabytes of online storage is pageable.

When calculating the number of frames that can be page fixed before a pageable storage shortage is detected, SRM uses the maximum of  $\text{MCCFXTPR} \times \text{the total online frames}$  and total online storage minus 64 gigabytes.

#### **MT\_CP\_MODE=1**

#### **MT\_ZIIP\_MODE=1|2**

Specifies the multithreading (MT) mode, which is the number of active threads per core for all online cores with a core type of general purpose processor (CP), or IBM z Integrated Information Processor (zIIP).

#### **MT\_CP\_MODE=**

The number of active threads to activate for each online CP core. Any value is limited to what the underlying hardware and operating system support.

#### **MT\_ZIIP\_MODE**

The number of active threads for each online zIIP core. Any value is limited to what the underlying hardware and operating system support.

A value of 1 is always accepted.

Activating an MT mode greater than 1 requires the following:

- The hardware must support multithreading.
- The system must be IPLed with LOADxx PROCVIEW CORE in effect.
- HIPERDISPATCH=YES must be in effect.

If these requirements are met, the MT mode for all cores of the respective processor class is changed to the specified value/mode if the current MT mode is different from that value. In a successful change of the MT Mode, message IWM066 is issued. For an unsuccessful request, message IWM067 is issued.

Changing the MT Mode for all cores of the same type can take multiple seconds to complete.

#### **PROJECTCPU=YES|NO**

Specifies whether to activate or deactivate the projection of how work could be offloaded from general purpose processors (CPs) to IBM z Integrated Information Processors (zIIP).

#### **Note:**

1. The PROJECTCPU parameter is not necessary if you can define a zIIP as a reserved processor in the LPAR configuration. The PROJECTCPU parameter is provided for users of earlier processors on which defining a zIIP as a reserved processor is not supported when no zIIP is purchased for planning purposes.
2. If the installation requires ZIIP statistics but there is no ZIIP defined (reserved or actual) on the LPAR, then PROJECTCPU=YES is required regardless of hardware model.
3. Any work that is eligible for being offloaded to a zIIP is reported as zIIP\_on\_CP work. This information can be used to understand the benefit of adding a special processor into the configuration.

**Values:** YES or NO

**Default:** NO. Projection is not done, unless a zIIP is configured to the system. In that case, the system collects projection values.

**RCCFXET=option**

SRM uses these thresholds to determine whether the system MPL needs to be increased or decreased based on the first 16 MB. The values that you can specify for *option* are as follows:

**(aaa,bbb)**

Specifies the low (RCCFXETL) and the high (RCCFXETH) percentages of storage that is fixed within the first 16 megabytes.

**AUTO**

Specifies that SRM determines the two threshold values that are based on the storage configuration of the system.

**Value range:** 0–100 percent, or AUTO

**Default:**

*aaa* = 82

*bbb* = 88

If the system has more than 64 GB of real storage, AUTO is enforced.

**RCCFXTT=option**

SRM uses these thresholds to determine if the system MPL needs to be increased or decreased. The values that you can specify for *option* are as follows:

**(aaa,bbb)**

Specifies the low (RCCFXTTL) and the high (RCCFXTTH) percentages of online storage that is fixed.

**AUTO**

Specifies that SRM determines the two threshold values that are based on the storage configuration of the system.

**Value range:** 0–100 percent, or AUTO

**Default:**

*aaa* = 66

*bbb* = 72

If the system has more than 64 GB of real storage, AUTO is enforced.

**RMPTTOM=xxxxxx**

Specifies the SRM invocation interval. The specified real-time interval is adjusted by relative processor speed to become SRM time in order to ensure consistent SRM control across various processors. The relationship of real time to SRM time for each processor is described in the [Advanced SRM parameter concepts](#) topic in *z/OS MVS Initialization and Tuning Guide*.

**Value range:** 1000–999999 msec

**Default:**

- 3000 (for systems with a uni-processor speed of more than 100 MIPS)
- 1000 (for systems with a uni-processor speed of 100 MIPS or less)

**RTBELEADTIME=x**

Specifies how far in advance (x minutes) of the end of the IPL Boost period WLM's sysplex routing recommendations reduce the routing weight. This means converging from boosted capacity to regular capacity.

**Value range:** 0–10

**Default:** 3**RTCAPLEADTIME=x**

Specifies how far in advance an upcoming soft capping should influence WLM's sysplex routing recommendations. When the estimated time to capping is less than x minutes, WLM considers the upcoming soft capping in its routing recommendations. Otherwise, it does not consider the upcoming soft capping in its routing recommendations.

**Value range:** 0–60

**Default:** 0

**RTPIFACTOR=xxx**

Specifies how much the server performance index (PI) should affect the server routing weights returned by WLM services IWM4SRSC and IWMSRSRS with FUNCTION=SPECIFIC or FUNCTION=SPECIFICIMP.

- When RTPIFACTOR is 0, the server weight is independent from the server PI.
- When RTPIFACTOR is 100 and the server PI is bigger than 1, the server weight is divided by the server PI.
- When RTPIFACTOR is between 1 and 99, it results in a corresponding intermediate influence of the server PI on the server weight returned by WLM.

**Value range:** 0–100

**Default:** 100

**STORAGENSWDP=option**

Specifies whether the system should select non-swappable address spaces to resolve a storage shortage.

STORAGENSWDP=YES specifies that the system should also select non-swappable address spaces to resolve the storage shortage. The system then sets non-swappable address spaces non-dispatchable and issues message IRA210E or IRA410E.

**Note:** The system does not set address spaces in service class SYSTEM non-dispatchable.

**Value range:** YES or NO

**Default:** YES

**STORAGESERVERMGT=option**

Specifies whether SRM should pass service class importance and goal information to the storage I/O priority manager in the IBM System Storage DS8000® series. The passed information enables the storage I/O priority manager to provide favored processing for I/O requests of important z/OS workloads that are missing their goals.

STORAGESERVERMGT=YES specifies that SRM should pass service class importance and goal information to the storage I/O priority manager. Before specifying STORAGESERVERMGT=YES, verify that your IBM System Storage DS8000 model incorporates the storage I/O priority manager feature.

If STORAGESERVERMGT=YES is specified, the storage I/O priority manager might throttle I/O requests to facilitate a favored access to storage server resources for other I/O requests. The storage I/O priority manager considers the properties of the service class period that is associated with an I/O request to determine whether the I/O request should receive a favored processing or might be throttled:

- For service class periods with a response time goal, the goal achievement and specified importance are considered.
- For service class periods with a velocity goal, the specified velocity goal and importance are considered.
- I/O requests associated with the system-provided service classes SYSTEM, SYSSTC, or SYSSTC1 - SYSSTC5 are not managed by the I/O priority manager.
- I/O requests associated with service class periods that have a discretionary goal are always throttled.

Throttle delays that are introduced by the storage IO priority manager are reflected in control unit queue delays. Therefore, if STORAGESERVERMGT=YES is specified, control unit queue delays are not considered when the achieved velocity and performance index are calculated for service class periods with a velocity goal.

If you have significant control unit queue delays in your installation, you might have to adjust the velocity goal of service class periods when you specify STORAGESERVERMGT=YES.

**Values:** YES or NO

**Default:** NO

### **STORAGEWTOR=option**

Specifies how the system handles address spaces in a critical storage shortage.

STORAGEWTOR=YES specifies that the system presents a list of address spaces on the console. The operator can reply to a WTOR (IRA221D or IRA421D) request and select which address space to cancel. STORAGEWTOR=AUTO is similar to STORAGEWTOR=YES, except that the IRA210I or IRA420I message presents up to 20 address spaces at once. This option is useful, when an automation product needs to answer the WTOR request.

**Values:** YES, AUTO, or NO

**Default:** YES

### **SUPPSAFINFOMSG=option**

Specifies whether SAF informational messages issued for successful completion of RACROUTE invocations in the WLM Begin Server Transaction (IWM4STBG) service should be suppressed.

SUPPSAFINFOMSG=YES specifies that SAF informational messages issued for successful completion of RACROUTE invocations in the WLM Begin Server Transaction (IWM4STBG) service are suppressed. Furthermore, an APPL class profile is passed on the RACROUTE invocation that allows RACF statistics to be restricted to once per user per day. The procedure name associated with the started task is used as the name of the APPL class.

For sample security definitions that restrict RACF statistics to once per user per day, see the topic on reducing application logon statistics in *z/OS Security Server RACF Security Administrator's Guide*

SUPPSAFINFOMSG=NO, which is the default, specifies that informational messages issued for successful completion of RACROUTE invocations in the WLM Begin Server Transaction (IWM4STBG) service are not suppressed. No APPL parameter is passed on the RACROUTE invocation.

**Values:** YES or NO

**Default:** NO

### **TIMESLICES=option**

Specifies the number of time slices that a CPU-intensive address space or enclave with a discretionary goal should be given before a dispatchable unit of equal importance is dispatched.

Increasing this parameter might increase the processor delay for some CPU-intensive work, but decrease the number of context switches between equal priority work, and therefore increase the throughput of the system. This parameter only affects discretionary work that is CPU-intensive as determined by significant mean time to wait (MTTW) (see parameter CCCSIGUR).

**Value range:** 1–255

**Default:** 1

### **VARYCPU=option**

Specifies whether LPAR Vary CPU management is available or not available. Vary CPU management is available only in a partition that is enabled for LPAR weight management. Also, Vary CPU management is automatically turned off no matter what is specified for VARYCPU, if HIPERDISPATCH is on.

#### **NO**

Specifies that LPAR Vary CPU Management is not available.

#### **YES**

Specifies that LPAR Vary CPU Management is available for this system.

**Value range:** YES or NO

**Default:** YES

**VARYCPUMIN=nn**

Specifies the minimum number of CPs (*nn*) that must stay online during WLM LPAR management. WLM LPAR management does not take CPs offline below this threshold.

**Value range:** 1–64

**Default:** 1

**WASROUTINGLEVEL=0|1**

Specifies the routing algorithm that is used by the WLM WebSphere® routing services.

**0**

WLM uses the most advanced routing algorithm that is supported by all systems in the sysplex.

- If the release level of the lowest system is z/OS R9 (or later), routing decisions are based on available or dispatchable capacity of general purpose processors and assist processors.
- If the release level of the lowest system is below z/OS R9, but has the APAR OA16486 installed, routing decisions are based on available or dispatchable capacity of general purpose processors only.
- If the release level of the lowest system is below z/OS R9 and runs without the APAR OA16486 installed, the routing algorithm round robin is used.

**1**

WLM uses the routing algorithm round robin. If this option is used, set it on all systems of the sysplex so that all are using the same algorithm; otherwise, the WebSphere routing service on each system uses the specific algorithm setting for the system, which can lead to inconsistent results.

**Default:** 0

**WLMIRDSTRUC=4DIGITS|5DIGITS|NONE**

Specifies to what IRD coupling facility structure the system attempts to connect at IPL time.

**4DIGITS**

Attempts to connect to a structure named SYSZWLM\_ *nnnnntttt*. If such a structure is not defined, the IRD CPU management and dynamic channel path management do not become active.

*nnnn* is the last four digits of the CPC sequence number and *tttt* is the machine type, such as 3931.

**5DIGITS**

Attempts to connect to a structure named SYSZWLM *nnnnnnntttt*. If such a structure is not defined, the IRD CPU management and dynamic channel path management do not become active. The use of WLMIRDSTRUC=5DIGITS is primarily intended for use by installations that are operating two or more CECs with identical last 4 digits CPC sequence numbers and CPC type, in the same sysplex with IRD functions active.

*nnnnn* is the last five digits of the CPC sequence number and *tttt* is the machine type, such as 3931.

**NONE**

No attempt is made to connect to any IRD structure. IRD CPU management remains inactive.

**Default:** 4DIGITS

**ZAAPAWMT=xxxxxx**

This parameter is deprecated and not used by SRM.

**ZIIPAWMT=xxxxxx**

Specifies an Alternate Wait Management (AWM) value for the IBM z Integrated Information Processor (zIIP) to minimize SRM and LPAR low utilization effects and overhead. In an LPAR, some n-way environments with a small workload may appear to have little capacity remaining because of the time spent waking up idle zIIPs to compete for individual pieces of work. The ZIIPAWMT parameter allows you to reduce this time so that capacity planning is more accurate and CPU overhead is reduced, even though it might take longer until arriving work gets dispatched.

**Value range:**

- For HIPERDISPATCH=NO, the valid range is 1–499999 microseconds. Any value 1–499999 makes AWM active. To deactivate AWM, set CCCAWMT to any value 500000–1000000.
- For HIPERDISPATCH=YES, the valid range is 1600–499999 microseconds. Any other value is reset to the default value of 3200. AWM is always active and cannot be turned off.

**Default:** AWM is active. For HIPERDISPATCH=NO, the default is 12000 (12 ms); for HIPERDISPATCH=YES, the default is 3200 (3.2 ms).

**Notes:**

1. The ZIIPAWMT parameter internally affects the *frequency* with which the specialty engines check the need for help. If help is required, the zIIP processor signals a waiting zIIP to help. If all zIIP specialty engines are busy and IIPHONORPRIORITY=YES is specified, the zIIP specialty engines ask for help from general purpose processors (CPs). Even if IIPHONORPRIORITY=YES is specified, a CP does not help the specialty engine for work in a discretionary service class.
2. Reducing the value that is specified for ZIIPAWMT causes the specialty engines to check and, if necessary, request help more frequently. If IIPHONORPRIORITY is set to YES, help is requested from one CP at a time, in priority order of work that is eligible for zIIP specialty engines, then to work that is not eligible for zIIP specialty engines. Setting the ZIIPAWMT value too low can cause CPs to run an excessive amount of workload that is eligible for zIIP specialty engines, which might result in delays for lower priority work that is not eligible for zIIP specialty engines. Conversely, increasing the value for ZIIPAWMT causes the specialty engines to request help after they are busy for a longer time, which might delay necessary help from CPs.





## Chapter 52. IEAPAKxx (LPA pack list)

IEAPAKxx is an installation-supplied member that contains groups of names of modules in the LPALST concatenation that are executed together or in sequence. (As an example, the load modules of a type-4 SVC routine are called sequentially and executed as a group.) The member is used only during a “cold” start (CLPA specified), when the PLPA is loaded from the LPALST concatenation.

The system uses the specified IEAPAKxx member(s) to determine the order in which modules are to be loaded from the LPALST concatenation into the pageable LPA. These modules are packed together, if possible, on a single page. The purpose is to reduce page faults. The LPA can greatly contribute to page faults because it is highly used. The IEAPAKxx list can significantly reduce page faults.

Each group ideally should not exceed 4K bytes in size. If a group exceeds 4K, the module in the group that causes 4K to be exceeded, and all later modules in the same group, will be loaded at the next page boundary in the LPA. In contrast, the system loads other modules (those not listed in IEAPAKxx) in size order, the largest modules first, then the smaller modules. Unused spaces within page boundaries are filled, if possible, with modules smaller than 4K.

You should select link pack area programs for inclusion in the system pack list to reduce the number of page faults from the pageable link pack area and thereby enhance system performance. The affinity of programs for each other and the size of the programs determine which should be selected for a pack list entry. Program affinity means that one program will usually refer to another program when the first program is invoked. By putting programs that refer to each other into the same pack list entry, and thereby on the same page, extra page faults are avoided, because the programs are always in storage together.

Very large programs that are to be put into the link pack area should be link edited so that CSECTs that have affinity or other CSECTs are placed within the same page. The linkedit ORDER statement can be used to group CSECTs into pages. This process will accomplish the same goal as the pack list entries, because page faults during execution will be reduced. The modules either execute concurrently or call each other.

**Note:** An installation can create one or more IEAPAKxx parmlib members, as needed. The system uses the IEAPAK00 member (if it exists) if PAK=xx is not included in the IEASYSxx parmlib member or is not specified by the operator. However, initialization continues whether or not there is an IEAPAK00 or IEAPAKxx member.

### Parameter in IEASYSxx (or supplied by the operator)

```
PAK={aa
      (aa,bb,...[,L])
      [,L]}
```

The two characters (A-Z, 0-9, @, #, or \$), represented by aa (or bb, etc.), are appended to IEAPAK to form the name of the IEAPAKxx parmlib member(s). If the ‘L’ option is specified, the system displays the contents of the IEAPAKxx member(s) at the operator's console when the system processes the member(s).

### Syntax rules for IEAPAKxx

The following rules apply to the creation of IEAPAKxx:

- The member consists of “groups” or entries containing load module names. Each group is enclosed in parentheses. For example: (IGG019CM,IGG019CN,IGG019CO,IGG019CP,IGG019CR).
- All modules in a group must have the same residence mode (RMODE).
- Separate modules within each group by commas.

- Separate each group from the next by a comma after the closing parenthesis.
- Do not use alias module names. The system processes only major names.
- All named modules must be refreshable because LPA modules must have this attribute.
- Lines that begin with an asterisk in column 1 are comments.
- On a line, data entered after the last group or load module name and after the optional comma continuation character is treated as a comment and ignored.
- Data records entered after the last data line are treated as comments and ignored.

## **IBM-supplied default for IEAPAKxx**

---

The IBM-supplied default parmlib member is IEAPAK00, which contains (IEFBR14).

## **Statements and parameters for IEAPAKxx**

---

Not applicable.

## Chapter 53. IEASLPxx (SLIP commands)

Use IEASLPxx to contain SLIP commands. The commands can span multiple lines, and the system processes the commands in order.

It is recommended that you move any SLIP commands in the COMMNDxx and IEACMDxx parmlib members into a IEASLPxx parmlib member. By using IEASLPxx to contain your SLIP commands, you avoid restrictions found in other parmlib members. For example:

- IEASLPxx supports multiple-line commands; IEACMD00 does not.
- IEASLPxx does not require any special command syntax; IEACMD00 does.

If you move SLIP commands from COMMNDxx and IEACMDxx to IEASLPxx, you must replace the commands in COMMNDxx and IEACMDxx with the following line, where xx is the ID of the IEASLPxx member to be used.

```
COM=' SET SLIP=xx '
```

See the descriptions of the COMMNDxx and IEACMDxx parmlib members for related information.

### Note:

1. For an SVC dump suppressed by a SLIP command with the action of NODUMP or NOSVCD, a LOGREC data set entry will contain a code indicating the reason for the suppression. For an ABEND dump suppressed by a SLIP command with the action of NODUMP, NOSYSU, NOSYSA, or NOSYSM, message IEA848I will indicate the reason for the suppression.
2. If a program loop causes an “out-of-space” abnormal termination (as in abend code B37) and you want a dump, specify a SYSABEND DD statement or a SYSMDUMP DD statement.
3. If you enter multiple non-ignore SLIP PER traps in IEASLPxx, only the first non-ignore SLIP PER trap will be enabled (if there were no enabled SLIP PER traps set prior to setting the traps out of IEASLPxx). The remaining non-ignore SLIP PER traps will be set, but will be disabled. The first non-ignore SLIP PER trap will be set but disabled if there was an enabled SLIP PER trap set prior to setting the traps out of IEASLPxx.
4. For a description of the SLIP command, see [z/OS MVS System Commands](#).

## Parameter in IEASYSxx (or supplied by the operator)

None

## Syntax rules for IEASLPxx

The following rules apply to the creation of IEASLPxx:

- Begin each command on a new line.
- Data, including comments, must be contained in columns 1-71; the system ignores columns 72-80.
- Comments must begin with an asterisk "\*" in column one.
- Enter the SLIP commands as you would enter them on the operator's console.
- Do not enclose the SLIP commands with double or single quotation marks or extra keywords.
- You can code multiple lines to specify a SLIP command.
- After the SET, MOD, or DEL keyword, the first blank ends the SLIP processing for that line. The system ignores all subsequent characters on that line.
- It does not matter whether the options end with a comma. If the END option has not yet been reached, the options continue with the first non-blank character on the next line.

The following is an example of a SLIP command within an IEASLPxx member:

```
SLIP SET,C=C06,
A=WAIT,END
```

## IBM-supplied default for IEASLPxx

IBM supplies member IEASLP00 in SYS1.PARMLIB. IEASLP00 contains IBM-supplied SLIP commands to suppress dumps that are considered unneeded because the system provides information (such as a message) that is normally sufficient for problem determination. For selected abend codes, the SLIP commands in IEASLP00 suppress either all dumps or specific types of dumps.

IEASLP00 contains the following commands:

```
SLIP SET,C=013,ID=X013,A=NOSVCD,J=JES2,END
SLIP SET,C=028,ID=X028,A=NOSVCD,END
SLIP SET,C=058,ID=X058,A=NODUMP,DATA=(15R,EQ,4,OR,15R,EQ,8,OR,
15R,EQ,C,OR,15R,EQ,10,OR,15R,EQ,2C,OR,15R,EQ,30,OR,
15R,EQ,3C),END
SLIP SET,C=071,SDATA=(ALLNUC,SQA,CSA,LPA,LSQA,ALLPSA,RGN,SUM,TRT),
REASON=30,ID=S071,A=SVCD,END
SLIP SET,C=071,SDATA=(ALLNUC,SQA,CSA,LPA,LSQA,ALLPSA,RGN,SUM,TRT),
REASON=20,ID=SS71,A=SVCD,END
SLIP SET,C=0E7,ID=X0E7,A=NOSVCD,END
SLIP SET,C=0F3,ID=X0F3,A=NODUMP,END
SLIP SET,C=13E,ID=X13E,A=NODUMP,END
SLIP SET,C=1C5,RE=00090004,ID=X1C5,A=NODUMP,END
SLIP SET,C=222,ID=X222,A=NODUMP,END
SLIP SET,C=322,ID=X322,A=NODUMP,END
SLIP SET,C=33E,ID=X33E,A=NODUMP,END
SLIP SET,C=3C4,REASON=1A,ID=S3C4,A=SVCD,END
SLIP SET,C=422,ID=X422,A=NODUMP,END
SLIP SET,C=422,RE=XXXX01A5,ID=X42X,A=IGNORE,END
SLIP SET,C=47B,DATA=(15R,EQ,0,OR,15R,EQ,8),ID=X47B,A=NODUMP,END
SLIP SET,C=622,ID=X622,A=NODUMP,END
SLIP SET,C=71A,ID=X71A,A=NODUMP,END
SLIP SET,C=804,ID=X804,A=(NOSVCD,NOSYSU),END
SLIP SET,C=806,ID=X806,A=(NOSVCD,NOSYSU),END
SLIP SET,C=80A,ID=X80A,A=(NOSVCD,NOSYSU),END
SLIP SET,C=81A,REASON=5,ID=X81A,A=NODUMP,END
SLIP SET,C=91A,ID=X91A,A=NODUMP,END
SLIP SET,C=9FB,ID=X9FB,A=NOSVCD,J=JES3,END
SLIP SET,C=B37,ID=XB37,A=(NOSVCD,NOSYSU),END
SLIP SET,C=C1A,ID=XC1A,A=NODUMP,END
SLIP SET,C=D37,ID=XD37,A=(NOSVCD,NOSYSU),END
SLIP SET,C=E37,ID=XE37,A=(NOSVCD,NOSYSU),END
SLIP SET,C=EC6,RE=0000FFXX,ID=XEC6,A=NODUMP,END
SLIP SET,C=EC6,RE=0000FDXX,ID=XXC6,A=NOSVCD,END
```

### Note:

1. IEASLP00 is read during system initialization because the IEACMD00 parmlib member contains the command SET SLIP=00. As a result, the SLIP traps specified in IEASLP00 member are in effect at IPL-time.
2. An installation that does not currently use SLIP commands should understand that the execution of IEASLP00 causes the system to allocate fixed storage for the SLIP processing modules and for the control blocks that define the SLIP traps supplied by IBM in IEASLP00. Approximately 30K bytes of storage will be fixed in the extended LPA for the SLIP processing modules and approximately 1K bytes of storage will be fixed in the extended SQA for the control blocks needed by the SLIP traps.
3. If you use a name other than JES2 or JES3 to start the job entry subsystem, the SLIP commands for abend codes X'013' and X'9FB' have no effect. Therefore, to suppress SVC dumps for these abend codes when you are not using JES2 or JES3 as the name of your job entry subsystem, place your own SLIP command in IEASLPxx. Specify NOSVCD on the ACTION=keyword (A=) and the name of your job entry subsystem on the JOBNAME=keyword (J=).

## Using system commands

When you issue SET SLIP=xx, the system processes all of the commands in IEASLPxx.

To view the status of the SLIP traps, use the DISPLAY SLIP command. For more information about the SET and DISPLAY commands, see [\*z/OS MVS System Commands\*](#).



## Chapter 54. IEASVCxx (installation-defined SVCs)

Use IEASVCxx to define your installation's own SVCs, which can be numbered from 200 through 255.

During system initialization, the system reads the IEASVCxx members, and places any SVCs you specified in the SVC table.

To dynamically replace or delete SVC table entries use the SVCUPDTE macro. For more information, see *z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO*.

### Parameter in IEASYSxx (or entered by the operator)

```
SVC= {aa
      {(aa,bb,...[,L])}}
```

The two alphanumeric characters (aa, bb, and so on) are appended to IEASVC to form the name of the parmlib member.

The contents of IEASVCxx appears on the operator's console if the (,L) option is specified with either the SVC= keyword or in response to the 'SPECIFY SYSTEM PARAMETERS' prompt.

### Syntax rules for IEASVCxx

The following rules apply to the creation of IEASVCxx.

- Data, including comments, must appear in columns 1 through 71. Do not use columns 72-80 for data; these columns are ignored.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/".
- One or more blanks may precede the SVC Parm statement.
- One or more blanks may follow the SVC Parm statement.
- The system processes each statement in a member sequentially.
- If you use multiple SVC Parm statements for the same SVC number, the first valid statement is processed. The rest are ignored.
- SVCNUM, REPLACE, and TYPE are required parameters for every statement.
- SVCNUM and REPLACE are positional parameters. SVCNUM must be coded as the first parameter with REPLACE following as the second parameter.

### Syntax examples of IEASVCxx

The following example shows the coding for a type 1 and type 3 SVC:

```
SVC Parm 245,REPLACE,TYPE(1),EPNAME(SVC245),LOCKS(CMS),APF(YES)
SVC Parm 244,REPLACE,TYPE(3),EPNAME(IGC0024D),LOCKS(LOCAL)
```

### IBM-supplied default for IEASVCxx

None.

## Statements and parameters for IEASVCxx

---

### **SVC** *PARM* **svcn**

Specifies the number of the installation-supplied SVC routine (a decimal number from 200 to 255). When a program issues an SVC instruction that contains this number, the system invokes the corresponding SVC routine.

### **,APF**(**{YES}** | **{NO}**)

Specifies whether the program that is invoking the SVC must be authorized. A program is considered to be authorized if it meets at least one of the following conditions:

- Runs in supervisor state
- Holds PSW key 0-7
- Is running with APF authorization.

When you specify YES, the program that is issuing the SVC must be authorized. When you specify NO, the program that issuing the SVC can be unauthorized.

**Default :** NO

### **,AR**(**{YES}** | **{NO}**)

Specifies whether the SVC can be issued in access register ASC mode.

**Default:** NO

### **,EPNAME**(*epname*)

Specifies the entry point name of the SVC routine. The *epname* value, if specified, must be one of the following values:

- IGCERROR. Identifies an SVC routine that results in abend Fxx when SVC xx is issued, where xx matches *svcn*
- Not IGCERROR.
  - For SVC types 3 and 4, *epname* must be the load module name (or alias) of a load module in the LPA.
  - For SVC types 1, 2, and 6, *epname* must be the entry point name (not the load module name, unless it is the same name) of a module in the nucleus region. The module must have been link-edited directly into the nucleus region, or added to the nucleus region through the NMLDEF macro or NUCLSTxx parmlib member.

For information about the NMLDEF macro, see [z/OS MVS Programming: Authorized Assembler Services Guide](#). For information about the NUCLSTxx parmlib member, see [Chapter 79, “NUCLSTxx \(customizing the nucleus region\),”](#) on page 677.

The EPNAME parameter is optional, unless you want to specify an EPNAME value other than the IBM default SVC naming convention.

The default naming convention for routines for SVC types 1, 2, and 6 is IGCnnn, where *nnn* is the decimal number of the SVC routine.

The default naming convention for SVC routines for SVC types 3 and 4 is IGC00nnn, where *nnn* is the signed decimal number of the SVC routine. Here, a *signed decimal* is a number that ends in either of the following ways:

- When the last digit of the SVC routine's load module name is a number from 1 - 9, specify an *epname* that ends with the EBCDIC character (A-I) that corresponds with the last digit. For example, the *epname* for a type 4 SVC 255 is IGC0025E.
- When the last digit of the SVC routine's load module name is zero, specify for the last character of *epname*, the display representation of hexadecimal C0; in EBCDIC, this is the left brace ({} character. For example, the EPNAME for a type 4 SVC 250 is IGC0025{.



**,LOCKS(lockname,lockname,...)**

Specifies the name of the system locks that this SVC requires. *lockname* can be either LOCAL or CMS.

Observe the following conventions for the LOCKS parameter:

- You do not need to specify the LOCAL lock for SVC type 1; the LOCAL lock is automatically obtained for SVC type 1.
- If you specify the CMS lock for SVC types 2, 3, or 4, you must also specify the LOCAL lock.
- You cannot specify a global spin lock for SVC types 3 or 4.
- You cannot specify locks for SVC type 6.

**,NPRMPT({YES} | {NO })**

Specifies whether the SVC is non-preemptible (YES) or can be preempted (NO).

**Default:** NO

**,REPLACE**

Specifies that an SVC table entry is to be updated.

**,TYPE(*typenum*)**

Specifies the SVC type (1, 2, 3, 4, or 6) being defined.



## Chapter 55. IEASYMxx (symbol definitions and IEASYSxx members)

IEASYMxx contains statements that define static system symbols and specify the IEASYSxx parmlib members that the system is to use.

You can use the HWNAME, LPARNAME, and VMUSERID parameters to limit the scope of statements in IEASYMxx. When you specify one or more of those parameters, the parameters on that statement apply only to the system that HWNAME, LPARNAME, or VMUSERID identify.

When the system finishes processing IEASYMxx, the system displays the system symbols that are defined in IEASYMxx and their associated substitution texts in message IEA009I.

**Before you code IEASYMxx:** Read [Chapter 2, “Sharing parmlib definitions,”](#) on page 31

### Parameter in LOADxx

To use IEASYMxx, append the 2-character identifier (aa, bb, and so forth) to the IEASYM parameter in the LOADxx parmlib member. Multiple members can be specified. If you specify a parameter in more than one IEASYMxx member, the system uses the value in the last member to be processed and ignores the values in preceding members.

See [Chapter 73, “LOADxx \(system configuration data sets\),”](#) on page 613 for information about specifying the IEASYM parameter in LOADxx.

### Performance implications

None.

### Syntax rules for IEASYMxx

The following syntax rules apply to IEASYMxx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- Blank lines are permitted.
- Delimiters are not required; the end of a physical record is considered to be a valid delimiter. However, you may optionally place a delimiter (space or comma) between a statement and a parameter.
- Multiple occurrences of a delimiter are accepted but treated as one.
- Comments may appear in columns 1-71 and must begin with "/"\* and end with "\*/".
- A statement can be continued even though there is no explicit continuation character.
- Do not use nested comments in this parmlib member.
- A statement type consists of 1-10 characters.
- A statement type must be the first data item on a record.
- A statement must begin with a valid statement type followed by at least one blank.
- Each parameter must consist of 1-10 characters (parameters cannot span more than one record).
- A logical record (a record that has the statement type and comments removed) cannot exceed 4 kilobytes (which is 56 72-character physical records). The count of characters in the logical record is after symbols have been resolved. A blank is used to separate parameter statements in the logical record. The count of blanks is included in the logical record length.
- You can use substrings of previously defined system symbols in definitions for other system symbols. See [“Step 1. Know the rules for using system symbols in parmlib”](#) on page 47 for more information about substringing system symbols.

IEASYMxx supports specifications that span lines (such as putting SYSDEF on one line and SYMDEF (or SYMD) on the next). The rules for multiple lines are as follows:

- For a given line, characters after the last non-blank non-comma are removed.
- For a given line, characters before the first non-blank non-comma are removed.
- A blank character is added between a line (to which the previous rules have been applied) and the next line (to which the previous rules have been applied).

## Syntax format of IEASYMxx

```
SYSDEF      [HNAME(processor-name)]
             [LPARNAME(lpar-name)]
             [VMUSERID(vm-userid)]
             [SYSPARM(aa[,bb...][,L])]
             [SYSNAME(system-name)      ]
             [SYSCONE(system-clone)     ]
             [SYMDEF(&symbol='sub-text')]
```

## IBM-supplied default for IEASYMxx

None.

## Statements and parameters for IEASYMxx

### HNAME(processor-name)

The name (identifier) of a central processor complex (CPC), as defined to hardware configuration definition (HCD).

If a processor does not have a hardware name, and you define the processor in the same IEASYMxx member that you define other processors with hardware names, specify HNAME() to indicate that a set of definitions is to apply only to the processor with no hardware name.

**Value range:** The processor-name is the 1- to 8-character name of the processor on which the system is running. Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$). The first character must be alphabetic (A–Z) or national (@ # \$).

**Default:** Match on any hardware name.

#### Example:

```
HNAME(C1)          /* First test processor */
HNAME()            /* Definitions apply only to processors */
                   /* to which no hardware name is defined */
```

To use this parameter, or accept its default value, ensure that the processor on which z/OS is running supports dynamic I/O configuration. Also, ensure that the I/O configuration data set (IOCD) was built using hardware configuration definition (HCD). See the information about dynamic I/O configuration in [z/OS Planning for Installation](#) for a list of processors that support dynamic I/O configuration.

### LPARNAME(lpar-name)

The name of a logical partition that is defined to a processor, which is one of the following:

- The partition name that is specified on the **Add Partition** panel in HCD (see [z/OS HCD User's Guide](#) for more information).
- The partition name that is specified on the RESOURCE or CHPID statement that is input to the I/O configuration program (IOCP).

A value of LPARNAME() indicates that a set of definitions applies to a processor that is not initialized in LPAR mode. For example, if you run a processor sometimes in LPAR mode and sometimes in basic mode, and you define separate symbols for each mode in the same IEASYMxx parmlib member,

specify LPARNAME ( ) to indicate that the system is to process a set of definitions only when running in basic mode.

**Note:** When z/OS is running under any virtual machine (z/VM or an alternate virtual machine), there is considered to be no LPAR name.

### **SYMDEF(&symbol='sub-text')**

Defines a static system symbol and its substitution text. Your installation can define at least 800 static system symbols in addition to the system symbols that z/OS provides, unless you are using symbols with substitution length longer than the symbol names as described below. You can define at least 700 static system symbols that are of the maximum length (16 characters) and the maximum substitution length (44 characters). You can optionally specify an ending period on &symbol.

You can use SYMD as a short name for SYMDEF.

These symbol names are supported:

- Symbol names with length up to 16 with substitution text length limited to NameLength + 1. The name can contain an underscore ( \_ ) in any character position other than the first one.
- Symbol names with length up to 16 with a last character of an underscore ( \_ ) with substitution text length up to 44.

Do not try to define in the system symbol table two symbols if one of them does not have any underscores and the name portion is no longer than 8 characters, and the other symbol begins with the name portion of the first immediately followed by an underscore. For example, do not define both &SYM and &SYM\_2.

Do not try to define a symbol that begins the same as a reserved system symbol but with an underscore right after the "normal" end of the reserved symbol (for example, since &SYSNAME is a reserved symbol, do not define &SYSNAME\_1).

When matching a pattern against symbols, an attempt is first made to match against a symbol with underscores. If a match is not made, then an attempt is made to match against a (shorter) symbol without underscores. For example, with just symbol &SYM\_2 defined, the string &SYM\_2 is replaced by the value for symbol &SYM\_2. But with just &SYM defined, the string &SYM\_2 is replaced by the value for symbol &SYM followed by "\_2".

**Restriction:** The length of the substitution text cannot exceed the length of the symbol name plus the ampersand (&) but not plus the trailing period (.) unless the symbol name ends with an underscore. In that case, the substitution text can be up to 44 characters long. Except for the ending-with-underscore case, this restriction prevents the flow of characters beyond established limits for text entry. For example, assume that the limit for text entry is column 71. If a line that contains a four-character symbol without the trailing period (for example, &SSSS) extends to column 71, a substitution text of greater than 5 characters would force the text beyond column 71. When you use a symbol that ends with an underscore, you accept that unintended results (such as truncation with no warning) might occur if the resulting substitution causes flow of characters to extend beyond an intended limit. For example, in the parmlib case, if using a symbol that ends with an underscore, make sure that the resulting substitution would not cause characters to extend beyond column 71. Programs are not expected to, but may, accommodate such line overflow.

**Value range:** &symbol is the 1–16 character name of a system symbol that your installation defines to the system. You can optionally specify an ending period on &symbol.

For &symbol, names must start with an ampersand (&). The ampersand must be followed by an alphabetic (A–Z) or national (@ # \$) character. Subsequent characters of the symbol name can be any valid alphanumeric (0–9 A–Z), national (@ # \$), or underscore characters. The trailing period is optional, but recommended.

'sub-text' is the substitution text for the system symbol to be defined. There are no restrictions on the types of characters that can be used. The rules for specifying sub-text are:

- Enclose the text in single quotation marks (as shown in the syntax diagram).

- The substitution text can contain other static system symbols (or substrings of another static system symbol) in any order and in any combination. However, do not specify dynamic system symbols in the substitution text. See [“Using substrings of system symbols” on page 48](#) for the syntax of substrings.
- When concatenating a static system symbol and a literal, terminate the static system symbol with a period.
- The substitution text can be a null value (for example, SYMDEF (&VAR1= ' ') and SYMDEF (&VAR2= ' &VAR1 ' ) are both valid.)
- The length of the resolved substitution text cannot exceed the length of *&symbol*, including the ampersand on *&symbol* and excluding the single quotation marks on '*sub-text*' unless the symbol ends with an underscore. For example, although the length of *sub-text* exceeds the length of the symbol &FRANKIE in the following example, the symbols that are contained in *sub-text* resolve to 1268ABC, which is a valid substitution text.

```
SYMDEF (&MARYJOE.= '1234568' )
SYMDEF (&FRANKIE.= ' &MARYJOE (1:2) . &MARYJOE (-2:2) . ABC ' )
```

However, the definition &JOHN= ' JOHNDOE ' is not valid because the resolved substitution text JOHNDOE contains more characters than the system symbol &JOHN. But the definition &LONG\_= ' THIS\_IS\_LONG ' is valid because the symbol name ends with an underscore.

**Restriction:** Do not specify blanks in SYMDEF statements, except in *sub-text*. For example, SYMDEF (&AB= ' AB ' ) and SYMDEF (&A. = ' A ' ) are not valid. SYMDEF (&AB= ' A B ' ) is valid.

**Default:** None. If you omit the SYMDEF parameter, the specified z/OS image does not use installation-defined static system symbols.

## SYSDEF

Defines the following for one or more z/OS systems in a multisystem environment:

- System symbols and their associated substitution texts.
- The suffixes of the IEASYSxx parmlib members to be used.

Each SYSDEF statement can contain:

### Filter parameters

The HWNAME, LPARNAME, and VMUSERID parameters specify the system to which one or more value parameters apply:

- A local SYSDEF statement contains at least one filter parameter. In other words, HWNAME, LPARNAME, or VMUSERID are present on the statement. The value parameters on a local SYSDEF statement apply only to the system that HWNAME, LPARNAME, or VMUSERID identifies.
- A global SYSDEF statement contains no filter parameters. In other words, HWNAME, LPARNAME, or VMUSERID are not present on the statement. The value parameters on a global SYSDEF statement apply to all systems that use IEASYMxx.

### Value parameters

The SYSPARM, SYSNAME, SYSCLONE, and SYMDEF parameters specify the static system symbols and IEASYSxx members that a system is to use. If one or more filter parameters precede a value parameter, value that is defined on that parameter applies only to the system identified by the filter parameters. If a filter parameter does not precede a value parameter, the value parameter applies to all systems that use IEASYMxx.

If two SYSDEF statements define the same symbol for the same system, the last statement that is processed overrides any previous definitions of that symbol. For example, suppose you code a SYSDEF statement at the beginning of IEASYMxx that defines a system symbol for all systems. Later in IEASYMxx, you code another SYSDEF statement that defines the same system symbol for a specific system that is identified on the HWNAME parameter. The second definition, which is identified by HWNAME, overrides the first.

**Value range:** The lpar-name is the 1–8 character name of a valid logical partition. Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$). The first character must be alphabetic (A–Z) or national (@ # \$). Do not specify all blanks for the lpar-name.

**Default:** Match on any LPAR name.

**Examples:**

```
LPARNAME(TEST1)           /* First test system */
LPARNAME()                 /* Processor is running */
                           /* in non-LPAR (basic) mode */
```

### **SYSCONE(system-clone)**

The value to be assigned to MVS static system symbol &SYSCONE; SYSCONE is a 1–2 character shorthand notation for the system name.

Each system in a sysplex must specify a unique SYSCONE value. Message IXC215I is issued if the substitution text for the &SYSCONE symbol is not unique in a sysplex.

**Value range:** Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$). Static system symbols can be used as long as the values substituted for the symbols are in the value range.

**Default:** The last two characters of the value that is specified on the SYSNAME parameter. This default is equivalent to &SYSNAME(-2:2).

**Examples:** Using a hardcoded value:

```
SYSCONE(01)               /* First test system */
```

Using another static system symbol:

```
SYSNAME(S1MVS)            /* Specify name for first test system */
SYSCONE(&SYSNAME(1:2))    /* Resolves to first 2 chars in SYSNAME */
```

### **SYSPARM(aa[,bb...][,L])**

The suffixes of the IEASYSxx parmlib members to be used when this SYSDEF statement is selected.

To display the contents of IEASYSxx at the operator console when the system processes each member, specify L anywhere after the first suffix and enclose the values in parentheses. For example, specify (01,L) on SYSPARM to tell the system to process IEASYS01 and display the contents of that member at the operator console. The system ignores the SYSPARM statement if the operator specifies on the LOAD parameter that the system should prompt for system information. The operator can accomplish this by specifying an A, P, S, or T IMSI character on the LOAD parameter on the system console. For details about IMSI characters, see the information about loading the system software in [z/OS MVS System Commands](#).

The suffixes of IEASYSxx members can also be specified:

- On the SYSPARM parameter in the LOADxx parmlib member.
- By the operator, in response to message IEA101A SPECIFY SYSTEM PARAMETERS.

See “Step 2. Determine where to specify system parameters” on page 39 for more information.

**Value range:** aa and bb are 1–2 character suffixes of a valid IEASYSxx parmlib member. Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$). Neither static nor dynamic system symbols are accepted.

**Default:** None. If you omit the SYSPARM parameter, the system uses the default member IEASYS00, the suffixes that are specified on the SYSPARM parameter in the LOADxx parmlib member, or the suffixes that are specified by the operator in response to the SPECIFY SYSTEM PARAMETERS prompt.

**Example:**

```
SYSPARM(00,01)           /* IEASYSxx parmlib members 00 and 01 */
```

**SYSNAME(system-name)**

The name to be assigned to this MVS system. The system name is also the substitution text for the &SYSNAME system symbol. The value on this parameter can be overridden by alternate parameters that are specified by the operator in response to the SPECIFY SYSTEMS PARAMETERS prompt.

**Value range:** The *system-name* is a 1–8 character name for an MVS system. Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$). Static system symbols can be used as long as the values substituted for the symbols are in the value range.

**Default:** For information about where to specify the system name, how the system determines which name to use, and how the default value is chosen, see [“Step 3. Determine where to specify the system name” on page 41.](#)

**Note:** MVS does not prevent two systems from having the same &SYSNAME value. If system resources on multiple systems are defined using &SYSNAME (such as page data sets), the results are unpredictable.

**VMUSERID(vm-userid)**

The user ID of a z/VM system under which a z/OS image is running as a guest. For information about running z/OS as a guest of z/VM, see *z/VM Running Guest Operating Systems*.

If you run a processor sometimes as a guest under z/VM and sometimes not, and you define both instances in the same IEASYMxx parmlib member, specify VMUSERID() to indicate that the system is to process a set of definitions only when it is not running as a guest under z/VM.

**Note:** If a system is identified by a z/VM user ID that is not a valid system name, the system prompts the operator to specify a valid name for the system.

**Value range:** The *vm-userid* is a 1- to 8- character name of a valid z/VM system. Valid characters are alphanumeric (0–9 A–Z) and national (@ # \$).

**Default:** Match on any z/VM user ID.

**Example:**

```
VMUSERID(AUTOLOG1)      /* z/VM system of which z/OS is a guest */
VMUSERID()              /* Process a set a definitions only when */
                        /* not running as a guest under z/VM */
```

**Examples**

The following are examples of IEASYMxx usage:

**Example 1:** Define a global system symbol called &LOGSYM to be used on all systems. The value for the symbol will be different on different systems. First, the IEASYMxx member is shown, then the value for &LOGSYM on various systems is listed.

```
SYSDEF
  SYMDEF(&LOGSYM='LOG1') /* Define &LOGSYM for all systems */
  SYMDEF(&ABCDEF='OWL') /* Define &ABCDEF for all systems */
  SYSPARM(BB)           /* Define SYSPARM for all systems */

SYSDEF
  HNAME(T0)             /* Identify a test processor */
  SYMDEF(&LOGSYM='LOGT') /* Override global &LOGSYM only */
                        /* for processor T0 */
  SYSDEF
    LPARNAME(R1)         /* Identify a runtime processor */
    SYMDEF(&LOGSYM='LOGR') /* Override global &LOGSYM only */
                        /* for LPAR R1 */

SYSDEF
  HNAME(T0) LPARNAME()   /* Identify a non-LPAR processor */
  SYMDEF(&LOGSYM='LOGN') /* Override global &LOGSYM only */
                        /* for T0 in non-LPAR mode */

For this system:      &LOGSYM will have this value:
HNAME  LPARNAME
D0     not LPAR mode  LOG1 (only first SYSDEF matched)
```



|      |               |      |                                   |
|------|---------------|------|-----------------------------------|
| T0   | R1            | LOGR | (1st, 2nd and 3rd SYSDEF matched) |
| T0   | R2            | LOGT | (1st and 2nd SYSDEF matched)      |
| T0   | not LPAR mode | LOGN | (1st and 4th SYSDEF matched)      |
| none | R1            | LOGR | (1st and 3rd SYSDEF matched)      |

**Example 2:** Define a symbol using a previously defined symbol and substrings. (See [“Using substrings of system symbols”](#) on page 48 for the syntax of substrings.)

```

SYMDEF(&SYMBOL2='(( ' ) /* &SYMBOL2 is assigned (( */
SYMDEF(&SYMBOL3='3,3,3 ' ) /* &SYMBOL3 is assigned 3,3,3 */
.SYMDEF(&SYMBOL1='&SYMBOL2(1:2).&SYMBOL3(1:1).)')
/* &SYMBOL1 resolves to the first two characters in */
/* &SYMBOL2, the first character in &SYMBOL3, and the */
/* two hard-coded right parentheses. &SYMBOL1=((3)) */

```

**Example 3:** Use the system-provided symbol to set the initial IPL VOLSER and also use substrings to define more IPL volumes. For this example, &SYSR1 = RESA01.

```

SYSDEF
SYMDEF(&SYSR2='&SYSR1(1:4).02') /*SYSR2 resolves to the first */
/*four characters in SYSR1 and */
/*the hard-coded 02. SYSR2=RESA02 */
SYMDEF(&SYSR3='&SYSR1(1:4).03') /*SYSR3 resolves to the first */
/*four characters in SYSR1 and */
/*the hard-coded 03. SYSR3=RESA03 */

```

**Example 4:** Use the system-provided symbol to set the initial IPL VOLSER and also use substrings to define more IPL volume names, using literal text. For this example, &SYSR1 = SRSAAA.

```

SYSDEF
SYMDEF(&SYSR2.='SRS2&SYSR1(-2:2)') /* &SYSR2 resolves to SRS2AA */
SYMDEF(&SYSR3.='SRS3&SYSR1(-2:2)') /* &SYSR3 resolves to SRS3AA */

```



## Chapter 56. IEASYSxx (system parameter list)

You can specify system parameters using a combination of IEASYSxx parmlib members and operator responses to the SPECIFY SYSTEM PARAMETERS message. You can place system parameters in the IEASYS00 member or in one or more alternate system parameter lists (IEASYSxx) to provide a fast initialization that requires little or no operator intervention.

IEASYS00 is the most likely place to put installation defaults or parameters that will not change from IPL to IPL. The system programmer can add to or modify parameters in IEASYS00. The alternate IEASYSxx members, in contrast, should contain parameters that are subject to change, possibly from one work shift to another.

Use of the IEASYS00 or IEASYSxx members can minimize operator intervention at IPL. Because IEASYS00 is read automatically, the operator can respond to SPECIFY SYSTEM PARAMETERS with ENTER or “U” and need not enter parameters unless an error occurs and prompting ensues.

The use of system parameter lists in parmlib offers two main advantages:

- The parameter lists shorten and simplify the IPL process by allowing the installation to preselect system parameters.
- The parameter lists provide flexibility in the choice of system parameters.

You can do one of the following to specify a parameter list other than IEASYS00 for an IPL:

- Have the operator specify the suffix of an alternate IEASYSxx member by replying SYSP=xx in response to the SPECIFY SYSTEM PARAMETERS message (see [SYSP](#) for more information).
- Specify one or more suffixes of alternate IEASYSxx members on the SYSPARM parameter in the LOADxx or IEASYMxx parmlib member.

For further information about IEASYSxx parmlib members and system initialization, see [“Step 2. Determine where to specify system parameters”](#) on page 39.

### Overview of IEASYSxx parameters

Table 24 on page 421 summarizes all system parameters that can be placed in an IEASYSxx or IEASYS00 member (or specified by the operator). Detailed discussions of these parameters are provided in later sections of the IEASYSxx topic.

**Note:** PAGE and GRS are the only mandatory parameters that have no default. They must be specified.

The GRSRNL parameter is mandatory when the GRS= parameter is specified as JOIN, TRYJOIN, START, or STAR. The GRSRNL parameter is ignored when GRS=NONE.

| Table 24. Overview of IEASYSxx parameters |   |
|---|---|
| Parameter                                 | Use of the parameter  |
| ALLOC                                     | Completes the names of one or more parmlib members (ALLOCxx) that describe installation defaults for allocation parameters.   |
| APF                                       | Names the parmlib member (IEAAPFxx) that contains authorized library names. IEAAPFxx can specify only a static APF list, which can only be updated at IPL and contain a maximum of 255 entries. |
| AUTOR                                     | Enables an installation to specify its own auto-reply policy during IPL, or to request that auto-reply processing is not to be activated.   |
| AXR                                       | Completes the names of one or more parmlib members (AXRxx) that specify System REXX options.  |
| BOOST                                     | Controls boosts that are intended to help IPL and shutdown run faster.  |
| CATALOG                                   | Specifies which IGGCATxx members to use during the current IPL.   |
| CEA                                       | Completes the name of the parmlib member (CEAPRMxx) that contains common event adapter (CEA) and associated instrumentation parameters.   |

Table 24. Overview of IEASYSxx parameters (continued)

| Parameter | Use of the parameter   |
|-----------|--|
| CEE       | Completes the name of the parmlib member (CEEPRMxx) that provides another level of Language Environment runtime options.   |
| CLOCK     | Completes the name of the parmlib member (CLOCKxx) that prompts the operator to initialize the TOD clock during NIP, and specifies the difference between the local time and Coordinated Universal Time (UTC).   |
| CLPA      | Causes NIP to load the link pack area with the modules contained in the LPALST concatenation. Also, CLPA purges VIO data set pages that were used in the previously initialized system. Thus, CLPA implies CVIO.   |
| CMB       | Specifies the I/O device classes for which measurement data is to be collected, in addition to the DASD and tape device classes. If the system is running on a z990 or later model processor, the system ignores anything you have specified on this parameter and creates ECMBs as needed.  |
| CMD       | Completes the name of the parmlib member (COMMNDxx) that contains commands to be issued internally during master scheduler initialization.   |
| CON       | Completes the name of the parmlib member (CONSOLxx) that centralizes control of the console configuration for your installation. CONSOLxx also contains the initialization values for communication tasks, the characteristics for the hardcopy log, and default routing codes for messages that do not have routing information. The CON parameter is also used to allow a system with both JES2 and any level of JES3 installed to run with JES2. This allows function that is incompatible with JES3 to operate successfully. |
| COUPLE    | Completes the name of the parmlib member (COUPLExx) that describes the sysplex environment for the initializing system.  |
| CRYPCTRS  | Identifies the processing state for crypto counters.   |
| CSA       | Specifies the sizes of the virtual common service area and extended common service area.   |
| CSCBLOC   | Determines the location of the CSCB control block chain.   |
| CVIO      | Deletes previously used VIO data set pages from the paging space. This parameter is automatically included when CLPA is specified.   |
| DEVSUP    | Completes the name if the parmlib member (DEVSUPxx) that specifies installation defaults for device support options.   |
| DIAG      | Completes the names of one or more parmlib members (DIAGxx) that specify whether the CSA/ECSA or SQA/ESQA tracking functions are turned on or off, whether GETMAIN/FREEMAIN/STORAGE (GFS) trace is turned on or off, and the trace records to be included in GFS trace output.   |
| DRMODE    | This parameter is no longer supported. Any specification of it has no effect on the system.  |
| DUMP      | Specifies whether SYS1.DUMP data sets for SVC dump are to be on direct access devices. This parameter can also indicate that no SYS1.DUMP data sets are to be made available for SVC dumps.  |
| EXIT      | Completes the name of one or more parmlib members (EXITxx) that contains the entry points and names of allocation installation exits.  |
| FIX       | Completes the name of one or more parmlib members (IEAFIXxx) that contain names of modules that are to be placed in a fixed LPA that lasts for the duration of the IPL.  |
| FXE       | Specifies one or more suffixes of the IBM Function Registry for z/OS parmlib member, FXEPRMxx, to be used by the system.   |
| GRS       | Specifies whether the system is to participate in a global resource serialization complex.   |
| GRSCNF    | Completes the name of the parmlib member (GRSCNFxx) that contains the information that is needed to initialize a system that is to be part of a global resource serialization complex.   |
| GRSRNL    | Completes the name of one or more parmlib members (GRSRNLxx) that contain resource name lists (RNLs) or specifies that no RNLs are to be used in the complex.  |
| GTZ       | Specifies one or more suffixes of the IBM Generic Tracker for z/OS parmlib member, GTZPRMxx, to be used by the system.   |
| HVCOMMON  | Specifies the size of the 64-bit common area.  |
| HVSHARE   | Specifies the size of the high virtual shared area.  |
| HZS       | Specifies one or more suffixes of the IBM Health Checker for z/OS parmlib member, HZSPRMxx, to be used by the system.  |
| HZSPROC   | Specifies the name of the procedure the system uses to automatically start IBM Health Checker for z/OS at IPL time.  |
| ICSF      | Specifies the suffix of the ICSF on z/OS, CSFPRMxx, to be used by the system.  |

Table 24. Overview of IEASYSxx parameters (continued)

| Parameter | Use of the parameter   |
|-----------|--|
| ICSFPROC  | Specifies the name of the ICSF procedure you want the system to use to automatically start ICSF on z/OS at IPL-time.   |
| IEFOPZ    | Completes the names of the one or more parmlib members (IEFOPZxx) that contain statements that define the data set optimization configuration for the system.  |
| IKJTSO    | Completes the name of the parmlib member (IKJTSOxx) that contains the TSO/E settings for the system.   |
| IOS       | Completes the name of the parmlib member (IECIOUSxx) that contains missing interrupt handler (MIH) statements used to modify MIH intervals and HOTIO statements used to modify recovery actions specified in the hot I/O detection table (HIDT).   |
| IQP       | Completes the names of one or more parmlib members (IQPPRMxx) that contain options to be used for managing PCIE-related devices.   |
| IXGCNF    | Completes the names of one or more parmlib members (IXGCNFxx) that specify the system logger parameters.   |
| IZU       | Completes the names of one or more parmlib members (IZUPRMxx) that specify the settings for IBM z/OS Management Facility (z/OSMF) on the system.   |
| LFAREA    | Specifies the amount of real storage that can be used to satisfy fixed 1 MB and 2 GB page requests.  |
| LICENSE   | Specifies whether the system is running with a z/OS or zNALC license.  |
| LNK       | Completes the name of one or more parmlib members (LNKLSTxx) that contain names of data sets that are to be concatenated to SYS1.LINKLIB to form the LNKLST concatenation. You can also use PROG to specify the PROGxx member that defines the LNKLST concatenation.   |
| LNKAUTH   | Specifies whether all data sets in the LNKLST concatenation are to be treated as APF-authorized or whether only those that are named in the APF table are to be treated as APF-authorized.   |
| LOGCLS    | Specifies the JES output class for the log data sets.  |
| LOGLMT    | Specifies the maximum number of WTLs (messages) for a log data set. When the limit is reached, the data set is scheduled for sysout processing.  |
| LOGREC    | Specifies the logrec recording medium for error recording.   |
| LPA       | Completes the name of one or more parmlib members (LPALSTxx) that contain names of data sets that are to be concatenated to SYS1.LPALIB for building the pageable LPA (PLPA and extended PLPA).  |
| MAXCAD    | Specifies the maximum number of SCOPE=COMMON data spaces to be allowed during an IPL.  |
| MAXUSER   | Specifies a value that the system uses (along with the RSVSTRT and RSVNONR parameter values) to limit the number of jobs and started tasks that the system can run concurrently during a given IPL.<br><b>Note:</b> Specifying a higher number can cause unintended resource shortages.  |
| MLPA      | Completes the name of one or more parmlib members (IEALPAXx) that names modules that are to be placed in a modified LPA that lasts for the duration of the IPL.  |
| MSTRJCL   | Completes the name of the MSTJCLxx data set that contains the JCL used to start the master scheduler address space.  |
| NONVIO    | Designates one or more local page data sets that are not to be used for VIO paging.  |
| NSYSLX    | Specifies the number of linkage indexes (LXs), in addition to those in the system function table, to be reserved for system linkage indexes (LXs).   |
| OMVS      | Specifies the parmlib member or members (BPXPRMxx) to use to locate the parmlib statements to configure the z/OS UNIX kernel.  |
| OPI       | Indicates whether the operator is to be allowed to override particular parameters, or all parameters, contained in IEASYSxx.   |
| OPT       | Completes the name of a parmlib member (IEAOPTxx) that contains parameters to be used by various algorithms of the system resources manager.   |
| OSPROTECT | Specifies the operating system mitigation mode for unauthorized programs and users.  |
| PAGE      | Gives the names of new page data sets to be used as additions to or replacements for existing page data sets. The first-named data set is used for the PLPA and extended PLPA pages. The second-named data set is used for MLPA and CSA. Alternatively, specify *NONE* for the first or second parameter (or both) to use Storage Class Memory (SCM) instead of a data set. The third and all subsequently named data sets are used as local page data sets. Replacement is possible only if the parameter is placed in IEASYSxx, and the operator selects this member by entering SYSP=xx. The PAGE parameter, when specified by the operator, can only add temporarily (until the next cold or quick start) to a parmlib page data set list. |

Table 24. Overview of IEASYSxx parameters (continued)

| Parameter | Use of the parameter   |
|-----------|--|
| PAGESCM   | Specifies the minimum amount of Storage Class Memory (SCM) that should be made available for use as auxiliary storage. The system reserves the amount of SCM specified during IPL for subsequent use as auxiliary storage. Additional memory is allocated on an as-needed basis if use of the amount that is specified by the PAGESCM parameter is exceeded.   |
| PAGTOTL   | Specifies the total number of page data sets that can be allocated for the life of the IPL.  |
| PAK       | Completes the name of one or more parmlib members (IEAPAKxx) that contain groups of names of modules in the LPALST concatenation that are processed together or in sequence.   |
| PLEXCFG   | Specifies the sysplex configuration into which the system is allowed to load the initial program.  |
| PRESCPU   | Causes system initialization processing to bring logically online the CPUs that appear to MVS to be physically online, without regard to the number of CPUs defined to be initially online in the logical partition profile.   |
| PROD      | Completes the name of one or more parmlib members (IFAPRDxx) that define the enablement policy for products or product features that can be dynamically enabled under z/OS.  |
| PROG      | Completes the name of one or more parmlib members (PROGxx) that specify the format and contents of the APF-authorized library list. PROGxx can specify either a static or dynamic APF list. A dynamic format allows users to update the APF list at any time during normal processing or at IPL. You can specify as many APF-authorized libraries as you need in a dynamic APF list; there is no system-imposed maximum number. PROGxx also contains statements that control the use of installation exits and installation exit routines.<br><br>You can also use PROGxx instead of LNKLSTxx to define the LNKLST concatenation and activate it at IPL. |
| RACF      | Specifies the parmlib member or members (IRRPRMxx) that are used to locate statements that define the RACF database configuration.   |
| RDE       | Specifies that the reliability data extractor feature is included. For information about RDE, see <a href="#">z/OS MVS Diagnosis: Tools and Service Aids</a> .   |
| REAL      | Specifies the maximum amount of central storage, in 1 KB blocks, that can be allocated for concurrent ADDRSPC=REAL jobs.   |
| RER       | Specifies that the reduced error recovery procedures for magnetic tapes are in effect if they are included on the OPTCD parameter of a data definition (DD) statement or on the DCB macro instruction. If the DD statement or the DCB macro does not specify the reduced error recovery procedures, all requests for them are ignored.   |
| RSU       | Specifies the number of central storage units to be made available for storage reconfiguration (dividing storage into logical partitions under PR/SM).   |
| RSVNONR   | Specifies the number of ASVT entries to be reserved for replacing those entries marked non-reusable for the duration of an IPL.  |
| RSVSTRT   | Specifies the number of address space vector table (ASVT) entries to be reserved for address spaces that are created in response to a START command.   |
| RUCSA     | Specifies the sizes of the virtual restricted use common service area (RUCSA) and extended RUCSA.  |
| SCH       | Specifies a parmlib member (SCHEDxx) from which the master scheduler obtains its parameters. This member centralizes control over the size of the master trace table, the program properties table (PPT), and the completion codes that are eligible for automatic restart.  |
| SMFLIM    | Specifies a parmlib member (SMFLIMxx) that allows installations to specify region and memlimit values according to the output fields in the IEFUSI SMF exit.   |
| SMF       | Specifies a parmlib member (SMFPRMxx) from which SMF obtains its parameters.   |
| SMFTBUFF  | Specifies the number of megabytes that SMF should designate as the size of the temporary buffer that is used to hold SMF data during IPL processing while SMF completes initialization.  |
| SMS       | Specifies a parmlib member (IGDSMSxx) from which SMS obtains its parameters when the system is initialized with partitioned data set extended (PDSE) support.  |
| SOLUT     | Specifies a Tailored Fit Pricing solution ID.  |
| SQA       | Specifies the size of the virtual system queue area to be created at IPL (in addition to the system's minimum virtual SQA and extended SQA).   |
| SSN       | Completes the name of the parmlib member IEFSSNxx, which contains the information to be used in identifying subsystems that are to be initialized.   |

| Table 24. Overview of IEASYSxx parameters (continued) |   |
|---|---|
| Parameter   | Use of the parameter  |
| SVC   | Completes the name of the parmlib member IEASVCxx, which contains the information that an installation supplies to define its own SVCs. NIP processing places these SVCs in the SVC table.  |
| SYSNAME   | Specifies the name of the system being initialized. The name that is specified is used by the system in various ways. For example, <ul style="list-style-type: none"> <li>In a multi-system global resource serialization complex, SYSNAME identifies each system in the complex.</li> <li>The system also uses this value to uniquely identify the originating system in messages in the multiple console support (MCS) hardcopy log and in the display created by the DISPLAY R command.</li> </ul> |
| SYSP  | Specifies one or more alternate system parameter lists (IEASYSxx) that are to be read by NIP in addition to IEASYS00. SYSP may be specified only by the operator.   |
| UNI   | Completes the name of the parmlib member (CUNUNIxx) that contains the Unicode statements that are required to enable Unicode Conversion services such as ADD, DELETE, REPLACE, IMAGE, and REALSTORAGE.  |
| VAL   | Names one or more parmlib members (VATLSTxx) that contain "mount" and "use" attributes of direct access devices.  |
| VIODSN  | Specifies the VSAM data set name for storing information about journaled VIO data sets.   |
| VRREGN  | Gives the default real-storage region size for an ADDRSPC=REAL job step that does not have a REGION parameter in its JCL.   |
| WARNUND   | Asks that the system warn when finding an undefined system parameter rather than prompt for new system parameters.  |
| WORKINST  | Specifies the processing state for workload instrumentation.  |
| ZAAPZIIP (Alias: ZZ)                                  | Determines whether the system can run zAAP processor eligible work on zIIP processors when no zAAP processors are installed on the machine.   |

## Changes to initialization parameters

For a list of parameters that have changed or that are no longer supported by the current level of MVS, see [z/OS Upgrade Workflow](#).

## Support for system symbols

You can specify system symbols in all parameter values in IEASYSxx *except* in the values for the SYSP and OPI parameters and in specifying CLPA and OPI.

If you intend to use system symbols to represent parmlib member suffixes in IEASYSxx, be careful when defining, in the IEASYMxx parmlib member, parentheses (such as in the case of list notation) or commas as part of the substitution text:

- Specify system symbols only to the right of the equals sign and before the comma in the IEASYSxx notation.
- Specify only “balanced” parentheses in either the defined substitution text or the hard-coded values.

Table 25 on page 425 shows examples of IEASYMxx and IEASYSxx notations that are valid and not valid. For more information about defining system symbols in IEASYMxx, see [“Step 4. Create an IEASYMxx parmlib member”](#) on page 41.

| Table 25. Example: IEASYMxx and IEASYSxx notation  |  |   |
|--|--|---|
| Notation   | IEASYMxx                                     | IEASYSxx                                |
| Valid; the left and right parentheses both appear in the system symbol definition.                                   | <code>SYMDEF (&amp;PAGTOTL=' (10) ' )</code> | <code>PAGTOTL=&amp;PAGTOTL .</code>     |
| Not valid; the parentheses are split between the system symbol definition and the hard-coded definition in IEASYSxx. | <code>SYMDEF (&amp;PAGTOTL=' 10) ' )</code>  | <code>PAGTOTL=( &amp;PAGTOTL . ,</code> |

**Example of using system symbols in IEASYSxx:** Suppose the following system symbols have the values:

- &SYSNAME = SYSA
- &SYSCLOCK = SA
- &SYSPLEX = PX01

Then, assume that you want to take the following steps in IEASYSxx:

1. Specify the LNKSTxx member identified by the last two letters in the sysplex name and also LNKSTxx members 03 and 00.
2. Specify the CLOCKxx member identified by &SYSCLOCK.
3. Specify the PROGxx member identified by the first two letters in the system name.
4. Specify a data set name for error recording that has the system name as a high-level qualifier.

Code IEASYSxx as follows:

```
LNK=(&SYSPLEX(-2:2) , 03,00,L) ,
CLOCK=&SYSCLOCK ,
PROG=&SYSNAME(1:2) ,
LOGREC=&SYSNAME . LOGREC
```

The values of the parameters resolve to:

```
LNK=(01,03,00,L) ,
CLOCK=SA ,
PROG=SY ,
LOGREC=SYSA . LOGREC
```

For details about how to use system symbols in parmlib, see [Chapter 2, “Sharing parmlib definitions,” on page 31](#).

## Parameter specified by the operator

```
SYSP=xx
```

The operator specifies this parameter to specify an alternate system parameter list in addition to IEASYS00. (See SYSP in [“Statements and parameters for IEASYSxx” on page 427](#).)

## Syntax rules for IEASYSxx

The following rules apply to the creation of IEASYSxx:

- Use columns 1 through 71 to specify parameters. The system ignores columns 72 through 80.
- Leading blanks in records are acceptable. Therefore, a parameter need not start at column 1.
- Enter data in uppercase characters only; the system does not recognize lowercase characters.
- Use commas to separate multiple parameters in a record, but do not leave blanks between commas and subsequent parameters.
- Enclose multiple subparameters in parentheses. The number of subparameters is not limited.
- Indicate record continuation with a comma followed by at least one blank.
- Lines that begin with an asterisk in column 1 are comments.
- The system ignores anything after a comma followed by one or more blanks. You can use the remainder of the line for comments, as [Figure 13 on page 427](#) shows.
- The system considers the first record that does not end in a comma to be the end of the member and ignores subsequent lines. You can use the remainder of the record, which contains the last parameter, for comments, providing there is at least one blank between the last parameter and the comments. You can also use additional lines after the last parameter for comments, as [Figure 13 on page 427](#) shows.



- A minimum IEASYSxx member can be created by specifying a blank line as the only record. Blank lines can also be used in comments, after the last statement in the record. Otherwise, do not use blank lines within record specifications.

```
*
* MY IEASYSxx MEMBER
*
  CON=01,MLPA=(00,01,02,03,L),    USE CONSOL01, IEALPA00-03
  COUPLE=&SYSCONE,                XCF SERIAL CTCS ARE DEFINED
  PLEXCFG=MULTISYSTEM,            TURN SYSPLEX ON
  LICENSE=Z/OS,                   THE SYSTEM IS RUNNING WITH A Z/OS LICENSE
  DIAG=01                         USE DIAG01.  LAST STMT; LIST ENDS HERE

THIS MEMBER CONTAINS SOME TRAILING COMMENTS WITH BLANK LINES AFTER
THE LAST RECORD.
```

Figure 13. Example of how to specify comments

## IBM-supplied default for IEASYSxx

None.

## Specifying the list option for IEASYSxx parameters

Certain parameters in IEASYSxx (such as CLOCK, CON, and MLPA) allow you to specify the list option (L). If you specify the L option, and message suppression is not active, the system writes all of the statements read from the associated parmlib member to the operator's console during system initialization. If message suppression is active (the default), the system writes the list to the console log only. While the L option is generally allowed, unless otherwise documented, you should not expect that any action is taken as a result of specifying it.

To ensure that messages are not suppressed, specify an appropriate initialization message suppression indicator (IMSI character) on the LOAD parameter. The IMSI characters that do not suppress messages are A, C, D, M, and T.

For more information about the LOAD parameter, see the topic on loading the system software in [z/OS MVS System Commands](#).

## Statements and parameters for IEASYSxx

The IEASYSxx parameters are listed alphabetically and are individually described. These parameters can optionally be issued by the operator, although such manual issuance would slow the IPL.

**Note:** *Value range*, if applicable, means the syntactically acceptable range of values, not necessarily a range of values reasonable for function or performance. The “associated parmlib member” refers to the parmlib member that is named by the parameter. For example, IEAAPF01 is named by the APF=01 parameter in IEASYSxx, or entered by the operator.

### ALLOC

**ALLOC={aa} {(aa,bb,...)}**

This parameter specifies the ALLOCxx members of parmlib. The two alphanumeric characters, represented by *aa* (or *bb*, and so on), are appended to ALLOC to form the names of the ALLOCxx members. The ALLOCxx parmlib members specify allocation values for the initializing system.

**Value range:** Any two alphanumeric characters.

**Default:** None.

**Associated parmlib member:** ALLOCxx

## APF

### APF=xx

The two characters (A-Z, 0-9, @, #, or \$), represented by xx, are appended to IEAAPF to form the name of parmlib member IEAAPFxx. This member lists the data set names and volume serial numbers of authorized data sets. SYS1.LINKLIB and SYS1.SVCLIB are automatically included as authorized data sets. In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

The installation creates the default parmlib member IEAAPF00.

**Tip:** The PROGxx parmlib member is an alternative to IEAAPFxx. If your installation decides to use PROGxx, add the PROG=xx system parameter (see [PROG](#)), remove the APF=xx system parameter from IEASYSxx, and remove APF=xx from IEASYS00. If you specify both the PROG=xx and the APF=xx parameters, the system places into the APF list the libraries that are listed in IEAAPFxx, followed by the libraries that are listed in the PROGxx members.

For information about the PROGxx parmlib member, see [Chapter 81, “PROGxx \(authorized program list, exits, LNKST sets and LPA\),”](#) on page 685.

**Value range:** Any two characters (A-Z, 0-9, @, #, and \$).

**Default:** The system always places SYS1.LINKLIB and SYS1.SVCLIB in the APF list. If the default for the LNKAUTH system parameter is taken (LNKAUTH=LNKST), or specified in IEASYSxx or by the operator, libraries in the LNKST concatenation are also authorized when accessed as part of the LNKST concatenation. If a library is in the LNKST concatenation, but is not APF authorized, referencing this library through a JOBLIB or STEPLIB DD statement will cause the library to be considered unauthorized for the duration of the job or step, respectively.

**Associated parmlib member:** IEAAPFxx

## AUTOR

```
AUTOR={xx
      {(xx[,xx]...)}
      {OFF
      {(OFF)}
```

The AUTOR parameter enables an installation to specify its own auto-reply policy during IPL, or to request that auto-reply processing is not to be activated. If auto processing is not to be activated, specify AUTOR=OFF or remove AUTOR00 from the member.

If AUTOR= is specified in response to IEA101A SPECIFY SYSTEM PARAMETERS, the AUTOR= value overrides any AUTOR= specification in the parmlib member IEASYSxx.

**Value range:** Any two characters (A-Z, 0-9, @, #, and \$).

**Default:** AUTOR=00

**Associated parmlib member:** AUTORxx

## AXR

```
AXR={aa
     {(aa,bb,...)}
```

The AXR parameter identifies the AXRxx parmlib members that specify System REXX options. The two alphanumeric characters are appended to AXR to form the name of the AXRxx member of SYS1.PARMLIB.

Syntax AXR=aa specifies a single member and syntax AXR=(aa,bb,...) for groups System REXX initialization statements across several AXRxx members.

If the same AXRxx parameter is specified in multiple members, the first occurrence takes precedence; however, the exception to this is the REXXLIB parameter that can be included in multiple members.

**Value range:** Any two alphanumeric characters.

**Default:** AXR=00

**Associated parmlib member:** AXRxx

## BOOST

**BOOST={SYSTEM| ZIIP | SPEED | NO[NE]}**

Two boosts are possible: zIIP boost and speed boost. These boosts are available when running z/OS on a machine with IBM z15™ capabilities only.

The zIIP boost configures online zIIPs in the standby state in accordance with the zIIP configuration of the LPARs. The zIIP boost will "blur" work between standard CPs and zIIPs. (That is, work that is normally eligible only for a standard CP may be run on a zIIP.) zIIP boost only applies to an LPAR that, at the time of boost activation, meets all of the following criteria:

- Has at least one online or standby zIIP
- Is not a dedicated partition
- Is running with HIPERDISPATCH=YES

In order for zIIPs to be configured online during boost processing, the zIIPs must be defined to the LPAR. They may be defined before IPL or they may be dynamically added to the configuration after IPL, depending on the LOADxx DYNCPADD parameter value in effect. zIIPs dynamically added after IPL do not apply to IPL boost but could be used by shutdown and recovery process boosts.

The speed boost makes a sub-capacity standard CP run at the speed of a (full-speed) zIIP. Speed boost only applies to an LPAR that, at the time of boost activation, does not have its standard CP(s) already running at the (full-capacity) speed of a zIIP.

Boost start is evaluated at three points:

- At IPL
- At the requested start of a recovery process boost
- At shutdown, as identified by using the command START IEASDBS

For more information on System Recovery Boost, see: [IBM Z System Recovery Boost Content Solution \(www.ibm.com/support/z-content-solutions/system-recovery-boost/\)](http://www.ibm.com/support/z-content-solutions/system-recovery-boost/) or [IBM Documentation \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).

### SYSTEM

Apply system rules. If the machine does not support boosts, treat as NONE. If the system does support boosts, activate all boosts that the machine supports.

### ZIIP

Activate only the zIIP boost. Do not activate the other (speed) boost.

### SPEED

Activate only the speed boost. Do not activate the other (zIIP) boost.

### NONE | NO

Do not activate either of the boosts.

The specification may be displayed using the DISPLAY IPLINFO,BOOST command.

**Value range:** Not applicable

**Default:** BOOST=SYSTEM

**Associated parmlib member:** None

## CATALOG

```
CATALOG={aa } { (aa,bb,...) }
```

This parameter identifies the IGGCATxx members to use during the current IPL. The two alphanumeric characters, represented by *aa* (or *bb*, and so on), are appended to IGGCAT to form the names of the IGGCATxx members.

The IGGCATxx parmlib members specify catalog parameters for the initializing system.

**Value range:** Any two alphanumeric characters.

**Default:** CATALOG=00

**Associated parmlib member:** IGGCATxx

## CEA

```
CEA={xx } { (xx,yy,...) }
```

This parameter identifies the CEAPRMxx parmlib member that describes the common event adapter (CEA) parameters for the initializing system. The two alphanumeric characters, *xx*, are appended to CEAPARM to form the name of the parmlib member, CEAPRMxx.

**Value range:** Any two alphanumeric characters except NO.

**Default:** CEA=00, causing selection of CEAPRM00.

**Associated parmlib member:** CEAPRMxx

## CEE

```
CEE={xx } { (xx,yy,...L) }
```

The two-character identifier (*xx*) is appended to the CEEPRMxx member of SYS1.PARMLIB. If you specify the L option in the syntax of the CEEPRMxx member, or in reply to the 'SPECIFY SYSTEM PARAMETERS' message, the system writes all statements read from the CEEPRMxx member to the operator's console.

The default IEASYS00 member does not specify a CEEPRM member. If you want to use CEEPRM, you must add the CEEPRM member to IEASYS00. IBM supplies a CEEPRM00 member in SCEESAMP.

**Value range:** Any two alphanumeric characters.

**Default:** None.

**Associated parmlib member:** CEEPRMxx

## CLOCK

```
CLOCK={aa } { (aa,bb,...L) }
```

The two alphanumeric characters are appended to CLOCK to form the name of the CLOCKxx member of SYS1.PARMLIB. If you specify the L option in the syntax of the CLOCKxx member, the system writes all statements read from the CLOCKxx member to the operator's console. The member specifies whether to prompt the operator to set the TOD clock during system initialization, provides the difference between the local time and UTC, and controls ETR usage.

**Value range:** Any two alphanumeric characters.

**Default:** CLOCK=00

**Associated parmlib member:** CLOCKxx

## CLPA

### CLPA

(See also the MLPA parameter for temporary additions to the LPA, and the CVIO parameter for the deletion of VIO data sets.) This parameter causes NIP to load the LPA with all modules contained in the LPALST concatenation. Modules that are listed in the specified LPA pack list member (IEAPAKxx) are packed together, preferably in one-page groups. (See description of IEAPAKxx.) Modules not in the pack list are loaded in size order, large modules first, then smaller modules to fill unused space.

PLPA pages are written to auxiliary storage. Only one set of PLPA pages can exist in paging space. Modules in the LPALST concatenation must be reenterable and refreshable because the system uses the processor's page protection facility, which enforces read-only access to each PLPA page.

CLPA should be specified after the installation has modified a data set in the LPALST concatenation and wants to reload the PLPA with new or changed modules.

**Note:** CLPA also implies CVIO, so that VIO data set pages on local page data sets are automatically purged. (See the description of CVIO for further information.)

The CLPA parameter is not needed at the first IPL. NIP detects the cold start condition internally, noting that the PLPA has not been loaded.

**Note:** CLPA is always enforced for Validated Boot for z/OS. No message is issued about this being done.

If CLPA is not specified, NIP tries to find a usable PLPA in the existing page data sets. If NIP is successful, a quick start or a warm start occurs, and the auxiliary storage manager (ASM) obtains the records that specify where the PLPA pages reside on auxiliary storage. It then reestablishes the previous set of PLPA pages. The old PLPA can be reused for any number of system initializations, if CLPA is not specified. However, page data sets that contain the last used set of PLPA pages must be mounted. If they are not, the operator is asked to mount them. If the operator bypasses mounting, ASM initialization requests a different page data set and forces a *cold* start. NIP then reestablishes the PLPA as it does when CLPA is specified. In this cold start, both the previously established PLPA and existing VIO data set pages are logically deleted from paging space.

The fixed LPA and the modified LPA, however, are not automatically reused in a quick start or a warm start. They must be respecified. Existing VIO data set pages on local page data sets are retained in a warm start, unless the CVIO or CLPA parameter is forced. Such pages are not retained in a quick start or a cold start. (See the description of the CVIO parameter.)

If CLPA is specified and a set of PLPA pages already exists on a paging data set, NIP frees the existing PLPA and updates the appropriate records to reflect the new PLPA pages on auxiliary storage. NIP loads the LPA from the LPALST concatenation, as previously described.

**Value range:** Not applicable

**Default:** Not applicable

**Associated parmlib member:** None

## CMB

**CMB={option}{(option,option[,option]) . . .}**

This parameter allows the installation to specify I/O device classes for which measurement data is to be collected, in addition to the DASD and tape device classes. (Measurement data is always collected for DASD and tape devices.) For each I/O device to be monitored, the system needs 32 bytes of central storage.

If your system is running on a z990 processor, or higher, the system ignores anything you have specified on this parameter. Storage is allocated for ECMBs as needed. Each ECMB requires 64 bytes of central storage. CMBs will only be used when running on a processor lower than z990.

The channel stores measurement data in the CMB on a device basis. SRM uses the measurement data to perform its device selection and I/O load balancing functions.

The operator is notified if the CMB parameter contains a syntax error (message IEA926I) or if there is insufficient storage to accommodate measurement of the specified I/O device classes (message IEA340I). In both cases, SRM prompts for respecification of the CMB parameter. If, after respecification, storage is still unavailable for measurement of the optional device classes, measurement will be done only for DASD and tape devices. If storage is not available for measurement of DASD and tape devices, SRM marks the measurement facilities as inoperative and informs the operator that device selection and I/O load balancing is performed without I/O measurement data (messages IEA966I and IEA340I).

One or more of the following options can be specified:

**UNITR**

Specifies unit record devices.

**COMM**

Specifies communications equipment, including the channel-to-channel adapter (CTC).

**GRAPH**

Specifies graphics devices.

**CHDR**

Specifies character reader devices.

**n**

Specifies the sum of the number of devices that you need to measure that are not DASD or tape or other types of devices specified using the options plus the number of devices that you plan to dynamically add and measure. See [z/OS HCD Planning](#) for more information about specifying the CMB parameter.

**Examples of valid CMB statements: :**

```
CMB=UNITR
CMB=(COMM,100)
CMB=(UNITR,CHDR,COMM,150)
CMB=50
```

**Value range:** *n* is a decimal integer from 0 through 65535.

**Default:** None

**Associated parmlib member:** None

## CMD

**CMD={aa}{(aa,bb...)}**

The two alphanumeric characters, represented by *aa* (or *bb*, and so on), specify one or more COMMNDxx members of parmlib. The installation can specify multiple members. Each member can contain automatic operator commands that the installation wants processed during master scheduler initialization. Examples of such commands are those that start GTF. Job entry subsystem commands are not accepted because automatic commands are processed before the job entry subsystem (JES2 or JES3) is started.

If the CMD parameter is not specified, the COMMND00 member is used if it exists. If COMMND00 does not exist or cannot be read, initialization continues without any internally issued commands.

**Value range:** Any two alphanumeric characters.

**Default:** CMD=00

**Associated parmlib member:** COMMNDxx

## CON

```
CON={aa}
  {(aa[,L][,NOJES3])}
  {NONE}
  {(NONE[,L][,NOJES3])}
  {NOJES3}
```

The two alphanumeric characters (*aa*) are appended to CONSOL to form the name of the installation-created CONSOLxx member of SYS1.PARMLIB.

If you specify the L option, the system lists all of the statements read from the CONSOLxx member on the operator's console.

If you specify NONE, the system uses all the IBM defaults for the CONSOLxx parmlib member to bring up the system. For information about when you would want to specify CON=NONE, see [z/OS MVS Planning: Operations](#).

When operating JES2 on a system with JES3 installed, IBM suggests the use of the NOJES3 option to allow the comma to be omitted between the REPLY ID and the command text when using short form reply.

The NOJES3 option has no effect when specified on a system that does not have JES3 installed.

The *aa* or NONE specification, if used, must precede the NOJES3 option. The L option, if used, can precede or follow the NOJES3 option. If you specify only NOJES3 on CON=, the system assumes you wanted (NONE,NOJES3).

The NOJES3 option, if specified, remains in effect for the duration of the IPL. If you specify NOJES3 with an error, (such as CON=(aa,NOJES3) for a CONSOLxx member that does not exist, or CON=(NONE,NOJES3) when a CONSOLxx member is required), the NOJES3 value remains in effect, regardless of how you respond to the system's prompt for CON=. To remove the NOJES3 specification, you must reload the initial program and omit the NOJES3 option when you respecify the CON= parameter.

**Value range:** NONE or any two characters (A-Z, 0-9, @, #, or \$) and, optionally, NOJES3.

**Default:** CON=NONE

**Associated parmlib member:** CONSOLxx

## COUPLE

```
COUPLE=xx
```

This parameter identifies the COUPLExx parmlib member that describes the sysplex environment for the initializing system. The two alphanumeric characters, *xx*, are appended to COUPLE to form the name of the parmlib member, COUPLExx. Only one suffix can be supplied.

Specify COUPLE=\*\* to cause XCF to initialize the system in XCF-local mode. COUPLE=\*\* does not refer to any actual parmlib member. Instead, it is an internal function within XCF that allows the system initial program to be loaded in XCF-local mode. Specifying COUPLE=\*\* also eliminates the need for the sysplex name specified in LOADxx to match the sysplex name specified in COUPLExx because COUPLE=\*\* uses the sysplex name in LOADxx. If a sysplex name is not specified in LOADxx, COUPLE=\*\* substitutes a sysplex name of LOCAL.

**Value range:** Any two alphanumeric characters, or two asterisks.

**Default:** COUPLE=00, causing selection of COUPLE00.

**Associated parmlib member:** COUPLExx

## CRYPTCTRS

**CRYPTCTRS={SYSTEM | ACTIVE | INACTIVE}**

This parameter identifies the processing state for crypto counters.

### **CRYPTCTRS=SYSTEM**

This is the default. Same as CRYPTCTRS=ACTIVE when the machine supports crypto counters; same as CRYPTCTRS=INACTIVE when the machine does not support crypto counters.

### **CRYPTCTRS=ACTIVE**

When the machine supports crypto counters, crypto counters are initially active. Counting can be deactivated later by use of the START IEACTRS,CRYPTO=INACTIVE command. When the machine does not support crypto counters, this is the same as CRYPTCTRS=INACTIVE.

### **CRYPTCTRS=INACTIVE**

Crypto counters are initially inactive. When the machine supports crypto counters, counting can be activated later by use of the START IEACTRS,CRYPTO=ACTIVE command. When the machine does not support crypto counters, no processing is done for the crypto counters.

When MACHMIG CRYPTCTRS is specified in the LOADxx member of parmlib, crypto counter processing will be treated as if the machine does not support crypto counters. When the MACHMIG CRYPTCTRS parameter is used, the crypto counter set is never activated for this IPL. No processing is done related to crypto counters, and no storage is obtained for counter sets as is done for CRYPTCTRS={ACTIVE | INACTIVE}. Any request to activate the crypto counters is rejected or ignored.

**Value range:** Not applicable

**Default:** CRYPTCTRS=SYSTEM

**Associated parmlib member:** None

## CSA

CSA=(a,b)

This parameter specifies the sizes of the virtual common service area (CSA) and extended CSA. The subparameter *a* specifies the size of the CSA, located below 16 MB. The subparameter *b* specifies the size of the extended CSA, located above 16 MB.

The specified size of the CSA is subtracted from the bottom of PLPA, after the bottom PLPA address is rounded down to the next 4 KB (page) boundary. If the resulting virtual address for the bottom of the CSA is not on a megabyte boundary, further rounding down occurs so that the bottom CSA address is on the next megabyte boundary.

Similarly, the specified size of the extended CSA is added to the top of the extended PLPA, after the top extended PLPA address is rounded up to the next 4-KB boundary. If the resulting virtual address for the top of the extended CSA is not on a megabyte boundary, further rounding up occurs so that the top extended CSA address is on the next megabyte boundary.

The CSA (including the extended CSA) is an address range in each address space that is used for common system functions (functions not related to a particular address space). For example, the system allocates buffers for LOG and SMF from the CSA.

In selecting values for the CSA parameter, understand that the system's process of rounding to a 1 MB boundary can cause up to 1 MB of storage from the private area to be allocated to the CSA. However, consider the following:

- If the virtual storage manager runs out of SQA, it tries to obtain space from the CSA.
- A large CSA size will reserve space for future LPA growth. Such growth would be hampered if users were allowed to obtain very large private areas. A large CSA specification effectively limits the maximum private area that a user job can acquire.

If a shortage occurs in CSA, ECSA, SQA, or ESQA, you can use the storage tracking function to collect information about jobs or address spaces that own storage in those areas. With that information,



you can identify jobs or address spaces that obtain an excessive amount of storage. If those jobs or address spaces have code to free the storage when they are canceled, you might relieve the shortage and avoid an IPL if you use an operator command to cancel those jobs or address spaces.

When you turn on the storage tracking function, you might experience a small performance degradation and an increase in ESQA usage. For more information about common storage tracking, including how to turn the function on or off, see [Chapter 30, “DIAGxx \(control common storage tracking and GFS trace\),”](#) on page 295.

If you allocate excessive amounts of CSA or SQA, the system generates a warning message, and you must respecify the CSA parameter. The system also generates a warning message when the size of the entire common area below 16 MB exceeds 8 MB.

**Value range:** Each *a* value can be expressed as:

- A decimal number, *n*, indicating *n* 1 KB (1024-byte) blocks. The number is 0 through 9999.
- A decimal number followed by K, *nK*, indicating *n* 1 KB blocks. The number is 0 through 9999.
- A decimal number followed by M, *nM*, indicating *n* 1 MB (1024\*1024-byte) blocks. The number is 0 through 9.

Each *b* value can be expressed follows. Note that the maximum values are accepted, but not recommended because they would result in a private region that is too small. Do not specify more than you think you might ever need.

- A decimal number, *n*, indicating *n* 1 KB blocks. The number is 0 through 2080767.
- A decimal number followed by K, *nK*, indicating *n* 1 KB blocks. The number is 0 through 2080767.
- A decimal number followed by M, *nM*, indicating *n* 1 MB blocks. The number is 0 through 2031.

**Default:** For each subparameter, 100 through 1023 KB (depending on the amount of storage added because of rounding to a segment boundary).

**Associated parmlib member:** Not applicable.

## CSCBLOC

**CSCBLOC={ABOVE| BELOW}**

This parameter determines whether the CSCB control block chain resides above or below 16 megabytes.

The CSCB is comprised of a 36-byte block which is always obtained below 16 megabytes and a 256-byte block whose residence is governed by this parameter. Be careful when specifying CSCBLOC=BELOW to not over-specify the MAXUSER or RSVSTRT values by too great an amount as they are used to determine the number of CSCBs allocated.

The system will reserve an initial block of memory to contain a minimum of 250 CSCBs or 1/8 of the combined MAXUSER and RSVSTRT value if that is larger. Therefore, at a minimum, over 9000 bytes are allocated below the line and additionally over 64000 bytes are allocated based on the CSCBLOC setting. Using large values for MAXUSER or RSVSTRT reduces the amount of CSA storage below 16 MB available for other applications. This might result in an ABEND878 when applications are started after IPL or cause a wait state 040 to occur at IPL time.

For example, if you specify a combined MAXUSER and RSVSTRT value of 5000, over 22500 bytes are initially allocated below 16 megabytes and additionally over 160000 bytes are initially allocated based on the CSCBLOC setting. In this example, if all of the MAXUSER and RSVSTRT entries are in use, 180000 bytes will be allocated below 16 megabytes and 1280000 bytes will be allocated above or below 16 megabytes based on the CSCBLOC setting

**Value range:** Not applicable

**Default:** CSCBLOC=ABOVE

**Associated parmlib member:** None

## CVIO

CVIO (Clear VIO)

This parameter specifies that all VIO data set pages on auxiliary storage are to be deleted from page space. A typical application would be the purging of VIO data set pages when the system initial program is reloaded after a previous end-of-day (EOD).

**Note:** If you want the auxiliary storage manager (ASM) to purge and reinitialize both the VIO data set pages and the PLPA pages, specify CLPA. CLPA always implies CVIO.

If you do not specify CVIO, a warm start IPL occurs and VIO data set pages are retained for restart processing. (Such restart would be possible for some data sets after a temporary system failure.) ASM reestablishes the VIO data set pages that had checkpoints set before the system failure. This action, of course, does not ensure that the job entry subsystem will reuse these data sets.

If one or more volumes that contain VIO pages are not mounted on a warm start IPL, ASM requests the operator to mount the missing volumes. If the operator does not mount all the requested volumes that contain VIO pages, ASM deletes all VIO data set pages, just as if CVIO or CLPA had been specified. The operator receives a message that indicates that CVIO has been forced.

**Value range:** Not applicable

**Default:** None

**Associated parmlib member:** None

## DEVSUP

DEVSUP={aa  
{(aa,bb,...)} }

This parameter specifies one or more DEVSUPxx parmlib members. The two alphanumeric characters, represented by *aa* (or *bb*, and so on), are appended to DEVSUP to form the name of the DEVSUPxx members.

The DEVSUPxx member specifies the installation default for whether data is stored in a compacted format on a 3480 or 3490 tape subsystem with the Improved Data Recording Capability feature.

**Value range:** Any two alphanumeric characters.

**Default:** None

**Associated parmlib member:** DEVSUPxx

## DIAG

DIAG={aa  
{(aa,bb,...)} }

This parameter specifies the DIAGxx members of parmlib. The two alphanumeric characters, represented by *aa* (or *bb*, and so on), are appended to DIAG to form the names of the DIAGxx members. The DIAGxx parmlib member turns the common storage tracking function on or off. It also controls GFS tracing.

**Value range:** Any two alphanumeric characters.

**Default value:** DIAG00

**Associated parmlib member:** DIAGxx

## DRMODE

DRMODE={NO} | {YES}

This parameter is no longer supported. Although the keyword can be specified, any specification of it has no effect on the system.

**Value range:** Not applicable.

**Default:** NO

**Associated parmlib member:** None

## DUMP

```
DUMP={NO           }
      {DASD        }
      {(DASD,xx-yy)}
```

This parameter specifies whether SYS1.DUMP data sets on direct access devices are to be made available at IPL time. SVC dump options are not included in IEASYSxx. The installation can specify the options, if it so desires, through the CHNGDUMP operator command, either in the COMMNDxx parmlib member or from the console.

When planning for dump data sets, the installation should be aware the dump data sets can sometimes contain privileged data. By using protected data sets (through passwords or other security methods), the installation can limit access.

**Note:** You can also allow the system to create dump data sets dynamically. For details, see [z/OS MVS Diagnosis: Tools and Service Aids](#).

### DASD

Specifies that the all currently cataloged SYS1.DUMPnn data sets (if any), on permanently resident direct access volumes, are to be used. The catalog will be scanned for SYS1.DUMP00 through SYS1.DUMP99. DASD is the default if the DUMP parameter is omitted.

Specifying DASD is equivalent to specifying DUMPDS ADD,DSN=ALL in the COMMNDxx parmlib member.

### (DASD,xx-yy)

Specifies that the currently cataloged SYS1.DUMPnn data sets (if any), on permanently resident direct access volumes, are to be used. The catalog will be scanned for SYS1.DUMPxx through SYS1.DUMPyy, where xx and yy are decimal digits in the range 00 through 99.

Specifying DASD is equivalent to specifying DUMPDS ADD,DSN=(xx-yy) in the COMMNDxx parmlib member.

Indicating which dump data sets are to be used by a particular system avoids unnecessary scanning of the possible 100 cataloged dump data sets and the possibility of more than one system using the same data sets.

### NO

Specifies that no dump data sets will be made available for SVC dump at IPL time. Dump data sets can be specified after IPL by using the DUMPDS command or by adding the DUMPDS command to COMMNDxx.

Following are examples of valid DUMP statements:

```
DUMP=NO
DUMP=DASD
DUMP=(DASD,00-05)
```

Dump data sets can only reside on direct access devices. Space for direct access data sets must be pre-allocated, and the data sets must be cataloged. Eligible device types consist of any direct access device supported by the system that has a track size of at least 4160 bytes (4160 bytes equals 1 SVC dump output record).

As many as 100 dump data sets may be allocated. They must be in the form SYS1.DUMPnn, in which nn may be digits 00 to 99.

**Note:** Specify both primary and secondary allocations for SYS1.DUMPnn data sets. IBM suggests using the DUMPDS ADD command in COMMNDxx and DUMP=NO in IEASYSxx to make the allocated dump data sets available to SVC dump. If you do this, MVS provides better diagnostic messages, which indicate which dump data sets were added, which were not added, and why.

For more information about allocating SYS1.DUMPxx data sets, see *z/OS MVS Diagnosis: Tools and Service Aids*.

The status and type of each dump data set is maintained by the system. The system records the data set status as empty or full. An empty data set is available for use by the system. A full data set can be printed (and emptied), or made empty by the DUMPDS CLEAR command.

A DASD data set is empty only if the first record is an end of data record. Otherwise, the data set is considered full.

When an SVC dump is requested, an empty data set is selected and that data set is then marked as being in use. When the DUMPDS CLEAR command is issued for a dump data set, that data set is marked as being available.

When an SVC dump is requested and there are no data sets marked as being available, the system reads the first record of each data set to see if it has been emptied (printed). If so, the first record is an end of data record. When the system finds such a data set, it uses it for the requested SVC dump.

**Restriction:** Tape data sets are not supported.

**Value range:** Not applicable

**Default:** DASD

**Associated parmlib member:** None

## EXIT

### EXIT=aa

This parameter specifies the EXITxx members of parmlib that contains the entry points and names of allocation installation exits. The two alphanumeric characters, represented by *aa*, are appended to EXIT to form the name of the EXITxx members.

**Note:** IBM provides the PROGxx member as an alternative to EXITxx. IBM suggests that you convert the format of EXITxx to PROGxx and provides the IEFEXPR REXX exec to do this. You should also add the PROG=xx system parameter to IEASYSxx (see [Chapter 81, “PROGxx \(authorized program list, exits, LNKLIST sets and LPA\),” on page 685](#)), remove the EXIT=xx system parameter from IEASYSxx, and remove EXIT=xx from IEASYS00. For information about how to begin using PROGxx, see [Chapter 81, “PROGxx \(authorized program list, exits, LNKLIST sets and LPA\),” on page 685](#).

**Value range:** Any two alphanumeric characters.

**Default:** None

**Associated parmlib member:** EXITxx

## FIX

```
FIX={aa                                     }
    {(aa[,L][,NOPROT])                     }
    {(aa,bb...[,L][,NOPROT])               }
```

This parameter specifies one or more IEAFIXxx members of parmlib. The two characters (A-Z, 0-9, @, #, or \$), represented by *aa* (or *bb*, and so on), are appended to IEAFIX to name the members. If the L option is specified, the system displays the contents of the IEAFIXxx parmlib members at the operator's console as the system processes the members.

The members contain names of modules that are to be fixed in central storage as a fixed LPA. The fixed LPA modules are active only for the duration of an IPL, and will not be automatically reinstated

by a quick start or a warm start IPL. You must respecify the FIX parameter in later IPLs if you want to reinstate the fixed LPA.

The LPA modules that are fixed in storage are also page-protected, by default. If an attempt is made to store into a page-protected module, a protection exception occurs. However, an installation can use the NOPROT option to override the page protection default. When NOPROT is specified, the LPA modules in the IEAFIXxx parmlib members are not page-protected in storage.

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$).

**Default:** None

**Associated parmlib member:** IEAFIXxx

## FXE

**FXE={x1|(x1,...,xn)}**

This optional parameter specifies one or more suffixes of FXEPRMxx parmlib members to be processed when the system starts. FXEPRMxx members contain statements that control the IBM Function Registry for z/OS, for example statements that affect the enablement state of individual function entries in the registry. In order for those statements to affect any targeted function entries, the owner of the product area that contains those function entries, must ensure early on that the product area is processed via a call to service EXECNTRL REQUEST=APPLYIPLPARM shortly before the product area is linked into the IBM Function Registry for z/OS data infrastructure.

The system command DISPLAY FXE,IPLPARMS displays information about the statements from FXEPRMxx parmlib members identified by system parameter FXE. The command output in particular includes information on whether an individual statement has been applied to any function entry yet or not.

**Value range:** Any two alphanumeric or national (\$, #, @) characters.

**Default:** None

**Associated parmlib member:** FXEPRMxx

## GRS

```
GRS={JOIN      }
    {TRYJOIN   }
    {START     }
    {NONE      }
    {STAR      }
```

This parameter specifies whether the system being initialized is to participate in a global resource serialization complex. In a multisystem sysplex, every system in the sysplex must be in the same global resource serialization complex. This allows global serialization of resources in the sysplex.

Specifying GRS=STAR indicates that the system being initialized is to participate in a global resource serialization star complex.

GRS=NONE indicates that the system is not to participate in a global resource serialization complex. GRS=START, GRS=JOIN, and GRS=TRYJOIN indicate that the system is to coordinate global resource requests with other systems in a global resource serialization ring complex.

Specifying GRS=START indicates that the system is to start a global resource serialization ring complex and honor the requests of other systems (those systems that specify GRS=JOIN) to join the complex. Specifying GRS=JOIN indicates that the system is to join an existing ring complex of active global resource serialization systems and also honor the requests of other systems to join the complex.

Specifying GRS=TRYJOIN allows the system to act on whether a ring complex already exists. If the complex does exist, the system joins the existing complex. If the system does not find any active global resource serialization systems, the system will start the complex.



**Attention:** When all the systems in a global resource serialization ring complex are not in a multisystem sysplex, there is a possibility of a split ring and a data integrity exposure when GRS=TRYJOIN is used. When all systems are in a multisystem sysplex, however, this option is recommended. For more information about specifying the GRS system parameters, see [z/OS MVS Planning: Global Resource Serialization](#).

**Note:** If you have specified anything other than GRS=NONE, then you must specify the GRSRNL parameter.

**Value range:** Not applicable

**Default:** None

**Associated parmlib member:** None

## GRSCNF

GRSCNF=xx.

Identifies the GRSCNFxx parmlib member to be used to initialize a system in the global resource serialization complex. The two alphanumeric characters, xx, are appended to GRSCNF to form the name of the parmlib member, GRSCNFxx. Only one suffix can be supplied. The installation creates the member and places it in parmlib.

The majority of GRSCNFxx parameters are specific to defining a global resource serialization ring complex. However, GRSQ is specific to star mode, and the following keywords are relevant for all modes, including GRS=NONE:

- ENQMAXA
- ENQMAXU
- SYNCHRES

**Value range:** Any two alphanumeric characters.

**Default:** GRSCNF00 is the parmlib member that is selected if you do not specify GRSCNF=xx.

**Associated parmlib member:** GRSCNFxx

## GRSRNL

```
GRSRNL={aa
        {aa,bb...)}
        {EXCLUDE}
```

This parameter can specify one or more GRSRNLxx parmlib members. The two alphanumeric characters, represented by aa (or bb, and so on), are appended to GRSRNL to form the name of the GRSRNLxx members.

The GRSRNLxx members contain resource name lists (RNLs). The system (specifically, global resource serialization) uses the RNLs to determine how to treat a resource that the installation defined in an RNL.

GRSRNL=EXCLUDE specifies that no resource name lists (RNLs) are to be used in the complex. All ENQ, RESERVE, and DEQ macro requests with a scope of SYSTEMS are treated as though they had been found in the SYSTEMS exclusion RNL. Their scope is changed to SYSTEM and they are processed locally.

The RNL=NO parameter, if specified on the request, prevents this exclusion. It allows the request to retain its scope of SYSTEMS and be serialized globally on all systems in the complex. See [z/OS MVS Planning: Global Resource Serialization](#) when to use GRSRNL=EXCLUDE.

**Note:** If you specify anything other than GRS=NONE during system initialization, the GRSRNL parameter is required.

**Value range:** Any two alphanumeric characters.

**Default:** None

**Associated parmlib member:** GRSRNLxx

## GTZ

```
GTZ={aa }
    {(aa,bb...)}

```

This parameter specifies one or more suffixes of the optional Generic Tracker for z/OS parmlib member GTZPRMxx to be used by the system. The two characters, represented by *aa* (or *bb*, and so on) are appended to GTZPRM to form the name of the GTZPRMxx members when the Generic Tracker address space, GTZ, starts.

The GTZPRMxx parmlib member contains parameters for managing IBM Generic Tracker for z/OS, including EXCLUDE statements for known track events.

In order to let the system successfully process the identified GTZPRMxx parmlib members at GTZ startup the following security setup is required:

- Have a user ID with permission to access the PARMLIB concatenation, for example, using:
  - ADDUSER GTZ NOPASSWORD
  - ADDSD 'SYS1.PARMLIB' UACC(NONE)
  - PERMIT 'SYS1.PARMLIB' CLASS(DATASET) ID(GTZ) ACCESS(READ)
- Associate this user ID with the GTZ address space, for example using:
  - SETROPTS GENERIC(STARTED)
  - RDEFINE STARTED GTZ.\* STDATA(USER(GTZ))
  - SETROPTS RACLIST(STARTED) REFRESH

**Value range:** Any two alphanumeric or national (\$, #, @) characters.

**Default:** None

**Associated parmlib member:** GTZPRMxx

## HVCOMMON

```
HVCOMMON = {xxxxxxxxxxG}
           {xxxxxxxxxxT}

```

This parameter specifies the size of the 64-bit common area. The IARV64 macro allows the allocation of common virtual storage above 2 gigabytes. The HVCOMMON parameter defines the size of the 64-bit common area.

The 64-bit common area is placed below the 4 T line.

The value that you specify is rounded up to a 2-gigabyte boundary.

You can also specify the HVCOMMON value by responding to message IEA101A.

**Value range:** 2 gigabytes (2 G) to 1 terabyte (which is 1024 gigabytes)

**Default:** 64 gigabytes (64 G)

**Note:** In addition to the 64-bit or other specified common area defined by this parameter, the system allocates an additional amount determined by the system at IPL. At a minimum you will see at least 66GB when the default is used.

## HVSHARE

```
HVSHARE={xxxxxxxxxxG}
         {xxxxxxxxxxT}
         {xxxxxxxxxxP}
```

This parameter specifies the size of the high virtual shared area. The IARV64 macro allows multiple address spaces to share virtual storage above 2 gigabytes (see [z/OS MVS Programming: Authorized Assembler Services Reference EDT-IXG](#) for details). The HVSHARE parameter defines how much virtual storage can be shared.

The size of the HVSHARE value determines where the system places the virtual shared area. If you specify a value less than 2 terabytes (2 T), the system obtains storage that straddles the 4-terabyte line; half of the storage comes from above the 4-terabyte line, and half of the storage comes from below the 4-terabyte line. If you specify a value larger than 2 T, the system obtains storage starting at the 2-terabyte line.

The value that you specify is rounded up to a 64-gigabyte boundary.

You can also specify the HVSHARE value by responding to message IEA101A.

**Value range:** 0 gigabytes (0G) to 1 exabyte (which is 1048576 terabytes or 1024 petabytes)

**Default:** 510 terabytes (510 T); placement starts at the 2 T line

**Associated parmlib member:** None.

## HZS

```
HZS={aa
    {(aa,bb...)} }
```

This parameter specifies one or more suffixes of the optional IBM Health Checker for z/OS parmlib member, HZSPRMxx to be used by the system. The two characters, represented by *aa* (or *bb*, and so on), are appended to HZSPRM to form the name of the HZSPRMxx members when HZSPRM=SYSPARM (or HZSPRM=PREV for IPL-time) is specified in the HZSPROC startup procedure for IBM Health Checker for z/OS.

The HZSPRMxx parmlib member contains parameters for managing IBM Health Checker for z/OS and checks, including overriding check defaults and defining policies for permanent updates to check defaults.

**Value range:** Any two alphanumeric or national (\$, #, @) characters.

**Default:** None

**Associated parmlib member:** HZSPRMxx

## HZSPROC

```
HZSPROC=hzsprocname
```

This parameter specifies the name of the HZSPROC procedure you want the system to use to automatically start IBM Health Checker for z/OS at IPL-time. Specify this parameter if you want to use a name other than the default, HZSPROC. The procedure specified must reside in a SYS1.PROCLIB data set.

You can customize your HZSPROC procedure. For more information, see [Steps for optimizing IBM Health Checker for z/OS](#) in [IBM Health Checker for z/OS User's Guide](#).

**Value range:** A 1-8 character string, where the first character is alphabetic or national (\$, #, @) and the other characters, if any, are alphanumeric or national.

A special value of \*NONE is accepted to signify that no procedure should be used and that Health Checker should not be started automatically at IPL time.



**Default:** HZSPROC

**Associated parmlib member:** None

## ICSF

**ICSF=xx**

The parameter specifies the suffix of the ICSF on z/OS, CSFPRMxx, to be used by the system. The two characters represented by xx are appended to CSFPRM during ICSF initialization to form the name of the CSFPRMxx member. When specified in conjunction with the ICSFPROC parameter, ICSF on z/OS starts at IPL-time.

The CSFPRMxx member contains parameters for initialization of ICSF on z/OS.

**Value range:** Any two alphanumeric or national (\$, #, @) characters.

A special value of NONE is accepted to signify that no procedure is used and that ICSF is not started automatically at IPL-time. If NONE is specified, ICSF must be started manually or by automation.

**Default:** None.

**Associated parmlib member:** None.

## ICSFPROC

**ICSFPROC=csfprocname**

This parameter specifies the name of the ICSF procedure you want the system to use to automatically start ICSF on z/OS at IPL-time. The procedure must reside in a SYS1.PROCLIB data set. When specified in conjunction with the ICSF parameter, ICSF on z/OS starts at IPL-time.

For more information on customizing your ICSF startup procedure, see 'Starting ICSF during IPL-time' in *z/OS Cryptographic Services ICSF System Programmer's Guide*.

**Value range:** A 1-8 character string, where the first character is alphabetic or national (\$, #, @), and the other characters, if any, are alphanumeric or national.

A special value of NONE is accepted to signify that no procedure is used and that ICSF is not started automatically at IPL-time. If NONE is specified, ICSF must be started manually or by automation.

**Default:** None.

**Associated parmlib member:** None.

## IEFOPZ

**IEFOPZ={aa  
{(aa,bb...)} }**

This parameter specifies one or more suffixes of the IEFOPZxx parmlib member to be used by the system. The IEFOPZxx parmlib member contains statements that define the data set optimization configuration. The two characters, represented by aa (or bb, and so on), are used as a suffix appended to IEFOPZ to form the name of the IEFOPZxx members to be used by the system. No more than 38 suffixes may be specified.

**Value Range:** Any two alphanumeric or national (\$, #, @) characters.

**Default Value:** None

**Associated Parmlib Member:** IEFOPZxx

## IKJTSO

IKJTSO=xx

This parameter specifies the parmlib member from which TSO/E settings are obtained. The two alphanumeric characters (xx), specified in the parameter, are appended to IKJTSO to form the parmlib member IKJTSOxx.

**Value range:** Any two alphanumeric characters

**Default:** 00 (specifies IKJTSO00)

**Associated parmlib member:** IKJTSOxx

## IOS

IOS=xx

This parameter specifies the parmlib member that contains intervals to be used by the missing interrupt handler (MIH) when scanning for missing interrupt conditions and device threshold values and recovery actions to be used in the detection of, and recovery from, hot I/O conditions. The two alphanumeric characters (xx), specified in the parameter, are appended to IECIOS to form the parmlib member IECIOSxx.

**Value range:** Any two alphanumeric characters

**Default:** None. The I/O supervisor assumes default options. For a list of these defaults and their explanations see the description of the IECIOSxx parmlib member.

**Associated parmlib member:** IECIOSxx

## IQP

IQP={aa  
      { (aa, bb . . . ) }

This parameter specifies the IQPPRMxx members of SYS1.PARMLIB. The two alphanumeric characters, represented by *aa* (or *bb*, and so forth) are appended to IQPPRM to form the names of the IQPPRMxx members. The IQPPRMxx parmlib members specify parameters that are used for managing PCIE-related devices.

**Value range:** Any two alphanumeric characters

**Default:** None

**Associated parmlib member:** IQPPRMxx

## IXGCNF

IXGCNF={aa  
      { (aa, bb . . . ) }

This parameter identifies the IXGCNFxx parmlib members to be used when system logger starts or is restarted on the initializing system within the sysplex. Syntax IXGCNF=aa specifies a single member and syntax IXGCNF=(aa,bb,...) identifies groups of system logger initialization statements across several IXGCNFxx members.

You can optionally create one or more members and place them in SYS1.PARMLIB.

When multiple IXGCNFxx members are concatenated, the individual system logger options are merged with the last parmlib member option taking precedence. The Display `LOGGER,IXGCNF[,options]` command displays the merged information

**Value range:** Any two alphanumeric characters

**Default:** None

**Note:** The L (list) option is syntactically allowed but ignored.

**Associated parmlib member:** IXGCNFxx

## IZU

```
IZU={aa
    {(aa,bb...)} }
```

This parameter specifies one or more suffixes of the optional z/OS Management Facility (z/OSMF) parmlib member, IZUPRMxx to be used by the system. The two characters, represented by *aa* (or *bb*, and so on), are appended to IZUPRM to form the names of the IZUPRMxx members, when IZUPRM=SYSPARM (or IZUPRM=PREV for IPL-time) is specified in the IZUSVR1 startup procedure for z/OSMF.

The IZUPRMxx parmlib member contains parameters for configuring z/OSMF and managing its behavior.

**Value range:** Any two alphanumeric or national (\$, #, @) characters.

**Default:** None

**Associated parmlib member:** IZUPRMxx

## LFAREA

```
LFAREA = {xM | xG | xT | x%}
          {(xM | xG | xT | x% [, INCLUDE1MAFC(YES|NO)])}
          {( [1M=(a [,b]) | 1M=(a% [,b%])]
            [,2G=(a [,b]) | ,2G=(a% [,b%])]
            [,PROMPT | ,NOPROMPT]
            [,INCLUDE1MAFC(YES|NO)]
          ) }
```

The LFAREA parameter specifies the maximum amount of online real storage below 4 TB available at IPL that can be used to satisfy fixed 1 MB and 2 GB page requests. The xM, xG, xT, and x% syntax form specifies the maximum amount of 1 MB pages, and the 1M= and 2G= syntax form specifies the maximum amount of 1 MB and 2 GB pages. The two syntax forms cannot be combined. Each syntax specification uses a different formula for calculating percentage requests and the system limit, as described in [“Request handling for the LFAREA system limit” on page 448](#) and [“Request handling for insufficiently contiguous online real storage” on page 449](#).

### Notes:

1. Specifying LFAREA for fixed 1 MB pages does not reserve an amount of real storage to be used exclusively for fixed 1 MB page requests. It simply specifies the target cap for the most fixed 1 MB page requests that can be satisfied for this system.
2. All online real storage above 4 TB is part of the 2G LFAREA in addition to what is specified by the LFAREA keyword. For example, an 8 TB system with LFAREA=(1M=1024,2G=512) results in a 1 MB LFAREA of size 1 GB, and a 2 GB LFAREA of size 5 TB (1TB for the specified 512 2 GB pages. This includes all of the real storage in the 4 TB minus 8 TB range).

In the following descriptions, 2 GB is equal to a decimal value of  $2^{31}$ , or 2147483648, and 4 GB is equal to a decimal value of  $2^{32}$ , or 4294967296.

**Value range:** The following value ranges apply to the value specified on the LFAREA parameter. The maximum values that can be specified for the LFAREA are described in [“Request handling for the LFAREA system limit” on page 448](#).

### xM or xG or xT

Specifies the maximum amount of online real storage that can be used to satisfy fixed 1 MB page requests. Up to six decimal digits can be specified for x: xM specifies the amount is in megabytes; xG specifies the amount is in gigabytes; xT specifies the amount in terabytes. A specification of 0M, 0G,

or OT results in the system using no real storage to satisfy fixed 1 MB page requests for the life of the IPL.

**x%**

Specifies the maximum amount of online real storage that can be used to satisfy fixed 1 MB page requests, as a percentage of the total online real storage at IPL up to 4 TB. Up to two digits can be specified. The percentage is calculated as  $(x\% \times \text{online real storage at IPL up to 4 TB}) - 2\text{G}$ . The maximum percentage that can be specified is 80%. A specification of 0% results in no successful fixed 1 MB page requests.

**1M=(a)**

Specifies the maximum number of 1 MB pages of that can be used to satisfy fixed 1 MB page requests. Up to eight decimal digits can be specified for  $a$ . A specification of  $1M=(0,0)$  results in the system using no real storage to satisfy fixed 1 MB page requests for the life of the IPL.

**1M=(a,b)**

Specifies the maximum number of 1 MB pages that can be used to satisfy fixed 1 MB page requests. Up to eight decimal digits each can be specified for  $a$  and  $b$ . The value that is specified for  $a$  is the target number of pages, and the value that is specified for  $b$  is the minimum number. The system attempts to meet the request at or as near as possible up to the target number, but at no less than the minimum number. The value that is specified for  $b$  must be less than or equal to the value specified for  $a$ , and can be zero. A specification of  $1M=(0,0)$  results in the system using no real storage to satisfy fixed 1 MB page requests for the life of the IPL. When the LFAREA parameter is processed, no additional amounts of storage are reserved later in an attempt to reach the target. Both a value and a percentage, such as  $1M=(a,b\%)$  or  $1M=(a\%,b)$ , cannot be specified.

**1M=(a%)**

Specifies the maximum amount of online real storage that can be used to satisfy fixed 1 MB page requests, as a percentage. Up to two digits can be specified. The storage amount is calculated as  $a\% \times ((\text{online real storage at IPL up to 4 TB}) - 4\text{ GB})$ , rounded down to the nearest 1 MB boundary. The maximum percentage that can be specified is 80%. A specification of  $1M=(0\%)$  results in the system using no real storage to satisfy fixed 1 MB page requests for the life of the IPL.

**1M=(a%,b%)**

Specifies the maximum amount of online real storage that can be used to satisfy fixed 1 MB page requests, as a percentage. Up to two digits each can be specified for  $a\%$  and  $b\%$ . The value that is specified for  $a\%$  is the target amount, and the value that is specified for  $b\%$  is the minimum amount. The system attempts to satisfy the request at or as near as possible up to the target amount, but at no less than the minimum amount. The percentages are calculated as  $\text{percent} \times ((\text{online real storage at IPL up to 4 TB}) - 4\text{ GB})$ , rounded down to the nearest 1 MB boundary. The maximum percentage that can be specified for  $a\%$  is 80%. The value that is specified for  $b\%$  must be less than or equal to the value for  $a\%$ , and can be zero. A specification of  $1M=(0\%,0\%)$  results in the system using no real storage to satisfy fixed 1 MB page requests for the life of the IPL. When the LFAREA parameter is processed, no additional amounts of storage are reserved later in an attempt to reach the target. Both a value and a percentage, such as  $1M=(a,b\%)$  or  $1M=(a\%,b)$ , cannot be specified.

**2G=(a)**

Specifies the number of 2 GB pages of online real storage below 4 TB to reserve in the large frame area. Up to eight decimal digits can be specified for  $a$ . A specification of  $2G=(0)$  results in zero 2 GB pages being reserved below 4 TB. Each 2 GB page is placed only in a 2 GB area of contiguous real storage on a 2 GB boundary, which means that enough 2 GB areas of contiguous online storage on 2 GB boundaries must be available at IPL for the number of 2 GB pages requested. In addition to what is specified, all real storage above 4 TB is also included in the large frame area as 2 GB frames.

**2G=(a,b)**

Specifies the number of 2 GB pages of online real storage below 4 TB to reserve in the large frame area. Up to eight decimal digits each can be specified for  $a$  and  $b$ . The value that is specified for  $a$  is the target number of pages, and the value that is specified for  $b$  is the minimum number. The system attempts to satisfy the request at or as near as possible up to the target number, but at no less than the minimum number. The value that is specified for  $b$  must be less than or equal to the value for  $a$ , and can be zero. A specification of  $2G=(0,0)$  results in zero 2 GB pages being reserved below 4 TB. When the LFAREA parameter has been processed, no additional amounts of storage are reserved later

in an attempt to reach the target. Both a value and a percentage, such as  $2G=(a,a\%)$  or  $2G=(a\%,a)$  cannot be specified. Each 2 GB page is placed only in a 2 GB area of contiguous real storage on a 2 GB boundary, which means that enough 2 GB areas of contiguous online storage on 2 GB boundaries must be available at IPL for at least the minimum number of 2 GB pages requested. In addition to what is specified, all real storage above 4 TB is also included in the large frame area as 2 GB frames.

### **2G=(a%)**

Specifies the amount of online real storage below 4 TB to reserve in the large frame area for 2 GB pages, as a percentage. Up to two digits can be specified for  $a$ . The storage amount is calculated as  $a\% * ((\text{online real storage at IPL up to 4 TB}) - 4 \text{ GB})$ , rounded down to the nearest 2 GB boundary. The maximum percentage that can be specified is 80%. A specification of  $2G=(0\%)$  results in zero 2 GB pages being reserved below 4 TB. Each 2 GB page is placed only in a 2 GB area of contiguous real storage on a 2 GB boundary, which means that enough 2 GB areas of contiguous online storage on 2 GB boundaries must be available at IPL for the amount of 2 GB pages requested. In addition to what is specified, all real storage above 4 TB is also included in the large frame area as 2 GB frames.

### **2G=(a%,b%)**

Specifies the amount of online real storage below 4 TB to reserve in the large frame area for 2 GB pages as a percentage. Up to two digits each can be specified for  $a\%$  and  $b\%$ . The value that is specified for  $a\%$  is the target amount, and the value that is specified for  $b\%$  is the minimum. The system attempts to satisfy the request at or as near as possible up to the target amount, but at no less than the minimum amount. The percentages are calculated as  $\text{percent} * ((\text{online real storage at IPL up to 4 TB}) - 4 \text{ GB})$ , rounded down to the nearest 2 GB boundary. The maximum percentage that can be specified for  $a\%$  is 80%. The value that is specified for  $b\%$  must be less than or equal to the value for  $a\%$ , and can be zero. A specification of  $2G=(0\%,0\%)$  results in zero 2 GB pages being reserved below 4 TB. When the LFAREA parameter has been processed, no additional amounts of storage are reserved later in an attempt to reach the target. Both a value and a percentage, such as  $2G=(a,b\%)$  or  $2G=(a\%,b)$ , cannot be specified. Each 2 GB page is placed only in a 2 GB area of contiguous real storage on a 2 GB boundary, which means that enough 2 GB areas of contiguous online storage on 2 GB boundaries must be available at IPL for at least the minimum amount of 2 GB pages requested. In addition to what is specified, all real storage above 4 TB is also included in the large frame area as 2 GB frames.

### **PROMPT | NOPROMPT**

Specifies whether the system prompts for respecification of the LFAREA parameter when the request cannot be satisfied. The default is **PROMPT**, which specifies for the system to prompt when either the 1M= or 2G= request cannot be satisfied. The value **NOPROMPT** specifies for the system to ignore the LFAREA request when either or both of the 1M= and 2G= requests cannot be satisfied, and to instead have zero 1 MB pages and zero 2 GB pages that can be used to satisfy fixed 1 MB and 2 GB page requests.

### **INCLUDE1MAFC(YES|NO)**

Specifies whether the 1 M LFAREA specification is included in the available frame count (RCEAFC). With z/OS V2R3, the INCLUDE1MAFC specification is ignored. The 1 M LFAREA specification is always included in the available frame count (RCEAFC).

#### **YES**

Specifies that the 1 M LFAREA specification is included in the available frame count. This is the default and the only accepted value.

For compatibility with applicable releases before z/OS V2R2, you can also specify INCLUDE1MAFC(YES) as INCLUDE1MAFC.

#### **NO**

Specifies that the 1 M LFAREA specification is not included in the available frame count.

This value is always ignored.

**Default:** INCLUDE1MAFC(YES).

**Notes:**

1. Application programs can check the RCEINCLUDE1MAFC bit to determine if INCLUDE1MAFC(YES) is in effect, regardless of z/OS release.
2. Application programs that use the STGTEST SYSEVENT must be assessed to determine if any changes need to be made. The STGTEST event returns information about the amount of storage available in the system, which includes the LFAREA. .

## Displaying LFAREA information

You can use the MODIFY AXR,IAXDMEM command to display memory utilization statistics associated with the LFAREA.

For more information, see [Displaying real storage memory statistics in z/OS MVS System Commands](#).

## Request handling for the LFAREA system limit

The system limits the amount of online real storage below 4 TB that can be used to satisfy fixed 1 MB and 2 GB page requests. The system applies this limit differently depending on which of the two syntax forms is used for the LFAREA request. The two syntax forms cannot be combined.

If the LFAREA request is specified using xM, xG, xT, or x% syntax:

- The system limit is calculated as: (80% \* online real storage available at IPL up to 4 TB) minus 2G.
- The value specified by xM, xG, xT, or x% is applied toward the limit, with the percentage calculated as (x% \* online storage available at IPL up to 4 TB) minus 2G.
- If the limit is exceeded, the system rejects the request and prompts for respecification of the LFAREA request.
- Storage above 4 TB is automatically part of the 2 GB large frame area and does not count toward the system limits.

If the LFAREA request is specified using the 1M= or 2G= syntax form:

- The system limit is calculated as: 80% \* ((online real storage available at IPL up to 4 TB) minus 4 GB).
- The system limit is imposed on the sum of the 1 MB and 2 GB pages.
- For the form 1M=(a) and 1M=(a%) and 2G=(a) and 2G=(a%), the value that is specified for a or a% is applied toward the limit, with the percentage value calculated as a% \* ((online storage available at IPL up to 4 TB) minus 4 GB).
- For the form 1M=(a,b) and 1M=(a%,b%) and 2G=(a,b) and 2G=(a%,b%), the value that is specified for b or b% is applied toward the limit, with the percentage value calculated as b% \* ((online storage available at IPL up to 4 TB) minus 4 GB).
- For any percentage request that is by definitively over 80%, the system rejects the request as a specification error and prompt for respecification of LFAREA, regardless of the PROMPT or NOPROMPT specification. The following examples are specification error cases:
  - LFAREA=(1M=81%)
  - LFAREA=(1M=(40%,20%),2G=(41%,20%))
  - LFAREA=(1M=(1,0),2G=80%)
- If either or both of the 1M= or 2G= requests and PROMPT (either explicitly or by default) are specified, and the applicable value or sum of values exceeds the system limit, the system issues a prompt to respecify LFAREA. Otherwise, when NOPROMT is specified, the LFAREA parameter is ignored and the system does not use any real storage to satisfy fixed 1 MB and 2 GB page requests for the life of the IPL.
- For any request containing a target and minimum specification where the target or sum of targets is above the system limit, the system attempts to satisfy the request at or less than the system limit, if the request can be satisfied at or above the minimum values specified.

## Request handling for insufficiently contiguous online real storage

In some cases, the LFAREA request cannot be satisfied even though it does not exceed the system limit. For example, real storage might be configured in such a way that some offline areas are interspersed among online areas, preventing the system from locating enough contiguous storage areas that start on a 2 GB boundary to use for the set of 2 GB pages.

When the LFAREA request is specified using the xM, xG, xT, or x% syntax form:

- For the syntax form xM, xG, and xT, the value that is specified for x is the maximum amount of real storage that can be used to satisfy fixed 1 MB page requests.
- For a percentage request, the amount is calculated as: (percent \* online real storage at IPL up to 4 TB) minus 2 GB
- When calculated, the percentage request is rounded down to the nearest 1 MB boundary.
- If rounding down the percentage request results in zero, the system does not use any real storage to satisfy fixed 1 MB page requests for the life of the IPL.
- If the amount of storage that is required to satisfy the request cannot be located, the request is satisfied at less than the requested amount and the system continues with the IPL.

When the LFAREA request is specified using the 1M= or 2 GB= syntax form:

- For the form 1M=(a) and 1M=(a%) and 2G=(a) and 2G=(a%), the value that is specified for a or a% is both the target and the minimum amount of real storage that the system is used to satisfy fixed 1 MB and 2 GB page requests from below 4 TB.
- For the form 1M=(a,b) and 1M=(a%,b%) and 2G=(a,b) and 2G=(a%,b%), the value that is specified for a or a% is the target amount, and b or b% is the minimum amount of real storage that can be used to satisfy fixed 1 MB and 2 GB page requests.
- For a percentage request, the amount is calculated as: percent \* ((online real storage at IPL up to 4 TB) minus 4G)
- Once calculated, the 1M= or 2G= percentage request is rounded down to the nearest respective 1 MB or 2 GB boundary.
- If rounding down the percentage request results in zero, and PROMPT is specified (either explicitly or by default), the system issues a prompt to respecify LFAREA. Otherwise, when NOPROMPT is specified, the LFAREA parameter is ignored and the system does not use any real storage to satisfy fixed 1 MB and 2 GB page requests for the life of the IPL.
- If the 1M= or 2G= request cannot be satisfied with at least the minimum amount requested, and PROMPT is specified (either explicitly or by default), the system issues a prompt to respecify LFAREA. Otherwise, when NOPROMPT is specified, the LFAREA parameter is ignored and the system does not use any real storage to satisfy fixed 1 MB and 2 GB page requests for the life of the IPL.

**Default Value:** None (No LFAREA is defined)

**Associated Parmlib Member:** None

## LICENSE

`LICENSE={Z/OS} | {ZNALC}`

This parameter specifies whether the system is running with a z/OS or ZNALC license.

**Value range:** Not applicable

**Default:** LICENSE=Z/OS

**Associated parmlib member:** None

## LNK

```
LNK={aa
    {(aa,bb,...[,L])}
    {(,L)}
```

This parameter specifies one or more LNKSTxx parmlib members that list program libraries to be concatenated to SYS1.LINKLIB, thus forming the LNKST concatenation.

The two characters (A-Z, 0-9, @, #, or \$) represented by *aa* (or *bb*, and so on), are appended to LNKST to identify one or more LNKSTxx members of parmlib.

If the L option is specified, the names of the data sets that are concatenated to SYS1.LINKLIB are displayed at the operator's console as the data sets are opened.

For information about the LNKSTxx member, see [Chapter 72, “LNKSTxx \(LNKST concatenation\)”](#) on [page 611](#). You can also use PROGxx to specify the concatenation.

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$).

**Default:** LNK=00, causing selection of LNKST00.

**Associated parmlib member:** LNKSTxx

## LNKAUTH

```
LNKAUTH={LNKST} | {APFTAB}
```

This parameter specifies whether all libraries in the LNKST concatenation are to be treated as APF-authorized when accessed as part of the concatenation, or whether only those libraries that are named in the APF table are to be treated as APF-authorized.

**Value range:** Not applicable

**Default:** LNKST, meaning that all libraries in the LNKST concatenation are to be treated as APF-authorized when accessed as part of the concatenation. If the default for the LNKAUTH system parameter is taken, or is specified in IEASYSxx or by the operator, libraries in the LNKST concatenation are APF-authorized when accessed as part of the LNKST concatenation.

If a LNKST library is not listed in the APF table, referencing the library through a JOBLIB or STEPLIB DD statement causes the library to be considered unauthorized for the duration of the job or step.

**Associated parmlib member:** None

## LOGCLS

```
LOGCLS=x
```

This parameter specifies the JES output class for the log data sets. A log data set is queued to this class when its WTL limit has been reached. (The limit is specified by the LOGLMT initialization parameter.)

**Example:** LOGCLS=L

In this example, the current log data set is queued to output class L when the limit on the number of WTLs has been reached.

If the specified LOGCLS value is not valid, or an I/O error occurs while the IEASYSxx member is being read, master scheduler initialization prompts the operator for a replacement LOGCLS value. If prompting is forbidden (the OPI operand was specified), the default value A is assigned.

The value of LOGCLS is being used as a default output class for the WRITELOG system command.

For the other log parameter, see [“LOGLMT” on page 451](#).

**Value range:** A single alphabetic or numeric character: A-Z or 0-9.



**Default:** A, which represents output class A.

**Associated parmlib member:** None

## LOGLMT

LOGLMT=nnnnnn

This parameter specifies the maximum number of WTLs (messages) allowed for each log data set. The value is used by log processing to determine when a log data set should be scheduled for sysout processing by JES. When the value is reached, log processing issues a simulated WRITELOG command to close and free the current log data set, and to allocate and open a new log data set.

**Example:** LOGLMT=004852

In this example, when 4,852 WTLs have been issued to a log data set, the data set is scheduled for sysout processing on the output class specified by the LOGCLS parameter. Log processing then allocates and opens a new log data set.

If the specified value is not valid or an I/O error occurs while the IEASYSxx member is being read, master scheduler initialization prompts the operator for a replacement LOGLMT value. If prompting is forbidden (the OPI operand was specified), the default value of 500 is assigned.

For the other log parameter, see LOGCLS. [“LOGCLS” on page 450](#)

**Note:** 000000-999999

**Default:** 500

**Associated parmlib member:** None

## LOGREC

LOGREC={*dsname* | LOGSTREAM | LOGSTREAM=*lsname* | IGNORE}

LOGREC specifies the LOGREC recording medium to be used for error and environmental recording. If this parameter is omitted, then SYS1.LOGREC is the default data set name specification.

### Tip:

#### *dsname*

Specifies the name of the LOGREC data set to be used for error recording. In a multisystem environment, if you specify a unique name for each of your LOGREC data sets, IBM suggests that you not place these names in the SYSTEMS exclusion resource name list in parmlib member GRSRNLxx.

Before an IPL, the LOGREC data set must have been allocated, cataloged (unless on the SYSRES) in the system master catalog, and initialized using IFCDIP00. In a multisystem environment, take care in running IFCDIP00 to ensure, if using the SYS1.LOGREC data set name default, that the correct LOGREC data set is initialized.

### LOGSTREAM | LS

Specifies that the LOGREC log stream (SYSPLEX.LOGREC.ALLRECS) is to be used for the error and environmental recording. The log stream provides a single repository for all of the MVS images in a sysplex. The log stream eliminates the need to allocate, catalog, and initialize a LOGREC data set on each system. When reporting programs, such as EREP, are run, the single log stream can be used as input to the program.

### LOGSTREAM=*lsname* | LS=*lsname*

Specifies the name of a log stream resource to which to record LOGREC entries. With this functionality, you can use a log stream other than the default SYSPLEX.LOGREC.ALLRECS.

### IGNORE

Specifies that error and environmental recording are to be ignored. Logrec records are not recorded to the output medium; no records are written to a LOGREC data set or to the LOGREC log

stream. Also, the system does not issue the ENF event code 36 signal for records when IGNORE is specified.



**Attention:** This specification is intended to be used only on test systems when a LOGREC data set is not established and the LOGREC log stream is not defined.

Table 26 on page 452 shows syntax examples of the LOGREC parameter and the results.

| Table 26. Syntax examples for the LOGREC parameter |  |
|--|--|
| Example  | Result   |
| LOGREC=SYSA.LOGREC                                 | The data set SYSA.LOGREC is used.  |
| LOGREC=SYSTEMA.LOGREC                              | The data set SYSTEMA.LOGREC is used.   |
| LOGREC=&SYSNAME..LOGREC                            | Assuming the value that is specified on the SYSNAME= parameter is SYSTEMA, the data set SYSTEMA.LOGREC is used.      |
| LOGREC=LOGSTREAM                                   | The LOGREC log stream, SYSPLEX.LOGREC.ALLRECS, is used by SVC 76 (LOGREC) to record error and environmental records. |
| LOGREC=LS  | SVC 76 (LOGREC) uses the LOGREC log stream SYSPLEX.LOGREC.ALLRECS to record error and environmental records.         |
| LOGREC=LOGSTREAM=LOGREC.TEST1                      | SVC 76 (LOGREC) uses the log stream LOGREC.TEST1 to record error and environmental records.                          |
| LOGREC=LS=LOGREC.TEST1                             | SVC 76 (LOGREC) uses the log stream LOGREC.TEST1 to record error and environmental records.                          |
| LOGREC=IGNORE                                      | No error or environmental recording by SVC 76 will occur.  |

**Value range:** One of the allowable specifications. The values for *dsname* and *lsname* can contain system symbols. When the *dsname* option is used, only one data set can be specified.

**Default:** SYS1.LOGREC

**Associated parmlib member:** When LOGSTREAM is specified, see [Chapter 24, “COUPLExx \(cross-system coupling facility \(XCF\) parameters\),”](#) on page 229.

## LPA

```
LPA={aa
    {(aa,bb,...[,L])}}
```

This parameter specifies one or more LPA<sub>STxx</sub> parmlib members. The two characters (A-Z, 0-9, @, #, or \$), represented by *aa* (or *bb*, and so on), are appended to LPA<sub>LIB</sub> to form the name of the LPA<sub>STxx</sub> members. If the L option is specified, the system displays (at the operator's console) the names of the data sets that were successfully concatenated to SYS1.LPA<sub>LIB</sub>.

The LPA<sub>STxx</sub> members list data sets that are to be concatenated to SYS1.LPA<sub>LIB</sub>. (For information about the use, contents, and syntax of LPA<sub>STxx</sub>, see [Chapter 74, “LPA<sub>STxx</sub> \(LPA library list\),”](#) on page 635.)

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$)

**Default:** None

**Associated parmlib member:** LPA<sub>STxx</sub>

## MAXCAD

MAXCAD=nnn

Reserves the number of entries available for SCOPE=COMMON data spaces on all primary address space access lists (PASN-ALs) in the system. For a description of data spaces, see [z/OS MVS Programming: Extended Addressability Guide](#).

A SCOPE=COMMON data space can be used by all programs in the system. It provides a commonly addressable area similar to the common storage area (CSA). SCOPE=COMMON data spaces are used by MVS and can also be used by subsystems and applications that need common storage.

Each SCOPE=COMMON data space uses one entry on all PASN-ALs in the system. Because the maximum number of entries in a PASN-AL is 510, each SCOPE=COMMON data space your program creates and adds to the PASN-AL, reduces the number of SCOPE=SINGLE and SCOPE=ALL data spaces that a program can address through its PASN-AL.

When you select a value for MAXCAD, you must take into account the number of SCOPE=COMMON data spaces that subsystems, applications, and MVS use.

If you code an incorrect number (less than 10 or greater than 250) the system uses the default number of 50 and issues an informational message.

**Value range:** 10-250

**Default:** 50

**Associated parmlib member:** None

## MAXUSER

MAXUSER=nnnnnn

This parameter specifies a value that, under most conditions, the system uses to limit the number of jobs and started tasks that can run concurrently during a given IPL. The number includes time sharing jobs, batch jobs, started system tasks, the master scheduler, JES2 or JES3. MAXUSER entries can also include ASIDs that have been marked non-reusable if their total number exceeds the RSVNONR value. This parameter is also used to allocate console control block areas in CSA that contain runtime job description data.

This value is extended for started tasks by the value specified for RSVSTRT and is extended by the value that is specified for RSVNONR when non-reusable ASIDs exist.

The MAXUSER value must be large enough to include all the active address spaces running concurrently during a given IPL. Therefore, the value you specify for MAXUSER must take into account the number of initiators, TSO/E USERMAX, available VTAM APPLs and any other factors that contribute to the number of active address spaces.

However, too large a buffer can cause the system to allocate more system resources than are needed during a given IPL. The excessive allocation of system resources because of incorporating too large a buffer can lead to potential problems such as the following examples:

- The specification of MAXUSER with CSCBLOC=BELOW and RSVSTRT can cause the system to allocate excessive storage below 16 M. See [CSCBLOC](#) for more details.
- An aggressively large MAXUSER, RSVSTRT, and RSVNONR can cause the system to allocate an excessive amount of storage, which can potentially lead to a wait state 204 reason 008. (Wait state 204 with reason 008: An error occurred during allocation initialization; the system could not obtain storage for device information.) The system enters a non-restartable wait state 204 at IPL time.

When there are no available MAXUSER ASIDs, the system can use the value that is specified on the RSVSTRT system parameter to allow creation of more started tasks.

When the system is heavily used, it can use the value that is specified on the RSVSTRT system parameter to allow more concurrent jobs and started tasks than the number specified by MAXUSER.

When there are non-reusable ASIDs, it can use the value that is specified on the RSVNONR systems parameter to allow the MAXUSER value to be honored until the number of non-reusable ASIDs exceeds the value of RSVNONR. When this happens, the number of jobs and started tasks that can run concurrently is reduced by the difference between the number of non-reusable ASIDs and the value of RSVNONR.

Assume, for example, that MAXUSER specifies 500 and RSVSTRT specifies 5. If there is an attempt to start an address space (using the START command), and none of the 500 address space entries that are defined by the MAXUSER parameter is available (meaning heavy system use), but an entry that is defined by the RSVSTRT parameter is available, the system uses that entry. Thus, when the system is heavily used, there can be more concurrent jobs and started tasks in the system than the number defined by MAXUSER. The absolute limit to the number of concurrent jobs and started tasks is the sum of the values that are specified for the MAXUSER and RSVSTRT system parameters. The maximum ASID value is the sum of the values that are specified for the MAXUSER, RSVSTRT, and RSVNONR system parameters.

If started tasks or batch jobs that create non-reusable ASIDs end enough times, they will exhaust all available ASIDs and the system will require an IPL. When IPL is not an acceptable option, determine which programs caused the problems and fix them. For methods that prevent running out of ASIDs, see *z/OS MVS Programming: Extended Addressability Guide*.

**Value range:** 0-32767. The sum of the values that are specified for the MAXUSER, RSVSTRT, and RSVNONR system parameters cannot exceed 32767.

**Default:** 255

**Associated parmlib member:** None

## MLPA

```
MLPA={aa                                     }
      {(aa[,L][,NOPROT])                     }
      {(aa,bb...[,L][,NOPROT)]}
```

This parameter specifies one or more IEALPAXx parmlib members, which list modules to be added to the pageable LPA, as a temporary LPA extension.

The two characters (A-Z, 0-9, @, #, or \$) represented by *aa* (or *bb*, and so on), are appended to IEALPA to form the name of the IEALPAXx members. If the L option is specified, the system displays the contents of the IEALPAXx parmlib members at the operator's console as the system processes the members.

The LPA modules in the IEALPAXx parmlib members are page-protected in storage, by default. If an attempt is made to store into a page-protected module, a protection exception occurs. However, the NOPROT option allows an installation to override the page protection default. When NOPROT is specified, the LPA modules in the IEALPAXx parmlib members are not page-protected.

The installation can use the MLPA parameter to temporarily modify an existing LPA at a quick start or a warm start IPL (without creating a new LPA through the CLPA parameter). The added modules are temporary in that they remain as an LPA extension only for the duration of the current IPL. The temporary modules will not be automatically reinstated by a quick start or a warm start IPL. That is, the MLPA parameter must be specified again in the next IPL to reinstate the modified LPA.

If the installation wants to retain the temporary modules as a permanent part of the LPA, it should use the IEBCOPY utility or the linkage editor to place the modules in a data set that is part of the LPALST concatenation, and specify the CLPA and LPA parameters at a future IPL to load the specified LPALST concatenation into the LPA.

For more information about the MLPA option, see IEALPAXx. For information about the fixed LPA option, see the [FIX](#) parameter and [Chapter 49, "IEAFIXxx \(fixed LPA list\)," on page 379](#).

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$), repeated if desired.

**Default:** None If MLPA is not specified, no modified LPA is created.

**Associated parmlib member:** IEALPAxx

## MSTRJCL

```
MSTRJCL=(xx[,L])
```

This parameter specifies the name of the data set that contains the JCL used to start the master scheduler address space and route JCL messages that are issued for master scheduler processing to consoles that receive operator information or system/error maintenance messages. Two alphanumeric characters, represented by xx, are appended to MSTJCL to form the name MSTJCLxx. The system first looks for a MSTJCLxx parmlib member that contains the master JCL. If one exists, the system uses that member. If the MSTJCLxx parmlib member does not exist, the system looks for the MSTJCLxx module in SYS1.LINKLIB.

When MSTRJCL=(xx[,L]) is specified, JCL messages that are issued for master scheduler processing are routed to consoles that receive operator information (routing code 2) or system/error maintenance (routing code 10) messages. Use MSTRJCL=(xx[,L]) only for debugging purposes.

Using the MSTRJCL system parameter allows an installation to test new master scheduler JCL. For example, you can store test JCL in MSTJCL01 and select it by using the MSTRJCL parameter (MSTRJCL=01). For more information, see [“Understanding the master scheduler job control language” on page 9](#).

MSTRJCL can be specified in the default system parameter list (IEASYS00), IEASYSxx members, or entered by the operator in response to the SPECIFY SYSTEM PARAMETERS message. The default value of 00 selects MSTJCL00 when no value is specified for MSTRJCL or if the operator presses the ENTER key in response to a prompt. If MSTJCL00 is not found, the operator is prompted until a MSTJCLxx member can be found. The IPL cannot continue without the JCL needed to start the master scheduler.

**Value range:** Any two alphanumeric characters.

**Default:** MSTRJCL=00, causing selection of MSTJCL00.

**Associated parmlib member:** MSTJCLxx

## NONVIO

```
NONVIO={dsname
        { (dsname1,dsname2,...,dsnameN) }
```

This parameter allows an installation to direct VIO paging away from the specified local page data sets. Specify one or more local page data sets that are not to be used for VIO paging when space is available on other local page data sets. The page data sets that are designated as non-VIO contain only address space pages or free slots. However, if space is depleted on the page data sets that allow VIO paging, the non-VIO page data sets are used for VIO paging. (Using non-VIO page data sets for VIO pages is called an *overflow condition*. The operator is notified if an overflow condition occurs.)

Each dsname that is specified must be a valid name consisting of a maximum of 44 characters whose format is the same as that required for the PAGE system parameter. Each dsname must specify a data set that was specified as a local page data set on the PAGE parameter, either in the IEASYSxx parmlib member or by the operator in response to the “SPECIFY SYSTEM PARAMETERS” prompt.

If you specify a name that the system cannot identify as the name of a local page data set, then the system ignores that name and issues a message to inform the operator that the data set cannot be recognized as a non-VIO page data set. If you omit the NONVIO parameter, then VIO pages are allowed on all local page data sets.

The name of the NONVIO data sets you specify can include the &SYSNAME system symbol. Using the same system symbol syntax with the NONVIO parameter that was used with the PAGE parameter can simplify your system maintenance.

For cold or quick starts a data set's NONVIO designation is not preserved; you must respecify the NONVIO system parameter. If you do not designate a data set as non-VIO on a cold or quick start, you can designate it in the NONVIO system parameter when you do a subsequent warm start; that data set is marked as non-VIO then, and no more VIO pages are sent to it (unless an overflow condition occurs). If the non-VIO paging data set remains on the system long enough, all VIO pages on it will eventually migrate, during the normal course of system operation, to other page data sets used for VIO.

For warm starts, a data set's NONVIO designation is preserved. A warm start preserves journaled VIO data set pages. Therefore, all local page data sets that contain VIO pages are required for a warm start. These required data sets would include non-VIO page data sets to which VIO paging was done because of an overflow condition.

**Note:** During a warm start, a quick start is forced if a local page data set, not specified as NONVIO, is unavailable or unusable, or a non-VIO local page data set that contains VIO pages was removed before all of its VIO pages had migrated to other page data sets used for VIO.

If you specify all local page data sets on the NONVIO data set name list, a message is issued to inform the operator of this condition. VIO pages can be written to all local page data sets. Similarly, if the directed VIO function is turned off via the DVIO parameter in the IEAOPTxx parmlib member, all local page data sets can receive VIO pages. If the directed VIO function is turned on again, then auxiliary storage management directs VIO away from any local page data sets designated as NONVIO. The VIO pages on these data sets will eventually migrate to VIO page data sets.

**Value range:** Any number of data set names can be specified up to the same limit as exists for the PAGE system parameter. The data set names can contain system symbols.

**Default:** None

**Associated parmlib member:** While there is no directly-associated parmlib member you must specify DVIO=YES in the IEAOPTxx parmlib member to activate the directed VIO function; DVIO=NO allows VIO pages to go to any local page data set.

**Note:** DVIO=YES is the default in the IEAOPTxx parmlib member allowing the use of the directed VIO.

## NSYSLX

```
NSYSLX={nn | (nn,mm)}
```

This parameter allows you to specify the number of linkage indexes (LXs) in addition to those in the system function table to be reserved for system LXs. See [z/OS MVS Programming: Extended Addressability Guide](#) for information about system LXs.

If you omit the NSYSLX parameter, the system reserves 165 system LXs. You might need to specify NSYSLX if either of the following conditions is true:

1. Your installation runs applications that request (through the LXRES macro) more than 165 system LXs.
2. An application that owns one or more system LXs fails and is restarted repeatedly. If the application does not reuse its original LX value, the supply is eventually exhausted. This condition requires reloading the initial program to reclaim the system LXs.

The total number of LXs consists of the sum of the non-system LXs, plus the number of LXs in the system function table, plus the value specified in the NSYSLX parameter. The total number of LXs you can have depends on your z/OS release level and hardware level:

- The total number of LXs can be up to 2048 on a system that is running on a processor prior to either a z990 or z890 processor at driver level 55.

- The total number of LXs can exceed 2048, up to a value of 8192 (extended LX support) if the system is running on either a z890 or z990 processor at driver level 55 or above.

***nn***

Specifies the number of LXs up to the value of 2048 to be reserved for system LXs. The value range for *nn* is between 10–512

***mm***

The second value, *mm*, specifies the number of LXs that exceed 2048, up to the value of 8192 (extended LX support) to be reserved for system LXs. To get more than 2048 LXs, your system must support extended LX function. If you specify *mm* on a system that does not support extended LXs, the system will not provide additional LXs above the 2048 limit. The value range for *mm* is between 40–8192.

**Note:** If the value of *nn* is specified but the value of *mm* is not, *mm* will be of the same value as *nn*.

If applications use more than 165 system LXs, specify the NSYSLX value a little higher than the number of system LXs used. If an application that owns one or more system LXs continues to fail, specify the NSYSLX value high enough so that, during processing, enough system LXs are available. This technique means you can put off reloading the initial program to reclaim the system LXs until when it is less disruptive.

**Value range:** 10–512 for *nn*, 40–8192 for *mm*

**Default:** 165 for both *nn* and *mm*

**Associated parmlib member:** None.

## OMVS

```
OMVS={nn      }
      {(nn)   }
      {(nn,mm)}
      {DEFAULT}
```

This parameter specifies the parmlib member or members to use to locate the parmlib statements to configure the kernel.

*nn* specifies the BPXPRMnn parmlib member and *(nn,mm)* specifies the set of parmlib members BPXPRMnn and BPXPRMmm. If you specify more than one parmlib member, any redundant parmlib statement data found in a later member in the list is ignored.

Specifying OMVS=DEFAULT indicates that the kernel is to be started in its minimum configuration mode with all parmlib statements taking their default values.

**Example:**

```
OMVS=(XX,YY,ZZ)
```

You can easily reconfigure a large set of z/OS UNIX system characteristics and keep the reconfiguration settings in a permanent location for subsequent reuse or reference. For more information about setting your parmlib values, see [z/OS UNIX System Services Planning](#).

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$).

**Default:** DEFAULT

**Associated parmlib member:** BPXPRMxx

## OPI

```
OPI={YES} | {NO }
```

This parameter specifies whether the operator is to be allowed to override system parameters that are in IEASYSxx members of parmlib. The YES operand allows operator overrides. The NO operand causes



overrides to be ignored. If, however, NIP detects an incorrect parameter in an IEASYSxx member in which OPI=NO applies, NIP ignores the OPI specification and prompts the operator.

OPI is specified only in an IEASYSxx member; it cannot be specified by the operator.

OPI can be specified either for individual system parameters or for the entire set of parameters.

The following examples show how to modify it.

```
IEASYSAA:  MLPA=(00,01),SQA=(10,OPI=NO)
IEASYSBB:  MLPA=(00,01),SQA=10,OPI=NO
```

For IEASYSAA, the operator can override MLPA values but not the SQA value. For IEASYSBB, however, the operator can override neither MLPA nor SQA values.

When you specify OPI for individual system parameters, you can use system symbols in the specified value. When you specify OPI for the entire set of parameters, do not use system symbols in the specified value.

**Note:** During system initialization, the system first uses the IEASYS00 parmlib member to establish parameters, then uses parameters from the operator or any other IEASYSxx parmlib member (identified by the SYSPARM parameter in the LOADxx parmlib member, the SYSPARM parameter in the IEASYSxx parmlib member, or the SYSP=xx parameter) to replace established parameters or add new ones. The OPI parameter in IEASYS00 carries over to any other IEASYSxx parmlib member identified during the IPL. If you specify OPI=NO in IEASYS00 for an IPL, the parameters that are affected by the OPI=NO cannot be changed by operator command during the IPL. Even if you use another IEASYSxx parmlib member and specify OPI=YES for that SYSP=xx, the operator cannot change any parameters that are affected by OPI=NO in IEASYS00.

In the following IEASYSxx parmlib members, the specification of CSA and SQA in IEASYS00 prevails for the life of the IPL even if the operator uses SYSP=01 to select IEASYS01 for the initialization process:

```
IEASYS00:  CSA=(100,OPI=NO),MLPA=(00,01),SQA=(10,OPI=NO)
IEASYS01:  CSA=(100,OPI=YES),MLPA=(00,01),SQA=10
```

**Value range:** Not applicable

**Default:** YES

**Associated parmlib member:** Not applicable

## OPT

```
OPT={xx          }
    {(xx[,L])    }
    {(,L)        }
```

This parameter specifies a parmlib member that contains the parameters that affect some decisions made by the system resources manager (SRM). The two alphanumeric characters, represented by xx, are appended to IEAOPT to form the name of the IEAOPTxx member. If the L option is specified, the system displays the contents of the IEAOPTxx parmlib member at the operator's console as the system processes the member.

If the member cannot be found or contains incorrect specifications, SRM prompts the operator to specify an alternate member by respecifying OPT=xx. If the operator cancels the parameter by replying with the ENTER key, SRM uses default values.

The operator can select a new OPT (that is, indicate that the system is to run under the control of an alternate IEAOPTxx member) between IPLs by issuing the SET OPT command.

**Value range:** Any two alphanumeric characters

**Default value:** None If OPT is not specified, SRM uses default values. (See *z/OS MVS Initialization and Tuning Guide* for the default values.)



**Associated parmlib member:** IEAOPTxx

## OSPROTECT

**OSPROTECT={SYSTEM|1|MIN}**

The OSPROTECT parameter specifies the operating system mitigation mode for unauthorized programs and users.

The operating system provides controls that are intended to help prevent unauthorized programs and users from being able to access restricted data by using conventional means. Malicious or compromised unauthorized programs and users may use a security exploit to try to circumvent these controls and access restricted data. A mitigation mode determines the extent of the security mitigation. The operating system supports the following mitigation modes:

### SYSTEM

Specifying SYSTEM as of z/OS V3R1 activates mitigation mode 1 unless you are using an IBM System z® Personal Development Tool (zPDT®) emulation system; otherwise, it activates mitigation mode MIN.

### 1

Specifying the number 1 activates mitigation mode 1, intended to help prevent unauthorized programs and users from being able to indirectly read restricted data. Mitigation mode 1 also includes MIN mitigation mode (see MIN). Mitigation mode 1 may have a minor impact to system performance, workload execution, or both.

### MIN

Specifying MIN uses the mitigation mode that is intended to help prevent unauthorized programs and users from accessing restricted data by using conventional means. This matches the mitigation mode identified by SYSTEM before z/OS V3R1.

**Value range:** Not applicable.

**Default:** SYSTEM.

**Associated parmlib member:** None.

## PAGE

**PAGE={dsname|\*NONE\*  
{(dsname1|\*NONE\*)[,dsname2|\*NONE\*,[dsname3,...[,L]]}  
{(,L)}**

This parameter allows the installation to name page data sets as additions to existing page data sets. The maximum number of page data sets is 256. The system determines which page data sets to use by merging information from three sources: IEASYS00, IEASYSxx, and the PAGE parameter.

During system initialization, the system first uses the list of page data sets specified on the PAGE parameter of the IEASYS00 parmlib member. It then uses any other IEASYSxx parmlib member (identified via the SYSP=xx parameter). The IEASYSxx PAGE data set name list overrides the one in IEASYS00.

PAGE=dsname and PAGE=(dsname1,dsname2,...[,L]) allow the operator to add page data sets to the list of data sets already specified in IEASYSxx. If the PAGE data set name list in IEASYSxx is null, the operator specification is used.

The system generates a list of all the page data sets that the initialization routines have opened. If the L keyword is specified (either in parmlib or from the operator's console) this list is, then written to the operator's console and to syslog. If the L keyword is not specified, the list is written only to the syslog.

The system interprets the final merged sequence of page data set names that are specified as follows:

- The first named data set on the list is used as the PLPA page data set. This data set contains pageable link pack area (PLPA) pages. If \*NONE\* is specified, no PLPA page data set is used and no quick or warm starts can be performed. \*NONE\* can only be used when Storage Class Memory (SCM) is online and used for paging (refer to “PAGESCM” on page 462).

- The second named data set in the list is used as the common page data set. This data set contains all of the common area pages that are not PLPA pages. If \*NONE\* is specified, no common area page data set is used. \*NONE\* can only be used when Storage Class Memory (SCM) is online and used for paging (refer to “PAGE<sub>SCM</sub>” on page 462).
- The third and all subsequently named data sets are used as local page data sets. These data sets contain all the system pages (including VIO pages) that are considered neither PLPA nor common data set pages.

**Note:** To replace local page data sets during an IPL, you must specify the CVIO parameter. (Note that CLPA implies CVIO.)

If Storage Class Memory (SCM) is online and used for paging (refer to “PAGE<sub>SCM</sub>” on page 462), SCM will be used for all page types, in addition to the page data sets specified by the PAGE= parameter.

When defining page data sets, you must ensure that the desired PLPA page data set is the first entry in the data set list, in both IEASYS00 and IEASYSxx.

During initialization, there are no checks on the sizes of user-supplied data sets. When initialization completes, the PAGEADD command can be used to add more local page data sets to the system. The most current page data set information is preserved so that it can be used for subsequent quick start and warm start IPLs.

The data set intended for PLPA should contain enough space for the entire PLPA, including the extended PLPA. If the entire PLPA cannot fit on this data set, the system puts the excess on the common page data set. And, if the common page data set gets full, its excess goes to the PLPA page data set. In the interest of good performance, however, you should make the common page data set big enough to prevent its “spilling over” to the PLPA page data set (except in cases forced by error situations). Finally, if both SCM and the PLPA and common data sets are full (or have \*NONE\* specified) then the system puts the excess on the local page data sets. Spilling PLPA into local page data sets results in the failure of subsequent warm and quick starts. For specific data set size and placement recommendations, see [z/OS MVS Initialization and Tuning Guide](#).

**How page data sets are specified:** Page data sets are specified by a merging of information from three sources: 1) IEASYSxx; 2) operator-issued PAGE parameter; and 3) the page data sets from a previous cold start. The system merges this information as follows:

- From the PAGE parameter in IEASYSxx (an alternate system list):
- From the PAGE parameter that is specified by the operator in the current IPL: The system merges this page specification with that in either IEASYS00 or IEASYSxx, but not both. The operator specification of page data sets lasts until the next cold or quick start.
- The page data sets previously in use: The system uses information about quick starts and warm starts (IPLs that do not specify the CLPA parameter). If a non-demountable device (such as a 3350) is used for the IPL, the device must be online before the IPL.

**Note:** Two other conditions are prerequisite for certain warm start or quick start situations:

1. The local page data sets that contain VIO pages from the previous IPL must be mounted for *all* warm starts, to make VIO slots available. Otherwise, ASM forces a quick start instead.
2. The common page data set from the previous IPL must be mounted for *both* quick starts and warm starts if the system's writing of the PLPA (and extended PLPA) to the PLPA page data set during the previous cold start resulted in spilling some of the PLPA pages into the common page data set.

Usually, page data sets specified by any means must have been allocated, cataloged in the system's master catalog, and preformatted in VSAM format before an IPL can start. You can format the data sets by using the DEFINE PAGESPACE command of access method services (for information about the formatting process, see [z/OS DFSMS Access Method Services Commands](#)).



**Attention:** Do not change or swap the names of systems in the sysplex when using page data set names containing system symbols. If name changes are required, each system in the sysplex must have a cold start IPL.

**Syntax examples for the PAGE parameter:** Table 27 on page 461 shows syntax examples of the PAGE parameter and the results they produce.

| Table 27. Syntax examples for the PAGE parameter |   |
|--|---|
| Syntax   | Result  |
| PAGE=dsname<br>PAGE=(dsname)                     | Statements each specify one page data set.  |
| PAGE=(dsname1,dsname2,dsname3)                   | Specifies three page data sets; dsname1 holds the PLPA pages, dsname2 holds the common pages, and dsname3 holds the private area pages.                   |
| PAGE=(dsname1,dsname2,...,dsnamen)               | Specifies <i>n</i> page data sets; dsname1 holds the PLPA pages, dsname2 holds the common pages, and dsname3 through dsnamen all hold private area pages. |

The following statement specifies only one page data set:

```
PAGE=(*NONE*,*NONE*,dsname1)
```

Storage-class memory (SCM) holds all page types.

**Note:**

1. If the operator specifies the PAGE parameter, ASM initialization adds (but does not replace) the data sets as specified. The PAGE data set name list in IEASYS00 or IEASYSxx contains the first named data sets. To ensure that the operator-specified data sets are used for the PLPA and common page data sets, it is necessary to use an IEASYSxx member that contains a null PAGE parameter; one that does not specify page data sets.
2. It is unnecessary to specify either UNIT or VOLSER because all page data sets must be cataloged in the system's master catalog. ASM initialization therefore does not need externally specified volume serial numbers. The operator can either pre-mount volumes or await a mount message.

**Minimum paging space:** ASM enforces minimum requirements for paging space. If the requirements are not satisfied, ASM is forced to end the IPL. Additionally, the use of minimum paging space is inadvisable because it can result in poor performance.

Minimum requirements are as follows:

- There must be at least a PLPA, a common, and a local page data set to IPL the system. However, \*NONE\* can be used in place of PLPA and common area page data sets when SCM is used for paging (refer to “PAGEscm” on page 462 for details).
- The PLPA and common page data sets must be able to hold the total combination of PLPA and common pages (excluding the SQA). If no errors occur, the auxiliary storage space for the PLPA and common page data sets is sufficient if the space equals the size of the PLPA and CSA divided between the two data sets.

If the PLPA and common page data sets spill back and forth because the space is not properly divided between the data sets, performance degradation can result. Severe performance degradation can result if the common page data set is not large enough and, therefore, spills to the PLPA page data set, which is normally read-only after IPL.

- Local page data sets are used to hold all private area and VIO pages. The amount of storage necessary varies with each system and can be calculated using the guidelines in *z/OS MVS Initialization and Tuning Guide*.

**Page space shortage:** Two warning messages appear when the system resources manager (SRM) detects a shortage of page space, the first when 70% of the available local paging space including SCM, if any has been allocated, and the second when 85% has been allocated. SRM reacts to the situation by preventing the creation of new address spaces. That is, new “start initiator” commands (\$SInn), LOGONs, MOUNT commands, and START commands for system tasks that run in their own address spaces do not work. Upon receipt of these messages, you can add paging space to the system dynamically by using

the CONFIG SCM,ONLINE or the PAGEADD operator command. For information about using PAGEADD or CONFIG, and for related information about using the PAGTOTL parameter, refer to *z/OS MVS System Commands*. For these situations, it is valuable to have preformatted, cataloged VSAM paging data sets or offline SCM available. The data sets can be formatted by using the DEFINE PAGESPACE processor of access method services; for more information, refer to *z/OS DFSMS Access Method Services Commands*.

When the page space usage has been decreased below 70% utilization, SRM informs the operator that there is no longer a shortage.

**Value range:** The total number of data sets specified must not exceed the combined limit for page data sets on the PAGTOTL= parameter. The data sets can contain system symbols.

**Default:** None

**Associated parmlib member:** None

**Note:** During NIP processing, the system might exhaust SQA and extended SQA if many local paging data sets were specified on the PAGE parameter. If this condition occurs, the value that is specified for the SQA parameter might be set too low. You can increase the SQA value in IEASYSxx.

## PAGESCM

```
PAGESCM={xxxxxxM
          {xxxxxxG
          {xxT
          {ALL
          {NONE
          {0
```

This parameter specifies the minimum amount of Storage Class Memory (SCM) that should be made available for use as auxiliary storage. The system reserves this amount of SCM during IPL for subsequent use as auxiliary storage. Additional SCM will be allocated on an as-needed basis if use of this initial amount of SCM is exceeded.

**Value range:** The following value ranges can be specified for the PAGESCM parameter to reserve SCM for paging at IPL:

### 0 | OM | OG | OT

Indicates that no SCM will be reserved for paging at IPL. Instead, SCM will be allocated as needed, based on paging demand.

### xxxxxxM

Specifies the amount of SCM to reserve for paging at IPL, in megabytes. This value can be from 1–6 decimal digits.

### xxxxxxG

Specifies the amount of SCM to reserve for paging at IPL, in gigabytes. This value can be from 1–6 decimal digits.

### xxT

Specifies the amount of SCM to reserve for paging at IPL, in terabytes. This value can be from 1–2 decimal digits. The maximum amount of SCM supported for paging is 16 terabytes (16 T).

### NONE

SCM is not used for paging. This parameter remains in effect until the next IPL.

### ALL

Reserves all SCM for paging at IPL.

**Default:** ALL

**Associated parmlib member:** None

## PAGTOTL

```
PAGTOTL
```

This parameter allows you to specify the total number of page data sets available to the system. The value that you specify for *ppp* is valid for the life of the IPL. You must include the following in the *ppp* value:

- APLPA page data set.
- A common page data set.
- A permanently reserved slot.
- A local page data set. You must have at least one local page data set to IPL or a WAIT03C will occur.

Therefore, the minimum *ppp* value that is required to IPL is 4. In addition, *ppp* should include any page data sets that can be dynamically added after IPL.

You can add page data sets by using the PAGEADD operator command until the total number reaches the value that is specified on the PAGTOTL parameter. However, if you try to exceed the limits set on the PAGTOTL parameter, the system truncates the excess specification.

The system supports a maximum of 256 page data sets (including 1 required page data set, a PLPA page data set, a common page data set, a reserved slot, and up to 252 additional local page data sets).

The system reserves ESQA space for each page data set that can be defined. Additional ESQA is required for each page data set that is in use by the system. The amount of additional storage depends on the size of every in-use page data set.

**How page number values are obtained:** The PAGTOTL parameter is specified in one of two sources: 1) IEASYS00 or IEASYSxx, or 2) by the operator-issued PAGTOTL parameter. An outline of these specifications is as follows:

- The PAGTOTL parameter in IEASYS00.
- The PAGTOTL parameter in IEASYSxx, an alternate system parameter list: If the operator selects this list (by using the SYSP parameter), the PAGTOTL parameter in IEASYSxx overrides the PAGTOTL parameter in IEASYS00.
- The PAGTOTL parameter that is specified by the operator in the current IPL: This PAGTOTL specification overrides the specification in IEASYS00 or IEASYSxx. The operator specification lasts only for the life of the IPL.
- If the number of page data sets specified on the PAGE parameter exceeds the PAGTOTL value, the PAGTOTL value is dynamically increased at IPL. A message is issued if this occurs.

**Syntax examples for the PAGTOTL parameter:** This specification causes the system to allow for the total of page data sets (*ppp*).

```
PAGTOTL=(ppp)
```

**Value range:** Valid *ppp* values are 0-256. This value is the maximum allowable number of page data sets that can be in use in the paging configuration at a time. Three spaces are reserved for IBM use (for the PLPA and common data sets, and one additional space). Therefore, the maximum number of local page data sets is 253.

**Default:** 40

**Note:** Even if the PLPA and Common page data sets are not defined in the system, the system will still reserve two spaces for them.

**Associated parmlib member:** None

**Note:** Swap data sets are no longer supported. If your PAGTOTL parameter is coded to include the number of swap data sets. In other words, if you are using the syntax PAGTOTL=(ppp,sss), the system generates informational message IEA051I during IPL to indicate that the swap parameter will be ignored.

## PAK

```
PAK={aa
    {(aa,bb,...[,L])}
    {(,L)}
```

This parameter specifies one or more IEAPAKxx parmlib members that contain groups of names of modules in the LPALST concatenation that are processed together or in sequence. The two characters (A-Z, 0-9, @, #, or \$), represented by *aa* (or *bb*, and so on), are appended to IEAPAK to form the name of the IEAPAKxx members. If the L option is specified, the system displays the contents of the parmlib members at the operator's console when the system processes the members.

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$).

**Default:** PAK=00, causing selection of IEAPAK00, if it exists.

**Associated parmlib member:** IEAPAKxx

## PLEXCFG

```
PLEXCFG={XCFLOCAL
        {MONOPLEX
        {MULTISYSTEM
        {ANY}
```

Specifies the type of configuration into which the system is allowed to IPL. You can specify one or more of the following system configurations:

### PLEXCFG=MULTISYSTEM

Specifies that the system is to be part of a sysplex consisting of one or more MVS systems that reside on one or more processors. The same sysplex couple data sets must be used by all systems.

You must specify a COUPLExx parmlib member that identifies the same sysplex couple data sets for all systems in the sysplex (on the COUPLE statement) and signaling paths between systems (on the PATHIN and PATHOUT statements). You must also specify in the CLOCKxx parmlib member whether you are using a Sysplex Timer that is real (ETRMODE=YES) or simulated (SIMETRID=YES).

Use MULTISYSTEM when you plan to IPL two or more MVS systems into a multi-system sysplex and exploit full XCF coupling services. GRS=NONE is not valid with PLEXCFG=MULTISYSTEM.

### PLEXCFG=XCFLOCAL

Specifies that the system is to be a single, stand-alone MVS system that is not a member of a sysplex and cannot use couple data sets. The COUPLExx parmlib member cannot specify a sysplex couple data set, and, therefore, other couple data sets cannot be used. Thus, functions such as using System Logger to write data to log streams, which require a couple data set, are not available.

In XCF-local mode, XCF does not provide signaling services between MVS systems. However, multi-system applications can create groups and members, and messages can flow between group members on this system. If signaling paths are specified, they are tested for their operational ability, but they are not used.

Use XCF-local mode for a system that is independent of other systems. In XCF-local mode, XCF services (except permanent status recording) are available on the system and you can do maintenance, such as formatting a couple data set or changing the COUPLExx parmlib member. The IBM-supplied default parmlib member COUPLE00 and the COUPLE=\*\* system parameter are intended to be used to bring up the system in XCF-local mode.

### PLEXCFG=MONOPLEX

Specifies that the system is to be a single-system sysplex that must use a sysplex couple data set. Additional couple data sets, such as those that contain policy information, can also be used. XCF coupling services are available on the system, and multi-system applications can create groups

and members. Messages can flow between members on this system (but not between this system and other MVS systems) through XCF signaling services. If signaling paths are specified, they are not used.

You must specify a COUPLExx parmlib member that gives the system access to a sysplex couple data set to be used only by this system. When a system IPLs into a single-system sysplex, no other system is allowed to join the sysplex.

Use MONOPLEX when you want only one system in the sysplex (for example, to test multi-system applications on one system) or when you want to use a function, such as WLM, that requires a couple data set.

#### **PLEXCFG=ANY**

Specifies that the system can be part of any valid system configuration. Specifying ANY is logically equivalent to specifying XCFLOCAL, MONOPLEX, or MULTISYSTEM. ANY is the default.

Generally avoid specifying PLEXCFG=ANY and explicitly specify the sysplex environment that you intend for the system to join. See *z/OS MVS Setting Up a Sysplex* for additional information about the PLEXCFG parameter and planning for XCF-local mode.

To prevent the operator from overriding the PLEXCFG parameter, specify OPI=NO on the PLEXCFG keyword in the IEASYSxx parmlib member. (For example, PLEXCFG=MULTISYSTEM,OPI=NO).

**Default:** PLEXCFG=ANY

**Associated parmlib member:** None

## **PRESCPU**

### **PRESCPU**

This parameter causes system initialization CPU processing to bring logically online those CPUs (and only those CPUs) that are physically online when the IPL is initiated, without regard to the number of CPUs defined to be initially online in the logical partition profile.

The purpose is to ensure that all CPUs that are online when an IPL is initiated are online when the IPL completes.

CPUs that are offline when an IPL is initiated remains offline. You might not want to use PRESCPU when WLM CPU management is active because that processing might be configured CPUs offline.

If PRESCPU is not coded, CPU initialization takes CPUs offline or brings CPUs online as needed to make the number of online CPUs equal to the number of initial CPUs defined for the partition, when that information is provided by the machine (as it should be on model 2064 (GA-3), model 2066, and later machines) and is not 0.

If the number of initial CPUs is not provided or is 0, CPU initialization attempts to bring online all CPUs that are physically online. On most models, those are the CPUs that were online just before the IPL was initiated. However, models 2064 and 2066 can configure additional CPUs online when an IPL is initiated, and CPU initialization also brings those CPUs online.

For information about how PRESCPU interacts with BOOST, see [Interaction of Shutdown Boost and PRESCPU in System Recovery Boost](#).

**Value range:** Not applicable

**Default:** Not applicable

**Associated parmlib member:** None

## **PROD**

```
PROD={aa
      {(aa,bb... )}}
```

The two characters (A-Z, 0-9, @, #, or \$), represented by *xx*, are appended to IFAPRD to specify the name of one or more IFAPRDxx members of parmlib. You can specify one or more members, which define the product enablement policy for the system.

The specified IFAPRDxx parmlib members must exist. The system processes the members in the order in which you specify them, stopping if it encounters any parmlib member that does not exist.

**Value range:** Any two alphanumeric characters

**Default:** None

**Associated parmlib member:** IFAPRDxx

## PROG

```
PROG={aa
      {(aa,bb,...)}
```

This parameter specifies the PROGxx members of parmlib. The two characters (A-Z, 0-9, @, #, or \$), represented by *aa* (or *bb*, and so on), are appended to PROG to form the names of the PROGxx members. The PROGxx parmlib member contains four statement types: APF, EXIT, SYSLIB, and LNKST.

- APF statements list the names and volume serial identifiers for APF-authorized libraries, and specify the format of the APF list, which is dynamic or static.
- EXIT statements control the use of exits and exit routines.
- SYSLIB statements define alternate data sets for SYS1.LINKLIB, SYS1.MIGLIB, and SYS1.CSSLIB at the beginning of the LNKST concatenation and an alternate data set for SYS1.LPALIB at the beginning of the LPALST concatenation.
- LNKST statements control the definition and activation of the LNKST set that forms the LNKST concatenation.

Use the PROG=xx rather than the APF=xx system parameter, which indicates the current IEAAPFxx parmlib member. IEAAPFxx can also be used to define the APF list, but only in a static format. If you specify both the PROG=xx and the APF=xx parameters, then the system places into the APF list the libraries listed in IEAAPFxx, followed by the libraries listed in the PROGxx member or members. IBM suggests that you convert IEAAPFxx to PROGxx (using a procedure described in [Chapter 43, “IEAAPFxx \(authorized program facility list\),” on page 361](#)), remove the APF=xx system parameter from IEASYSxx, and remove APF=xx from IEASYS00.

Use PROG=xx rather than the EXIT=xx system parameter, which indicates the current EXITxx parmlib member. EXITxx can also be used to specify exits, but you can specify only one exit routine at a time for each exit. IBM suggests that you convert EXITxx to PROGxx (using the IEFEXPR REXX exec provided by IBM), remove the EXIT=xx system parameter from IEASYSxx, and remove EXIT= from IEASYS00.

Use PROG=xx rather than LNK=xx to activate the LNKST concatenation at IPL. In the PROGxx member, you can also define alternate data sets for the system defaults to appear at the beginning of the LNKST and LPALST concatenations. If you specify both PROG=xx for a member with an LNKST ACTIVATE statement and LNK=xx the system uses the definitions in PROGxx and issues message CSV478I:

```
LNK IPL PARAMETER HAS BEEN IGNORED.
LNKST SET lnk1stname IS BEING USED
```

**Value range:** Any two characters (A-Z, 0-9, @, #, or \$).

**Default:** If PROG=xx and APF=xx are not specified, the system automatically places SYS1.LINKLIB and SYS1.SVCLIB in the APF list. If the default for the LNKAUTH system parameter (LNKAUTH=LNKST) is accepted or specified, libraries in the LNKST concatenation are also authorized (when they are accessed as part of the LNKST concatenation). If a library is in the LNKST



concatenation but is not APF-authorized, the system will consider the library to be unauthorized for the duration of the job or step if the library is referred to through a JOBLIB or STEPLIB DD statement.

In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

If PROG=xx is not specified, the system uses LNK=xx for the LNKLIST concatenation.

**Associated parmlib member:** PROGxx

## RACF

```
RACF={aa      }
      {(aa,bb) }
      {(aa,bb,cc)}
```

The IRRPRMxx parmlib member contains data for the RACF data set name table, range table, and sysplex communications options. Use an IRRPRMxx member to specify statements that describe the RACF data set name table and the range table, that were previously defined by ICHRDSNT and ICHRRNG.

For the data set name table, the statements include the primary and backup data set name, update backup options, and resident index blocks.

Sysplex communication options can also be specified in the parmlib member.

Each individual section can be in its own parmlib member, however, no section can be split between multiple members. A maximum of 3 parmlib members can be specified.

For complete information about the IRRPRMxx parmlib member, including syntax and parameters, see [Specifying RACF database options in z/OS Security Server RACF System Programmer's Guide](#).

## RDE

```
RDE={YES}|{NO }
```

This parameter specifies whether the reliability data extractor (RDE) feature is to be included (YES) or not (NO). For information about RDE, see [z/OS MVS Diagnosis: Tools and Service Aids](#).

**Default range:** Not applicable.

**Default :** NO. This default applies if you omit the RDE parameter, or specify an incorrect value for it.

**Associated parmlib member:** None

## REAL

```
REAL=nnnn
```

This parameter specifies the maximum amount of central storage, in 1 KB blocks, that can be allocated concurrently for ADDRSPC=REAL jobs (that is, V=R jobs). The value is rounded to a multiple of 4 KB.

**Syntax example:** REAL=150 150/4=37.5 pages. Rounding to the next page boundary yields 38 pages, or a value of 152 K. This statement allows up to 152 K (152 x 1024) bytes to be allocated for use by V=R jobs.

1. If possible, avoid a large value for the REAL parameter because a large value degrades system performance even when no REAL regions are allocated.
2. The system allocates virtual equals real (V=R) regions upon request by those programs that cannot tolerate dynamic relocation. Jobsteps can request to run in a V=R region by using the ADDRSPC=REAL keyword on the EXEC or JOB statement. If you are sure you have no requirement for running V=R jobs, then specifying REAL=0 will disallow the use of ADDRSPC=REAL on any JCL.

3. In order to eliminate the impact of transition swaps, set REAL=0 and RSU=0 if you have no requirement for reconfiguring storage and no need to run a V=R job.

**Value range:** 0-9999. The operand can be from one to four digits.

**Default:** 0.

**Associated parmlib member:** None

## RER

**RER={YES} | {NO}**

This parameter specifies whether the reduced error recovery (RER) procedures for magnetic tapes are to be used (YES) or not (NO). This parameter has meaning only when the procedures are stated on the OPTCD parameter on a data definition (DD) statement or on the DCB macro.

**Value range:** Not applicable

**Default:** NO. This default applies if you omit the RER parameter, or specify an incorrect value for it.

**Associated parmlib member:** None

## RSM

**RSM={aa }  
{(aa,bb,...)}**

The RSM parameter identifies the IARPRMxx parmlib members that specify Real Storage Manager options. The two alphanumeric characters are appended to IARPRM to form the name of the IARPRMxx member of SYS1.PARMLIB. Syntax RSM=aa specifies a single member and syntax RSM=(aa,bb,...) specifies groups of RSM initialization statements across several IARPRMxx members. If the same IARPRMxx parameter is specified in multiple members, the last occurrence takes precedence.

**Value range:** Any two alphanumeric characters.

**Default:** NONE.

**Associated parmlib member:** IARPRMxx

## RSU

**RSU=xxxx**

```
RSU={xxxx      }
    {OFFLINE    }
    {xx%        }
    {xxxxxxxxM   }
    {xxxxxxxxG   }
    {xxxxxxxxT   }
```

This parameter specifies the amount of central storage to be made available for storage reconfiguration. The frames in these storage increments are not to be used for long-term pages and are designated the nonpreferred area. (Long-term pages include SQA pages, common area fixed pages, and LSQA or private area fixed pages associated with nonswappable address spaces.)

An address space is nonswappable:

- If the program name is in the program properties table (PPT) and the appropriate flags are set. (For more information about the PPT, see [Chapter 82, “SCHEDxx \(PPT, master trace table, and abend codes for automatic restart\),” on page 713.](#))
- If ADDRSPC=REAL is specified on the JOB or EXEC statement.

- If the address space issues the TRANSWAP sysevent. The DONTSWAP and HOLD sysevents also make an address space nonswappable, but these specifications are considered to be of short duration, and associated LSQA and private area pages are not necessarily put into preferred storage.

During IPL, MVS assigns the V=R area to the low end of storage and assigns the current SQA to the high end of storage. Then, to satisfy an RSU specification, the system can define reconfigurable storage increments, starting with the first auxiliary storage increment at the low end of storage and proceeding upward. If the system cannot satisfy the request from auxiliary storage, it proceeds to define reconfigurable storage increments with the online storage increments. The system starts with the first online storage increment at the high end of storage and proceeds downward, defining reconfigurable storage increments by using only those online storage increments that do not contain V=R, SQA, LSQA, or nucleus frames.

After the system is defined the reconfigurable storage increments, it defines the remainder of the processor storage increments as the preferred area for long-term pages.

For systems with more than 4 TB processor storage, reconfiguration of storage is disabled and the RSU parameter is ignored. No storage is reconfigurable.

#### Value range:

##### 0

If your processor complex is not using PR/SM, or if your processor complex is using PR/SM but you are not using dynamic storage reconfiguration, set the RSU parameter to 0 (the default).

Values from 1–9999 are supported, but it is recommended that you either use the megabyte, gigabyte, or terabyte format that is described below, or use RSU=OFFLINE.

If you specify a value of 1-9999 without a qualifier (M, G, T, or %), the value is considered to be the number of the units, and the default storage increment size is used. For example, if your machine has a storage increment size of 64 megabytes, specifying 20 causes 20 units of 64M (1.25G in total) to be set aside for storage reconfiguration. Note that the storage increment size is entirely hardware-dependent, based not only on the hardware model, but possibly also on the amount of real storage installed on the physical machine (not the LPAR). Therefore, using an unqualified value of 1-9999 might have unexpected results because its meaning can change dramatically with a simple upgrade to the amount of real storage on the system.

##### xxxxxxM

Specifies the RSU value in megabytes of storage. You can specify a six-digit value in z/Architecture mode. The value that you specify might be rounded up. See *PR/SM Planning Guide* for specific information.

##### xxxxxxG

Specifies the RSU value in gigabytes of storage. You can specify a six-digit value in z/Architecture mode. The value that you specify might be rounded up. See *PR/SM Planning Guide* for specific information.

##### xxxxxxT

Specifies the RSU value in terabytes of storage. You can specify a six-digit value in z/Architecture mode. The value that you specify might be rounded up. See *PR/SM Planning Guide* for specific information.

##### OFFLINE

Indicates that all of the offline storage increments that are not part of Dedicated Memory are to be made reconfigurable.

##### xx%

Indicates that the RSU is specified as a percentage of all storage, both online and offline. The actual number of storage increments that become reconfigurable are rounded up to a whole number of storage increments.

#### Note:

1. An uncorrectable storage error might prevent you from reconfiguring the processor. If this happens, specify an extra storage increment (on the RSU parameter), at the next IPL, to increase the chance that reconfiguration might work.
2. To eliminate the impact of transition swaps, set REAL=0 and RSU=0 if you have no requirement for reconfiguring storage and no need to run a V=R job.

If you specify an RSU value that the system cannot fully satisfy, the system defines as many reconfigurable storage increments as possible, and issues message IAR004I to indicate that the RSU parameter was not satisfied. The operator can then issue the display matrix (D M) command to determine how many increments were made available for reconfiguration.

However, if you specify an RSU value that is greater than the total amount of real storage available on the system, message IAR026I is issued by the system during IPL indicating an RSU over-specification condition and showing the amount of real storage available on the system. This message is followed by an IAR006A message prompting for a valid RSU value. You must select the right RSU value for the system. A large RSU value can ultimately cause system performance problems and degradation.

For information about how to choose the correct RSU value, see RSU Parameter Specification section and Specifying the RSU parameter section in [z/OS MVS System Commands](#).

#### **Syntax examples for the RSU parameter: :**

1. RSU=0. Indicates that you are not using PR/SM, or that you are not using dynamic storage reconfiguration.
2. RSU=25%. This example requests that 25 percent of all storage, including online and offline, be made available for storage reconfiguration.
3. RSU=300M. This example requests that 300 megabytes of storage be made available for storage reconfiguration.

**Default:** 0. If the RSU parameter is omitted or specified as 0, all processor storage increments are available for preferred storage.

**Associated parmlib member:** None

## **RSVNONR**

RSVNONR=nnnnnn

This parameter specifies the number of entries in the address space vector table that are to be reserved for replacing entries that are marked non-reusable. RSVNONR entries are used to keep the number of entries specified by MAXUSER and RSVSTRT at their specified levels. If RSVNONR entries are not available, an address space that is marked non-reusable will result in the total number of available address spaces being depleted.

A non-reusable address space is one where a job that ended had been running in a cross memory environment. When such a job ends, the system ends the address space and marks its associated ASVT entry non-reusable (unavailable) until all of the address spaces the job had cross memory binds with have ended.

The value you choose for RSVNONR depends on what subsystems you are running, how often you restart the subsystems, and how often you IPL. The more subsystems you have, the higher the RSVNONR value must be. Frequent restarts of subsystems also require a higher RSVNONR value. Conversely, the more often you IPL, the lower the RSVNONR value needs to be. The ASIDs are reset each time you IPL. If you IPL frequently you are less likely to exhaust the available ASIDs, and you need not reserve as many entries in the address space vector table. For example, if you IPL once every three months, you need a RSVNONR value that is three times higher than if you IPL every month.

However, too large a buffer can cause the system to allocate more system resources than are needed during a given IPL. The excessive allocation of system resources because of incorporating too large a buffer can lead to potential problems such as the following examples:

- An aggressively large RSVNONR value could cause a wait state 040 to occur at IPL time. Wait state 040 means the system abended a task during nucleus initialization program (NIP) processing.
- An aggressively large MAXUSER, RSVSTRT, and RSVNONR can cause the system to allocate an excessive amount of storage, which can potentially lead to a wait state 204 reason 008 at IPL time. (Wait state 204 with reason 008: An error occurred during allocation initialization; the system could not obtain storage for device information.)

If started tasks or batch jobs that create non-reusable ASIDs end enough times, they will exhaust all available ASIDs and an IPL will be required. When loading the initial program is not an acceptable option, determine which programs caused the problems and fix them. For methods that prevent running out of ASIDs, see [z/OS MVS Programming: Extended Addressability Guide](#).

**Value range:** 0-32767. Note that the sum of the values specified for the RSVNONR, RSVSTRT, and MAXUSER system parameters cannot exceed 32767.

**Default:** 100

**Associated parmlib member:** None

## RSVSTRT

RSVSTRT=nnnnnn

This parameter specifies the number of entries in the address space vector table (ASVT) that are to be reserved for address spaces created in response to a START command (such as an initiator, the APPC address space or the library lookaside address space). The RSVSTRT entries are only used after the number of entries specified by MAXUSER is obtained. It is not recommended to depend on using the RSVSTRT entries under normal operating conditions. By reserving RSVSTRT entries in the ASVT for such address spaces, you can often avoid having to reinitialize the system because there is no available entry in the ASVT for a critical address space. For example, if library lookaside (LLA) ends and you issue a START LLA command to restart LLA, but no ASVT entry is available, LLA does not be restarted. However, if there are reserved entries for critical address spaces (such as LLA), it is more probable that an entry will be available and the LLA address space can be created without having to reinitialize the system.

However, too large a buffer can cause the system to allocate more system resources than are needed during a given IPL. The excessive allocation of system resources because of incorporating too large a buffer can lead to potential problems such as the following examples:

- The specification of RSVSTRT in conjunction with CSCBLOC=BELOW and MAXUSER can cause the system to allocate excessive storage below 16M. See [CSCBLOC](#) for details.
- An aggressively large MAXUSER, RSVSTRT, and RSVNONR can cause the system to allocate an excessive amount of storage, which can potentially lead to a wait state 204 reason 008 at IPL time. (Wait state 204 with reason 008: An error occurred during allocation initialization; the system could not obtain storage for device information.)

If started tasks or batch jobs that create non-reusable ASIDs end enough times, they will exhaust all available ASIDs and an IPL will be required. When loading the initial program is not an acceptable option, determine which programs caused the problems and fix them. For methods that prevent running out of ASIDs, see [z/OS MVS Programming: Extended Addressability Guide](#).

**Value range:** 0-32767. The sum of the values that are specified for the RSVSTRT, RSVNONR, and MAXUSER system parameters cannot exceed 32767.

**Default:** 5

**Associated parmlib member:** None

## RUCSA

RUCSA=( [xM] , [yM] )

Specifies the sizes of the virtual restricted use common service area (RUCSA) and extended RUCSA.

#### **xM**

Specifies the size of the non-extended RUCSA, located below 16 MB.

#### **yM**

Specifies the size of the extended RUCSA, located above 16 MB.

**Tip:** After the system is initialized, you can use the DISPLAY IPLINFO,RUCSA system command to determine the RUCSA specification that was used.

RUCSA is located between the private area and CSA. Extended RUCSA is located between the extended private area and extended CSA. For details about the location of the RUCSA, see [The virtual storage address space in z/OS MVS Initialization and Tuning Guide](#).

In selecting values for the RUCSA parameter, consider the following points:

- RUCSA is reserved exclusively for user-key CSA storage requests.
  - If the virtual storage manager runs out of SQA, it will not try to obtain space from RUCSA.
  - If the virtual storage manager runs out of CSA, it will not try to obtain space from RUCSA. Likewise, if the virtual storage manager runs out of RUCSA, it will not try to obtain space from CSA.
- A large RUCSA size will reserve space for future growth in user-key CSA usage. Such growth would be hampered if users were to obtain very large private areas. A large RUCSA specification effectively limits the maximum private area that a user job can acquire.

Similar to CSA, ECSA, SQA, and ESQA, you can use the common storage tracking function to collect information about jobs or address spaces that own storage in RUCSA and extended RUCSA. With that information, you can identify jobs or address spaces that obtain an excessive amount of storage. If those jobs or address spaces contain logic to free the storage when they are canceled, you might release the storage and avoid an IPL by using an operator command to cancel those jobs or address spaces.

#### **Value ranges:**

- The x value can be a decimal number, 0 - 9, indicating the number of 1 MB (1024\*1024 bytes) blocks of storage.
- The y value can be a decimal number, 0 - 2031, indicating the number of 1 MB (1024\*1024 bytes) blocks of storage.

Note that the maximum values are accepted but are not recommended because they would result in a private region that is too small. Do not specify more than you think you might ever need.

**Default:** For each sub-parameter, the default is 0M.

**Associated parmlib member:** None.

## **SCH**

```
SCH={ (aa)          }
      { (aa,L)        }
      { (aa,bb...)    }
      { (aa,bb...,L) }
```

This parameter specifies certain system characteristics. The two alphanumeric characters, represented by *aa,bb...*, specify one or more SCHEDxx members of SYS1.PARMLIB. SCHEDxx can include the following statement types:

#### **MT**

Specifies the size of the master trace table, if one exists.

#### **PPT**

Allows an installation to add entries to the program properties table.

**RESTART**

Allows an installation to add eligible restart codes to the restart codes table.

**NORESTART**

Allows an installation to delete eligible restart codes from the restart codes table.

If you specify the L option, the system displays the contents of the SCHEDxx SYS1.PARMLIB member at the operator's console as the system processes the member.

If a SCHEDxx member contains incorrect specifications, the system prompts the operator to specify another member. The response is in the form SCH=aa. To cancel the parameter, the operator replies by hitting the ENTER key. For more information about the SCHEDxx member, see [Chapter 82, “SCHEDxx \(PPT, master trace table, and abend codes for automatic restart\),” on page 713.](#)

**Value range:** Any two alphanumeric characters.

**Default:** None

**Associated parmlib member:** SCHEDxx

**SMF**

SMF=xx

This parameter specifies the parmlib member, SMFPRMxx, from which SMF obtains its options. The two alphanumeric characters, represented by xx, are appended to SMFPRM to name the member. For more information about SMF parameters, see [Chapter 84, “SMFPRMxx \(system management facilities \(SMF\) parameters\),” on page 735.](#)

**Value range:** Any two alphanumeric characters.

**Default:** 00 (Specifies SMFPRM00, the IBM-supplied default parmlib member.

**Associated parmlib member:** SMFPRMxx

**SMFTBUFF**

SMFTBUFF=nnn

This parameter specifies the number of megabytes that SMF should designate as the size of the temporary buffer that is used to hold SMF data during IPL processing while SMF completes initialization. See the information about the BUFSIZMAX, BUFUSEWARN, DSPSIZMAX, NOBUFFS, and SMFTBUFF SMF buffer options in *z/OS MVS System Management Facilities (SMF)* for additional information about the SMF temporary buffer.

**Value range:** 5 - 512

**Minimum value length:** 3, including leading zeros

**Default:** 5

**SMS**

SMS=xx

This parameter specifies the parmlib member, IGDSMSxx, from which the storage management subsystem (SMS) will obtain its options when the system is initialized for partitioned data set extended (PDSE) support. The two alphanumeric characters, represented by xx, are appended to IGDSMS to name the member. NIP saves the name until SMS is initialized. If initialization of PDSE support fails, the IGDSMSxx parmlib member is selected from the IEFSSNxx parmlib member by

using the ID=xx keyword (for detailed information, see [Chapter 62, “IGDSMSxx \(storage management subsystem definition\),”](#) on page 531).

**Value range:** Any two alphanumeric characters.

**Default:** 00 (Specifies IGDSMS00, the IBM-supplied default parmlib member)

**Associated parmlib member:** IGDSMSxx

## SOLUT

SOLUT=*solution-id*

This parameter specifies a 64-character solution ID (*solution-id*) that is provided to you by IBM.

The solution ID associates the system with a Tailored Fit Pricing solution. All system activity that is not otherwise associated with a different solution ID by way of WLM tenant resource groups will be associated with the specified solution ID. The solution ID is reported in SMF type 89 subtype 1 and subtype 2 records.

**Value range:** An IBM-provided, 64-character Tailored Fit Pricing solution ID.

**Default:** None. (The system is not associated with a Tailored Fit Pricing solution.)

**Associated parmlib member:** None.

## SQA

SQA=(*a*,*b*)

This parameter specifies the sizes of the virtual system queue area (SQA) and extended SQA. The subparameter *a* specifies the size of the SQA, located below 16 MB. The subparameter *b* specifies the size of the extended SQA, located above 16 MB. These values are added to the system's minimum SQA of eight 64 KB blocks (or 512 KB) and minimum extended SQA of approximately 8 MB. Both the SQA and extended SQA are fixed in central storage as they are used.

The system also reserves additional SQA and ESQA storage for the I/O configuration. The amount of SQA and ESQA depends on the number of devices and control units installed. Because the system adds these amounts to the SQA and ESQA blocks specified on the SQA parameter in IEASYSxx, the actual amounts of SQA and ESQA allocated might be more than you specified. Also, MVS will not round the lowest address of SQA down, or the uppermost address of ESQA up, to cause these areas to start or end on a 64 K, page, or segment boundary.

### Notes:

1. During IPL processing, the system reserves eight 64-K blocks of virtual storage for SQA and thirty-five 64 K blocks of virtual storage for extended SQA. During the IPL, both these storage areas are available to fulfill requests for SQA virtual storage. This SQA virtual storage is the minimum allocation for SQA and extended SQA. It is also called the *initial allocation of SQA*.

The system also reserves 8 MB of extended SQA to be used for the common area page tables. This storage area is not available to fulfill requests for SQA virtual storage until NIP completes processing the CSA parameter. After the CSA parameter is processed when the size of the common area and the amount of storage required for the common area page tables are known, the reserved storage not needed for the page tables becomes available to fulfill requests for extended SQA virtual storage.

2. During a quick start (that is, when the CLPA parameter is not specified), NIP determines if the currently specified SQA values are equal to the previously specified (cold start) values. If not, NIP issues an informational message and uses the cold start SQA values. (See [CLPA](#) for a discussion of *cold start* and *quick start*.)



3. Large amounts of messages at IPL time (whether suppressed or displayed) increase ESQA storage needs. For example, the installation of unlabeled DASD without OFFLINE=YES specified used to result in many issuances of the following message:

```
IEA311I UNLABELED DASD ON device
```

To avoid common storage exhaustion, message IEA656I is issued if it finds at least 32 unlabeled DASD devices. If this happens, message IEA311I will not be issued for any additional unlabeled DASD, and subsequent unlabeled DASD devices will continue to be marked offline. See the description of message IEA656I in *z/OS MVS System Messages, Vol 6 (GOS-IEA)* for details.

4. Additional device-related ESQA is required by self-describing devices (self-description is the ability of components of a system to provide unique identification information about themselves dynamically on request). It may be necessary to increase the ESQA specification when new devices are added to the system.

MVS determines the amount of expanded storage installed on the processor and automatically calculates the blocks of extended SQA necessary to initialize the expanded storage. This amount is added to the minimum system allocation and any increase you specify with the SQA parameter.

**SQA space shortage:** For a GETMAIN storage request for SQA storage where the request can be satisfied with storage either below or above 16 MB, the virtual storage manager (VSM) will try to satisfy the request with space above 16 MB. That is, VSM attempts to satisfy the request with space in the extended SQA, and, if such space is not available, VSM then attempts to satisfy the request with space in the extended common service area (extended CSA). If there is no space available above 16 MB, VSM will then try to satisfy the request with space below 16MB, first from the SQA, and finally from the CSA.

For a GETMAIN request for SQA storage where the request must be satisfied with storage below 16 MB, VSM tries to satisfy the request with space in the SQA, and, if none is available, VSM then tries to satisfy the request with space in the CSA.

**Note:** If excessive amounts of CSA or SQA are allocated, a warning message is generated and the parameter must be respecified. A warning message is also generated when the size of the entire common area below 16 MB exceeds 8 MB.

VSM keeps track of the remaining virtual SQA below 16 MB, and informs the system resources manager, via a SYSEVENT macro, when the total of available virtual SQA plus available virtual CSA has reached two threshold values. The system resources manager reacts to the situation by issuing an "SQA shortage" message at each of the two thresholds. During an SQA shortage, the system inhibits the creation of new address spaces by disallowing start initiator commands, LOGON commands, MOUNT commands, and START commands for system tasks that require their own address spaces, such as START VTAM. For additional information regarding SQA shortages and the two thresholds, see the "Virtual Storage Overview" topic in *z/OS MVS Initialization and Tuning Guide*.

**SQA space shortage during NIP:** During NIP processing, it is possible that the system's minimum allocation for SQA and extended SQA might be depleted before NIP processes the SQA parameter. If this situation occurs, you can increase the minimum SQA and extended SQA allocations. See the INITSQA parameter in the LOADxx parmlib member ([Chapter 73, "LOADxx \(system configuration data sets\)," on page 613](#)). However, if SQA is exhausted after processing local page data sets has begun, the value that is specified for the SQA parameter might be too low. Here, do not increase the initial SQA allocation. Instead, increase the SQA value in IEASYSxx.

**Value range:** Each *a* value can be expressed as:

- A decimal number, *n*, indicating *n* 64 KB (65536-byte) blocks. The number is 0 through 256.
- A decimal number followed by K, *nK*, indicating *n* 1 KB blocks. The number is 0 through 16384.
- A decimal number followed by M, *nM*, indicating *n* 1 MB (1024\*1024-byte) blocks. The number is 0 through 16.

Each *b* value can be expressed follows. The maximum values are accepted, but not recommended because they would result in a private region that is too small. Do not specify more than you think you might ever need.

- A decimal number, *n*, indicating *n* 64 KB blocks. The number is 0 through 32511.
- A decimal number followed by K, *n*K, indicating *n* 1 KB blocks. The number is 0 through 2080767.
- A decimal number followed by M, *n*M, indicating *n* 1 MB blocks. The number is 0 through 2031.

When *a* and *b* are specified in kilobytes and megabytes, the system rounds the space up to a whole number of 64 KB blocks.

**Syntax example:** SQA=(4,5). The first value requests that, for the SQA, (4 x 64K) be added to the system's minimum virtual allocation. The second value requests that, for the extended SQA, (5 x 64K) be added to the system's minimum allocation.

This example can also be specified as SQA=(256K,320K).

**Default:** For the *a* subparameter, the default is 1. This means one 64 K block is added to the initial SQA allocation of 512 K for a default size of 576 K for the SQA. For the *b* subparameter, the default is 0. This means that no 64 K blocks are added to the minimum extended SQA allocation of approximately 8 MB.

**Associated parmlib member:** None

## SSN

```
SSN={aa      }
    {(aa,bb,...)}
```

Specify this parameter to identify one or more IEFSSNxx parmlib members that contain the information needed to define and initialize selected subsystems. The two alphanumeric characters are appended to the characters, IEFSSN, to form the name of the parmlib member. NIP saves the parmlib name or names until the subsystems are to be initialized. For information about the IEFSSNxx parmlib member, see [Appendix A, “IEFSSNxx \(subsystem definitions\) - positional parameter form,” on page 789](#).

**Value range:** Any two alphanumeric characters

**Default:** SSN=00

**Associated parmlib member:** IEFSSNxx

## SVC

```
SVC={aa      }
    {(aa,bb,...)}
```

The two alphanumeric characters, (*aa*, *bb*, and so on) are appended to IEASVC to form the name of the parmlib members. This member contains the installation-defined SVCs. NIP processing uses the members to place the specified SVCs in the SVC table.

**Value range:** Two alphanumeric characters

**Default:** None

**Associated parmlib member:** IEASVCxx

## SYSNAME

```
SYSNAME=name
```

This parameter optionally specifies the name that identifies this system. The name must be 1-8 characters long; the valid characters are A-Z, 0-9, \$, @, and #. The name specified remains in effect

for the duration of the IPL. The following values can override the value specified on the SYSNAME parameter:

- The value specified on the SYSNAME parameter in the IEASYMxx parmlib member.
- The value specified on the SYSNAME parameter in one or more alternate sets of parameters in IEASYSxx. The operator specifies the alternate parameters on the SYSP parameter on the REPLY command.

The value of SYSNAME is also the substitution text for the &SYSNAME system symbol. &SYSNAME can be specified in parmlib members to help support multisystem environments. For details about how to use &SYSNAME and other system symbols, see [Chapter 2, “Sharing parmlib definitions,” on page 31](#).

The system name defined by the SYSNAME parameter is used during the initialization of global resource serialization to identify the GRSCDEF statement in the GRSCNFxx parmlib member that is to apply to this system. The system prompts the operator for a valid system name if the system name specified does not have the proper syntax. If the system name specified does not match any of the MATCHSYS keyword values in the GRSCNFxx parmlib member, the operator is informed, via an error message, to either reload the initial program or specify GRS=NONE. The operator also uses the system name defined by SYSNAME parameter to refer to the system in the system commands that control global resource serialization.

The system name defined by the SYSNAME parameter is also used to identify the originating system for messages in the multiple console support (MCS) hardcopy log and in the display that is created by the DISPLAY R command. Without specific SYSNAME= values in multisystem complexes, it is impossible to determine which system issued the message in the hardcopy log. SYSNAME is used in the SYSLOG heading and in all message formats where the system name is requested.

System logger can use the system name as part of the staging data set name. The system name that is specified here allows you to use a digit as the first character, but this is not valid in a staging data set name. If you use a digit as the first character in the system name, system logger substitutes 'STG' for the digit and uses part of the system name as the low-level qualifier for the staging data set name. For complete information, see [z/OS MVS Setting Up a Sysplex](#) and look for the topic on *Naming Conventions for the Log Stream and DASD Log data sets*.

**Value range:** 1-8 of these characters: A-Z, 0-9, \$, @, #.

**Default value:** If the system name is not specified in IEASYMxx or IEASYSxx, the default is one of the following:

- The processor name that is defined to HCD (if not in LPAR mode).
- The LPAR name for the processor.
- The VM user ID, if the MVS image is running as a guest under z/VM.

**Associated parmlib member:** None

## SYSP

```
SYSP={aa      }
      {(aa,bb... )}
```

**Restriction:** This parameter can be specified only by the operator. It cannot be specified in a system parameter list. It is included here for the sake of completeness.

The SYSP parameter specifies that one or more alternate system parameter lists (for example, IEASYS01, IEASYS02, and so on) that the system is to read after the default list IEASYS00. The two alphanumeric characters, represented by *aa*, *bb*, and so on, are appended to IEASYS to name the alternate lists. You can specify any number of alternate parameter lists. The specification cannot be prohibited by the OPI parameter.

When specifying alternate parameter lists on SYSP, consider the following points about the way the system processes parameter lists:

## IEASYSxx

- If a system parameter is specified in both IEASYS00 and an alternate parameter list selected by the operator, the value in the alternate parameter list overrides the value in IEASYS00.
- You can also specify alternate parameter lists on the SYSPARM parameter in the IEASYMxx and LOADxx parmlib members. See [“Step 2. Determine where to specify system parameters”](#) on page 39 for information about how the system processes the alternate parameter lists that are specified in IEASYMxx, LOADxx, and on SYSP.
- The system processes the suffixes on SYSP from left to right. If the suffixes indicate two or more parameter lists that contain the same parameter, the value on the parameter that is processed *last* overrides the values on any parameters that were processed previously.

Do not specify system symbols on the SYSP parameter.

**Example:** The operator responds to SPECIFY SYSTEM PARAMETERS by entering:

```
R 00,SYSP=(01,02)
```

Assume that the two specified members contain the following parameters:

- IEASYS01: MLPA=(00,01),SQA=8
- IEASYS02: MLPA=02,SQA=10

NIP would accept MLPA=02 and SQA=10, in addition to other parameters contained in IEASYS00.

**Value range:** Any two alphanumeric characters

**Default:** 00, which specifies IEASYS00.

**Associated parmlib member:** IEASYSxx

## UNI

```
UNI=xx
```

This parameter specifies the CUNUNIxx member of parmlib that contains the image name and real storage information required to enable the Unicode Conversion Services using a customized image, rather than performing IPL with no UNI= parameter specified and running with the Unicode default image. See *z/OS Unicode Services User's Guide and Reference* for more information. The two alphanumeric characters (xx) are appended to CUNUNI to form the name of the parmlib member CUNUNIxx.

**Value range:** Any two alphanumeric characters.

**Default:** None

**Associated parmlib member:** CUNUNIxx

## VAL

```
VAL={aa      }  
    {(aa,bb,...)}
```

This parameter specifies the VATLSTxx member or members of parmlib. Volume attribute processing reads this member or members during initialization to obtain mount and use attributes for direct access volumes. The mount and use attributes are set in the UCBs whose volume serial numbers are listed in the VATLSTxx members. If multiple members are specified, the lists are read in the order in which they appear in the VAL parameter. If a particular volume serial number appears on more than one entry, the volume attributes specified in the last entry for that volume serial is accepted. (For additional information, refer [Chapter 86, “VATLSTxx \(volume attribute list\),”](#) on page 775.)

**Value range:** Any two alphanumeric characters

**Default:** 00 (This means that VATLST00, if it exists, will be read.)

**Associated parmlib member:** VATLSTxx

## VIODSN

VIODSN={dsname | IGNORE}

VIODSN specifies the name of the VSAM data set for holding information about journaled VIO data sets. For warm start processing, the system assumes that the name of the VSAM data set you specify is the same one used for the last IPL. If you do not specify a value for VIODSN or if the system cannot allocate or open the data set you specify, VIO journaling will not take place, and journaled VIO jobs from the previous IPL will have to be restarted. If you specify a new name, and the data set is allocated and opened, this new data set is used, and will require the restart of previous jobs.

If you specify IGNORE, VIO journaling is not activated. No VIO journaling can take place until the next IPL.

In a multisystem environment, if you specify a unique name for each of your VIODSN data sets, do not put these names in the SYSTEMS exclusion resource name list in parmlib member GRSRNLxx.

Before an IPL, the VIO journaling data set must have been allocated, and cataloged in the system master catalog.

**Syntax examples for the VIODSN parameter:** Table 28 on page 479 shows syntax examples of the VIODSN parameter and the results they produce.

| Table 28. Syntax examples for the VIODSN parameter |   |
|--|---|
| Example  | Result  |
| VIODSN=SYS1.VIODSN                                 | The data set SYS1.VIODSN is used.   |
| VIODSN=IGNORE                                      | There is no VIO journaling during this IPL.   |
| VIODSN=&SYSNAME;.STGINDEX                          | Assuming the value that is specified on the SYSNAME= parameter is SYSTEMA, the data set SYSTEMA.STGINDEX is used. |
| VIODSN=&SYSNAME;&SYSNAME;DATA.FILE                 | Assuming the value that is specified on the SYSNAME= parameter is S1, the data set S1S1DATA.FILE is used.         |

**Value range:** Only one data set can be specified. The data set can contain system symbols.

**Default:** SYS1.STGINDEX

**Associated parmlib member:** None

## VRREGN

VRREGN=nnnn

This parameter specifies the default real-storage region size for an ADDRSPC=REAL job step that does not have a REGION parameter in its JCL. The numerical value of the operand (*nnnn*) indicates the real-storage region size in 1 KB blocks. The VRREGN parameter has no meaning if REAL=0 is specified.

**Note:** The following VRREGN values prevent an ADDRSPC=REAL job step from running if it omits a REGION parameter:

- VRREGN value that is greater than the value of the REAL parameter or
- VRREGN value of zero.

**Value range:** 0-9999

**Default:** 64, which means a default REGION size of 64 K.

**Associated parmlib member:** None

## WARNUND

### WARNUND

This parameter asks that the system warn you when it finds an undefined system parameter rather than prompt for new system parameters. When the WARNUND parameter is found, it applies to all subsequent system parameter processing.

**Tip:** If you want WARNUND processing for all IEASYSxx parmlib members, put WARNUND at the beginning of IEASYS00 so that it covers all subsequent system parameters within IEASYS00 and any other IEASYSxx members processed. If you only need WARNUND processing before a specific parameter in an IEASYSxx member, you can place WARNUND just before that parameter. If you want WARNUND processing for your reply to IEA101A SPECIFY SYSTEM PARAMETERS, you must specify it within the reply text (earlier within that reply than any unknown parameter). For example, you might reply:

```
R 0, WARNUND, SYSP=01, NEWPARM=VALUE
```

**Note:** WARNUND only applies to primary system parameters that are listed in IEASYSxx and not to their associated subparameters.

Do not use unknown parameters within this reply text that imply that you do not need WARNUND within the reply text.

**Default:** None

**Associated parmlib member:** None

## WORKINST

### WORKINST={SYSTEM|YES|NO}

This parameter specifies the processing state for the system's workload instrumentation collection.

#### **WORKINST=SYSTEM**

This is the default. Use the system's capabilities. If the system supports workload instrumentation, this is equivalent to WORKINST=YES. If the system does not support workload instrumentation, this is equivalent to WORKINST=NO. Use the DISPLAY IPLINFO,WORKINST,STATE command after IPL to determine if workload instrumentation data is being collected

#### **WORKINST=YES**

When the hardware supports the workload instrumentation facility, specify WORKINST=YES to collect workload instrumentation data.

#### **WORKINST=NO**

The system does not collect workload instrumentation data regardless of the hardware capabilities.

**Value range:** Not applicable

**Default:** SYSTEM

**Associated parmlib member:** None

## ZAAPZIIP

### ZAAPZIIP=NO|YES

Use the ZAAPZIIP (or ZZ as its alias) parameter to request the system to run zAAP processor eligible work on zIIP processors making work that would otherwise be zAAP processor eligible instead be zIIP processor eligible when certain conditions are met.

The zAAP on zIIP function is active only when all of the following conditions are true:

- ZAAPZIIP=YES is specified, defaulted, or enforced.
- There are (or could be, through dynamic CPU addition) zIIPs defined to this LPAR.
- No zAAPs are defined to this LPAR, whether online, offline or in the reserved state.

If you specify ZAAPZIIP=NO on a machine that does not support zAAPs, the system issues message IEA988I and continues as if you had specified ZAAPZIIP=YES.

To correct an error you make in specifying ZZ, you must specify the value on ZAAPZIIP instead of ZZ. The system issues message IEA341A to indicate this situation.

**Default:** Yes.

**Note:** The default of ZAAPZIIP is NO in z/OS V1R9 and z/OS V1R10; and the default is YES as of V1R11. Only the alias ZZ is valid in z/OS V1R9 and z/OS V1R10.

**Associated parmlib member:** None





## Chapter 57. IECIOSxx (I/O related parameters)

IECIOSxx contains records that the installation creates to accomplish the following tasks:

- Modify the time intervals which, when exceeded, result in the missing interrupt handler (MIH) detecting a missing interrupt. (MIH parameter).
- Modify the I/O timing limits. The system uses the I/O timing limits to monitor queued and active I/O requests. If an I/O request exceeds the time limit that you specify, the system abnormally ends the request. (MIH IOTIMING parameter).
- Specify whether an I/O Timing condition is allowed to trigger a HyperSwap, and if so, whether the timed-out I/O operation is posted back with permanent error. (MIH IOTHSWAP and IOTTERM parameters).
- Specify I/O timing HyperSwap options.
- Modify the device threshold values and recovery actions in the hot I/O detection table (HIDT). The system uses the HIDT information to detect, and recover from, hot I/O conditions. (HOTIO parameter)
- Specify recovery actions to recover from a hung interface (that is, a terminal condition). (TERMINAL parameter).
- Specify trace options other than the default for IOS component trace. (CTRACE parameter).
- Specify whether FICON® switch statistics gathering is to be enabled or disabled and whether FICON fabric I/O priority is to be enabled or disabled on a system. (FICON parameter).
- Specify whether IOS storage blocks are to be obtained in 24 or 31-bit storage. (STORAGE parameter).
- Specify whether to enable write protection on captured UCBs or as a result of a SETIOS=xx command. (CAPTUCB parameter).
- Specify whether the MIDAW facility is to be enabled or disabled on a system. (MIDAW parameter).
- Specify whether the HyperPAV facility is to be used. (HYPERPAV parameter).
- Specify whether IBM zHyperWrite data replication is enabled or disabled. (HYPERWRITE parameter).
- Specify the Encryption Key Management primary and secondary host names and the maximum number of concurrent socket connections that are allowed for the communication with the encryption key manager. (EKM parameter).
- Specify IOS recovery options. (RECOVERY parameter).
- Specify whether the High Performance FICON for IBM z Systems® (zHPF) facility is to be enabled or disabled on a system (ZHPF parameter) and what zHPF options are to be used (ZHPFOPTS parameter).
- Specify the IOSSPOF System Service options. (SPOF parameter) .
- Specify the zHyperLink system options (ZHYPERLINK parameter).

### Parameter in IEASYSxx (or specified by the operator)

#### **IOS=xx**

The two alphanumeric characters (xx) are appended to IECIOS to identify the IECIOSxx parmlib member. If the IOS parameter is not specified, the system uses defaults for MIH processing, defaults for hot I/O, and defaults for IOS CTRACE processing.

To change the IECIOSxx member after initialization, you can specify the SET IOS=xx command. The SET IOS=xx command changes the I/O timing limits, MIH intervals and FICON statistics option. It does not, however, change the values initialized for hot I/O detection and it does not change the current IOS CTRACE options. Changing the hot I/O detection or recovery values requires a reIPL. Changing the CTRACE parmlib member or options requires the use of the TRACE operator command. For a description of the TRACE operator command, see [z/OS MVS System Commands](#).

You can change the FICON, STORAGE, CAPTUCB, MIDAW, HYPERPAV, SPOF, HYPERWRITE, EKM, RECOVERY, ZHPF and ZHPFOPTS parameters dynamically using the SETIOS command. See [z/OS MVS System Commands](#).

You can change all of the parameters dynamically using the SETIOS command with the exception of the HOTIO, TERMINAL and CTRACE parameters. See [z/OS MVS System Commands](#).

## IBM-supplied default for IECIOSxx

There is no default IECIOSxx parmlib member. However, the system establishes default IOS component tracing options at IPL time.

## Syntax rules for IECIOSxx

The following rules apply to the creation of IECIOSxx:

- Use columns 1 through 71 for data; columns 72 through 80 are ignored.
- Continuation is indicated by a comma followed by one or more blanks. The next record can start in any column.
- If a verb can have multiple keywords, they can be expanded to multiple records, however, a keyword and its value must be specified on the same record.
- An asterisk (\*) in column 1 indicates a comment record. Comment records cannot be continued and that comments cannot appear in a parameter record.
- Each record must start with MIH, HOTIO, TERMINAL, FICON, STORAGE, CAPTUCB, EKM, SPOF, RECOVERY, ZHPFOPTS, or ZHYPERLINK followed by one or more blanks, or must be a valid CTRACE, MIDAW, HYPERPAV, HYPERWRITE, or ZHPF specification in the format given as follows.
- If duplicate keywords are found, the last occurrence of the keyword is used.
- Two different verbs cannot be specified in the same record.
- The format for each record is as follows. The following sections describe the IECIOSxx I/O-related parameters and list-specific syntax requirements.

```
MIH parameter[,parameter]. . .
MIH IOTIMING mm:ss,parameter[,parameter]. . .
HOTIO parameter[,parameter]. . .
TERMINAL parameter[,parameter]. . .
CTRACE(parmlib_member_name)
FICON parameter
STORAGE parameter
CAPTUCB parameter
MIDAW=parameter
HYPERPAV=parameter
HYPERWRITE=parameter
EKM parameter
RECOVERY parameter
ZHPF=parameter
ZHPFOPTS parameter
SPOF parameter
[ {ZHYPERLINK|ZHL} parameter]
```

## Missing interrupt handler (MIH)

The MIH detects missing interrupt conditions. The following device conditions qualify as missing interrupts if the specified time interval has elapsed:

- Primary status interrupt pending
- Secondary status interrupt pending
- Start pending condition
- Idle with work queued
- Mount pending

If the MIH detects a missing interrupt, processing will be done that is dependent on the detected condition. For any detected missing interrupt, the MIH performs one or more of the following actions:

- Invokes the device dependent MIH exit (if it exists)
- Records the condition in the SYS1.LOGREC data set
- Notifies the system operator
- Clears the condition
- Simulates an interrupt
- Redrives the device
- Requeues the I/O request

When specifying time intervals, consider the following:

- The MIH detects a missing interrupt condition within 1 second of the time interval that you specify.
- If the time interval is too short, a false missing interrupt can occur and cause early termination of the channel program. For example, if a 30-second interval is specified for a tape drive, a rewind might not complete before the MIH detects a missing interrupt.
- If the time interval is too long, a job or system could hang because the MIH has not yet detected a missing interrupt. For example, if a 15-minute time interval is specified for a tape drive used as an IMS log tape, the MIH could delay IMS for 15 minutes because of MIH detection.
- During IPL (if the device is defined to be ONLINE) or during the VARY ONLINE process, some devices may present their own MIH timeout values, via the primary or secondary MIH timing enhancement contained in the self-describing data for the device. The primary MIH timeout value is used for most I/O commands, but the secondary MIH timeout value may be used for special operations such as long-busy conditions or long running I/O operations. Any time a user specifically sets a device or device class to have an MIH timeout value that is different from the IBM-supplied default for the device class, that value will override the device-established primary MIH time value. This implies that if an MIH time value that is equal to the MIH default for the device class is explicitly requested, IOS will **not** override the device-established primary MIH time value. To override the device-established primary MIH time value, you must explicitly set a time value that is not equal to the MIH default for the device class.

**Note:**

1. To cancel MIH processing for specific devices, specify 00:00 for the time interval value (mm:ss) defined for the associated devices.
2. During IOS recovery processing, the system will override your time interval specification and may issue MIH messages and MIH error records in SYS1.LOGREC at this IOS determined interval.
3. Any dynamic change that causes a device's UCB to be deleted and then re-added will cause the device's MIH time interval to be reset to the default MIH setting for its device class. Once the dynamic change is completed, users should reissue the SETIOS MIH MVS command to reestablish any specific MIH setting for the device. For more information about the SETIOS MIH command, see [z/OS MVS System Commands](#).

## I/O timing

The I/O timing facility abnormally ends the following I/O requests that exceeded the I/O timing limits that are specified for a device:

- Queued requests that are waiting for execution.
- Start pending requests.
- Active requests.

The I/O timing facility can be enabled to trigger a HyperSwap when an I/O timeout occurs for a device that is monitored for HyperSwap. Optionally, the user can specify whether a timed-out I/O operation that initiates a HyperSwap is to be terminated or allowed to be started on the swap 'TO' device.

For any I/O request that exceeds the I/O timing limit, the system performs the following actions:

- When the I/O timing trigger is not enabled for HyperSwap, or is enabled and the IOTTERM option is also enabled:
  - Abnormally ends the I/O request that exceeded the time limit, and does not requeue the request for execution.
  - Issues a message.
  - Writes an entry in the SYS1.LOGREC data set for the abnormally ended I/O request.
- When the I/O timing trigger is enabled for HyperSwap and the IOTTERM option is disabled:
  - Abnormally ends the I/O request that exceeded the time limit, and requeues the request for later execution on the swap 'TO' device at the completion of the HyperSwap.
  - Issues a message for the first timeout condition that triggers a HyperSwap on the associated DASD subsystem.
  - Writes an entry in the SYS1.LOGREC data set for the abnormally ended I/O request.

Installations that want the system to issue an I/O timing message and record in SYS1.LOGREC, but do not want to abnormally end the I/O request can do so with I/O timing message-only processing. Message-only processing allows the system to detect I/O timeout conditions, but, provides the ability to allow the user to decide which I/O requests should be terminated.

The system records data associated with the original I/O error, if any exists.

**IBM recommendations for I/O timing limits:** Within 1 second, the system abnormally ends an I/O request that exceeded the I/O timing limit. IBM suggests setting your I/O timing limits to 6 seconds or longer. An I/O timing limit of less than 6 seconds can result in a loss of service information that is required to correct a DASD subsystem hardware failure that triggered the long I/O event. In addition, a limit of less than 6 seconds can result in a loss of SYS1.LOGREC records.

**Notes:**

1. To cancel the I/O timing limit, (that is, to have no time limit on I/O requests) specify IOTIMING=00:00.
2. I/O timing is only supported for non-paging DASD devices and for TAPE devices. I/O timing for TAPE devices requires MSGONLY=YES to be in effect because full I/O timing support is not available.
3. An I/O timeout will not trigger a HyperSwap if message-only recovery is specified for the device or as the result of a timeout condition that is specified by an I/O driver program.

## Interaction of MIH and I/O timing processing

You may specify that both MIH processing and I/O timing processing monitor your I/O requests. When the value you specify for the I/O limit is less than or equal to the value you specify for MIH, I/O timing processing takes precedence over MIH processing. The system will abnormally end the I/O request when it exceeds the I/O timing limit that you have specified. MIH processing will not get control.

When the value that you specify for the I/O timing limit is greater than the value that you specify for MIH, normal MIH recovery will be in effect until the I/O timing limit is reached. Once the I/O request exceeds the I/O timing limit that you have specified, the system will abnormally end the I/O request.

To get the full benefit of MIH recovery, your MIH time intervals plus your MIH time intervals for the HSCH and CSCH instructions should be at least 1 second less than your I/O timing limit.

## I/O timing trigger for HyperSwap

The I/O timing trigger for HyperSwap defines an I/O timing timeout event to initiate a HyperSwap operation. This allows an application to switch over from failing devices to their mirror images without failing transactions for the end user. When the I/O timing timeout condition is detected for DASD devices monitored for HyperSwap, a HyperSwap event is triggered. If the HyperSwap operation is successful, the I/O request remains queued to the device so that it can be re-driven when the swap completes. If the HyperSwap operation is not successful, the I/O request is posted back with a permanent error.

## Statements and parameters for MIH

Do not set a MIH time value for any device that establishes its own primary or secondary time interval. Overriding the device-supplied primary MIH timeout value might adversely affect MIH recovery processing for the device or device class. Refer to the specific device's reference manuals to determine whether the device supports self-describing MIH time values. See [“Missing interrupt handler \(MIH\)”](#) on page 484 for more information.

### **CHAR=mm:ss**

Specifies the MIH time interval to be used for the character reader device class, where *mm* is minutes and *ss* is seconds.

#### **Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

### **COMM=mm:ss**

Specifies the MIH time interval to be used for the communications device class, where *mm* is minutes and *ss* is seconds.

#### **Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

### **CTC=mm:ss**

Specifies the MIH time interval to be used for the channel-to-channel device class, where *mm* is minutes and *ss* is seconds.

#### **Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

### **DASD=mm:ss**

Specifies the MIH time interval to be used for all direct access devices (DASD), where *mm* is minutes and *ss* is seconds.

#### **Value range:**

- *mm* = 00-99
- *ss* = 00-59

In general, the default time interval (15 seconds) is sufficient for most DASD configurations. However, IBM suggests you not specify any MIH for DASD if you have any DASD hardware in your configuration that uses the primary or secondary MIH timing enhancement. See [“Missing interrupt handler \(MIH\)”](#) on page 484 for more information.

**Default:** 00:15

### **DEV=devnum**

Specifies the device numbers for the devices for which specific time intervals are to be used. To specify more than one device number, use a comma to separate the device numbers. To specify a range of device numbers, use a hyphen to separate the beginning and ending device numbers. If more than one device number is specified, enclose the device numbers in parentheses.

**Restriction:** The DEV keyword must precede or follow the TIME keyword on the same record.

**Value range:** 1 - 4 hexadecimal digits, optionally preceded by a slash (/).

**Default:** None

**GRAF=mm:ss**

Specifies the MIH time interval to be used for the graphics device class, where *mm* is minutes and *ss* is seconds.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

**HALT=mm:ss**

Specifies the MIH time interval to be used for monitoring Halt (HSCH) and clear (CSCH) subchannel operations. This keyword is device independent; setting it affects all devices on the system.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 00:05

**IOTDASD=mm:ss**

Specifies the I/O timing limit to be used for all non-paging direct access storage devices (DASD), where *mm* is minutes and *ss* is seconds. The maximum I/O timing limit is 5,999 seconds. When IOTDASD is set to 00:00, I/O timing is not in effect for the DASD device class.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

Initially, the time interval is set to 00:00, which indicates that the I/O timing facility is not active for any DASD.

The MSGONLY keyword can also be used to set I/O timing message-only processing on or off for all DASD devices.

**Default:** 00:00

**IOTHSWAP=YES|NO**

Specifies whether the I/O timing facility is enabled for HyperSwap.

**Default:** The default is NO. The I/O timing facility is not enabled to trigger a HyperSwap.

**IOTTAPE=mm:ss**

Specifies the I/O timing limit to be used for all TAPE devices, where *mm* is minutes and *ss* is seconds. The maximum I/O timing limit is 5,999 seconds. When IOTTAPE is set to 00:00, I/O timing is not in effect for the TAPE device class.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

Initially, the time interval is set to 00:00, which indicates that the I/O timing facility is not active for any TAPE devices. Also, the MSGONLY=YES keyword must be used to set I/O timing message-only processing on for all TAPE devices because full I/O timing support is not available.

**Default:** 00:00

**IOTTERM=YES|NO**

Valid only when IOTHSWAP=YES. Specifies whether a timed out I/O operation that triggers a HyperSwap is terminated with a permanent error or allowed to be started on the swap 'TO' device.

**Default:** The default is NO. The timed out I/O operation is allowed to be started on the swap 'TO' device.

**MNTS=*mm:ss***

Specifies the MIH time interval to be used for monitoring mount pending conditions for DASD and TAPE devices.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

**MOUNTMSG=YES|NO**

Specifies that MIH is to issue all MIH mount pending messages.

**Default:** NO

**MSGONLY=YES|NO**

Specifies whether an I/O timeout condition is processed using full I/O timing recovery (MSGONLY=NO) or message only recovery (MSGONLY=YES). When MSGONLY=NO is specified and an I/O request exceeds the I/O timing interval, a message is issued to the operator, a record is written to SYS1.LOGREC, and the I/O request is abnormally terminated. When MSGONLY=YES is specified and an I/O request exceeds the I/O timing interval, a message is issued to the operator and a record is written to SYS1.LOGREC, however, the I/O request is NOT abnormally terminated. Instead, the request is left in the system.

Message-only processing allows the system to detect I/O timeout conditions, but, provides the ability to allow the user to decide which I/O requests should be terminated.

**Notes:**

1. If more than one MSGONLY keyword appears on a record, the last valid MSGONLY keyword is used.
2. The MSGONLY keyword is only valid when the IOTDASD or IOTTAPE keyword are specified or when the DEV and IOTIMING keywords are specified. Otherwise, the MSGONLY keyword is ignored. This implies that the MSGONLY keyword value only relates to devices that are affected by the IOTDASD, IOTTAPE, or DEV/IOTIMING keywords.

**Default:** NO

**STND=*mm:ss***

Specifies the MIH time interval to be used for all of the following device classes:

- Character readers (CHAR)
- Communications (COMM)
- CTCs (CTC)
- Graphics (GRAF)
- Tapes (TAPE)
- Unit records (UREC).

Specify the time interval as *mm:ss*, where *mm* is minutes and *ss* is seconds.

If you code STND following CHAR, COMM, CTC, GRAF, TAPE, or UREC, the value for STND overrides the values for those device classes. Similarly, if you code CHAR, COMM, CTC, GRAF, TAPE, or UREC following STND, the values for those device classes override the value for STND.

In this example, the value for the CTC device class is 4:00, because the value specified for STND overrides the value that is specified for CTC. However, the value for the tape device class is 5:00, because the value specified for TAPE overrides the value that is specified for STND. Thus, this MIH record sets the values for CHAR, COMM, CTC, GRAF, and UREC to 4:00, and sets the value for TAPE to 5:00.

```
SETIOS MIH,CTC=01:00,STND=04:00,DASD=00:10,HALT=00:08,TAPE=05:00
```

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00**TAPE=*mm:ss***

Specifies the MIH time interval to be used for the tape device class, where *mm* is minutes and *ss* is seconds.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

Use the following time intervals, which are based on tape device class:

| Tape device class  | Time interval |
|--|---------------|
| 3480   | 5 minutes     |
| 3490   | 5 minutes     |
| 3490E  | 10 minutes    |
| 3490E (When loaded with IBM Enhanced Capacity Cartridge System Tape) | 20 minutes    |

**Note:** You can specify either TAPE (such as TAPE=10:00), or a combination of DEV and TIME, for example:

```
DEV=(4A1-4E7),TIME=10:00
```

The time interval you set with the TAPE parameter applies to all tape device types. You cannot set time intervals for specific esoteric or generic groups.

Do not specify any MIH for the tape device class if you have any tape device in your configuration that uses the primary or secondary MIH timing enhancement. See [“Missing interrupt handler \(MIH\)”](#) on page 484 for more information.

**Default:** 03:00**TEST**

Specifies the system is to dynamically test MIH parameters and values. The TEST parameter is ignored during initialization. The system uses this parameter when you issue a SET IOS=xx command to syntax check the MIH updating.

**TIME=*mm:ss***

Specifies the MIH time interval to be used for the devices that are identified on the DEV keyword, where *mm* is minutes and *ss* is seconds.

**Note:** The TIME keyword must precede or follow the DEV keyword on the same record.

**Value range:**

- *mm* = 00-99
- *ss* = 00-59

**Default:** None**UREC=*mm:ss***

Specifies the MIH time interval to be used for the unit record device class, where *mm* is minutes and *ss* is seconds.

**Value range:**



- *mm* = 00-99
- *ss* = 00-59

**Default:** 03:00

### Syntax considerations for MIH:

- On MIH records, specify the DEV and TIME keywords as a pair. That is, use them together on one record to define time intervals for specific device numbers.
- On MIH records, only one pair of DEV and TIME keywords can appear on any one record. They can appear in any order, and can be separated by other keywords.
- On MIH records, if the same device number exists in more than one DEV keyword, the time interval that is specified for the last occurrence of the DEV keyword (containing the device number) is used.
- You can code an MIH time interval and I/O timing limit on the same record when either of the following is true:
  - All the devices that are listed in the record are to be monitored by both the MIH and the I/O timing facility. In the following example, device A20 and devices A11, A12, and A14 have both an MIH time interval of 5 seconds and an I/O timing limit of 11 seconds:

```
MIH DEV=(A20,A11-A14),TIME=00:05,IOTIMING=00:11
```

- A device class is to be monitored by the MIH, and an individual device (or range of devices) is to be monitored by the I/O timing facility.

When the device class is DASD, the MIH monitors all DASD devices, including those specified on the DEV parameter. The I/O timing facility monitors only those devices that are specified on the DEV parameter. In the following example, the DASD device class has an MIH time interval of 5 seconds. Device A20 and devices A11, A12, A13, and A14 have an MIH time interval of 5 seconds, and will also have an I/O timing limit of 11 seconds.

```
MIH DASD=00:05,DEV=(A20,A11-A14),IOTIMING=00:11
```

When the device class is not DASD, the MIH monitors the device class, and the I/O timing facility monitors only those devices that are specified on the DEV parameter. In the following example, the tape device class has an MIH time interval of 5 minutes. Device B12 is a DASD device, because only DASD devices can be monitored by the I/O timing facility. Device B12 has an I/O timing limit of 10 seconds.

```
MIH TAPE=05:00,DEV=B12,IOTIMING=00:10
```

- To request that the MIH monitor one device (or range of devices) and the I/O timing facility monitor device (or range of devices), code two separate records.
- You can establish I/O timing for the entire DASD device class by using a device class name of IOTDASD. In the example below, an I/O timing limit of 1 minute is established for all DASD devices.

```
MIH IOTDASD=01:00
```

- When the IOTDASD device class name is specified with the DEV and IOTIMING keywords, all devices that are specified on the DEV keyword have an I/O timing limit equal to the limit specified on the IOTIMING keyword. In the example, an I/O timing limit of 5 seconds is established for DASD devices 180 through 18F and an I/O timing limit of 30 seconds is established for all other DASD devices.

```
MIH IOTDASD=00:30,DEV=(180-18F),IOTIMING=00:05
```

- To request that the I/O timing facility monitor a device (or devices) with message-only processing active, use the MSGONLY keyword. In the following example, an I/O timing limit of 1 minute is established for all DASD devices. Furthermore, message-only processing is established for all DASD devices. This implies that if any I/O request to any DASD device exceeds the I/O timing limit, then the system issues a message, record the condition in SYS1.LOGREC, and will not abnormally terminate

the I/O request. Instead, the request is left in the system. If another I/O timing interval expires, the system reissues a message, and rerecords the condition in SYS1.LOGREC.

```
MIH IOTDASD=01:00,MSGONLY=YES
```

In the following example, an I/O timing limit of 10 minutes and message-only processing is established for device 180 through 18F.

```
MIH DEV=(180-18F),IOTIMING=10:00,MSGONLY=YES
```

To turn off message-only processing, either use the MSGONLY=NO keyword, or set the I/O timing limit for the device (or devices) to zero (00:00).

**Note:** Indicating IOTDASD=00:00 will not turn off I/O timing nor reset message-only processing for any devices that were explicitly set up for I/O timing using the DEV and IOTIMING keywords.

- You can code I/O Timing HyperSwap options to specify if the I/O timing facility is allowed to trigger a HyperSwap and if so, whether to terminate the I/O operation that is timed out or allow it to be started on the swap TO device.

The following conditions must be true before an I/O timeout triggers a HyperSwap:

- The I/O timing facility must be enabled for HyperSwap.
- The product must be installed at a level that supports the I/O timing trigger.
- Message-only recovery is not in effect for the device on which the timeout occurred and the timeout is not the result of timing that is specified by the I/O driver program.

The following example specifies that the I/O timing facility is enabled for HyperSwap and that timed-out I/O operations are allowed to be started on the swap 'TO' device:

```
MIH,IOTHSWAP=YES,IOTTERM=NO
```

- On MIH records, specify the IOTHSWAP and IOTTERM keywords as a pair. That is, use them together on one record to define the actions to be taken for an I/O Timing HyperSwap trigger.

## Hot I/O (HOTIO)

*Hot I/O* refers to a hardware malfunction that causes repeated, unsolicited I/O interrupts. If such I/O interrupts are not detected, the system can loop or the system queue area (SQA) can be depleted. IOS tries to detect the hot I/O condition and perform recovery before the system requires a reIPL.

When the number of repeated, unsolicited I/O interrupts reaches the threshold value that is defined in the HIDE, IOS assumes that there is a hot I/O condition and proceeds to perform recovery actions. Recovery actions that are taken for a “hot” device depend on the type of device and its reserve status.

| Table 29. HOTIO parameters              |           |              |          |              |
|---|-----------|--------------|----------|--------------|
| Device                                  | Non-ESCON |              | ESCON    |              |
|   | Reserved  | Not Reserved | Reserved | Not Reserved |
| DASD or dynamic pathing device          | DFLT112   | DFLT111      | SDFT112  | SDFT111      |
| non-DASD and non-dynamic pathing device | --        | DFLT110      | --       | SDFT110      |

You can use HOTIO statements in IECIOSxx to modify the HIDE, and to eliminate operator intervention where recovery actions defined in the HIDE (by default) require the operator to respond to a message.

**Note:** To cancel hot I/O processing (that is, to have no detection and no recovery from hot I/O conditions) specify 0 for the device threshold value — DVTHRS=0.

**HOTIO DVTHRS=dddd**

Specifies the device threshold for unsolicited I/O interrupts, which must be reached for hot I/O recovery to begin.

**Value range:** 0-32767

**Default:** 100

**DFLT110=(options)**

Specifies the recovery action to be taken for a non-DASD, non-dynamic pathing device. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (BOX,BOX)

**DFLT111=(options)**

Specifies the recovery action to be taken for a DASD or a dynamic pathing device that is not reserved or assigned. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (CHPK,BOX)

**DFLT112=(options)**

Specifies the recovery action to be taken for a DASD or a dynamic pathing device that is reserved or assigned. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (CHPK,BOX)

**SDFT110=(options)**

Specifies the recovery action to be taken for a non-DASD, non-dynamic pathing device that is attached to an IBM ESCON (or future) channel path. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (BOX,BOX)

**SDFT111=(options)**

Specifies the recovery action to be taken for a DASD or a dynamic pathing device that is not reserved or assigned and is attached to an IBM ESCON (or future) channel path. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (CUK,BOX)

**SDFT112=(options)**

Specifies the recovery action to be taken for a DASD or a dynamic pathing device that is reserved or assigned and is attached to an IBM ESCON (or future) channel path. (For the recovery actions that can be specified as options, see [“Options for HOTIO recovery” on page 494.](#))

**Default:** (CUK,BOX)

**BOX\_LP=(device\_classes)**

Specifies which device classes should be boxed instead of performing channel path recovery when all of the following conditions are true:

- The device is defined on the CHPID being recovered.
- Either all of the device's paths are undergoing recovery or this is the only path to the device.
- The device is currently reserved or assigned.

The device classes you can specify for BOX\_LP are DASD, TAPE, UREC, COMM, CTC, and GRAF. You can also specify:

- NONE, to turn off BOX\_LP processing for all device classes.
- ALL, to turn on BOX\_LP processing for all device classes. ALL is the recommended setting.

**Default:** (ALL)

## Options for HOTIO recovery

The parameters (DFLT110, DFLT111, DFLT112, SDFT110, SDFT111, and SDFT112) that are used to specify recovery actions have default options defined in the HIDE. Each of these parameters has a default option for non-recursive hot I/O conditions and a default option for recursive hot I/O conditions. You can override one or both options.

For example, if you want to override the DFLT111 non-recursive default option (CHPK) so that the recovery action would have to be obtained from the operator, code: DFLT111=(OPER,). Note that the options are enclosed in parentheses and separated by a comma.

The following options can be specified for both non-recursive and recursive hot I/O conditions. Code the options with the DFLT110, DFLT111, DFLT112, SDFT110, SDFT111, and SDFT112 parameters, and use the following format:

```
Parameter=(a,b)
```

**a**

the action to be taken for a non-recursive hot I/O condition

**b**

the action to be taken for a recursive hot I/O condition.

| Option | Meaning and Use   |
|--------|---|
| BOX    | Specifies that the device is to be forced offline.  |
| CHPF   | Specifies that the channel path over which the last interrupt for the hot device was received is to be forced offline.  |
| CHPK   | Specifies that channel path recovery is to be initiated for the channel path over which the last interrupt for the hot device was received. If successful, the channel path is to remain online.<br><br><b>Note:</b> If a device on the channel path undergoing channel path recovery belongs to a device class specified in the BOX_LP=(...) parameter, then that device may become boxed instead of undergoing channel path recovery. |
| OPER   | Specifies that the recovery action is to be obtained from the operator.<br><br><b>Note:</b> There are conditions when the message issued to prompt the operator will be issued using the Disabled Console Communication Facility (DCCF). IBM suggests that you do not choose this option unless the installation can properly handle responding to messages that were issued using DCCF.  |
| CUK    | Specifies that control unit recovery is to be initiated for the channel path over which the last interrupt for the hot device was received.<br><br><b>Note:</b> The CUK option is valid only for IBM ESCON channel paths (SDFT110, SDFT111, and SDFT112).   |

## TERMINAL

### TERMINAL BOX\_LP =(device\_classes)

Specifies special recovery actions for recovering from a terminal or hung interface condition. The TERMINAL statement specifies which device classes should be boxed instead of performing channel path recovery to recover from a hung interface (or terminal condition). Box processing will override channel path recovery processing when all of the following are true:

- the device is defined on the CHPID being recovered
- either all of the device's paths are undergoing recovery or this is the only path to the device.
- the device is currently reserved or assigned.

The device classes you can specify for BOX\_LP are DASD, TAPE, UREC, COMM, CTC, and GRAF. You can also specify:

- NONE to turn off BOX\_LP processing for all device classes.
- ALL to turn on BOX\_LP processing for all device classes. ALL is the recommended setting.

**Default:** (ALL)

Syntax considerations for TERMINAL

- If multiple TERMINAL statements are found, only the last valid one specified applies. All others will be ignored.
- TERMINAL statements that are found in IECIOSxx members that are activated via the SET IOS=xx operator command will be processed so you can dynamically change the setting for this value, or make the initial specification.

## CTRACE

---

IOS traces events during its processing that may aid in the debugging of problems involving the IOS component. You can use the CTRACE statement in IECIOSxx to identify the SYS1.PARMLIB member that contains the IOS component trace options. If no CTRACE statement is specified, IOS component trace is initialized with default minimum trace options. For more information about IOS component tracing, see *z/OS MVS Diagnosis: Tools and Service Aids*.

### CTRACE(*parmlib\_member\_name*)

where *parmlib\_member\_name* is an 8-character SYS1.PARMLIB member name which must be in the format CTnIOSxx, where:

**n**

is an alphanumeric character that specifies the source of the member. IBM-supplied members use "I".

**xx**

is any two alphanumeric characters.

**Default:** None

Note that if the CTRACE parameter is not used, then IOS component tracing is activated to trace minimum operations.

For more information about specifying options for the IOS component trace, or for more information IOS minimum operations see *z/OS MVS Diagnosis: Tools and Service Aids*. For information about coding the component trace member of SYS1.PARMLIB, see [Chapter 26, "CTncccxx \(component trace parameters\)," on page 249](#).

On CTRACE records, you cannot indicate more than one CTRACE specification per record. That is, once "CTRACE(xxxxxxx)" has been found, the rest of the record is treated as comments.

## FICON

---

Use the FICON statement to enable or disable switch statistics gathering (FICON STATS) and fabric I/O priority (FICON FABRICPRTY) on a system.

### FICON STATS

If enabled, FICON switch statistics are gathered on each system for all online FICON switches. In a sysplex environment it is not necessary for all systems to gather statistics, and, in fact, doing so might lead to I/O contention issues. If no FICON statement is specified, the system gathers switch statistics by default. To reduce I/O contention at FICON switches, IBM suggests that when in a sysplex environment FICON switch statistics gathering be disabled on all but one system.

### FICON STATS=YES|NO

Specifies whether FICON switch statistics gathering is enabled or disabled on a system.

**Tip:** If you specify STATS=NO to disable FICON statistics gathering, you might also want to turn off FICON Director Activity Reporting in Resource Measurement Facility (RMF).

**Default:** Yes

## FICON FABRICPRTY

If enabled, a switch fabric priority is assigned to I/O requests to allow higher-priority work to receive preference when a switch fabric becomes congested. This only enables z/OS to use the priority function. In order to fully exploit fabric priority, the following conditions must be true:

- The processor must support fabric priority and the global priority queuing option must be enabled.
- The control units must support fabric I/O priority. Contact your storage vendor for more information.
- The switch must support fabric I/O priority, and the switch ports connected to FICON channels and control units must be enabled for fabric priority. Contact your switch vendor for more information.
- A switch device must be defined in your I/O configuration and brought online to z/OS.

### FICON FABRICPRTY=YES|NO

Specifies whether FICON switch fabric I/O priority is enabled or disabled on a system.

**Default:** Yes

## STORAGE

---

Use the STORAGE statement to set storage properties for IOS. If no STORAGE statement is specified, IOS blocks will be obtained in 31-bit storage.

### STORAGE IOSBLKS=24|31

Specifies if IOS blocks will be obtained in 24 or 31 bit storage.

**Default:** 31

## CAPTUCB

---

Use the CAPTUCB statement to enable or disable write protection on captured UCBs. If no CAPTUCB statement is specified, write protection will be enabled on the system by default.

### CAPTUCB PROTECT=YES|NO

Specifies whether to enable write protection on captured UCBs.

**Default:** YES

## MIDAW

---

Use the MIDAW statement to enable or disable the MIDAW facility on a system. If no MIDAW statement is specified, the MIDAW facility is enabled on the system by default.

### MIDAW=YES|NO

Specifies whether the MIDAW facility is enabled or disabled on a system.

**Default:** YES

## HYPERPAV

---

Use the HYPERPAV statement to indicate whether HyperPAV mode is to be used and, if so, whether in BASEONLY mode or XPAV mode. The absence of this keyword in the parmlib member will cause no change to the system. For the initial IPL, the absence of the HYPERPAV keyword causes the system to IPL in HYPERPAV=NO mode.

### HYPERPAV=NO|BASEONLY|YES|XPAV

Specifies whether HyperPAV mode is to be used.

**NO**

Specifies that HyperPAV mode is not to be used.

**BASEONLY**

Specifies that I/O is to be run only on non-PAV-alias devices in HyperPAV mode.

**YES**

Specifies that HyperPAV mode is to be used.

**XPAV**

Specifies that HyperPAV mode is to be used, and wherever possible, allow aliases to be used for peer control units in the defining alias management group (AMG). This HyperPAV mode is also known as SuperPAV mode.

Control units on a storage controller with the exact same paths, in order, and those that share the alias management group number, as defined by the storage controller, are eligible to share alias devices when the system is operating in SuperPAV mode.

**Default:** NO

## HYPERWRITE

---

Use the HYPERWRITE statement to enable or disable IBM zHyperWrite data replication on a system. If no HYPERWRITE statement is specified, IBM zHyperWrite data replication is enabled on the system by default.

**HYPERWRITE=YES|NO**

Specifies whether IBM zHyperWrite data replication is enabled or disabled on a system-wide basis.

**Note:** Certain exploiting applications, such as DB2®, can also provide their own controls to enable or disable the use of this function.

IBM zHyperWrite processing can be used by I/O drivers, such as Media Manager, for certain write I/O operations to perform software mirroring to peer-to-peer remote copy (PPRC) devices that are monitored for HyperSwap processing (with GDPS® or TPC-R). IBM zHyperWrite data replication can be used to reduce latency in these HyperSwap environments. For maximum benefit, IBM zHyperWrite data replication should only be used when all synchronously mirrored relationships are managed by HyperSwap. Devices support IBM zHyperWrite data replication when the following conditions are true:

- The devices support IBM zHyperWrite data replication. Both the primary and secondary devices in a synchronous PPRC relationship must support this function.
- The devices in the synchronous PPRC relationship are managed by HyperSwap (either GDPS HyperSwap or TPC-R HyperSwap).

**NO**

IBM zHyperWrite data replication is disabled.

**YES**

IBM zHyperWrite data replication is enabled system-wide.

**Default:** YES

## EKM

---

Specify the encryption key management primary and secondary host names and the maximum number of concurrent socket connections that are allowed for the communication with the encryption key manager. By default, the primary and the secondary host names for the encryption key manager are set to NONE. Use the MAXCONN keyword to set the maximum number of socket connections that are possible with the encryption key manager. Some of the socket connections can remain open for faster communication. Use the MAXPCONN keyword to set the number of connections that remain open for faster communication. By default, the maximum number of socket connections to the encryption key manager is 255; eight socket

connections are permanently connected. However, if the sockets for communication are not needed, the sockets are not opened.

In-band tape encryption requires that the IOS address space has security permission for a z/OS UNIX System Services segment. The z/OS UNIX System Services segment is only for TCP/IP connectivity. UID(0) or super user ability is not required. For example, in RACF, issue the following command:

```
ADDUSER IOSAS OMVS(UID(xxxx) HOME('/'))
where xxxx is a unique user id.
```

**PRIMARY=host\_name[:port|,PRIPORT=port]|ipv4\_address[:port | ,PRIPORT=port]|  
ipv6\_address[,PRIPORT=port]| NONE**

Specifies the host name, IPv4 address or IPv6 address and optional port number of the primary key manager. The primary host is used exclusively unless a failure occurs and all attempts to retry fail. In subsequent requests after a failure, the primary host is retried before the use of the secondary host. When a connection to the primary host is established again, normal operation continues.

**host\_name[:port | ,PRIPORT=port]**

The host name of the encryption key manager.

**port**

The port number of the encryption key manager. The specification of port is mutually exclusive with the PRIPORT keyword. If port is not specified and the PRIPORT keyword is not specified, the default port is 3801.

**PRIPORT=port**

Specifies the port number for the host name or IP address for the primary key manager. PRIMARY= must be specified for PRIPORT= to be valid.

**Default:** 3801 (if not specified on the PRIMARY keyword)

**ipv4\_address[:port | ,PRIPORT=port]**

The IP address of the encryption key manager. The IP addresses must be specified as a dotted decimal quad: *ddd.ddd.ddd.ddd*.

**port**

The port number of the encryption key manager. The specification of port is mutually exclusive with the PRIPORT keyword. If port is not specified and the PRIPORT keyword is not specified, the default port is 3801.

**PRIPORT=port**

Specifies the port number for the host name or IP address for the primary key manager. PRIMARY= must be specified for PRIPORT= to be valid.

**Default:** 3801 (if not specified on the PRIMARY keyword)

**ipv6\_address[,PRIPORT=port]**

The IP address of the encryption key manager in IPv6 format (for example, ::FFFF:127.0.0.1 or 2001:0db8:85a3:08d3:1319:8a2e:0370:7344).

The optional port number for an IPv6 address must be specified with the PRIPORT keyword.

**PRIPORT=port**

Specifies the port number for the host name or IP address for the primary key manager. PRIMARY= must be specified for PRIPORT= to be valid.

**Default:** 3801 (if not specified on the PRIMARY keyword)

**NONE**

No encryption key manager is specified.

**Default:** None.

**SECONDARY=host\_name[:port | ,SECPOR=port] | ipv4\_address[:port | ,SECPOR=port]|  
ipv6\_address[,SECPOR=port]| NONE**

Specifies the host name, IPv4 address, or IPv6 address and optional port number of the secondary key manager.



**host\_name[:port | ,SECPORT=port]**

The host name of the encryption key manager.

**port**

The port number of the encryption key manager. The specification of port is mutually exclusive with the SECPORT keyword. If port is not specified and the SECPORT keyword is not specified, the default port is 3801.

**SECPORT=port**

Specifies the port number for the host name or IP address for the primary key manager. SECONDARY= must be specified for SECPORT= to be valid.

**Default:** 3801 (if not specified on the SECONDARY keyword)

**ipv4\_address[:port | ,SECPORT=port]**

The IP address of the encryption key manager. The IP addresses must be specified as a dotted decimal quad: *ddd.ddd.ddd.ddd*.

**port**

The port number of the encryption key manager. The specification of port is mutually exclusive with the SECPORT keyword. If port is not specified and the SECPORT keyword is not specified, the default port is 3801.

**SECPORT=port**

Specifies the port number for the host name or IP address for the secondary key manager. SECONDARY= must be specified for SECPORT= to be valid.

**Default:** 3801 (if not specified on the SECONDARY keyword)

**ipv6\_address[,SECPORT=port]**

The IP address of the encryption key manager in IPv6 format (for example, *::FFFF:127.0.0.1* or *2001:0db8:85a3:08d3:1319:8a2e:0370:7344*). The optional port number for an IPv6 address must be specified with the SECPORT keyword.

**SECPORT=port**

Specifies the port number for the host name or IP address for the secondary key manager. SECONDARY= must be specified for SECPORT= to be valid.

**Default:** 3801 (if not specified on the SECONDARY keyword)

**NONE**

No encryption key manager is specified.

**Default:** None.

**MAXCONN=ddd**

Specifies the maximum number of concurrent socket connections for Encryption Key Management. If high network stress occurs because of the high socket utilization for Encryption Key Management, this number can be lowered.

**Value range:** 1 to 255

**Default:** 255

**MAXPCONN=ddd**

Specifies the maximum number of concurrent socket connections for Encryption Key Management that remain open to prevent the overhead of opening and closing socket communication. This MAXPCONN keyword specifies the number of total connections reserved to be permanent connections.

**Value range:** 0 to the number specified in MAXCONN

**Default:** 8

The following figure shows syntax examples. To prevent contention while updating the EKM parameter, it is suggested that all operands are specified on the same EKM statement.

```

EKM PRIMARY=key.manager.com:3801,SECONDARY=key.manager.com
EKM PRIMARY=127.0.0.1:3801,SECONDARY=127.0.0.1
EKM PRIMARY=127.0.0.1,PRIPORT=3801,
  SECONDARY=127.0.0.1,SECPORT=3801
EKM PRIMARY=: :1
EKM PRIMARY=: :FFFF:127.0.0.1,PRIPORT=3801
EKM PRIMARY=2001:0db8:85a3:08d3:1319:8a2e:0370:7344,
  PRIPORT=3801
EKM PRIMARY=NONE, SECONDARY=NONE
EKM MAXCONN=255,MAXPCONN=8

```

## RECOVERY

Use the RECOVERY statement to enable or disable certain IOS recovery options on a system. The following recovery options are available:

- DCCF usage
- Limited recovery time
- Path recovery

### DCCF usage

If a no-paths or intervention-required condition is detected, MSGIOS002A or MSGIOS003A may be issued during IOS-enabled interrupt processing. If the error is on a paging device that is not currently enabled for hyperswap, IOS-enabled interrupt processing will not issue the IOS002A or IOS003A message, but will invoke the Disabled Console Communication Facility (DCCF) to issue a IOS115A WTOR. DCCF prevents all other work from running on the system until the operator replies to the WTOR. Loading a non-restartable wait state is preferable to issuing the IOS115A WTOR message.

The DCCF keyword is used to specify whether IOS-enabled interrupt processing will load a non-restartable wait state instead of issuing the IOS115A WTOR if a no-paths or intervention-required condition occurs on a paging device.

#### DCCF=MESSAGE

If DCCF=MESSAGE is specified, when a no-paths or intervention-required condition occurs on a paging device, IOS-enabled interrupt processing will invoke DCCF to issue the IOS115A WTOR. Refer to [z/OS MVS Planning: Operations](#) for information about DCCF processing. DCCF=MESSAGE is the default.

#### DCCF=WAIT\_STATE

If DCCF=WAIT\_STATE is specified, when a no-paths or intervention-required condition occurs on a paging device, IOS-enabled interrupt processing will load a non-restartable wait state X'140'. The wait state reason code will be 0000 for a no-paths condition and 0001 for an intervention-required condition. Message IOS140W will be issued with an indication of the error condition.

IBM recommends setting RECOVERY DCCF=WAIT\_STATE in IECIOUSxx to avoid the complexity of DCCF processing for the IOS115A WTOR message.

### Limited recovery time

A LIMITED\_RECTIME between 2 and 14 seconds can be specified for either Direct Access Storage Devices (DASD) or only devices that have the I/O timing facility enabled. When the limited recovery time function is enabled, IOS will use this value to time an IOS recovery I/O request to the qualified devices. If this I/O request suffers a start pending, a missing channel end or device end, or an interface timeout condition, the IOS recovery I/O request will not be retried on that device-path. To disable the limited recovery time function, specify LIMITED\_RECTIME=0.

When specifying limited recovery time interval, consider the following situations.

- If the limited recovery time interval is longer than the I/O timing time interval for the device, an I/O time out condition is detected first and exploiting the limited recovery time function provides no value.
- If the limited recovery time interval is longer than the MIH time interval for the device, the MIH time out condition is detected first and exploiting the limited recovery time function provides no value.



**Attention:** With the specification of LIMITED\_RECTIME, a Sense Path Group ID (SNID) CCW timeout on a device-path will be considered a permanent error, which will result in the path being taken offline. If the SNID to the last available path also times out, the device will be boxed. Therefore, the LIMITED\_RECTIME option should be used with caution by installations that want to reduce the allowable time for a recovery I/O request but are also able to handle device availability issues. Customers who consider exploiting the limited recovery time function are making a conscious trade-off between minimizing IOS recovery elapsed time and 100% availability of I/O resources.

Note that, in general, specifying LIMITED\_RECTIME will not help in the case of a no paths condition and will not cause a device to be boxed unless a reserve is lost.

## Path recovery

In a defined I/O configuration, many devices share common hardware components (such as channels, channel cards, switches, control unit ports, control unit adapter cards, and fiber-optic links). For example, all devices for a specific control unit definition share hardware components since they share channels and control unit ports. Therefore, when a hardware-related error occurs on a channel path, multiple devices are affected.

When an error occurs on a channel path, the system performs path recovery, which consists of issuing one or more recovery-related I/Os to test the channel path to see whether it is still usable. If path recovery determines that the channel path is no longer usable, the path is removed (varied offline) from the affected device. Otherwise, the channel path remains online to the device.

Path recovery is typically performed one device at a time. This means that when an error occurs on one device, only that device is processed. Errors on other devices are processed independently, even if they share common hardware components. This might affect application performance since the application is delayed while the system performs path recovery and then retries the original I/O request. If the application uses multiple devices that share a failing or malfunctioning hardware component, additional errors are encountered and further delays occur.

Additionally, certain types of path errors can be intermittent. That is, an error occurs, but path recovery is successful, so the path is not removed from the device. This also affects performance because applications might encounter errors multiple times. If this occurs, consider manually removing the bad path or paths from the affected devices to stop the errors from occurring.

Specify a PATH\_SCOPE of either CU or DEVICE to enable path recovery either for all devices that are attached to the control unit (CU) or to use a traditional path recovery on a device-by-device basis (DEVICE). The default is PATH\_SCOPE=DEVICE.

The PATH\_SCOPE option of CU, along with the PATH\_THRESHOLD and PATH\_INTERVAL options, can reduce the elapsed time that it takes for the system to recover from certain channel path-related errors and helps prevent system performance problems that can occur when a significant amount of time is spent in repetitive channel path error recovery.

### PATH\_SCOPE=CU

If PATH\_SCOPE=CU is specified and path recovery determines that a channel path needs to be removed from a device, for certain types of errors, the path is removed from all devices that are defined to the control unit. Additionally, for certain intermittent channel path errors, the system collects error statistics over a period of time, and if the number of errors reaches or exceeds a threshold value, the channel path is removed from all devices that are defined to the control unit. The time period and threshold are controlled by the PATH\_INTERVAL and PATH\_THRESHOLD parameters as follows:

- PATH\_INTERVAL specifies the length of time to monitor for errors (for example, 10 minutes).

- `PATH_THRESHOLD` specifies the minimum number of path-related errors that must occur every minute for the specified period of time (`PATH_INTERVAL`) before the path from the failing hardware component is removed from all the affected devices.

For example, specifying a `PATH_INTERVAL` of 10 (minutes) and a `PATH_THRESHOLD` of 20 (errors per minute) means that at least 20 errors must occur every minute for 10 consecutive minutes before the path from the failing hardware component is removed from all the affected devices.

#### Notes:

1. Do not set the interval and threshold values to a very low value (for example: setting `PATH_THRESHOLD=1` and `PATH_INTERVAL=1`) because low values might prematurely trigger path recovery or with normal system recovery and cause the system to remove channel paths unnecessarily.
2. Changing the value of the interval and the threshold keywords does not take effect until the next error is encountered and will not affect actions that were previously taken.

### Important `PATH_SCOPE` considerations

The default value is `RECOVERY PATH_SCOPE=DEVICE`. The operating system will perform traditional z/OS device recovery. When an error occurs that causes z/OS to remove the path, the path is removed only from that device. No thresholding of interface control checks (IOS050 and IOS051 messages) or other path related errors occurs.

It is often difficult to predict how quickly errors can and will occur. However, the impact of the repetitive FICON fabric errors will affect system performance. Typical fabric errors will occur in bursts; therefore, installations may opt to be more proactive in terms of how quickly to remove a path from a control unit. If the desired outcome is to be more proactive, consider using `PATH_SCOPE=CU` with more aggressive `PATH_INTERVAL` and `PATH_THRESHOLD` values than the defaults.

When `PATH_SCOPE=CU` is specified, for certain intermittent channel path errors, the system collects error statistics over a period of time on a control unit basis rather than single device and focuses recovery on a control unit basis. If this option is used, the system reacts by taking the affected path offline to all devices on a control unit versus a single device when `RECOVERY PATH_SCOPE=DEVICE` is specified.

If `PATH_SCOPE=CU` is specified, the default values are:

```
PATH_INTERVAL=10
PATH_THRESHOLD=10
```

This means that 10 channel detected errors must occur every minute for 10 consecutive minutes for the system to take the path offline to the control unit.

Consider the following options which are more aggressive:

```
SETIOS RECOVERY,PATH_SCOPE=CU,PATH_THRESHOLD=10,PATH_INTERVAL=1
```

- `PATH_SCOPE=CU` collects error statistics for each path on a control unit basis rather than single device.
- `PATH_INTERVAL=1` shortens the error time to 1 minute instead of the default 10 minutes.
- `PATH_THRESHOLD=10` is the number of errors on a path for a given control unit that need to incur within the interval, as specified by the `PATH_INTERVAL` keyword. In this case, the path will be removed if there are 10 errors in a 1-minute interval.

**Note:** This `RECOVERY` function will *not* remove a path from a particular device on the given control unit if this is the last path to the device, regardless of whether the device is allocated or not.

### `PATH_SCOPE=DEVICE`

If `PATH_SCOPE=DEVICE` is specified, then path recovery is on a device-by-device basis and no monitoring of intermittent errors is performed.

**Note:** `PATH_INTERVAL` and `PATH_THRESHOLD` are not valid keywords with `PATH_SCOPE=DEVICE`.

## Statements and parameters for RECOVERY

### **DCCF=MESSAGE|WAIT\_STATE**

Specifies the action that IOS-enabled interrupt processing will take when a no-paths or intervention-required condition occurs on a paging device. With the MESSAGE option, DCCF is invoked to issue the IOS115A WTOR. With the WAIT\_STATE option, a non-restartable wait state X'140' is loaded.

To avoid the complexity of DCCF processing for the IOS115A WTOR message, set RECOVERY DCCF=WAIT\_STATE in IECIOSxx .

**Default:** MESSAGE.

### **DEV=DASD|IOTIMING**

Specifies the devices that exploit the limited recovery time function. Valid options are all DASD devices or only devices that have the IOTIMING facility enabled.

### **LIMITED\_RECTIME=ss**

Specifies the time in seconds to be used for certain IOS recovery functions. Specify 0 seconds to disable the limited recovery time function. If the limited recovery time function is disabled, IOS continues to use its predefined value to time the IOS recovery I/O requests. The limited recovery time function is disabled by default.

**Value range:** 2-14 (seconds).

### **PATH\_INTERVAL=nnn**

Specifies the length of time to monitor for channel path errors in minutes. This keyword can only be used when PATH\_SCOPE=CU is specified or when PATH\_SCOPE=CU is the current value for the scope of the path recovery.

**Value range:** 1-10 (minutes).

**Default:** 10.

### **PATH\_SCOPE={CU|DEVICE}**

Specifies whether the scope of the path recovery is for all devices that are attached to the control unit (CU) or on a device-by-device basis (DEVICE).

PATH\_SCOPE=CU applies to a selected group of path-related errors. See [“Usage notes for RECOVERY”](#) on page 503.

**Default:** DEVICE.

### **PATH\_THRESHOLD=nnn**

Specifies the minimum number of channel path-related errors that must occur every minute for the specified time (PATH\_INTERVAL) before IOS takes action. This keyword can only be used when PATH\_SCOPE=CU is specified or when PATH\_SCOPE=CU is the current value for the scope of the path recovery.

**Value range:** 1-100 (errors).

**Default:** 10.

PATH\_THRESHOLD applies to a selected group of path-related errors. See [“Usage notes for RECOVERY”](#) on page 503.

## **Usage notes for RECOVERY**

A path is automatically taken offline to all devices in a control unit when one of the following occurs and PATH\_SCOPE=CU is specified:

- If a SNID command fails for a device (other than for a no paths condition):
  - SNID (Sense Path Group Id) can be issued to validate the state of a path when path-related errors occur, for example, an interface timeout (message IOS051I) or missing interrupt condition (message IOS071I) will cause the system to issue SNID commands.

- If an inoperative path condition is detected on one or more paths to a device (IOS001E) and the processor link error threshold was exceeded (IOS2001I or IOS2002I indicates a LINK RECOVERY THRESHOLD EXCEEDED condition).
- If Path\_Threshold is specified and the threshold is reached as a result of the following errors:
  - Interface control checks for DASD and tape devices; for example, messages IOS050I and IOS051I.
  - Unit checks for tape devices that indicate some sort of path-related error.

Other errors such as missing interrupt conditions (IOS071I) are not counted towards the error threshold.

## Syntax example

```
RECOVERY PATH_SCOPE=CU,PATH_INTERVAL=10,PATH_THRESHOLD=100
```

## SPOF

Use the SPOF statement to set options for the IOSSPOF system service. The IOSSPOF service is used by programs to check for I/O configuration redundancy of DASD devices or pairs of DASD devices.

**SPOF IGNORE=**{([parameter])|(parameter[,parameter]...)|NONE}

Specifies which IOSSPOF service checks to ignore.

**parameter** is one of the following:

### PCU

Specifies that physical control unit single point of failure (SPOF) checks for devices that share the same physical control unit not be performed.

### PDRAWER

Specifies that processor drawer SPOF checks for host chpids sharing the same processor drawer not be performed.

### PCUHSWAP

Specifies that physical control unit single point of failure (SPOF) checks for HyperSwap managed devices that are ignored or not performed.

### NONE

Specifies that all SPOF checks be performed.

**Default:** NONE

### Notes:

1. You cannot specify NONE with any of the other SPOF IGNORE parameters. If you specify NONE with any of the other SPOF IGNORE parameters, the system gives you a syntax error for the SPOF IGNORE statement.
2. On SPOF IGNORE statements with a list of parameters, the parameters can appear in any order.
3. The PCU and PCUHSWAP operands are mutually exclusive with each other.
4. The PCUHSWAP option only applies for those devices that are in a HyperSwap configuration. If a device is not part of a HyperSwap configuration, a physical control unit SPOF message is issued. Note that a device is also not part of a HyperSwap configuration immediately after IPL or immediately after a HyperSwap.

## ZHPF

Use the ZHPF statement to enable or disable the High Performance FICON for IBM z Systems (zHPF) facility on a system. If no ZHPF statement is specified, the zHPF facility is disabled on the system by default.

**ZHPF=YES|NO**

Specifies whether the zHPF facility is enabled or disabled on a system.

**Default:** NO

**Note:** A reserve is done synchronously regardless of any SYNCHRES=NO specification if ZHPF is enabled and the device operates I/O in Transport Mode.

## ZHPFOPTS

---

Use the ZHPFOPTS statement to set options for the High Performance FICON for IBM z Systems (zHPF) facility on a system. ZHPF may currently be enabled or disabled when this command is issued.

**MAXSIZE={nnnn | SYSTEM}**

Specifies the maximum data transfer size for zHPF I/O requests. If *nnnn* is specified, this represents the maximum transfer size in megabytes, where 1 megabyte = 1,048,576 bytes. If the value specified is larger than the maximum data transfer size supported for a device, the device maximum will be used. If SYSTEM is specified, the maximum data transfer size for zHPF I/O requests is determined by the system based on the maximum data transfer size supported by the device and its online CHPIDs.

**Important:** The maximum data transfer size should only be set at the direction of IBM support. Otherwise, I/O performance may be impacted.

**Value range:** 1 - 1024 (1 MB to 1 GB) or SYSTEM

**Default:** SYSTEM

**READSEC={YES|NO}**

Specifies whether the consistent read from secondary facility is enabled (YES) or disabled (NO) for zHPF and zHyperLink read I/O operations on a system-wide basis.

**Default:** NO

## ZHYPERLINK

---

Use the ZHYPERLINK statement to enable, disable the zHyperlink facility. If no ZHYPERLINK statement is specified, the zHyperlink facility is disabled on the system by default. The ZHYPERLINK keyword may be abbreviated as ZHL.

**ZHYPERLINK OPER=ALL|READ|WRITE|NONE,READLIMIT=n]****ZHL OPER=ALL|READ|WRITE|NONE,READLIMIT=n]**

Specifies whether the zHyperlink facility is enabled on a system for all I/O operations, only read I/O operations, only write I/O operations, or disabled for all I/O operations.

**,READLIMIT=n]**

*n* indicates the read data limit, expressed in KB. For example, when 4 is specified, the read data limit is 4 K + 32 (32 bytes is always added to the specified limit). The valid range is 0 to 32.

If no value is specified or 0 is specified, the system uses the default for the detected zHyperLink capability. When original zHyperLink capability is detected, regardless of what is specified, the read data limit remains at 4 K + 32. When zHyperLink Acceleration is detected, the default read data limit is 16 K + 32.

This value is made available to access methods that use ZHYPERLINK. It is up to the access method to use this data limit when determining whether I/Os are candidates for ZHYPERLINK read attempts. For example, IBM Media Manager may be used to read a VSAM dataset with CI size of 8 K. IBM Media Manager would use the read limit that is in effect for one or more devices that contain the VSAM dataset and decides whether ZHYPERLINK read operations can be used. For more information about ZHYPERLINK I/O operations, see [zHyperLink I/O in z/OS DFSMS Using Data Sets](#) and [Defining use of zHyperlinks in z/OS DFSMSdfp Storage Administration](#).

**Default:** NONE

## Syntax examples for IECIOSxx

In Figure 14 on page 506, the last two MIH records specify IOTIMING=00:00 and TIME=00:00. These specifications cancel MIH or I/O timing processing for the device numbers on the associated DEV keyword. Similarly, you can cancel hot I/O processing by specifying:

```
HOTIO DVTHRS=0
```

**Note:** For 3800 devices, the default of 3 minutes for the MIH interval might not be sufficient. The recommended MIH interval for a 3800 is 5 minutes.

```
HOTIO DVTHRS=200
MIH STND=02:30,DASD=00:10,DEV=03C0,TIME=01:30
MIH DEV=(2E8-2FF,7300-7370),TIME=00:30
MIH 3851=15:00
HOTIO DFLT110=(BOX,BOX)
HOTIO DFLT111=(CHPK,BOX)
HOTIO DFLT112=(CHPK,BOX)
HOTIO SDFT110=(BOX,BOX)
HOTIO SDFT111=(CUK,BOX)
HOTIO SDFT112=(CUK,BOX)
HOTIO BOX_LP=(DASD,TAPE,UREC,COMM,CTC,GRAF,CHAR,ALL)
HOTIO BOX_LP=(DASD,TAPE,UREC)
HOTIO BOX_LP=(ALL)
MIH IOTIMING=00:12,DEV=(2E8-2FF,730-737)
MIH IOTIMING=00:12,DEV=200,MSGONLY=YES
MIH IOTDASD=10:00,MSGONLY=YES
MIH CTC=02:30,IOTIMING=00:00,DEV=(180-187,230,B10-B17)
MIH TIME=00:00,DEV=(180-187,230,B10-B17)
TERMINAL BOX_LP=(DASD)
TERMINAL BOX_LP=(TAPE,UREC)
TERMINAL BOX_LP=(ALL)
CTRACE(CTIIOS00)
CAPTUCB PROTECT=YES
FICON STATS=YES
FICON FABRICPRTY=YES
STORAGE IOSBLKS=31
MIDAW=YES
HYPERPAV=YES
ZHPF=YES
ZHPFOPTS,MAXSIZE=SYSTEM,READSEC=YES
HYPERWRITE=YES
SPOF IGNORE=(PDRAWER,PCU)
SPOF IGNORE=(PDRAWER,PCUHSWAP)
SPOF IGNORE=NONE
SPOF IGNORE=PCU
SPOF IGNORE=PDRAWER
SPOF IGNORE=PCUHSWAP
ZHYPERLINK,OPER=ALL
```

Figure 14. Syntax examples for IECIOSxx



## Chapter 58. IEFOPZxx (data set optimization configuration)

IEFOPZxx contains statements that define the load library data set optimization configuration, which could, for example, provide a list of pairings of an old COBOL load library and the intended new load libraries (one for each desired architecture level) and specifies which members are to be processed (optimized). The system will accomplish this by concatenating the new library ahead of the old library.

The IEFOPZ configuration is defined primarily in terms of IEFOPZ-Old/IEFOPZ-New load library data set pairs and DDNAME/JOBNAME pairs. A load library data set identified by the OLD parameter in IEFOPZxx is referred to as an IEFOPZ-Old data set. A load library data set identified by the NEW parameter in IEFOPZxx is referred to as an IEFOPZ-New data set.

Use of IEFOPZxx requires the use of PROGxx and not LNKSTxx for defining the LNKST; otherwise you will be prompted to acknowledge that IEFOPZ processing will not be in effect. IEFOPZxx is acted upon by the IEFOPZ system parameter and the SET IEFOPZ system command.

All character string values (*ddname*, *dsname*, *jobname*, *owner*, *plexname*, *sysname*, *volname*) will be translated to uppercase.

**Note:** The system will not manage security-related considerations for the data sets; that is up to you. Some examples of security-related considerations are APF-authorized data sets and RACF access control to data sets. For example, if you have an IEFOPZ-Old data set that is APF-authorized, you might want the related IEFOPZ-New data set to be APF-authorized. Similarly, you might want to grant RACF access to the IEFOPZ-New data set that is similar to that currently granted to the IEFOPZ-Old data set.

### Parameter in IEASYSxx (or supplied by the operator)

```
IEFOPZ={aa
        { (aa,bb... ) }
```

This parameter specifies one or more suffixes of the IEFOPZxx parmlib member to be used by the system. The two characters, represented by *aa* (or *bb*, and so on), are used as a suffix appended to IEFOPZ to form the name of the IEFOPZxx members to be used by the system. No more than 38 suffixes can be specified. The IEFOPZxx parmlib member contains parameters for managing the IEFOPZ configuration.

### Syntax rules for IEFOPZxx

These rules apply to the creation of IEFOPZxx:

- Enter data only in columns 1 through 71.
- Do not enter data in columns 72 through 80; the system ignores these columns.
- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.

The system will keep track of a parmlib member suffix list, which identifies the parmlib members that comprise the IEFOPZ definition. It starts with the data from the IEFOPZ system parameter and is replaced upon any subsequent successful SET IEFOPZ command. The parmlib member suffix list can be displayed by the DISPLAY IEFOPZ,STATUS command. All of the parmlib member statements are treated as replacements of the existing data.

### Syntax format of IEFOPZxx

```
[SYSNAME(* | sysname)] [SYSPLEX(* | plexname)]
[KEEPOERROR( {NONE | VALID} )]
[CHECKALL | CHECKACTIVE]
[MAXARCH(nn | CURRENT)]
```

```

OWNER(owner) MINARCH(nn)
OLDNEW(...)
  [OWNER(owner)]
  OLD(DSNAME(dsname) [VOLUME(volname)])
  NEW(DSNAME(dsname1) [VOLUME(volname1)] [ARCH(nn1)])
  NEW(DSNAME(dsname2) [VOLUME(volname2)] [ARCH(nn2)])
  NEW(...)
  [INCLUDEMEMBERS(memberlist)
   [EXCLUDEMEMBERS(memberlist)]]
  [ACTIVE | INACTIVE]
)
DDNAME(ddname) JOBNAME(jobname)
LLA(YES | NO)
LNKLST(YES | NO)
[REINITIALIZE]

```

The system will keep track of a parmlib member suffix list, which identifies the parmlib members that comprise the IEFOPZ definition. It starts with the data from the IEFOPZ system parameter. It is replaced upon a subsequent successful SET IEFOPZ command. The parmlib member suffix list can be displayed by the DISPLAY IEFOPZ,STATUS command. All of the parmlib member statements are treated as replacements of the existing data.

## IBM-supplied default for IEFOPZxx

---

None.

## Statements and parameters for IEFOPZxx

---

### **SYSNAME(\* | *sysname*)**

Is a filtering statement used to specify the system or systems to which the subsequent statements are to apply. *sysname* specifies a 1-8 character system name that can include wildcards. Do not use embedded blanks within a quoted *sysname*.

All subsequent statements (except for other filtering statements, which will update the specified filter) until the end of the parmlib member will be processed using *sysname* as a filter. If running with a system name that matches *sysname*, the statement will be processed. If not (aside from checking for some syntax and semantics errors) the statement will be ignored.

**Default:** SYSNAME(\*), which specifies to match all systems.

### **SYSPLEX(\* | *plexname*)**

Is a filtering statement used to specify the sysplex or sysplexes to which the subsequent statements are to apply. *plexname* specifies a 1-8 character sysplex name that can include wildcards. Do not use embedded blanks within a quoted *plexname*.

All subsequent statements (except for other filtering statements, which will update the specified filter) until the end of the parmlib member will be processed using *plexname* as a filter. If running with a sysplex name that matches *plexname*, the statement will be processed. If not (aside from checking for some syntax and semantics errors) the statement will be ignored.

**Default:** SYSPLEX(\*), which specifies to match all sysplexes.

### **KEEPONERROR(NONE|VALID)**

Defines the system behavior when errors are encountered when processing the IEFOPZxx parmlib members. Some possible errors are syntax errors and errors in the accessibility of the specified IEFOPZ-Old or IEFOPZ-New data sets. This specification (subject to SYSPLEX and SYSNAME filtering) applies to the entire processing of the IEFOPZ system parameter or SET IEFOPZ command regardless of where it is specified in the set of identified parmlib members. If multiple valid specifications are encountered, the last one will be in effect.

### **KEEPONERROR(NONE)**

Indicates that none of the processed statements are to be placed into the configuration (that is, the configuration is to remain unchanged). If there is a problem reading one of the identified parmlib members (such as would happen if it does not exist), KEEPONERROR(NONE) is used even if KEEPONERROR(VALID) is in effect.

**KEEPONERROR(VVALID)**

Indicates that the configuration is to be formed from the valid statements. For example, there might still be valid MAXARCH and OLDNEW statements.

The default is:

- KEEPONERROR(NONE) when processing the SET IEFOPZ command
- KEEPONERROR(VVALID) when processing the IEFOPZ system parameter.

**CHECKALL|CHECKACTIVE**

Specifies the extent of data set checking to be done.

**CHECKALL**

Specifies that the system is to validate all the IEFOPZ-Old and IEFOPZ-New data sets that match the SYSNAME/SYSPLEX criteria. Exploiters that might be dealing with IEFOPZ-Old data sets that are inactive or with IEFOPZ-New data sets that do not correlate to the MAXARCH value might benefit from CHECKALL processing, because it will alert you to problems that those exploiters might have with any of those data sets.

**CHECKACTIVE**

Specifies that the system is to validate only IEFOPZ-Old data sets that are active and the single IEFOPZ-New data set for that IEFOPZ-Old data set that correlates to the MAXARCH value. The system IEFOPZ processing itself uses only these data sets (but exploiters might use others). CHECKACTIVE does less processing than CHECKALL.

CHECKACTIVE can be specified as CHECKACT.

**Default:** CHECKALL

**MAXARCH(nn|CURRENT)**

Identifies the maximum architecture level to be used, even if the machine is at a higher level. The default is the architecture level of the machine. If you want to specify the default, specify MAXARCH(CURRENT). You can specify a value greater than the architecture level of any current machine, but if you do, the architecture of the current machine will be used for MAXARCH. For a given IEFOPZ-Old data set, the system will use the IEFOPZ-New data set with ARCH value closest to, but not exceeding, MAXARCH. This is referred to as the data set corresponding to MAXARCH. *nn* must be 1-2 decimal digits with a value in the range 8-99, indicating that the minimum MAXARCH is for a z10, which is the minimum for z/OS V2R2. The optimization product could have a supported range that is different than that and might reject specifications that are outside of its supported range. See the description of the ARCH parameter for examples of the value corresponding to a particular machine.

**OWNER(owner) MINARCH(nn)**

Identifies the minimum architecture level that this particular owner accepts, specifically for the case where that minimum level is greater than the minimum level accepted, in general, by IEFOPZ processing. This specification is solely to help the system detect, as early as possible, entry errors in ARCH.

**OWNER(owner)**

OWNER(*owner*) identifies the owner for which the MINARCH value is to be set. It can contain wildcard characters. *owner* can be no longer than 16 characters. Unless specified within quotes, aside from wildcard characters, it should consist of characters from among: alphanumeric, national, period, and underscore. If specified within quotes, *owner* can contain embedded blanks.

OWNER can be specified as OWN.

**MINARCH(nn)**

Identifies the minimum architecture level that this particular owner accepts, specifically for the case where that minimum level is greater than the minimum level accepted, in general, by IEFOPZ processing.

The value range for MINARCH(*nn*) is the same as the value range for MAXARCH.

The OWNER for an OLDNEW statement will be matched against the OWNER/MINARCH pairs. The MINARCH value for the first matching non-wildcarded OWNER will be used. If no matching non-wildcarded OWNER is found, the MINARCH value for the first matching wildcarded OWNER will be

used. If an IEFOPZ-New data set has an ARCH value less than this MINARCH value, this OLDNEW statement will be rejected. See the description of the ARCH parameter for examples of the value corresponding to a particular machine.

### **OLDNEW(parameters)**

Identifies an IEFOPZ-Old/IEFOPZ-New relationship. OLDNEW must contain one OLD statement and one or more NEW statements. There can be an INCLUDE MEMBER list. There can be an EXCLUDE MEMBER list. The pairing can be designated as active or inactive. For an OLDNEW that is active, at least one of the NEW specifications must have an ARCH value less than or equal to the MAXARCH value. There can be multiple OLDNEW specifications. All such specifications are used.

The parameters of the OLDNEW statement are:

#### **OWNER(owner)**

Identifies the owner of the application that will use this definition. The default owner is IBM. *owner* can be no longer than 16 characters. Unless specified within quotes, it must consist of characters from among: alphanumeric, national, period, and underscore. If specified within quotes, the *owner* value can contain embedded blanks.

#### **OLD(DSNAME(dsname)[,VOLUME(volname)])**

Identifies the pre-optimized load library.

##### **DSNAME(dsname)**

*dsname* is a valid 1 to 44 character data set name. The data set specified by *dsname* is known as an IEFOPZ-Old data set.

Other considerations for specifying an IEFOPZ-Old data set data set are:

- The system expects, but does not enforce, that the IEFOPZ-Old data set is a load library, that it is not a tape data set, and that it is not a GDG Base.
- An IEFOPZ-Old data set must not match any IEFOPZ-New data set.
- Do not specify an alias of an IEFOPZ-Old data set as an IEFOPZ-New data set, or vice versa. The system might not enforce this.
- An IEFOPZ-Old data set must not have the same name as any of the data sets identified by the PROGxx SYSLIB statement as being automatically part of the LNKLIST, or any of the defaults for those data sets (SYS1.LINKLIB, SYS1.CSSLIB, SYS1.MIGLIB, SYS1.SIEALNKE, SYS1.SIEAMIGE). The system will enforce the case of not using the defaults, and after IPL only will enforce the case of using a data set identified by the SYSLIB statement as being automatically part of the LNKLIST.

DSNAME can be specified as DSN.

##### **VOLUME(volname)**

Optionally specifies a volume to be used. *volname* must be 1 to 6 characters. It must be a valid volume name once normal symbol substitution has occurred. You can use a value of *"\*MCAT"* to indicate that the data set is located on the volume containing the IPL-time master catalog. The system is to use the data set on that volume. Note that, as with normal allocation processing (as described for the VOLUME parameter in the z/OS MVS JCL Reference), if the volume is SMS-managed, then the system will find and allocate the data set to the volume on which it resides, even if that is different from the volume specified.

When no volume is specified, the system uses the catalog to determine the volume to use.

VOLUME can be specified as VOLSER or VOL.

The following rule will be applied for a JCL (or dynamic allocation) case that provides DSN without volume (the system will locate the volume from the catalog as part of its processing and will determine the real data set name if the specification was an alias). In all cases, it is that real data set name that is used for the match.

- If there is an IEFOPZ-Old data set with matching DSN and with a specified volume that matches what the system found, then that IEFOPZ-Old data set is used.

- Else if there is an IEFOPZ-Old data set with no specified volume and with matching DSN (the match uses the IEFOPZ-Old data set's DSN's real DSN if the IEFOPZ-Old data set's DSN was an alias) then this IEFOPZ-Old data set is used (whether or not the earlier system look up of the DSN in the catalog found the same volume that the system located in the catalog this time)
- Else there is no match

The following rule will be applied for a JCL (or dynamic allocation) case that provides both DSN and volume (for example, DSN=MY.DS,VOL=SER=V):

- If there is an IEFOPZ-Old data set with matching DSN and with a specified volume that matches, then that IEFOPZ-Old data set is used
- Else if there is an IEFOPZ-Old data set with no specified volume and with matching DSN (the match uses the IEFOPZ-Old data set's DSN's real DSN if the IEFOPZ-Old data set's DSN was an alias) but when the system earlier had looked up the DSN in the catalog the volume that was found matches, then this IEFOPZ-Old data set is used
- Else there is no match. This includes the case of an IEFOPZ-Old data set with no specified volume where, for example, when the IEFOPZ-Old data set was created, the catalog entry for MY.DS was for volume V2. In the example, then, the JCL had MY.DS on V, and the IEFOPZ-Old data set has MY.DS for V2. The system does not look up MY.DS in the catalog when processing the JCL in order to avoid undesirable extra overhead, and thus does not know if the current catalog entry is for volume V.

If the IEFOPZ-Old data set is in the IPL-time LNKST, then the data set must either be cataloged in the master catalog or the volume must be specified. Also, the data set must be cataloged in the post-IPL catalog (just not necessarily in the master catalog).

**Note:** For an IEFOPZ-Old data set that is provided without volume, the system will recognize that a data set of that name in the LNKST is the same as the IEFOPZ-Old data set only if the LNKST data set was provided without volume. Conversely, for an IEFOPZ-Old data set that is provided with volume, the system will recognize that a data set of that name in the LNKST is the same as the IEFOPZ-Old data set only if the LNKST data set was provided with that same volume.

#### **NEW(DSNAME(*dsname*)[,VOLUME(*volname*)][,ARCH(*nn*)])**

identifies an optimized load library and its architecture level.

##### **DSNAME(*dsname*)**

*dsname* identifies an optimized load library (1 to 44 characters). It must be a valid data set name. The data set specified by *dsname* is known as an IEFOPZ-New data set.

IBM suggests that a naming convention be used that includes the ARCH value or machine class (such as z13) in the name, so that it is easy to tell at a glance what is the intended ARCH level of the code in the IEFOPZ-New data set.

The default is to use the volume located by the catalog. Alternatively, you can provide the volume to be used. If the IEFOPZ-New data set that corresponds to MAXARCH is for an IEFOPZ-Old data set in the IPL-time LNKST, then the master catalog entry for the IEFOPZ-New data set will be used when no volume is provided. For the LNKST case, even when no volume is provided, the data set must still be cataloged, just not necessarily in the master catalog. The IEFOPZ-New data sets for an IEFOPZ-Old data set must have unique ARCH level values.

The system expects, but does not enforce, that the IEFOPZ-New data set is a load library, that it is not a tape data set, and that it is not a GDG Base.

Other considerations for specifying an IEFOPZ-New data set are:

- No IEFOPZ-New data set can match any IEFOPZ-Old data set. You must not specify the same IEFOPZ-New data set with different ARCH levels.
- Do not specify an IEFOPZ-New data set with a certain ARCH level along with an alias of that IEFOPZ-New data set with a different ARCH level. The system might not enforce this.
- You can specify the same IEFOPZ-New data set for multiple IEFOPZ-Old data sets.

- Do not specify for NEW a data set with the same name as any of the data sets identified by the PROGxx SYSLIB statement as being automatically part of the LNKLIST, or the defaults for those data sets (SYS1.LINKLIB, SYS1.CSSLIB, SYS1.MIGLIB, SYS1.SIEALNKE, SYS1.SIEAMIGE). The system will enforce the case of not using the defaults, and after IPL only will enforce the case of using a data set identified by the SYSLIB statement as being automatically part of the LNKLIST.

DSNAME can be specified as DSN.

#### **VOLUME(*volname*)**

specifies a volume to be used for this IEFOPZ-New data set. *volname* must be 1 to 6 characters. It must be a valid volume name once normal symbol substitution has occurred. You can use a value of `"*MCAT"` to indicate that the data set is located on the volume containing the IPL-time master catalog. The system is to use the data set on that volume. Note that, as with normal allocation processing (as described for the VOLUME parameter in the z/OS MVS JCL Reference), if the volume is SMS-managed, then the system will find and allocate the data set to the volume on which it resides, even if that is different from the volume specified.

When no volume is specified, the system uses the catalog to determine the volume to use.

VOLUME can be specified as VOLSER or VOL.

#### **ARCH(*nn*)**

Identifies the architecture level of this IEFOPZ-New data set. It must be 1-2 decimal digits with a value from the minimum MAXARCH to 99. When optimized code is placed into this data set, it is expected to have been done under control of that architecture level definition. ARCH is required. The values available for *nn* match those of the ARCH parameter supported by the C/C++ compiler. For example, ARCH(8) corresponds to the z10 machine, ARCH(9) to the z196 machine, ARCH(10) to the zEC12 machine, and ARCH(11) to the z13 machine. Specifying a value higher than any machine for which you might use this specification will result in a data set that is not used. The ARCH value can exceed the MAXARCH value of the IPL'd-upon machine, so that you can use the same parmlib member for multiple machines. You must not specify an ARCH level outside the range of values supported by the optimization process (which will document that range), but the maximum value will not be enforced. Specifying a value outside of the range will result in not producing valid members in the IEFOPZ-New data set, because the optimization process will not complete successfully.

If the IEFOPZ-Old data set is in the LNKLIST, the IEFOPZ-New data set that corresponds to MAXARCH will be placed into the concatenation immediately ahead of IEFOPZ-Old data set. If the IEFOPZ-New data set is already in the concatenation ahead of where the IEFOPZ-Old data set will go, it will be left in that position. If the IEFOPZ-New data set is already in the concatenation but below where the IEFOPZ-Old data set will go, it will be moved to the proper place. That IEFOPZ-New data set must either be cataloged in the master catalog or the volume must be specified. The volume for a data set in the LNKLIST must match the volume in the catalog entry that LLA will find when it looks up the data set by its name (this is the same rule that applies to all LNKLIST data sets)

#### **INCLUDEMEMBERS(*memberlist*)**

Identifies the members that the optimization product is to process for this IEFOPZ-Old data set. *memberlist* is a comma delimited list of 1 to 8 character member names. Wildcards can be used. Do not use embedded blanks within a quoted member name. All matching members will be processed. The default is to process all members. z/OS itself does nothing with this list other than return it upon request by the IEFOPZQ service.

INCLUDEMEMBERS can be specified as IMEM, INCLUDEMEM, or INCLUDEMEMBER.

#### **EXCLUDEMEMBERS(*memberlist*)**

Identifies the members that the optimization product is not to process for this OLD. *memberlist* is a comma delimited list of 1 to 8 character member names. Wildcards can be used. Do not use embedded blanks within a quoted member name. Members matching the specification will not be processed. The default is that no members are excluded.

When forming the list of members to process, the INCLUDEMEMBERS list is created and then the EXCLUDEMEMBERS list is removed from the first list. Thus, if a member (whether specifically or by wildcarding) appears in both lists, it will be excluded. z/OS itself does nothing with this list other than return it upon request by the IEFOPZQ service.

EXCLUDEMEMBERS can be specified as EMEM, EXCLUDEMEM, or EXCLUDEMEMBER.

### **ACTIVE|INACTIVE**

Identifies whether the pairing is to be used (ACTIVE) or is not to be used (INACTIVE) in manipulating the JCL. INACTIVE is intended to be used when the customer wants to interact with the optimization product to get the IEFOPZ-New data set populated, but does not yet want the JCL to be manipulated with respect to IEFOPZ-New and IEFOPZ-Old data sets.

ACTIVE can be specified as ACT. INACTIVE can be specified as INACT.

**Default:** ACTIVE

### **DDNAME(ddname) JOBNAME(jobname)**

identifies a DDNAME/JOBNAME pair for which the OLDNEW processing is to be performed. *ddname* must be a valid 1 to 8 character DDNAME. *jobname* must be a valid 1 to 8 character JOBNAME. Both *ddname* and *jobname* can contain wildcard characters. For a *ddname* or *jobname* that has wildcard characters, the system processes more quickly if the only wildcard character is an asterisk as the last non-blank character or if the only wildcard character is an asterisk as the first character.

These parameters apply to DDNAMEs identified in JCL; they do not apply to dynamic allocation. Processing will always be done for JOBLIB and STEPLIB. The default is to do no processing other than for JOBLIB and STEPLIB. There can be multiple DDNAME/JOBNAME specifications. All such specifications are used. The DDNAME/JOBNAME specifications add to the default system processing of always doing OLDNEW processing for ddnames JOBLIB and STEPLIB.

When the system checks if a particular DDNAME is to undergo IEFOPZ processing for a particular jobname, it checks the DDNAME/JOBNAME pairs of the IEFOPZ configuration in the following order:

- The DDNAME has no wildcard characters (searching only the hash synonym chain for this DDNAME, thus not all DDNAMEs with no wildcard characters) and:
  - the JOBNAME has no wildcard characters
  - the JOBNAME is "\*" (match all)
  - the JOBNAME has as its only wildcard character an "\*" as the last or first nonblank character
  - the JOBNAME has a more complex wildcard usage.
- The DDNAME is "\*" or has as its only wildcard character an "\*" as the last or first nonblank character and:
  - the JOBNAME has no wildcard characters
  - the JOBNAME is "\*" (match all)
  - the JOBNAME has as its only wildcard character an "\*" as the last or first nonblank character
  - the JOBNAME has a more complex wildcard usage
- The DDNAME has a more complex wildcard usage and:
  - the JOBNAME has no wildcard characters
  - the JOBNAME is "\*" (match all)
  - the JOBNAME has as its only wildcard character an "\*" as the last or first nonblank character
  - the JOBNAME has a more complex wildcard usage

DDNAME can be specified as DD or DDN. JOBNAME can be specified as JOB.

### **LLA(YES|NO)**

Indicates whether to do automatic IEFOPZ processing for LLA (such as adding to LLA management an IEFOPZ-New data set if LLA is managing the IEFOPZ-Old data set). LLA(NO) indicates not to do automatic IEFOPZ processing for LLA.

**Default:** YES

### **LNKLST(YES|NO)**

Indicates whether to do automatic IEFOPZ processing for the LNKLST (such as adding to the LNKLST an IEFOPZ-New data set if the LNKLST contains an IEFOPZ-Old data set). LNKLST(NO) indicates not to do automatic IEFOPZ-processing for the LNKLST.

**Default:** YES

### **REINITIALIZE**

is to be used only in case of emergency. If there has been an overlay of the IEFOPZ configuration control structures, it might adversely affect significant parts of system processing. The REINITIALIZE statement indicates to start over, throwing away all existing control structures (not freeing any of that storage). This statement takes effect regardless of where in the parmlib members it exists, as long as it is not ignored due to mismatching SYSNAME/SYSPLEX filters. PARMLIB member IEFOPZ01 is provided with just this statement in it, so that it is most quickly available. For any SET IEFOPZ command for which the only statement is REINITIALIZE, the system will not change the IEFOPZ parmlib suffix list that is in effect. Thus, following such a SET IEFOPZ command (for example, SET IEFOPZ=01 to access the IBM-provided IEFOPZ01 member that has only a REINITIALIZE statement), you can then issue SET IEFOPZ=REFRESH to have the system process the suffix list that was in effect prior to the REINITIALIZE.

REINITIALIZE can be specified as REINITIAL or REINIT.

## **Usage notes for IEFOPZxx**

---

After the optimization completes, change the parmlib members so that the state of these IEFOPZ-Old and IEFOPZ-New pairings is active, and issue SET IEFOPZ with the suffix list to process (and activate) these pairings (or re-IPL with a suitable IEFOPZ system parameter). The general rule is that a pairing applies only to allocations done after the pairing was activated.

- If a pairing relates to LNKLST libraries, you must use dynamic LNKLST operations to create and activate a new LNKLST that identifies the IEFOPZ-Old library (and the system automatically processes the IEFOPZ-New library as well). Only jobs that are started (or re-started) after this is done get the new data. If you want existing address spaces to get the new data, re-IPL or restart the job. As a last resort, you could try the LNKLST UPDATE operation with unpredictable results.
- If a pairing relates to non-LNKLST libraries that are managed by LLA, LLA adds to its management list the corresponding NEW library. (This will happen for a LNKLST library that is managed by LLA.) Any NEW library that was added to LLA previously remains within LLA management unless explicitly removed.
- For other cases, you might need to restart the relevant application/subsystem to get a new allocation that processes the updated data.



## Chapter 59. IEFSSNxx (subsystem definitions) - keyword parameter form

**Note:** IBM suggests that you use the keyword parameter form of the IEFSSNxx parmlib member, which is described here. However, the positional parameter form of the IEFSSNxx parmlib member is still supported. See [Appendix A, “IEFSSNxx \(subsystem definitions\) - positional parameter form,”](#) on page 789 for more information. Subsystems defined in the keyword parameter form of the IEFSSNxx parmlib member can use dynamic SSI services, while subsystems defined in the positional form of the IEFSSNxx parmlib member cannot use dynamic SSI services. See [z/OS MVS Using the Subsystem Interface](#) for more information about dynamic SSI services.

IEFSSNxx contains parameters that define the primary subsystem and the various secondary subsystems that are to be initialized during system initialization. IEFSSNxx allows you to:

- Name the subsystem initialization routine to be given control during master scheduler initialization.
- Specify the input parameter string to be passed to the subsystem initialization routine.
- Specify a primary subsystem name and whether you want it started automatically.
- Specify whether the initialization routines for the subsystem are to run in parallel.

For information about writing subsystems, see [z/OS MVS Using the Subsystem Interface](#).

Unless you are starting the Storage Management Subsystem (SMS), specify the primary subsystem (JES) first. Some subsystems require the services of the primary subsystem in their initialization routines. Problems can occur if subsystems that use the subsystem affinity service in their initialization routines are defined before the primary subsystem. If you are starting SMS, specify its record before you specify the primary subsystem record.

Before z/OS V1R12, the order in which the subsystems were defined depended on the order in which they were specified in the IEFSSNxx parmlib member on the SSN parameter. Beginning with z/OS V1R12, you can specify the BEGINPARALLEL statement that allows the initialization routines for any subsystem that supports parallel processing to be invoked in parallel. For the SMS subsystem or any subsystem that does not support parallel processing, be sure to specify the BEGINPARALLEL statement after you specify the subsystem definitions. For the SMS subsystem, if the BEGINPARALLEL statement is encountered before the SUBSYS statement, the system issues message IEF009E about potential errors. See the BEGINPARALLEL statement in [Statements/parameters for IEFSSNxx](#).

The format of the IEFSSNxx record for SMS is described in [“Defining SMS through the IEFSSNxx member”](#) on page 531.

**Note:** In general, it is a good idea to make the subsystem name the same as the name of the member of sys1.proclib used to start the subsystem. If the name does not match, you may receive error messages when you start the subsystem.

### Restrictions for IEFSSNxx

The following restrictions apply:

- All subsystem definitions in a single IEFSSNxx member must use the same format. A single member cannot contain both positional and keyword definitions.
  - If a member begins with the positional format and switches to the keyword format, processing of the member stops, and the IEFJ002I message is issued. The last subsystem definition processed for the member is the last positional format definition before the switch. The system does not process another definition of either format from the member, but continues processing with the next member, if any.

- If a member begins with the keyword format and a positional format definition is found, the system issues a syntax error message, and processing continues with the next definition of the keyword format.
- Once a subsystem name is defined to the system, any attempt to start that subsystem (or any started task with the same name as that subsystem) via a START command which does not explicitly specify SUB=JES2 (or JES3) will result in that subsystem or started task being started under the Master subsystem rather than under the job entry subsystem. Because the only procedure libraries available to the Master subsystem are those specified in the MSTJCLxx's IEFPSI data set, any procedures being started that are defined in the job entry subsystem's PROC00 data set, but not in the MSTJCLxx's IEFPSI data set, will be unavailable. Therefore they will not be found; the system will issue message IEF612I.

Only subsystems that have been defined using the keyword format IEFSSNxx parmlib member, the IEFSSI REQUEST=ADD macro or the SETSSI ADD system command can use the following dynamic SSI services:

- Macros
  - IEFSSI REQUEST=ACTIVATE
  - IEFSSI REQUEST=DEACTIVATE
  - IEFSSI REQUEST=OPTIONS
  - IEFSSI REQUEST=SWAP
  - IEFSSI REQUEST=GET
  - IEFSSI REQUEST=PUT
  - IEFSSVT
- System commands
  - SETSSI ACTIVATE
  - SETSSI DEACTIVATE

You cannot use dynamic SSI services for subsystems defined with the positional form of this member. See Appendix A, “IEFSSNxx (subsystem definitions) - positional parameter form,” on page 789 for more information about the positional form of this member.

## Parameter in IEASYSxx (or supplied by the operator)

The SSN parameter in IEASYSxx identifies the IEFSSNxx member that the system is to use to initialize the subsystems, as follows:

```
SSN={aa
    { (aa,bb,...) }
```

The two-character identifier, represented by aa (or bb, and so forth) is appended to IEFSSN to identify IEFSSNxx members of parmlib. If the SSN parameter is not specified, the system uses the IEFSSN00 parmlib member.

The order in which the subsystems are specified on the SSN parameter is the order in which they are defined. For example, a specification of SSN=(13,Z5) would cause those subsystems specified in the IEFSSN13 parmlib member to be defined first, followed by those subsystems specified in the IEFSSNZ5 parmlib member. If you specify duplicate subsystem names in IEFSSNxx parmlib members, the system issues message IEFJ003I to the SYSLOG, the INTIDS console, and consoles that monitor routing code 10 messages.

Some exits that use system services may run before other system address spaces are active. You must ensure that any address spaces required by the system services are available prior to invoking the service.

For more information, see the topic on handling errors in defining your subsystem in [z/OS MVS Using the Subsystem Interface](#).

## Syntax rules for IEFSSNxx

The following rules apply to the creation of IEFSSNxx:

- Each SUBSYS statement in IEFSSNxx defines one subsystem to be initialized.
- Use columns 1 through 71. Do not use columns 72-80, because the system ignores these columns.
- Comments may appear in columns 1-71 and must begin with "/" and end with "/".
- A statement must begin with a valid statement type followed by at least one blank or end-of-line. If there is an error in the statement type, the system will flag the error on the preceding statement.
- A statement ends with the beginning of the next valid statement type or end-of-file. Therefore, if there is an error in a statement type, the system will flag the error on the preceding statement.
- A statement can be continued even though there is no explicit continuation character. Be aware that if the system cannot recognize the start of a statement (for example, if a statement starts with an error in the statement type), the system will automatically assume that it is a continuation of the previous statement, and flag an error on the previous statement.
- Operands must be separated by valid delimiters. Valid delimiters are a blank, or column 71. If the operand contains parentheses, then the right parenthesis is accepted as a valid delimiter.
- Multiple occurrences of a delimiter (except for parentheses) are accepted, but treated as one.

## IBM-supplied default for IEFSSNxx

If you do not specify the SSN system parameter, the system uses the IEFSSN00 parmlib member. IEFSSN00 specifies JES2 as the primary subsystem.

If you specify a set of IEFSSNxx members that do not identify a primary subsystem, the system issues a message that prompts the operator to specify the primary subsystem.

## Statements and parameters for IEFSSNxx

```
SUBSYS      SUBNAME(subname)
             [CONSNAME(consname)]
             [INITRTN(initrtn)
              [INITPARM(initparm)]]
             [PRIMARY({NO|YES})]
             [START({YES|NO})]]
BEGINPARALLEL
```

### BEGINPARALLEL

The statement that indicates that the subsystem initialization routines specified in SUBSYS statements that follow the BEGINPARALLEL statement are invoked in parallel to reduce the amount of time it takes for all subsystems to initialize.

For subsystems that do not support parallel processing, you must ensure that the SUBSYS statement appears before the BEGINPARALLEL statement. For example, for the SMS subsystem definition IGDSSIN, be sure to specify the subsystem definitions before you specify the BEGINPARALLEL statement. For SMS, if you specify BEGINPARALLEL before the subsystem definition, the system issues message IEF009E about potential problems. All initialization routines that are specified before the BEGINPARALLEL keyword are invoked serially, and all routines that are specified after the BEGINPARALLEL keyword are invoked in parallel. The BEGINPARALLEL keyword must be specified after the SMS entry.

For the z/OS Communications Server TNF and VMCF subsystems, you must specify the subsystem definitions before you specify the BEGINPARALLEL statement if the INITRTN parameter is included on the subsystem definitions. For information about starting the TNF and VMCF subsystems, see [z/OS Communications Server: IP Configuration Guide](#)

If you do not specify BEGINPARALLEL, the subsystem initialization routines run serially, and you do not obtain any performance benefits of parallel processing. See the configuration or installation documentation of the subsystem for information about whether the subsystem initialization routines can support running in parallel.

You only need to specify one BEGINPARALLEL statement. If you specify more than one statement, the system issues a message that it is using the first BEGINPARALLEL statement that it finds and ignores any other statements. This is also true if you specify multiple concatenated IEFSSNxx members with BEGINPARALLEL statements across a sysplex.

### **CONSNAME(*consname*)**

The name of the console to which any messages that the SSI issues as part of initialization processing are to be routed. This name is optional and can be 2-8 characters long. This console name is also passed to the routine named on the INITRTN keyword if it is specified.

The default is to issue messages to the consoles that are receiving the INTIDS routing attribute.

### **INITPARM(*initparm*)**

Input parameters to be passed to the subsystem initialization routine. The input parameters are optional and are variable in length for a maximum of 60 characters. If blanks, commas, single quotation marks, or parentheses are included in the input parameters, the entire parm field must be enclosed in single quotation marks. If the parm field is enclosed in single quotation marks, a single quotation mark within the field must be specified as two single quotation marks.

The INITPARM keyword can only be specified if the INITRTN keyword is specified.

### **INITRTN(*initrtn*)**

The name of the subsystem initialization routine. This name is optional and can be 1-8 characters long. The first character can be either alphabetic or national (#, @, or \$). The remaining characters can be either alphanumeric or national. The routine receives control in supervisor state key 0. It must be the name of a program accessible through LNKST.

### **PRIMARY({NO|YES})**

Parameter indicating whether this is the primary subsystem. The primary subsystem is typically a job entry subsystem (either JES2 or JES3).

This parameter is optional. Initialize the primary subsystem before any secondary subsystem except SMS. If you specify PRIMARY on more than one statement, the system issues message IEFJ008I and defines the second subsystem but ignores the PRIMARY specification.

The IEFSSNxx parmlib member is the only place that you can define the primary subsystem. It cannot be defined using the dynamic SSI services IEFSSI REQUEST=ADD macro or the SETSSI ADD command.

**Default:** NO

### **START({YES|NO})**

Parameter indicating whether an automatic START command should be issued for the primary subsystem.

If the parmlib entry for the primary subsystem is START(NO), the operator must start it later with a START command. If the parmlib entry for the primary subsystem does not specify the START parameter, it defaults to START(YES).

The START parameter cannot be specified for a secondary subsystem. If you specify the PRIMARY(NO) parameter, there is no default for the START parameter.

**Default:** YES

### **SUBSYS**

The statement that defines a subsystem that is to be added to the system. If more than one SUBSYS statement appears for the same subsystem name, the first statement is the one used to define the subsystem. The duplicate statements are rejected with a failure message that is sent to the console.

**SUBNAME(subname)**

The subsystem name. The name can be up to 4 characters long; it must begin with an alphabetic or national character (#, @, or \$), and the remaining characters (if any) can be alphanumeric or national.

You can include any number of records in the IEFSSNxx parmlib member.

## Examples of IEFSSNxx member

---

This section contains several examples of how to code the IEFSSNxx member.

- This example defines subsystem 'JES2' as a primary subsystem and the START command to be issued by the system. No initialization routine is required because subsystem JES2 builds the SSVT when the START command is issued.

```
SUBSYS SUBNAME(JES2) PRIMARY(YES)
```

- This next example defines subsystem 'ABC'. Call its initialization routine, which will build the SSVT.

```
SUBSYS SUBNAME(ABC) INITRTN(INITPGM)
```

- This example specifies that the initialization routines for RACF, and IRLM run in parallel:

```
SUBSYS SUBNAME(SMS)
  INITRTN(IGDSSIIN)
  INITPARM(ID=ZX)
SUBSYS SUBNAME(JES2) /* JES2 AS PRIMARY SUBSYSTEM */
  PRIMARY(YES)  START(YES)
BEGINPARALLEL
SUBSYS SUBNAME(RACF) INITRTN(IRRSSI00) INITPARM('#,M')
SUBSYS SUBNAME(IRLM)
```



## Chapter 60. IFAPRDxx (product enablement policy)

Use the IFAPRDxx parmlib member to define the enablement policy for products or product features that support product enablement. The policy lists the products and features, as well as the system environment in which they are enabled to run.

With z/OS, IBM supplies a tailored IFAPRD00 member of SYS1.PARMLIB. This tailored member enables the product and any optional features ordered with the product. Your installation can, however, order additional optional features from IBM at a later time, then enable these features after contacting IBM, subject to the product's license terms and conditions. For information about how to define a specific IBM product, see *z/OS MVS Product Management*.

To enable an optional product or feature, you add it to the policy; that is, you add the product to an IFAPRDxx member, then activate the member. Adding a product to the policy is the most common task related to IFAPRDxx; you can, however, disable a product or remove it from the policy. Note that adding a product or feature might require changes to other SYS1.PARMLIB members and an IPL before the product or feature can run.

The system builds the enablement policy from the PRODUCT statements and WHEN statements in the active IFAPRDxx member(s). Each WHEN statement defines a system environment. PRODUCT statements identify products and product features that are enabled or disabled when running in the system environment defined on the preceding WHEN statement.

The system checks the policy when a product, such as an optional z/OS feature, calls the Register service during its initialization. If a product in the policy is not defined or not found, the type of register request determines whether the product is treated as enabled or disabled. For information about the Register service, see *z/OS MVS Programming: Product Registration*. For information about how to set up your system to report on registered products, including those that support product enablement, see *z/OS MVS Product Management*.

When the system checks the policy for a match with a product that is registering, all comparisons allow wildcard characters (\* and ?). You can thus define WHEN statements that match multiple system environments and PRODUCT statements that match multiple products.

To determine enablement, the system matches the product that is registering against the statements in the enablement policy. It is possible, because of wildcard characters (? and \*) in the policy statements, that multiple policy statements might match the given input product. In that case, MVS uses the "best" match to determine whether or not the product is enabled, using the following rules:

1. An exact match is better than a wildcard match. There is no differentiation between two wildcard matches.
2. The parameters are processed in the following order: Prodowner, ProdID, Prodname, Featurename, Prodvers, Prodrel, and Prodmod. An exact match on a parameter earlier in the list (such as Prodowner) is better than a match on a parameter later in the list (such as Prodname).
3. If, after applying the first two rules, more than one match remains, MVS uses the first match of those that remain.

### Before creating the member

The contents of this member are controlled by the z/OS product terms and conditions for those PRODUCT statements that contain both IBM CORP as product owner and z/OS as product name. Before making changes to the PRODUCT statements supplied by IBM in the tailored IFAPRD00 member, see *z/OS MVS Product Management*.

To create or change an IFAPRDxx member, you need to know how to define a system environment and how to define a product:

- The system environment can include the system name, sysplex name, LPAR name, hardware name, and VM user ID, if the system is running as a VM guest.
- The product definition can include the product owner (such as "IBM CORP"), product name, name of a product feature, product identifier, and version, release, and modification level for the product. The definition must include the state, which indicates whether the product is enabled to run on the system, disabled (not allowed) to run on the system, or not defined.

If the active member includes more than one definition for a product, the system uses the last definition it encounters.

## Usage considerations

Note the following when using the IFAPRDxx member:

- You can use the SET PROD operator command to modify the enablement policy dynamically by specifying which IFAPRDxx member(s) the system is to use. Statements in the member(s) modify, not replace, an existing policy.

The change to the policy takes place immediately but does not affect any product instances that are already running.

- The system does not automatically list the IFAPRDxx parameters at IPL or when the operator issues SET PROD, but the operator can issue the DISPLAY PROD,STATE command to display the active enablement policy.

For more information, see [z/OS MVS System Commands](#).

## Parameter in IEASYSxx (or issued by the operator)

```
PROD={aa
      {(aa,bb... )}}
```

The two alphanumeric characters (aa or bb) are appended to IFAPRD to identify an IFAPRDxx parmlib member. If you do not specify the PROD parameter, there is no active enablement policy; all products that attempt to register are treated as not found.

To change the IFAPRDxx member(s) after IPL, the operator can issue the SET PROD command to specify one or more different active members. Some products check the enablement policy during IPL; a policy change for such a product does not take effect until the next IPL.

## Syntax rules for IFAPRDxx

The following syntax rules apply to IFAPRDxx:

- Use columns 1-71. Do not use columns 72-80; the system ignores them.
- Blank lines are allowed anywhere in the member.
- Comments can appear in columns 1-71 and must begin with "/"\* and end with "\*/". You can continue a comment; it does not need to end on the line on which it begins.
- You can use both uppercase and lowercase letters; the system translates lowercase letters to uppercase letters before processing.
- The system recognizes the end of a statement when it encounters either the beginning of the next valid statement or an end-of-file (EOF) indicator.
- Use valid delimiters to separate keyword parameters. A valid delimiter is a comma, a blank, or column 71. The system treats multiple blanks as one. Column 71, when within a string enclosed in quotation marks, is not a valid delimiter.
- Blanks can appear between keyword parameters, between values, and between statements. Blanks cannot appear within a keyword value unless the value is enclosed in single quotation marks.



## Syntax format of IFAPRDxx

There are two kinds of statements in IFAPRDxx: WHEN and PRODUCT. The WHEN statement defines a system environment; all PRODUCT statements that follow identify products running on the system that the preceding WHEN statement defines.

The following diagram shows the syntax of the WHEN statement:

```
WHEN ([LPARNAME(l)]
      [SYSNAME(sn)]
      [SYSPLEX(sp)]
      [HWNAME(h)]
      [VMUSERID(v)])
```

As you use the diagram, consider:

- The WHEN parameter begins the WHEN statement.
- All parameters are optional.
- You must surround any parameters you specify with parentheses.

The following diagram shows the syntax of the PRODUCT statement:

```
PRODUCT [OWNER(o)]
        [ID(i)]
        [NAME(n)]
        [FEATURENAME(fn)]
        [VERSION(v)]
        [RELEASE(r)]
        [MOD(m)]
        STATE({ENABLED|DISABLED|NOTDEFINED})
```

As you use the diagram, consider:

- The PRODUCT parameter begins the PRODUCT statement.
- The STATE parameter is required; all other parameters are optional.

## IBM-supplied default for IFAPRDxx

IBM supplies a tailored IFAPRD00 member, one that reflects the optional features that have been ordered.

## Statements and parameters for IFAPRDxx

### PRODUCT

Begins a PRODUCT statement. A PRODUCT statement defines a product and its enablement state.

When a product attempts to register, the system matches the input product against the policy statements.

When it compares an input request with a policy statement, MVS uses wildcard matching. PRODUCT statement parameters can include wildcard characters (\*) and (?) that allow a single parameter to match many different input requests. For example, NAME(NM?) matches product names like NM1 or NMA but not NAM1. NAME(N\*) matches N1 or NMA or NAM1. If you omit a PRODUCT statement parameter, MVS treats the parameter as if you had specified an asterisk (\*), and, because of wildcard matching, it always compares as true; it matches the input request.

It is thus possible that multiple policy statements might match the given input request. In that case, MVS uses the best match to determine whether the product is enabled, using the following rules:

1. An exact match is better than a wildcard match. There is no differentiation between two wildcard matches.

2. The parameters are processed in the following order: OWNER, ID, NAME, FEATURENAME, VERSION, RELEASE, and MOD. An exact match on a parameter earlier in the list (such as OWNER) is better than a match on a parameter later in the list (such as NAME).
3. If, after applying the first two rules, more than one match remains, MVS uses the first match of those that still remain.

**Note:** When MVS is building the policy, it adds to the policy any PRODUCT statement that it finds after a valid WHEN statement. When there is a syntax error in a WHEN statement, MVS ignores the WHEN statement and checks the subsequent PRODUCT statements for syntax errors but does not add them to the policy.

### **ID(*i*)**

Specifies the product identifier. The identifier must be 1–8 characters long.

The characters must be alphabetic, numeric, national (@, #, \$), underscore (\_), slash (/), hyphen (-), or period (.). The system allows wildcard matching; the identifier can contain wildcard characters (\* and ?).

If the identifier includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in ID('lc34').

The system translates underscores to blanks for comparison and display, and it performs all comparisons in uppercase.

**Default:** ID(\*), which matches any product identifier.

### **FEATURENAME(*fn*)**

Specifies the name of a feature of the product. The name must be 1–16 characters long.

The characters must be alphabetic, numeric, national (@, #, \$), underscore (\_), slash (/), hyphen (-), or period (.). The system allows wildcard matching; the name can contain wildcard characters (\* and ?).

If the name includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in FEATURENAME('lowercase').

The system translates underscores to blanks for comparison and display, and it performs all comparisons in uppercase.

**Default:** FEATURENAME(\*), which matches any feature name.

FN is an accepted abbreviation of FEATURENAME.

### **MOD(*m*)**

Specifies the product modification level. *m* must be 1–2 characters long.

The characters must be alphabetic or numeric. The system allows wildcard matching; the modification level can contain wildcard characters (\* and ?).

If *m* includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in MOD('c2').

The system performs all comparisons in uppercase.

**Default:** MOD(\*), which matches any modification level.

### **OWNER(*o*)**

Specifies the name of the product owner, such as 'IBM CORP'. The name must be 1–16 characters long.

The characters should be alphabetic, numeric, national (@, #, \$), underscore (\_), slash (/), hyphen (-), or period (.). The system allows wildcard matching; the name can contain wildcard characters (\* and ?).

If the name includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in OWNER('lowercase').

The system translates underscores to blanks for comparison and display, and it performs all comparisons in uppercase.

**Default:** OWNER(\*), which matches any product owner name.

### NAME(*n*)

Specifies the product name. The name must be 1–16 characters long.

The characters must be alphabetic, numeric, national (@, #, \$), underscore (\_), slash (/), hyphen (-), or period (.). The system allows wildcard matching; the name can contain wildcard characters (\* and ?).

If the name includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in NAME('lowercase').

The system translates underscores to blanks for comparison and display, and it performs all comparisons in uppercase.

**Default:** NAME(\*), which matches any product name.

### RELEASE(*r*)

Specifies the product release number. *r* must be 1–2 characters long.

The characters must be alphabetic or numeric. The system allows wildcard matching; the release number can contain wildcard characters (\* and ?).

If *r* includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in RELEASE('1a').

The system performs all comparisons in uppercase.

**Default:** RELEASE(\*), which matches any release number.

REL is an accepted abbreviation of RELEASE.

### STATE({ENABLED|DISABLED|NOTDEFINED})

The state of the product. If you specify ENABLED or EN, the registering product can continue to run. If you specify DISABLED, DI, or DIS, the registering product is not to continue. When you specify NOTDEFINED or ND, the system removes from the policy any existing entry for the product.

### VERSION(*v*)

Specifies the product version, where *v* must be 1–2 characters long.

The characters must be alphabetic or numeric. The system allows wildcard matching; the version can contain wildcard characters (\* and ?).

If *v* includes lowercase alphabetic characters, embedded blanks, or other characters, enclose the parameter in single quotation marks, as in VERSION('1c').

The system performs all comparisons in uppercase.

**Default:** VERSION(\*), which matches any product version.

VER and VERS are accepted abbreviations of VERSION.

## WHEN

Begins a WHEN statement, which specifies a system environment.

To match the system environment you specify on the WHEN statement with the actual system, MVS compares each specified parameter with the actual system. If all parameters match the actual system, the WHEN statement is considered to be true, and the system processes the PRODUCT statements that follow the WHEN statement. Otherwise, the WHEN statement is considered to be false, and the system ignores the subsequent PRODUCT statements.

When it compares a parameter with an actual system condition, MVS allows wildcard matching. WHEN statement parameters can include wildcard characters (\* and ?) that allow a single parameter to match many different actual conditions. For example, SYSNAME(SY?) matches system names like SY1 or SYA but not SYS1. SYSNAME(S\*) matches S1 or SYA or SYS1. If you omit a parameter, MVS treats

the parameter as if you had specified an asterisk (\*), and, because of wildcard matching, it always compares as true; it matches the actual system.

The initial state of the WHEN statement is true; that is, if PRODUCT statements appear before any WHEN statement, MVS processes these PRODUCT statements as if they followed a true WHEN statement.

When the SET PROD command or the PROD system parameter specifies more than one member, however, the WHEN state carries over from one member to the next. To avoid a false WHEN state from a preceding member, begin each member with a WHEN statement, even WHEN(), which is always true.

When MVS finds a syntax error in a WHEN statement while it is building the policy, MVS ignores the WHEN statement and checks the following PRODUCT statements for syntax errors but does not add them to the policy.

#### **HWNAME(h)**

Specifies the hardware name, the name (identifier) of a central processor complex (CPC) defined to HCD. To match an actual hardware name, specify the 1–8 character name, which can include wildcard characters (\* and ?). To match any hardware name or to match when the hardware name related to the actual system is not known, specify HWNAME(\*) or omit the HWNAME parameter. To match only when the hardware name related to the actual system is not known, specify HWNAME().

If you specify a hardware name when the hardware name related to the actual system is not known, the comparison uses an actual hardware name of 8 blanks, and there is no match.

#### **LPARNAME(l)**

Specifies the LPAR name, the name of a logical partition that is defined through HCD or IOCP. To match an actual LPAR name, specify the 1–8 character name, which can include wildcard characters (\* and ?). To match any LPAR name or to match when the system is not running in a logical partition, specify LPARNAME(\*) or omit the LPARNAME parameter. To match only when the system is not running in a logical partition, specify LPARNAME().

If you specify an LPAR name when the actual system is not running in a logical partition, the comparison uses an actual LPAR name of 8 blanks, and there is no match.

#### **SYSNAME(sn)**

Specifies the system name, which must be 1–8 characters in length. For the WHEN statement to be true, the name must match the actual system name. The comparison allows wildcard matching; the name can contain wildcard characters (\* and ?).

**Default:** SYSNAME(\*), which matches any system name.

#### **SYSPLEX(sp)**

Specifies the sysplex name, which must be from 1–8 characters in length. For the WHEN statement to be true, the name must match the actual sysplex name. The comparison allows wildcard matching; the name can contain wildcard characters (\* and ?).

**Default:** SYSPLEX(\*), which matches any sysplex name.

#### **VMUSERID(v)**

Specifies the user ID of a z/VM system under which the z/OS image is running as a guest. (For information about running z/OS as a z/VM guest, see *z/VM: Running Guest Operating Systems*.)

To match an actual z/VM user ID, specify the 1–8 character user ID, which can include wildcard characters (\* and ?). To match any z/VM user ID or to match when the actual system is not running as a z/VM guest, specify VMUSERID(\*) or omit the VMUSERID parameter. To match only when the actual system is not running as a z/VM guest, specify VMUSERID().

If you specify a z/VM user ID when the actual system is not running as a z/VM guest, the comparison uses an actual z/VM user ID of 8 blanks, and there is no match.

## Examples of IFAPRDxx statements

---

**Example 1:** To enable the GDDM REXX feature of z/OS, first see [z/OS MVS Product Management](#) for information about enabling IBM products. Then, use the following PRODUCT statement:

```
PRODUCT OWNER('IBM CORP')
        NAME(z/OS)
        ID(5645-001)
        FEATURENAME(GDDM-REXX)
        STATE(ENABLED)
```

For a z/OS feature, do not specify VERSION, RELEASE, or MOD; either omit the parameter or specify an asterisk (\*).

**Example 2:** To indicate that the subsequent PRODUCT statements apply only when the products are running on system S in sysplex SP, specify:

```
WHEN ( SYSNAME(S) SYSPLEX(SP) )
```

**Example 3:** To indicate that the state of product XXXX owned by YYY INC is to be disabled, specify:

```
PRODUCT OWNER('YYY INC') NAME(XXXX) STATE(DISABLED)
```

Specifying OWNER(YYY\_INC) would have the same result.

**Example 4:** To remove product XXXX owned by YYY from the enablement policy, specify:

```
PRODUCT OWNER(YYY) NAME(XXXX) STATE(NOTDEFINED)
```

**Example 4:** To indicate that all products with names that begin with the letter I are to be enabled, specify:

```
PRODUCT NAME(I*) STATE(ENABLED)
```



## Chapter 61. IFGPSEDI (enhanced data integrity)

Enhanced data integrity can prevent users from concurrently accessing a shared sequential data set on DASD for output or update processing, thus avoiding any resulting loss of data. You can activate enhanced data integrity by creating an IFGPSEDI parmlib member.

When you activate enhanced data integrity, you can request that multiple users no longer have concurrent output or update access to a sequential data set on DASD. Enhanced data integrity applies only to sequential data sets. Authorized applications can exclude their sequential data sets from enhanced data integrity protection. For information about how to exclude sequential data sets from enhanced data integrity, see *z/OS DFSMS Using Data Sets*.

If you do not need enhanced data integrity, do not create the IFGPSEDI member of SYS1.PARMLIB.

**Activating Enhanced Data Integrity at IPL and afterward:** After you create IFGPSEDI, you can activate enhanced data integrity in either of the following ways:

- At IPL, by specifying MODE(ENFORCE) or MODE(WARN) in the IFGPSEDI parmlib member.
- After IPL, through the S IFGEDI command.

### Syntax rules for IFGPSEDI

The following syntax rules apply to IFGPSEDI

- If MODE is specified it must be the first keyword in the first record and start in column 1
- Multiple data set names can be included in a single 80 byte record, but the last data set name must be complete. It cannot be continued on to the next record.
- Blanks and commas can be used as delimiters between keywords, but blanks are not allowed between a keyword and the opening parenthesis.
- Comments may appear in columns 1-80 and must begin with "/\*". After finding an opening comment delimiter, the rest of the line will be ignored. Therefore, comments may appear as the only entry in a line, or following keyword statement, but comments cannot span more than one line. Multiple line comments can be included as a series of one-line comments, each starting with the opening comment delimiter.
- Uppercase and lowercase letters can be used.
- Multiple lines are allowed, but every statement specification must be complete on a single line.
- It is not required to have a comma at the end of a statement in order to continue to the next line.
- Use columns 1-71. Do not use columns 72-80 for data; these columns are ignored.

### Syntax examples

The following is an example of a complete IFGPSEDI member:

```
MODE(ENFORCE),DSN(AONE.ATWO),DSN(HIQUAL.*.LOWQUAL),DSN(DEFG.*),DSN(THIS.FILE.NAME)
```

### Syntax format of IFGPSEDI

```
MODE{(WARN|ENFORCE|DISABLE)}[,DSN(datasetname)][,DSN(datasetname)]...
```

## IBM-supplied default for IFGPSEDI

---

None.

## Statements and parameters for IFGPSEDI

---

### **DSN(datasetname)**

Specifies the name of a data set that should be excluded from enhanced data integrity support. The data set name can either be a discrete name (meaning that the entire data set name is specified) or a partially qualified name. To specify a partially qualified name, use an asterisk, \*, or a percent sign, %, anywhere within the data set name.

Specifies the name of a data set that should be excluded from enhanced data integrity support. The data set name can either be a discrete name (meaning that the entire data set name is specified) or a partially qualified name. To specify a partially qualified name, use an asterisk, \*, or a percent sign, %, anywhere within the data set name. If two or more consecutive asterisks are specified, they must be immediately preceded by a period or left parenthesis; for example, ex . DSN (\*\*).

Use a percent sign as a generic character for a single position. For example, TEST% would include only names with exactly five characters, such as TESTA, TEST9 or TESTZ.

Use an asterisk as a generic character for zero or more characters. For example, TEST\* would include names with only one qualifier such as TEST, TESTX and TEST1000. Use a double asterisk as a generic character for any number of qualifiers. For example, SYS1.\*\* would include a data set name with any number of qualifiers as long as the first qualifier is SYS1 (for example, data sets SYS1.TEST, SYS1.LIST.XP and SYS1.MEMO.EMPL.A would be included).

You can specify any number of data set name parameters. However, a high number of exclusions might affect performance, so you should keep the number to a minimum. By including data set names in the IFGPSEDI exclude list, you exclude all data sets with that same name. There can be multiple data sets on different volumes with the same name that are not SMS-managed. If the name you specify matches a name in the exclude list, then all data sets by that name bypasses EDI processing.

**Default:** None

### **MODE{(WARN|ENFORCE|DISABLE)}**

Use the MODE parameter to specify how you want the system to handle enhanced data integrity violations.

#### **ENFORCE**

The system issues an ABEND 213 with reason code FD if an attempt to open a sequential data set that is already open for output occurs.

#### **DISABLE**

Ends enhanced data integrity support without having to re-IPL. You can modify IFGPSEDI to specify MODE(DISABLE) and issue the command S IFGED I.

#### **WARN**

The system issues a warning message IEC984I or IEC985I if a violation occurs. MODE(WARN) allows processing of the data set to continue if a violation occurs.



## Chapter 62. IGDSMSxx (storage management subsystem definition)

IGDSMSxx contains the parameters that initialize the storage management subsystem (SMS) and specify the names of the active control data set (ACDS) and the communications data set (COMMDS).

### Parameter in IEASYSxx

The SMS parameter in IEASYSxx identifies the IGDSMSxx member from which the storage management subsystem (SMS) will obtain its options when the system is initialized for partitioned data set extended (PDSE) support, as follows:

#### SMS {xx}

The two alphanumeric characters, xx, are appended to IGDSMS to name the member. The nucleus initialization program (NIP) saves the name until SMS is initialized. If initialization of the PDSE fails, the IGDSMSxx PARMLIB member is selected from the IEFSSNxx PARMLIB member, using the ID=xx keyword.

### Defining SMS through the IEFSSNxx member

You can start SMS only after you define it to MVS as a valid subsystem. Do this by adding a record for the SMS subsystem to parmlib member IEFSSNxx. IEFSSNxx defines how MVS is to initialize the SMS address space.

Use keyword parameters to code the IEFSSNxx member.

Figure 15 on page 531 shows the syntax of the keywords that you can use to define SMS in IEFSSNxx.

```
SUBSYS SUBNAME(SMS)
[INITRTN(IGDSSIIN) [INITPARM( ' ID=yy, PROMPT=NO      ' )]]
                        [ YES      ]
                        [ DISPLAY ]
```

Figure 15. Keyword format of the SMS record in IEFSSNxx

Figure 16 on page 531 shows the positional format of the SMS definition in IEFSSNxx (for users of positional parameters).

```
SMS[, [IGDSSIIN] [, ' ID=yy] [, PROMPT={YES      } ' ]]]
                        {DISPLAY}
                        {NO      }
```

Figure 16. Positional format of the SMS record in IEFSSNxx

This record differs somewhat from the one discussed in [Appendix A, “IEFSSNxx \(subsystem definitions\) - positional parameter form,”](#) on page 789; do not use the optional parameters PRIMARY or NOSTART.

**Tip:** Place the SMS record before the primary subsystem (JES2 or JES3) record in IEFSSNxx to start SMS before starting the primary subsystem.

The fields within the SMS record are as follows:

#### SMS

Identifies the subsystem as SMS.

**IGDSSIIN**

Identifies the SMS subsystem initialization routine. If you include this field, SMS is automatically started at IPL. If you omit this field, SMS is defined to MVS as a valid subsystem, but is not automatically started at IPL.

**ID=yy**

Specifies the two-character suffix of the IGDSMSxx member to be used to start SMS in either of the following special cases:

- The SMS parameter of IEASYSxx does not specify a valid IGDSMSxx member and default member IGDSMS00 does not exist.
- A system error prevents the initialization of system functions that manage PDSEs (for example, the PDSE address space fails to start).

To avoid confusion, specify the same value on the SMS keyword in IEASYSxx and on the ID keyword in IEFSSNxx.

If you specify both ID and PROMPT, enclose them in one pair of single quotation marks and separate them with a comma.

**Default:** 00

**PROMPT={YES|DISPLAY|NO}**

Specifies the amount of control the operator is to have over the SMS initialization parameters. You can specify one of the following values for PROMPT.

**DISPLAY**

The system displays only the parameters of the IGDSMSxx member. The operator cannot change these parameters.

**NO**

The system does not display the parameters or allow the operator to change them.

**YES**

The system prompts the operator (through a write-to-operator-with-reply (WTOR) message) to change the parameters specified in the IGDSMSxx member. The system displays the current status of parameters before it issues the WTOR. The effect of any change lasts only for the duration of the IPL; the operator's action, if any, does not change the contents of the IGDSMSxx member.

If you specify both ID and PROMPT, enclose them in one pair of single quotation marks and separate them with a comma.

**Default:** NO

## Example of an SMS record in IEFSSNxx

Figure 17 on page 532 shows an example of an SMS record in IEFSSNxx. This record:

- Defines SMS as a valid subsystem of MVS.
- Causes SMS to be started automatically at IPL.
- Identifies IGDSMS60 as the IGDSMSxx member that contains the SMS options.
- Specifies that SMS is to prompt the operator for changes to the SMS parameter options.

```
SUBSYS SUBNAME(SMS) INITRTN(IGDSSIIN)
      INITPARM('ID=60,PROMPT=YES')
```

*Figure 17. Example: SMS record in IEFSSNxx*

For more information about defining subsystems through IEFSSNxx, see [Appendix A, “IEFSSNxx \(subsystem definitions\) - positional parameter form,”](#) on page 789.

## Starting SMS - at IPL and afterward

After you have created IGDSMSxx and defined control data sets for SMS to use, you can start SMS in either of the following ways:

- At IPL, by having specified IGDSSIIN in the SMS record in IEFSSNxx.
- After IPL, through the SET SMS=xx (or T SMS=xx) command, where xx identifies the particular IGDSMSxx member that contains the SMS initialization parameters.

For more information about using the MVS SET SMS command, see [z/OS MVS System Commands](#).

## Specifying SMS parameters through SETSMS and SET SMS

After you activate an SMS configuration, you can use the SET SMS or SETSMS operator commands to specify SMS parameters, as follows:

- Use the SET SMS command to start SMS if it is not started at IPL or to change SMS parameters if SMS is already running. The SMS parameters are taken from the IGDSMSxx member in SYS1.PARMLIB.
- Use the SETSMS command when SMS is already running to change a single SMS parameter. You enter the parameter to be changed on the command line.

**Note:** Some parameters in the IGDSMSxx parmlib member are read at IPL time, but do not have any effect unless it is the first time the parameters are specified for a new configuration. As indicated in the section on changing IGDSMSxx parameters to support the coupling facility in [z/OS DFSMSdfp Storage Administration](#), you must issue the SETSMS command for any changes to take effect. In particular, the values used by VSAM RLS for the following keywords are remembered from last initialization, but not overridden by the IGDSMSxx specifications at IPL time unless the SETSMS command is issued.

- CF\_TIME
- DEADLOCK\_DETECTION
- RLS\_MAXCFFEATURELEVEL
- RLS\_MAX\_POOL\_SIZE
- RLSABOVETHEBARMAXPOOLSIZE
- RLSFIXEDPOOLSIZE
- SMF\_TIME

For more information about using SETSMS and SET SMS, see [z/OS MVS System Commands](#).

## Syntax rules for IGDSMSxx

You can separate the keywords in IGDSMSxx with blanks or commas. You do not need to specify continuation characters for records that span multiple lines.

Comments may appear in columns 1-71. They must begin with /\* and end with \*/. Comments are allowed between parameters.

## Syntax format of IGDSMSxx

The following diagram shows the syntax format of the keywords that you code in IGDSMSxx.

```
SMS    ACDS(dsname) COMMDS(dsname)
        [ACSDFAULTS({YES|NO})]
        [ACS_LOGWRITES({ENABLE|DISABLE})]
        AKP({nnn[,nnn[...nnn]]|1000})
        [ASID({asid|*[(TRACE|T|VOLSELMSG|V)[,asid|*[(TRACE|T|VOLSELMSG|V)]]})]
        [AUTO_VOLSTATUS_EXTPOOL(YES|NO[,nnn|120])]
        [AUTO_VOLSTATUS_VTOC(YES|NO)]
        [BLOCKTOKENSIZE({REQUIRE|NOREQUIRE})]
        [BREAKPOINTVALUE(0-65520)]
        [BYPASS_CLUSTER_PREFERENCING (YES|NO)]
        [CACHETIME({nnn|3600})]
```

```

[CA_RECLAIM(NONE|{DATACLAS|DATACLASS})]
[CF_TIME({nnnnn|3600})]
[CICSVR_INIT({YES|NO})]
[CICSVR_BACKOUT_CONTROL({backout control string})]
[CICSVR_DSNAME_PREFIX({DWW.|dsname prefix})]
[CICSVR_GENERAL_CONTROL({general control string})]
[CICSVR_GRPNAME_SUFFIX({grpname suffix})]
[CICSVR_RCDS_PREFIX({rcds prefix})]
[CICSVR_UNDOLOG_CONTROL({undolog control string})]
[CICSVR_UNDOLOG_PREFIX({undolog prefix})]
[CICSVR_ZZVALUE_PARM({zzvalue parm})]
[COMPRESS({TAILORED|GENERIC|ZEDC_R|ZEDC_P})]
[DB2SSID(ssid)]
[DEADLOCK_DETECTION({iiii|15, kkkk|4})]
[DESELECT({event[, event][, ...]|ALL})]
[DINTERVAL({nnn|150})]
[DSNAME({dsname|*})]
[DSNTYPE({LIBRARY|PDS|ZFS})]
[DSSTIMEOUT({nnnn|0})]
[FAST_VOLSEL(ON|OFF)]
[GDS_RECLAIM(YES|NO)]
[HONOR_DSNTYPE_PDSE (YES|NO)]
[INTERVAL({nnn|15})]
[JOBNAME({jobname|*}]
[(TRACE|T|VOLSELMSG|V)[, jobname|*(TRACE|T|VOLSELMSG|V)]]]
[LOG_OF_LOGS(logstream)]
[MAXGENS_LIMIT(0-2000000000)]
[MAXLOCKS({max|0}, {incr|0})]
[OAMPROC(procname)]
[OAMTASK(taskid)]
[OVRD_EXPDT({YES|NO})]
[PDSE_BMFTIME|BMFTIME(nnn)]
[PDSE_BUFFER_BEYOND_CLOSE (YES|NO)]
[PDSE_DIRECTORY_STORAGE (nnn|2G)]
[PDSE_HSP_SIZE|HSP_SIZE(nnn)]
[PDSE_LRUCYCLES|LRUCYCLES(nnn)]
[PDSE_LRUTIME|LRUTIME(nnn)]
[PDSE_MONITOR({YES|DISPLAY|DUMPNEXT|NO}[, interval[, duration]])]
[PDSE_PENDING_DELETE_INTERVAL(nnn)]
[PDSE_RESTARTABLE_AS(YES|NO)]
[PDSE_VERSION({1|2})]
[PDSE1_BMFTIME(nnn)]
[PDSE1_BUFFER_BEYOND_CLOSE (YES|NO)]
[PDSE1_DIRECTORY_STORAGE (nnn|2G)]
[PDSE1_HSP_SIZE(nnn|0)]
[PDSE1_LRUCYCLES(nnn|15)]
[PDSE1_LRUTIME(nnn|60)]
[PDSE1_MONITOR({YES|DISPLAY|DUMPNEXT|NO}[, interval[, duration]])]
[PDSESHARING({NORMAL|EXTENDED})]
[PDSE_SYSEVENT_DONTSWAP({NO|YES})]
[PS_EXT_VERSION({1|2})]
[QTIMEOUT({nnn|300})]
[REVERIFY({YES|NO})]
[RLSINIT({NO|YES})]
[RLS_MAX_POOL_SIZE({nnnn|100})]
[RLS_MAXCFFEATURELEVEL({Z|A})]
[RLS_RECOV_LOGGING(YES|NO)]
[RLSTMOUT({nnn|0})]
[RLSABOVETHEBARMAXPOOLSIZE({(ALL, size)|(sysname1, size1
[, sysname2, size2[...; sysname32, size32]])})]
[RLSFIXEDPOOLSIZE({(ALL, size)|(sysname1, size1
[, sysname2, size2[...; sysname32, size32]])})]
[SAM_USE_HPF(YES|NO)]
[SELECT({event[, event][, ...]|ALL})]
[SIZE(nnnnnnK|nnnM|nnnnnn|128K)]
[SMF_TIME(YES|NO)]
[STEPNAME({stepname|*})]
[SUPPRESS_DRMSG (YES|NO)]
[SUPPRESS_SMSMSG (YES|NO, IGD17002I, IGD17054I, IGD17227I, IGD17395I)]
[SYSNAME(sysname1[, sysname2[, ..., sysname32]])]
[SYSTEMS({8|32})]
[TRACE(ON|OFF)]
[TRACEEXIT(user_trace_exit)]
[TVSAMCOM({minval|1}, {maxval|0})]

[TVSNAME(nnn1[, nnn2[, ..., nnn32]])]
[TV_START_TYPE({WARM|COLD}[, {WARM|COLD}[, ..., {WARM|COLD}]]])]
[TYPE({ALL|ERROR|(TRACE|T|VOLSELMSG|V)[, ALL|ERROR|(TRACE|T|VOLSELMSG|V)]]])]
[USEEAV({YES|NO})]
[USE_MOST_FREE_SPACE ({YES|NO})]
[USE_RESOWNER({YES|NO})]
[USER_ACSVAR([[, [value1][, [, [value2][, [, [value3]]]])]]]

```

```
[VOLSELMSG({ON|OFF,0|nnnnn|ALL})]
[VSAM_ZHYPERLINK(YES|NO)]
```

## IBM-supplied default for IGDSMSxx

If you do not define an IGDSMSxx member, the system will attempt to use member IGDSMS00 by default. IBM does not supply this member; your installation must create it.

## Required keywords for IGDSMSxx

You must code the following keywords; there are no defaults.

### **SMS**

Specifies that this record is for SMS.

### **ACDS(dsname)**

Specifies the name of the active control data set (ACDS). If you omit *dsname*, the system will prompt the operator for a value. For information about the ACDS, see [z/OS DFSMSdfp Storage Administration](#).

### **COMMDS(dsname)**

Specifies the name of the communications data set (COMMDS). If you omit *dsname*, the system will prompt the operator for a value. For information about the COMMDS, see [z/OS DFSMSdfp Storage Administration](#).

## Optional keywords for IGDSMSxx

The following keywords are optional. Defaults, if any, are noted.

### **ACSDEFAULTS(YES | NO)**

Specifies whether SMS initializes the following automatic class selection (ACS) routine variables from an additional call to RACF:

- &APPLIC
- &DEF\_DATACLAS
- &DEF\_MGMTCLAS
- &DEF\_STORCLAS

Specify YES to request that RACF or a functional equivalent gives SMS the values. Because SMS must set these variables every time a data set is created, specifying NO reduces the overhead of using RACF. If you specify NO, these variables have no values that are associated with them.

The ACSDEFAULTS keyword is not applicable for OAM.

**Default:** NO

### **ACS\_LOGWRITES( ENABLE | DISABLE )**

Enable or disable the logging requested by the LOGWRITES ACS statement.

**Default:** DISABLE

### **ACS\_ROUTINE\_DEBUG ({ENABLE [,JOBVL(ALL | *jobname*)] | DISABLE})**

Allows you to control information output by enabling ACS WRITE statements to print to the job log for all, one, or no jobs. These statements will appear as additional messages outside of the original message chain.

#### **ENABLE or ENABLE,JOBVL(ALL)**

When ENABLE is specified without the optional *jobname*, or ALL is input in place of a jobname, every ACS WRITE statement will issue a message to the job log for all jobs. These messages will appear within JESMSGGLG as additional messages.

**ENABLE,JOBLVL(*jobname*)**

When ENABLE is specified and the *jobname* input matches the current running job, every ACS WRITE statement will issue a message to the job log only for the specified job. These messages will appear within JESMSG LG as additional messages.

**DISABLE**

When DISABLE is specified, no additional ACS WRITE statements will print to the job log for any jobs.

**Default:** DISABLE

**AKP({*nnn*[,*nnn*[...,*nnn*]] | 1000})**

Specifies the activity keypoint trigger value, which is the number of logging operations between keypoints. Up to 32 activity keypoint values can be specified. AKP values must be specified in the same order as DFSMStvs instance names. Specify a value from 200 to 65535.

You can allow some values to default while specifying others. For example, in AKP(800, , 3000), the value for the DFSMStvs instance in the second position defaults to 1000, and sets the values for the first and third DFSMStvs instances to 800 and 3000 respectively.

If AKP is specified with only the TVSNNAME parameter without an identifier, AKP applies to the system on which the parmlib member is being read. TVSNNAME must be specified with the AKP parameter.

Activity keypointing is the process of accounting for all the log records in the undo and shunt logs that are involved in active units of recovery. Activity keypointing enables DFSMStvs to delete records that are no longer involved in active units of recovery. It also enables DFSMStvs to update the undo log to optimize its restart performance related to reading the log stream.

An ideal AKP value is a balance between processing activity keypoints too frequently and not frequently enough. Specifying an AKP value that is too low might increase CPU usage unnecessarily, while too high an AKP value increases the storage requirements of the logstreams. To calculate an ideal AKP value, consider how many transactions the logs need to hold concurrently, the duration of those transactions, and how many updates each transaction performs.

To begin calculating your AKP value, start with a value that is greater than the average number of updates that occur during the length of a transaction, and lower than 3 times the maximum of that value. This can be expressed by the following formula:

$$\text{AKP} > \text{Avg}(\text{TranTime}) \times \text{Avg}(\text{UpdPerTran}) \times \text{Avg}(\text{TranPerTime})$$

$$\text{AKP} < 3 \times \text{Max}(\text{TranTime}) \times \text{Max}(\text{UpdPerTran}) \times \text{Max}(\text{TranPerTime})$$

Where the average and maximum of each of the following parameters is known:

*TranTime* = Transaction running time (in a time unit such as seconds)  
*UpdPerTran* = Updates per transaction  
*TranPerTime* = Transactions per time unit (same units as *TranTime*)

While this calculation provides a starting point for your AKP setting, it is recommended that you then monitor the logstream usage and adjust the AKP value as necessary.

**Default:** 1000

**ASID(*asid*|\*[(TRACE|T|VOLSELMSG|V)[,*asid*|\*(TRACE|T|VOLSELMSG|V)]])**

Specifies whether SMS is to limit tracing (TRACE(ON)) or issue volume selection messages (VOLSELMSG(ON)) to a specific address space (*asid*) or all address spaces (\*).

***asid*|\***

Limit tracing and volume selection analysis messages for a certain address space, or all address spaces (\*). You can enter up to 4 digits for the ASID keyword. If you leave off the leading zeros, they are inserted.

**[(TRACE|T|VOLSELMSG|V)[,*asid*|\*(TRACE|T|VOLSELMSG|V)]]**

These are optional subparameters. TRACE|T or VOLSELMSG|V associated with the first subparameter specifies whether the required value, *asid*, or \*, specified in the first subparameter applies to TRACE or VOLSELMSG facility. The second subparameter is optional and can be used to specify another value and facility after the first subparameter is specified. When

none of these optional subparameters are specified, the value that is specified in the first subparameter applies to both TRACE and VOLSELMSG. For example, if you want to have ASID 0010 for the SMS TRACE facility, and ASID 0020 for the VOLSELMSG facility, you might code: ASID(10(TRACE),20(VOLSELMSG)).

**Default:** \*

#### **AUTO\_VOLSTATUS\_EXTPOOL(YES|NO[,*nnn*|120])**

Specifies whether or not an online SMS volume is monitored for exhausted extent pool activity. This monitor only applies to compression extent pools and enables or disables the SMS Compression Extent Pool Alert. When SMS receives a Compression Extent Pool Out of Space Condition event (ENF) signal, all volumes associated with the flagged extent pool will have its SMS volume status modified to be QUINNEW if the status is currently ENABLE. Upon receiving a Compression Extent Pool Relief event (ENF) signal, all associated SMS volumes affected by the initial out of space condition will have its SMS status restored after *nnn* seconds.

**Note:** When the change occurs in the SMS volume status due to the extent pool's out of space constraint, the effect will restrict the selection of the volume only during new data set allocation. This will help prevent the SMS volumes and the extent pool space from further constraint.

#### **YES**

The SMS volume will be monitored for exhausted extent pool activity. This applies to devices that have space exceed the warning threshold.

#### **NO**

The SMS volume will not be monitored for any exhausted extent pool activity.

#### ***nnn***

This optional subparameter is measured in seconds and defaults to 120. *nnn* is the delayed time between receiving the Compression Extent Pool Out of Space relief event (ENF) signal and the SMS volume status resuming its original status. This delay will allow SMS to ignore rapid fluctuations between an extent pool entering and leaving the warning threshold. Valid values between 1 and 9999 seconds. Note: This *nnn* delay subparameter only applies to relief event processing.

**Default:** YES and 120 seconds.

#### **AUTO\_VOLSTATUS\_VTOC(YES|NO)**

Specifies whether or not an online SMS volume VTOC and Index record usage will be monitored. Does not affect volumes that are defined as DISABLE or DISNEW.

#### **YES**

The SMS volume's VTOC and Index record statistics will be monitored. If the VTOC begins to run out of space and exceeds a 90% threshold usage rate, then SMS will set the volume status to QUINNEW and issue message IGD418I. This QUINNEW status will cause this volume to have lower priority when SMS selects a volume for new allocation. If the VTOC usage rate reaches 100%, SMS will set the volume status to DISNEW and the volume will not be chosen by SMS for new dataset allocations. When the space constraint is relieved and drops below the 90% threshold, the original defined SMS volume status will be set.

**Note:** The change in the SMS volume status due to VTOC space constraint will only restrict the selection of the volume during new data set allocation. It is not mean tot make the volume more available as defined. If the volume was defined DISABLE from the ACDS, the status will not be set to QUINNEW or DISNEW as the VTOC exceeds 90%

The VTOC Index record statistics will be monitored but the SMS status will not be modified based on the usage rate. When an SMS volume's VTOC Index begins to run out of space and exceeds the 90% threshold usage, SMS will issue a warning message IGD419I to notify the storage administrator of the space constraint.

**NO**

The SMS volume's VTOC and Index record statistics will not be monitored.

**Default:** YES

**BLOCKTOKENSIZE(REQUIRE|NOREQUIRE)****NOREQUIRE**

Allows applications to access large format data sets under more conditions without having to specify BLOCKTOKENSIZE=LARGE on the DCBE macro.

When NOREQUIRE is in effect, programs that use the following access methods can open large format data sets without specifying BLOCKTOKENSIZE=LARGE on the DCBE macro:

- QSAM or BSAM without the NOTE or POINT macros.
- BSAM with the NOTE or POINT macros (MACRF=xP) only if the data set has 65535 or fewer tracks on the volume and the OPEN option is INPUT or UPDAT.
- EXCP (MACRF=E) and only when the data set has 65535 or fewer tracks on the volume and the OPEN option is INPUT.

**REQUIRE**

Requires every open for a large format data set to use BLOCKTOKENSIZE=LARGE on the DCBE macro, indicating that the application has made needed changes to support the data sets. The exception to this is if the data set contains no more than 65535 tracks on each volume and is open for input using EXCP, BSAM or QSAM, or for update using BSAM or QSAM.

**Default:** NOREQUIRE

**BREAKPOINTVALUE(0-65520)**

Specifies the disk space request (primary or secondary), expressed in the number of cylinders (0-65520), where the system should prefer the cylinder-managed space (CMS) on an extended address volume (EAV).

BREAKPOINTVALUE is applicable only to data sets that are eligible for extended addressing space (EAS). Data sets that are not EAS-eligible must reside in the track-managed region of a volume.

When a disk space request is equal to or greater than the value of BREAKPOINTVALUE, the system uses the cylinder-managed space for that extent. If not enough CMS is available, the system uses track-managed space (TMS) or both CMS and TMS. If the requested disk space is less than the BREAKPOINTVALUE, the system uses TMS. If not enough TMS is available, the system uses CMS or both of TMS and CMS.

BREAKPOINTVALUE is an optional field. If it is not specified at the storage group level, the system uses the default value that is specified in the IGDSMSxx member of SYS1.PARMLIB. If BREAKPOINTVALUE is not specified, a value of 10 cylinders is used instead.

For more information about **BreakPointValue**, see [Values for defining a pool storage group in z/OS DFSMSdfp Storage Administration](#).

**BYPASS\_CLUSTER\_PREFERENCING(YES|NO)****NO**

SMS data set allocation prefers volumes that match the storage controller server of the source data set.

**YES**

SMS data set allocation selects volumes independent of the storage controller server.

**Note:** FlashCopy on IBM DS8000 devices performs best when the FlashCopy target is allocated on the same server (cluster) as the FlashCopy source.

**Default:** NO.



**CACHETIME({nnnnn}) {3600 }**

Specifies the number of seconds between recording SMF records for device cache use. The CACHETIME parameter applies only to the volumes behind an IBM 3990 Storage Control with cache unit. You can specify a value from 1 to 86399 (23 hours, 59 minutes, 59 seconds), and the default is 3600 (one hour). For information about the control unit cache summary recorded in SMF record type 42, see *z/OS MVS System Management Facilities (SMF)*.

**Default:** 3600

**CA\_RECLAIM(NONE|{DATACLAS|DATACLASS})**

Specifies whether to use CA reclaim for KSDSs according to the CA Reclaim attribute in their data classes.

**DATACLAS|DATACLASS**

Indicates that the SMS-managed KSDSs and non-SMS-managed KSDSs go by the data class specification of CA Reclaim=Y|N at define time or subsequent ALTER setting. Only the resultant catalog setting of CA Reclaim=Y does CA reclaim; CA Reclaim=N does not do CA reclaim. It is the way to specify some KSDSs not to use CA reclaim. The default is DATACLAS. If CA\_RECLAIM is not specified in SYS1.PARMLIB, the CA\_RECLAIM(DATACLAS) default is in effect, which means the default is CA reclaim enabled.

**NONE**

Indicates that none of the KSDSs is using CA reclaim, regardless of the data class specification. To ensure CA reclaim is disabled, specify CA\_RECLAIM(NONE).

**Default:** DATACLAS

**CF\_TIME({nnnnn}) {3600}**

Specifies the interval (in seconds) for recording SMF record 42 (subtypes 15, 16, 17, 18, 19) for the SMSVSAM address space's use of the coupling facility.

If you record these subtypes, you can use CF\_TIME to synchronize SMF type 42 data with SMF and RMF data intervals.

Specify a value from 1 to 86399 (23 hours, 59 minutes, 59 seconds). The default is 3600 (one hour).

The SMF\_TIME keyword, if set to YES, overrides the CF\_TIME keyword.

In a sysplex, the first system that is initialized with an IGDSMSxx member having a valid CF\_TIME specification determines the CF\_TIME value for the other systems in the sysplex. You can change this value through the SETSMS or SET SMS commands.

**Default:** 3600

**CICSVR\_INIT(YES|NO)**

Specifies whether the CICSVR server address space should be started during an IPL.

**NO**

The CICSVR start is deferred. If you specify CICSVR\_INIT(NO), you must issue a SETSMS CICSVR\_INIT(YES) command before you can activate the CICSVR server.

**YES**

Starts the CICSVR server address space at system initialization.

**Requirement:** Every system in a sysplex must have an IGDSMSxx set up for the CICSVR server address space.

**Default:** NO.

**CICSVR\_BACKOUT\_CONTROL(cicsvr\_backout\_control\_string)**

Specifies the CICSVR batch backout control string that is used to control CICSVR batch backout. The *cicsvr\_backout\_control\_string* is up to 17 characters long. The valid characters are alphanumeric (A-Z, 0-9) and national (\$, @, #) characters, blanks, and comma.

**Default:** A blank character string.

For more information about CICSVR, see *CICS Transaction Server for z/OS* ([www.ibm.com/docs/en/cics-ts](http://www.ibm.com/docs/en/cics-ts)).

**CICSVR\_DSNAME\_PREFIX(*DWW|dsname prefix*)**

Defines a prefix for all CICSVR required data sets. This prefix is used for the data sets that must be pre-allocated before you can start the CICSVR server address space (for example, data sets that are allocated to the DD name, DWWMSG).

**Note:** CICSVR\_DSNAME\_PREFIX is required if you specify CICSVR\_INIT(YES). This defines a prefix for all CICSVR—required data sets excluding RCDS data sets, DWWCON1, DWWCON2, and DWWCON3.

**Default:** DWW

**CICSVR\_GENERAL\_CONTROL(*cicsvr\_general\_control\_string*)**

Specifies the CICSVR general control string that is used to general control CICSVR. For example, CICSVR general control string and service functions can be used to invoke a CICSVR scavenger or to display the current setting of all CICSVR control strings.

The *cicsvr\_general\_control\_string* is up to 17 characters long. The valid characters are alphanumeric (A-Z, 0–9) and national (\$, @, And #) characters, blanks, and comma.

**Default:** A blank string that is interpreted as SUBMIT NONE.

For more information about CICSVR, see [CICS Transaction Server for z/OS \(www.ibm.com/docs/en/cics-ts\)](http://www.ibm.com/docs/en/cics-ts).

**CICSVR\_GRPNAME\_SUFFIX(*cicsvr\_grpname\_suffix*)**

Defines the CICSVR XCF group name suffix that the CICSVR server address space uses to create a unique XCF group name for the sysplex and connect to the XCF group. All the systems that share the same suffix and are active belongs to the same CICSVR XCF group. The *cicsvr\_grpname\_suffix* is up to four characters long. The valid characters are alphanumeric (A-Z, 0–9) and national (\$, @, And #) characters.

**Default:** PROD

**CICSVR\_RCDS\_PREFIX(*cicsvr\_rcds\_prefix*)**

Defines a prefix of the CICSVR Recovery Control Data set (RCDS) name that the CICSVR server address space uses to allocate the RCDS to the CICSVR server. The *cicsvr\_rcds\_prefix* is up to 17 characters long. It follows the syntax rules for data set names. The prefix can contain up to two qualifiers that are separated by a period.

**Default:** DWW

**CICSVR\_UNDOLOG\_CONTROL(*cicsvr\_undolog\_control\_string*)**

Specifies the CICSVR UNDO logging control string. The *cicsvr\_undolog\_control\_string* is up to 17 characters long. The valid characters are alphanumeric (A-Z, 0–9) and national (\$, @, And #) characters, blanks, and comma.

**Default:** A blank string that is interpreted as ENABLE CONT.

For more information about CICSVR, see [CICS Transaction Server for z/OS \(www.ibm.com/docs/en/cics-ts\)](http://www.ibm.com/docs/en/cics-ts).

**CICSVR\_UNDOLOG\_PREFIX(*cicsvr\_undolog\_prefix*)**

Defines a CICSVR UNDO log name prefix that the CICSVR server address space uses to determine the log stream name that should be written to by CICSVR UNDO logging. The *cicsvr\_undolog\_prefix* is up to 8 characters long. It follows the syntax rules for data set names.

**Default:** DWW

**CICSVR\_ZZVALUE\_PARM(*zzvalue\_parm\_string*)**

Specifies the ZZVALUE parameter string that is used to control CICSVR debugging and diagnostics. The *zzvalue\_parm\_string* must be up to 17 characters long, padded on the right with blanks if necessary. The valid characters are alphanumeric (A-Z, 0–9), national (\$, @, And #) characters, blank, and comma.

**Default:** A blank character string.

**COMPRESS({TAILORED|GENERIC|ZEDC\_R|ZEDC\_P})**

Specifies the type of compression to be used for the data set.

**GENERIC**

Specifies that the data set be compressed using generic Dictionary Building Block (DBB) compression. The dictionary is derived from a defined set of compression algorithms in data set SYS1.DBBLIB.

**TAILORED**

Specifies that the data set is eligible for compression that is tailored to the data set. A tailored dictionary is built, using the initial data written to the data set, and embedded into the data set. The dictionary is issued to compress or expand data written to or read from the data set. This type of compression applies only to sequential data sets, not to VSAM KSDSs.

To convert an existing DBB-based compressed data set to use tailored compressions, you must set the COMPRESS parameter to TAILORED and copy the generic DBB-based data set to a new data set that meets compression requirements.

**ZEDC\_P**

Specifies that the data set be compressed using zEDC compression, as with the ZEDC\_R option. But here, the system does not fail the allocation request, but rather create either a tailored compressed data set if the zEDC function is not supported by the system, or create a non-compressed extended format data set if the minimum allocation amount requirement is not met.

**ZEDC\_R**

Specifies that the data set be compressed using zEnterprise data compression (zEDC). No separate dictionary is created, as zEDC compression hides the dictionary in the data stream. A new dictionary starts in each compression unit. The system can decompress the segment as is.

With this option (as opposed to ZEDC\_P), the system fails the allocation request if the zEDC function is not supported by the system, or if the minimum allocation amount requirement is not met.

**Note:**

1. Use tailored compression only when all systems in the SMS complex have been converted to DFSMS/MVS 1.4 or later, and when there is no need to revert to a prior release level for local recovery or remote recovery with Aggregate Backup and Recovery Support (ABARS). The date of general availability for DFSMS/MVS 1.4 was in 1997.
2. To convert an existing DBB-based (generic) compressed data set to use tailored compression, or to convert from either generic or tailored to zEDC compression, first set the COMPRESS parameter to TAILORED, ZEDC\_R, or ZEDC\_P in the IGDSMSxx parmlib member. Use IEBGENER, ICEGENER, REPRO, or any QSAM or BSAM application to copy the data set to a new data set that meets compression requirements.
3. The zEDC feature must be installed on all systems before using zEDC compression. For more information on zEDC compression, see [\*z/OS MVS Programming: Callable Services for High-Level Languages\*](#).
4. For an interactive starting point, and access to various technical resources about Integrated Accelerator for zEDC, see [Integrated Accelerator for zEDC \(www.ibm.com/support/z-content-solutions/compression/\)](http://www.ibm.com/support/z-content-solutions/compression/).

**Default:** GENERIC

**DB2SSID(ssid)**

For a classic OAM configuration, this keyword specifies the name of the Db2<sup>®</sup> subsystem which is used by Object Access Method (OAM) for object storage. *ssid* can be from one to four characters. If your installation does not use OAM for object storage, omit this keyword or specify a value of NONE.

For a multiple OAM configuration, this keyword is ignored and instead each OAM subsystem configured in IEFSSNxx is required to specify the name of the Db2<sup>®</sup> subsystem with which it is associated.

**Default:** There is no default.

**DEADLOCK\_DETECTION(nnnn|15,kkkk|4)**

This keyword specifies the intervals for local and global deadlock detection.

*nnnn* specifies the local system's deadlock detection interval (in seconds). Specify *nnnn* as a one to four-digit numeric value in the range 1-9999.

*kkkk* specifies the number of local deadlock cycles that must expire before the sysplex performs global deadlock detection. Specify *kkkk* as a one to four-digit numeric value in the range 1-9999.

In a sysplex, the first system that is initialized with an IGDSMSxx member that has a valid DEADLOCK\_DETECTION specification determines the DEADLOCK\_DETECTION value for the other systems in the sysplex. You can change this value through the SETSMS or SET SMS commands.

**Default:** 15,4

### **DESELECT({event[,event][,...]|ALL})**

Deletes items from the list of events and services to be traced (if SMS tracing is active). DESELECT has no default. If you specify events that conflict in SELECT and DESELECT, the keyword that appears last has final authority. The events that you can specify on SELECT and DESELECT are as follows:

| Table 30. Events that you can specify on SELECT and DESELECT (IGDSMSxx parameter) |   |
|---|---|
| Event   | Description   |
| ACSINT  | ACS services interfaces.                                  |
| ACSPRO  | Perform ACS processing.                                   |
| ALL   | All of the options in this list.                          |
| CATG  | SMS catalog services.                                     |
| CDSC  | Control data set changes.                                 |
| CONFA   | Activate a new configuration.                             |
| CONFC   | Configuration changes.                                    |
| CONFR   | Return data from an active configuration.                 |
| CONFS   | SMS configuration services.                               |
| DEBUG   | Debug service.  |
| DCF   | SMS device control facility.                              |
| DISP  | SMS disposition processing exit.                          |
| DPN   | SMS device pool name select subsystem interface.          |
| DSTACK  | Trace execution of SMS data set stacking.                 |
| ERR   | SMS error recovery and recording services.                |
| IDAX  | SMS interpreter/dynamic allocation.                       |
| MODULE  | SMS module entry or exit.                                 |
| MSG   | SMS message services.                                     |
| OPCMD   | Operator commands.  |
| RCD   | SMS recording services or SMS fast VTOC/VVDS access.      |
| SCHEDP  | SMS scheduling services (prelocated catalog orientation). |
| SCHEDS  | SMS scheduling services (system select).                  |
| SMSSJF  | SMS/SJF interfaces.                                       |
| SMSSSI  | SMS/SSI interfaces.                                       |
| TVR   | SMS tape volume record update facility.                   |
| VOLREF  | SMS VOLREF services.                                      |
| VTOCA   | SMS VTOC/data set services (add a volume to a data set).  |
| VTOCC   | SMS VTOC/data set services (allocate new data set).       |
| VTOCD   | SMS VTOC/data set services (delete existing data set).    |

Table 30. Events that you can specify on SELECT and DESELECT (IGDSMSxx parameter) (continued)

| Event | Description  |
|-------|--|
| VTACL | SMS VTOC/data set services (allocate existing data set). |
| VTOCR | SMS VTOC/data set services (rename existing data set).   |

**DINTERVAL({nnn}) {150}**

Specifies the interval (in seconds) that SMS waits between reading device statistics from the 3990-3 control unit (applicable only if the 3990-3 is installed and has at least one SMS-managed volume). Specify a value from 1 to 999 (16 minutes, 39 seconds).

**Default:** 150

**DSNAME(DSNAME|\*)**

Limits the number of issued volume selection analysis messages activated by VOLSEGMSG(ON) that are issued to the hardcopy and job logs for a certain data set name or for all data set names. For a VSAM data set, this is the cluster's entry name. Specify \* to issue volume selection analysis messages for all data set names.

**Default:** \*

**DSNTYPE(LIBRARY|PDS|ZFS)**

Specifies the installation default for data sets allocated with directory space but without a data set type specified. If DSNTYPE is PDS, the default is a partitioned data set format; if DSNTYPE is LIBRARY, the default is a PDSE (partitioned data set extended) format. If DSNTYPE is ZFS, the default is a hierarchical file system format. For more information about data set types, see [z/OS DFSMS Using Data Sets](#).

**Default:** PDS

**DSSTIMEOUT({nnn}) (0)**

Specifies the number of seconds that the dss component of DFMSMS waits during backup processing for quiesce data set requests to complete. Specify a value from zero to 65536 seconds (which is more than 18 hours). If you specify a value between 1 and 299 seconds, the system uses a value of 300 seconds (which equals 5 minutes).

The value that is specified in the DSSTIMEOUT parameter value is activated when the first instance of the SMSVSAM address becomes active in the sysplex. All subsequent SMSVSAM instances use the same value.

You can alter the DSSTIMEOUT value dynamically in the following ways:

- Using the SETSMS DSSTIMEOUT(nnnn) command
- By adding or updating the DSSTIMEOUT parameter in IGDSMSxx parmlib member and then activating it with the SET SMS=xx command

**Default:** 0

**FAST\_VOLSEL(ON|OFF)**

Specifies whether to use the "fast" approach during SMS volume selection.

For striping allocations, fast volume selection is automatically activated regardless of the specification of the FAST\_VOLSEL parameter.

If you specify ON, SMS first selects volumes typically until DADSM rejects 100 volumes for insufficient free space. SMS issues message IGD17294I to indicate that fast volume selection was entered and then excludes volumes that do not have sufficient free space in the volume statistics. This 'fast' approach can inadvertently exclude volumes that have sufficient free space but for which SMS volume statistics indicates that they do not. SMS volume statistics can occur for the following events:

- The VTOC index is broken.
- OEM products bypass CVAf processing.

- In an SMSplex when the SMS synchronization time interval has not yet been driven to update the SMS configuration with the most current space statistics. These statistics are based on updates that can occur on another system in the SMSplex.

If you specify OFF, SMS uses the 'normal' approach to select volumes.

**Default:** OFF

### **GDS\_RECLAIM(YES|NO)**

Specifies whether the system reclaims generation data sets. GDS\_RECLAIM is an optional keyword.

If you specify YES, the system reclaims generation data sets.

Note:

**Note:** GDS\_RECLAIM processing is only valid for DASD data sets. It is not valid for tape data sets.

For complete information about how reclaim processing works, see [Reclaiming Generation Data Sets](#) in *z/OS DFSMS Using Data Sets*.

**Default:** YES

### **HONOR\_DSNTYPE\_PDSE (YES|NO)**

Specifies whether DSNTYPE of LIBRARY or ZFS are honored during the data set creation, regardless of what DSORG is specified and regardless of whether directory blocks have been specified. If YES is specified, then DSNTYPE of LIBRARY or ZFS is honored even if the DSORG is not set to PO and there are no directory blocks specified. If NO is specified, DSNTYPE of LIBRARY or ZFS is honored only when the DSORG is set to PO or directory blocks are specified. Otherwise, a physical sequential data set is created.

**Default:** NO

### **INTERVAL({nnnn}) {15 }**

Specifies the synchronization interval of the system, which is the number of seconds between system checks of the COMMDS for information about SMS configuration changes from other systems in the SMS complex. You can specify a value from 1 to 999 (16 minutes, 39 seconds).

If your installation has multiple systems simultaneously trying to update the SMS configuration and you have your INTERVAL value set too low, you might experience contention. The larger the number of SMSplex members and the larger the configuration, the more contention you might experience. SMS makes several attempts to complete the configuration updates, but after a predefined number of attempts are blocked by contention, the system issues the 6040 configuration services reason code. This is more likely to happen in installations with multiple SMSplex members (8 or more) and large SMS configurations (50,000 or more volumes). To reduce the amount of contention and 6040 reason codes you experience, set your INTERVAL value higher.

**Default:** 15

### **JOBNAME(jobname|\*[(TRACE|T|VOLSELMSG|V)[,jobname|\*(TRACE|T|VOLSELMSG|V)])]**

Specifies whether SMS is to limit tracing (TRACE) and volume selection analysis messages (VOLSELMSG(ON)) for a certain job (*jobname*), or permit tracing and volume selection analysis messages on all jobs. This keyword supports objects or tape libraries.

**jobname|\***

Limit tracing and volume selection analysis messages for a certain job, or all jobs (\*). Specify "\*" to issue for all jobs.

**[(TRACE|T|VOLSELMSG|V)[,jobname|\*(TRACE|T|VOLSELMSG|V)]**

These are optional subparameters. TRACE|T or VOLSELMSG|V associated with the first subparameter specifies whether the required value, jobname or \*, specified in the first subparameter applies to TRACE or VOLSELMSG facility. The second subparameter is optional and can be used to specify another value and facility after the first subparameter is specified. When none of these optional subparameters are specified, the value specified in the first subparameter

applies to both TRACE and VOLSELMSG. For example, if you want to have all jobs for the SMS TRACE facility, and a particular job, JOB111, for the VOLSELMSG facility, you might code: `JOBNAME(*(TRACE),JOB111(VOLSELMSG))`.

**Default:** \*.

### **LOG\_OF\_LOGS(logstream)**

Specifies the log stream that is to be used as the log of logs. This log contains copies of tie-up and file-close records written to forward recovery logs and is used by forward recovery products. If this parameter is not specified, no log of logs is used. This parameter is unique to each system in the sysplex. As each instance of DFSMStvs starts, it uses the log of logs name that is found in its member of SYS1.PARMLIB. If you run test and production systems within the same sysplex, use a separate parmlib member for the test system and specify a different log of logs in it.

If you specify the LOG\_OF\_LOGS parameter for use with DFSMStvs, you must also specify the TVSNAME(*nnn*) parameter.

**Default:** None.

### **MAXGENS\_LIMIT(0-2000000000)**

Specifies an upper limit for the MAXGENS parameter on the DD statement in JCL. MAXGENS specifies the number of generations for version 2 PDSEs. The value is stored in the DFAMAXGN field.

For information about the MAXGENS parameter, see [z/OS MVS JCL Reference](#).

**Default:** 0

### **MAXLOCKS({max|0},{incr|0})**

Specifies a pair of values in the range of 0 to 999999. The two values are the maximum number of unique lock requests that a single unit of recovery can make and an increment value. Once the maximum number of unique lock requests is reached, warning messages are issued every time the number of unique lock requests over the maximum increases by a multiple of the increment. When the maximum number is reached, warning message IGW859I and informational message IGW10074I are issued to the system console. The messages include the name of the job that is holding the locks. This information helps you to determine whether the job should be canceled. In that case, the unit of recovery is backed out, and the locks remain held until the backout completes. Specifying a value of 0 indicates that warning messages IGW859I and IGW10074I should not be issued.

If you specify the MAXLOCKS parameter, you must also specify the TVSNAME(*nnn*) parameter. This parameter applies across all systems.

#### **Notes:**

1. Lock requests are considered unique if they lock different records within the base cluster. Repeated requests for the same base cluster records do not result in the count being increased.
2. Warning messages IGW859I and IGW10074I are not issued for units of recovery that are in backout. This is because a unit of recovery that is in backout cannot obtain locks on any additional records.
3. Messages IGW859I and IGW10074I are issued until the unit of recovery reaches commit. Once the unit of recovery reaches commit, no additional messages are issued.
4. To avoid flooding the system console with messages, messages IGW859I and IGW10074I are issued by an asynchronous timer driven task that wakes up every 10 seconds. This means that the messages do not reflect the exact values specified for the maximum and the increment, but rather reflects the values which represent the state of the unit of recovery at the time the task awakens.
5. MAXLOCKS takes into account the number of unique lock requests. It does not count the actual number of locks obtained. The number of locks requested differs from the number of locks held when alternate indexes are used. If an update modifies alternate keys, a lock is obtained for the base record, for each old alternate key, and for each new alternate key. Therefore, if *n* alternate keys are modified, a single lock request can result in obtaining (2*n*+1) locks.

Some examples of how this parameter can be specified are:



**MAXLOCKS(0,0)**

Valid - messages IGW859I and IGW10074I are not issued.

**MAXLOCKS(,)**

Valid - this is the equivalent of specifying MAXLOCKS(0,0); messages IGW859I and IGW10074I are not issued.

**MAXLOCKS(5000,0)**

Valid - messages IGW859I and IGW10074I are issued when the asynchronous task wakes up and a unit of recovery made its 5000th lock request.

**MAXLOCKS(0,2000)**

Not valid

**MAXLOCKS(4500,1000)**

Valid - messages IGW859I and IGW10074I are issued when the asynchronous task wakes up and a unit of recovery made its 4500th lock request and again every 1000 unique lock requests thereafter.

**MAXLOCKS(1000,2300)**

Valid - messages IGW859I and IGW10074I are issued when the asynchronous task wakes up and a unit of recovery has made its 1000th lock request and again every 2300 unique lock requests thereafter.

**MAXLOCKS(3200,)**

Valid - this is the equivalent of specifying MAXLOCKS(3200,0); messages IGW859I and IGW10074I are issued when the asynchronous task wakes up and a unit of recovery made its 3200th lock request.

**MAXLOCKS(,2000)**

Not valid

The default for both values is 0

**OAMPROC(procname)**

In a classic OAM configuration, this keyword specifies the name of the procedure that is to start an OAM address space when SMS is initialized. You must specify this keyword if you want an OAM address space to be started during IPL. The procedure name can be from one to eight characters.

In a multiple OAM configuration, this keyword can be used to start only one of the OAM address spaces. It is recommended that this procedure name be used for the single OAM address space configured for Tape Library processing (if needed and if the OAM address space can be started before your tape management system).

Regardless of which procedure name is used, an additional OAM configuration must be performed for the associated OAM subsystem definition in IEFSSNxx to identify the appropriate Db2 identifier and for the procedure itself to identify the appropriate Db2 identifier. In the case of the specification of the recommended procedure used to start the single OAM address space (configured for Tape Library processing), the OAM configuration for the associated OAM subsystem and procedure must specify 'NONE' for the Db2 identifier.

**Default:** There is no default.

**OAMTASK(taskid)**

Specifies the ID of the task that is to be used to start the OAM address space. OAMTASK is optional; if you specify it without an OAMPROC value, it is ignored. If you omit OAMTASK, the task ID defaults to the procedure name specified in OAMPROC. OAM keywords take effect only if you start SMS at IPL; otherwise, the system ignores them. The task ID can be from one to eight characters.

**OVRD\_EXPDT(YES|NO)**

Specifies whether the expiration date or retention period for an SMS-managed DASD data set is to be overridden when a user attempts to delete the data set in one of the following ways:

- DISP parameter on the JCL DD statement.
- Dynamic allocation.
- IEHPRGM utility.



- ISPF/PDF D or DEL line commands.

Specify YES to override an expiration date or retention period for an SMS-managed DASD data set. The data set is deleted regardless of expiration dates or retention period and the system does not prompt for confirmation. Note that this is a system-level parameter that affects all jobs running on the system. Exercise caution in using it, so that you do not accidentally delete needed data sets.

When you specify YES, ensure that all appropriate personnel at your installation know that specifying an expiration date or retention period for an SMS-managed DASD data set does not prevent the data set from being deleted.

Specify YES when:

- Expiration dates or retention periods are not used for data sets, or are overridden by appropriate management classes.
- Data sets allocated to tape are redirected using tape mount and the retention periods and expiration dates for these data sets are not overridden by management classes.

Specify NO to honor the expiration date or retention periods.

**Default:** NO

### **PDSE\_BMFTIME|BMFTIME(nnn)**

With the introduction of a second PDSE address space, two sets of PDSE parameters exist depending on the release of the z/OS system. For z/OS 1.8, PDSE\_BMFTIME applies. For z/OS 1.8 and later, BMFTIME applies and is associated with the SMSPDSE address space. For information about parameters for z/OS releases earlier than z/OS 1.8, see the appropriate version and release level of the information.

Specifies the number of seconds that SMS is to wait between recording SMF type 42 subtype 1 records for buffer manager facility (BMF) cache use and SMF type 42 subtype 6 interval records. You can specify a value from 1 to 86399 (23 hours, 59 minutes, 59 seconds), and the default is 3600 (one hour).

For information about the buffer management statistics that are recorded in SMF record type 42, see [z/OS MVS System Management Facilities \(SMF\)](#).

**Default:** 3600

### **PDSE\_BUFFER\_BEYOND\_CLOSE (YES|NO)**

For the SMSPDSE address space, specifies whether to keep cached directory and member data in storage beyond the last close on this system of a PDSE data set. If the NO option is selected or defaulted, the cached directory and member data of a PDSE is purged from the in-memory cache when the last close of the data set occurs. If you specify the YES option, the cached PDSE directory and member data are retained in the in-memory cache beyond the last close of the data set.

**Default:** NO

### **PDSE\_DIRECTORY\_STORAGE(nnn|2G)**

Specifies the size in gigabytes or megabytes of 64-bit virtual storage that is used to cache PDSE directory buffers in the SMSPDSE address space. The size values are defined with nnnM for megabytes, or nnnG for gigabytes. For example, to request a 500-megabytes size for the PDSE server address space directory cache, specify PDSE\_DIRECTORY\_STORAGE(500M).

**Default:** 2 gigabytes

The maximum is 16 gigabytes.

The minimum is 64 megabytes.

### **PDSE\_HSP\_SIZE|HSP\_SIZE(nnn)**

With the introduction of a second PDSE address space, two sets of PDSE parameters exist. HSP\_SIZE is synonymous with PDSE\_HSP\_SIZE and is associated with the SMSPDSE address space.

You can use the HSP\_SIZE parameter to request up to 2047 megabytes for the PDSE hyperspace. You can indicate that the hyperspace is not to be created by setting HSP\_SIZE to 0. If the hyperspace is not created, the system does not cache PDSE members.

On systems that are running in z/Architecture mode, by default the PDSE hyperspace is not created and PDSE member caching is disabled.

The system uses the valid values for HSP\_SIZE to create the PDSE hyperspace at IPL-time. The HSP\_SIZE value remains in effect during the the IPL.

If not enough of the appropriate storage is available to satisfy the HSP\_SIZE value, the system uses some portion of the available storage (up to the full amount) for the PDSE hyperspace depending on the amount of caching activity in the system. If the available storage becomes full, the system stops caching PDSE members.

Use the HSP\_SIZE parameter with care. If you specify an HSP\_SIZE value that is too low for normal PDSE hyperspace usage, you can degrade PDSE performance. If you specify a value for HSP\_SIZE that is too large, and there is contention for storage on the system, you can degrade performance of other components or applications in the system.

To determine current HSP\_SIZE value of the PDSE hyperspace, use the DISPLAY SMS,OPTIONS command, or review the messages that are written to syslog when SMS is started.

You can examine SMF type 42, subtype 1, records to evaluate the effectiveness of a particular HSP\_SIZE value.

PDSE Caching statistics at the data set level are available in SMF type 14 and 15 records. You can also display PDSE Caching details using the DISPLAY SMS,PDSE,HSPSTATS command.

**Default:** 0 for z/Architecture mode, 256 for non-z/Architecture mode.

#### **PDSE\_LRUCYCLES|LRUCYCLES(nnn)**

LRUCYCLES specifies the maximum number of times (5 to 240 cycles) that the least recently used (LRU) routine passes over inactive buffers before making them available for reuse. While this parameter sets the maximum value, the LRU algorithm dynamically changes the actual number of times it passes over inactive buffers.

LRUCYCLES is related to LRUTIME. A change to the LRUCYCLES value introduced by this parameter takes effect on the next execution of the LRU routine. Use the default value. In some very high data rate situations, you can tune this value. Monitor the SMF 42 type 1 record to determine the amount of caching activity in the BMF data space. See *z/OS MVS System Management Facilities (SMF)* for information about the buffer management statistics recorded in SMF record type 42.

With the introduction of a second PDSE address space in z/OS 1.6, two sets of PDSE parameters exist. LRUCYCLES is associated with the SMSPDSE address space.

**Default:** 15 for z/Architecture mode, 240 for non-z/Architecture mode.

#### **PDSE\_LRUTIME|LRUTIME(nnn)**

With the introduction of a second PDSE address space in z/OS 1.6, now two sets of PDSE parameters exist. For information about parameters for z/OS releases earlier than z/OS 1.6, see the appropriate version and release level of this information.

LRUTIME specifies the number of seconds (5 to 60) that the system waits between calls to the LRU (least recently used) routine. The LRU routine releases inactive buffers in the data space that are used to cache PDSE (partitioned data set extended) directory data and in the hyperspace that is used to cache PDSE member data.

LRUTIME is related to LRUCYCLES. A change to the LRUTIME value takes effect on the next execution of the LRU routine. Use the default value. In some very high data rate situations you can tune this value. Monitor the SMF 42 type 1 record to determine the amount of caching activity in the data space. See *z/OS MVS System Management Facilities (SMF)* for information about the buffer management statistics recorded in SMF record type 42.

**Default:** 60 for z/Architecture mode, 15 for non-z/Architecture mode.

**PDSE\_MONITOR({YES|DISPLAY|DUMPNEXT|NO},{interval[,duration]})**

Specifies how the processing for the PDSE monitor should be started or modified for the non-restartable PDSE address space, SMSPDSE.

**DISPLAY**

Turns on monitor processing and causes any possible error messages to be displayed to the console.

**DUMPNEXT**

Turns on monitor processing and causes a dump to be taken. The system issues message IGW031I for the next error detected. Only one dump is taken.

**NO**

Turns off monitor processing.

**YES**

Turns on monitor processing.

If the PDSE parameter is omitted, the monitor is started with default values for 60 seconds for interval and 15 seconds for duration.

***duration***

Specifies the number of seconds a possible error condition must exist before it is treated as an error. If the PDSE\_MONITOR keyword is specified, but duration is omitted, the duration remains unchanged, except at IPL time when the duration is set to 15.

***interval***

Specifies the number of seconds between successive scans of the monitor. If the PDSE\_MONITOR keyword is specified, but interval is omitted, the interval remains unchanged, except at IPL time when the interval is set to 60.

**Default:** YES

**Note:** If the PDSE\_MONITOR parameter is not specified in IGDSMSxx and you issue the D SMS,OPTIONS command, then the display shows (YES,0,0). This indicates that the default values of (YES,60,15) are in use. To avoid any confusion with display output when using the defaults, code (YES,60,15) in the IGDSMSxx parmlib member.

**PDSE\_PENDING\_DELETE\_INTERVAL(nnnn)**

Specifies the interval, in minutes, between automatic pending delete processing. This is intended for installations which have PDSEs which are left open for output for long periods of time. Normally pending delete processing is only performed when the first open for output occurs on a system.

If 0 is specified, this new processing never occurs.

If specified, this interval should be greater than the time specified by PDSE(1)\_LRUCYCLES and PDSE(1)\_LRUTIME. For example, the default value for these two parameters is 15 cycles and 60 seconds, which are 15 minutes. The value of PDSE\_PENDING\_DELETE\_INTERVAL should be greater than 15.

**Default:** 0

The minimum is 0.

The maximum is 9999.

**PDSE\_RESTARTABLE\_AS(YES|NO)**

Specifies whether PDSE initialization during IPL NIP processing brings up a second restartable PDSE address space.

If you specify PDSE\_RESTARTABLE\_AS(YES), with PDSESHARING(EXTENDED), and EXTENDED sharing is not used, processing does not allow PDSE initialization to create a second restartable PDSE address space.

The PDSE\_RESTARTABLE\_AS specification is set in the IGDSMSxx member of SYS1.PARMLIB. This value cannot be changed through an operator command.

**Default:** NO

**Note:** The PDSE parameters must be specified in the IEASYSxx SMS=xx rather than in IEFSSNxx.

### **PDSE\_VERSION({1|2})**

Specifies the version number to be used as a default for data sets that are allocated with a DSNTYPE of LIBRARY.

The PDSE\_VERSION specification is set in the IGDSMSxx member of SYS1.PARMLIB. This value cannot be changed through an operator command.

**Default:** 1

### **PDSE1\_BMFTIME(nnn)**

Specifies the number of seconds that SMS is to wait between recording SMF type 42 subtype 1 records for buffer manager facility (BMF) cache use and SMF type 42 subtype 6 interval records. You can specify a value from 1 to 86399 (23 hours, 59 minutes, 59 seconds). For information about the buffer management statistics recorded in SMF record type 42, see *z/OS MVS System Management Facilities (SMF)*.

**Default:** 3600 (one hour)

**Note:** With the introduction of a second PDSE address space in z/OS 1.6, two sets of PDSE parameters now exist. For z/OS 1.6 and later, PDSE1\_BMFTIME is associated with the restartable SMSPDSE1 address space. See the PDSE\_RESTARTABLE\_AS(YES) parameter for information about the SMSPDSE1 address space.

### **PDSE1\_BUFFER\_BEYOND\_CLOSE (YES|NO)**

For the SMSPDSE1 address space, specifies whether to keep cached directory and member data in storage beyond the last close on this system of a PDSE data set. If the NO option is selected or defaulted, the cached directory and member data of a PDSE is purged from the in-memory cache when the last close of the data set occurs. If you specify the YES option, the cached PDSE directory and member data are retained in the in-memory cache beyond the last close of the data set.

**Default:** NO

### **PDSE1\_DIRECTORY\_STORAGE(nnn|2G)**

Specifies the size in gigabytes or megabytes of 64-bit virtual storage that is used to cache PDSE directory buffers in the SMSPDSE1 address space. The size values are defined with nnnM for megabytes, or nnnG for gigabytes. For example, to request a 10-gigabytes size for the PDSE1 server address space directory cache, specify PDSE1\_DIRECTORY\_STORAGE(10G).

**Default:** 2 gigabytes

The maximum is 16 gigabytes.

The minimum is 64 megabytes.

**Note:** The PDSE1\_DIRECTORY\_STORAGE amount is not a hard limit. This amount can be exceeded during periods of heavy PDSE processing.

### **PDSE1\_HSP\_SIZE(nnn|0)**

PDSE1\_HSP\_SIZE parameter specifies the size of the hiperspace in megabytes that is used for PDSE member caching for SMSPDSE1.

You can use the PDSE1\_HSP\_SIZE parameter to request up to 2047 megabytes for the PDSE1 hiperspace. Or, you can indicate that the hiperspace is not to be created by setting PDSE1\_HSP\_SIZE to 0. If the hiperspace is not created, the system does not cache PDSE members.

On systems that are running in z/Architecture mode, by default the PDSE1 hiperspace is not created and PDSE member caching is disabled.

If you specify a valid value for PDSE1\_HSP\_SIZE, the system uses it to create the PDSE1 hiperspace at IPL-time. The PDSE1\_HSP\_SIZE value might be changed by a SET SMS=xx command, and then the new value is used if the SMSPDSE1 address space is restarted.

If not enough of the appropriate storage is available to satisfy the PDSE1\_HSP\_SIZE value, the system uses some portion of the available storage (up to the full amount) for the PDSE1 hiperspace, depending on the amount of caching activity in the system. The system stops caching PDSE members if the available storage becomes full.

Use the PDSE1\_HSP\_SIZE parameter with care. If you specify an PDSE1\_HSP\_SIZE value that is too low for normal PDSE hiperspace usage, you can degrade PDSE performance. If you specify a value for PDSE1\_HSP\_SIZE that is too large, and there is contention for storage on the system, you can degrade performance of other components or applications in the system.

To determine the current PDSE1\_HSP\_SIZE value of the PDSE1 hiperspace, use the DISPLAY SMS,OPTIONS command, or review the messages that are written to syslog when SMS is started.

You can examine SMF type 42, subtype 1, records to evaluate the effectiveness of a particular HSP\_SIZE value.

PDSE Caching statistics at the data set level are available in SMF type 14 and 15 records. You can also display PDSE Caching details using the DISPLAY SMS,PDSE1,HSPSTATS command.

**Note:** With the introduction of a second PDSE address space in z/OS 1.6, two sets of PDSE parameters now exist. For z/OS 1.6 and later, PDSE1\_HSP\_SIZE is associated with the restartable SMSPDSE1 address space. See the PDSE\_RESTARTABLE\_AS(YES) parameter for information about the SMSPDSE1 address space.

**Default:** 0

#### PDSE1\_LRUCYCLES(nnn|15)

PDSE1\_LRUCYCLES specifies the maximum number of times (5 to 240 cycles) that the least recently used (LRU) routine passes over inactive buffers before making them available for reuse. The LRU algorithm dynamically changes the **actual** number of times it passes over inactive buffers.

PDSE1\_LRUCYCLES is related to PDSE1\_LRUTIME. A change to the PDSE1\_LRUCYCLES value takes effect on the next execution of the LRU routine. Use the default value. In some very high data rate situations, you can tune this value. Monitor the SMF 42 type 1 record to determine the amount of caching activity in the BMF data space. See *z/OS MVS System Management Facilities (SMF)* for information about the buffer management statistics that are recorded in SMF record type 42.

**Note:** With the introduction of a second PDSE address space in z/OS 1.6, now two sets of PDSE parameters now exist. For z/OS 1.6 and later, PDSE1\_LRUCYCLES is associated with the restartable SMSPDSE1 address space. See the PDSE\_RESTARTABLE\_AS(YES) parameter for information about the SMSPDSE1 address space.

**Default:** 15 for z/Architecture mode, 240 for non-z/Architecture mode.

#### PDSE1\_LRUTIME(nnn|60)

PDSE1\_LRUTIME specifies the number of seconds (5 to 60) that the system waits between calls to the LRU (least recently used) routine. The LRU routine releases inactive buffers in the data space that are used to cache PDSE (partitioned data set extended) directory data and in the hiperspace that is used to cache PDSE member data.

PDSE1\_LRUTIME is related to PDSE1\_LRUCYCLES. A change to the PDSE1\_LRUTIME value takes effect on the next execution of the LRU routine. Use the default value. In some very high data rate situations, you change this value for tuning purposes. Monitor the SMF type 1 record to determine the amount of caching activity in the data space. See *z/OS MVS System Management Facilities (SMF)* for information about the buffer management statistics that are recorded in the SMF type 42 record.

**Note:** With the introduction of a second PDSE address space in z/OS 1.6, two sets of PDSE parameters now exist. For z/OS 1.6 and later, PDSE1\_LRUTIME is associated with the restartable SMSPDSE1 address space. See the RESTARTABLE\_PDSE\_AS(YES) parameter for information about the SMSPDSE1 address space.

**Default:** 60

**PDSE1\_MONITOR({YES|DISPLAY|DUMPNEXT|NO}[interval[,duration]])**

Specifies how the processing for the PDSE1 monitor is to be started or modified for the restartable PDSE address space, SMSPDSE1.

**DISPLAY**

Turns on monitor processing and causes any possible error messages to be displayed to the console.

**DUMPNEXT**

Turns on monitor processing and causes a dump to be taken. The system issues message IGW031I for the next error detected. Only one dump is taken.

**NO**

Turns off monitor processing.

**YES**

Turns on monitor processing.

If the PDSE1 parameter is omitted, and the restartable PDSE address space is created, the monitor is started with default values for 60 seconds for interval and 15 seconds for duration.

**interval**

Specifies the number of seconds between successive scans of the monitor. If the PDSE1\_MONITOR keyword is specified, but interval is omitted, the interval remains unchanged, except at IPL time when the interval is set to 60.

**duration**

Specifies the number of seconds a possible error condition must exist before it is treated as an error. If the PDSE1\_MONITOR keyword is specified, but duration is omitted, the duration remains unchanged, except at IPL time when the duration is set to 15.

**Default:** YES

**PDSESHARING(NORMAL|EXTENDED)**

Specifies how PDSEs can be shared across systems in a sysplex. NORMAL allows users to share read access to PDSEs across systems in the sysplex. EXTENDED allows users to share read and write access to PDSEs across systems in the sysplex.

All systems that share PDSEs must use the same sharing protocol, either NORMAL or EXTENDED. The first system in the sysplex to IPL determines which sharing protocol is used. If EXTENDED has been established as the protocol and a system that is not able to run with EXTENDED PDSE sharing joins the sysplex, that system cannot use the PDSEs.

For more information about sharing PDSEs across a sysplex, see [z/OS MVS Setting Up a Sysplex](#).

**Default:** NORMAL

**PDSE\_SYSEVENT\_DONTSWAP(NO|YES)**

Specifies if the task that enters the SMSPDSE or SMSPDSE1 address spaces should be placed in run DONTSWAP to prevent the task from being swapped out while holding internal PDSE latches or locks. Specifying this parameter can delay the system from being swapped out but prevents PDSE processing from being delayed by a swapped address space. In addition, it causes the SYSEVENT ENQHOLD to be issued against a latch holder to ensure that the holder completes its processing and releases the latch.

For more information about sharing PDSEs across a sysplex, see [z/OS MVS Setting Up a Sysplex](#).

**Default:** NO

**PS\_EXT\_VERSION(1|2)**

This parameter indicates the format in which the system should create sequential extended format data sets. The default is PS\_EXT\_VERSION(1) to denote the version 1 format. That means that if the sequential extended format data set is not striped and has multiple volumes, FlashCopy® cannot process it.

DFSMSdss must use conventional I/O to copy this type of data set. When the option is PS\_EXT\_VERSION(2), any new sequential extended format data sets created is in version 2 format.

This allows FlashCopy to copy the data set much more efficiently if it has multiple volumes and is not striped. The system saves this version number in the field DFASEFVR in the DFA, which is mapped by the IHADFA macro as described in *z/OS DFSMSdfp Advanced Services*.

Each data set's catalog entry indicates whether the data set is version 1 or version 2. You can display the data set version using IDCAMS LISTCAT and DCOLLECT.

Encrypted data sets are created in version 2 format for any user specification.

**Default:** 1

### **QTIMEOUT({nnn|300})**

Specifies the quiesce exit timeout value, in seconds. The quiesce timeout value specifies the amount of time the DFSMSStvs quiesce exits allow to elapse before concluding that a quiesce cannot be completed successfully. Only one quiesce timeout value can be specified. The first instance of DFSMSStvs that is brought up within the sysplex determines the value. Subsequent SFSMSStvs instances use the value established by the first system, regardless of what can be specified in their members of SYS1.PARMLIB. Specify a value between 60 and 3600.

If you specify the QTIMEOUT parameter, you must also specify the TVSNAME(nnn) parameter. This parameter applies across all systems.

**Default:** 300

### **REVERIFY(YES|NO)**

Specifies whether SMS is to check a user's authority to allocate a new data set and use storage or management class at job interpretation time or at both job interpretation time and execution time. If you want SMS to check the authority at both times, code YES; NO directs SMS to check only at job interpretation time.

**Default:** NO

### **RLSINIT({NO|YES})**

Specifies whether you want the SMSVSAM address space started as part of system initialization or through the V SMS,SMSVSAM,ACTIVE command.

#### **NO**

Does not start SMSVSAM during system initialization or through the command. If you specify NO, you must take the following steps to start SMSVSAM later:

1. Change RLSINIT to YES.
2. Issue the SET SMS=xx command to activate the parmlib member you updated with RLSINIT(YES).
3. IPL or issue the V SMS,SMSVSAM,ACTIVE command to start the SMSVSAM address space.

#### **YES**

Starts the SMSVSAM address space as part of system initialization or through the command. This value applies only to the system accessed by the parmlib member and is acted upon when SMSVSAM is next started.

**Default:** NO

### **RLS\_MAX\_POOL\_SIZE({nnnn|100})**

Specifies the maximum size in megabytes of the SMSVSAM local buffer pool. SMSVSAM attempts to not exceed the buffer pool size you specify, although more storage might be temporarily used. Because SMSVSAM manages buffer pool space dynamically, this value does not set a static size for the buffer pool.

Use SMF 42, subtype 19 records to help you determine the maximum size of the SMSVSAM local buffer pool.

You can specify a two to four-digit numeric value, with 10 as the minimum value. If you specify a value less than 10, the field is set to 10. If you specify a value greater than 1500, SMSVSAM assumes there is no maximum limit. IBM suggests that you limit the size of the local buffer pool.



**Default:** 100

### **RLS\_MAXCFFEATURELEVEL({Z|A})**

Specify the method that VSAM RLS should use to determine the size of the data that is placed in the CF cache structure. You can use the RLS\_MAXCFFEATURELEVEL keyword to limit the connect level when the sysplex has a mixed level of releases and maintenance. If you do not specify a value, or if you specify Z, then only VSAM RLS data that has a Control Interval (CI) value of 4K or less is placed in the CF cache structure. If you specify A, caching proceeds using the RLSCFCACHE keyword characteristics that are specified in the SMS data class that is defined for the VSAM sphere.

RLS\_MAXCFFEATURELEVEL is a sysplex-wide value. The first system activated in the sysplex sets the value; all other systems use the value set by the first system.

**Default:** Z

#### **Notes:**

1. If A is specified for the RLS\_MAXCFFEATURELEVEL parameter, systems lower than V1R3 cannot connect to the CF cache structure.
2. If a lower-level system is the first system activated in the sysplex, RLS\_MaxCfFeatureLevel defaults to Z, and all systems can connect to the CF cache structure.

### **RLS\_RECOV\_LOGGING(YES|NO)**

Specifies whether the SMSVSAM address space will start with VSAM Record Level Sharing (RLS) Replication Logging Support (write the replication log records to the log stream) the next time SMSVSAM address space is initialized on this system.

#### **YES**

Start the SMSVSAM address space with VSAM RLS Replication Logging Support.

- VSAM RLS will write the replication log records to the log stream for the updates to eligible data sets defined with the IDCAMS LOGREPLICATE parameter.

When VSAM RLS is initialized with the Replication Logging Support, the following commands are also available:

```
DISPLAY SMS,LOG(log stream id|all)
DISPLAY SMS,DSNAME(data set name)
VARY SMS,LOG(logstreamid),QUIESCE|Q|DISABLE|ENABLE|E
```

For more information about these commands refer to [z/OS System Commands \*z/OS MVS System Commands\*](#).

#### **NO**

Start the SMSVSAM address space without VSAM RLS Replication Logging Support.

- VSAM RLS batch opens for non recoverable data sets defined with the IDCAMS LOGREPLICATE parameter will fail.

**Default:** NO.

### **RLSTMOUT({nnn|0})**

Specifies the maximum time, in seconds, that a VSAM RLS or DFSMSrvs request is to wait for a required lock before the request is assumed to be in deadlock and ended with VSAM return code 8 and reason code 22(X'16'). Specify a value in seconds between 0 to 9999. A value of 0 means that the VSAM RLS or DFSMSrvs request has no timeout value; the request waits for as long as necessary to obtain the required lock.

VSAM RLS detects deadlocks within VSAM and DFSMSrvs. It cannot detect deadlocks across other resource managers, and uses the timeout value to determine when such deadlocks might have occurred. You can specify a global timeout value in the IGDSMSxx member of SYS1.PARMLIB, a step level timeout value on the JCL, or a timeout value on the RPL passed for each VSAM request.

For a particular VSAM RLS or DFSMSrvs request, the value used for timeout is in the following order:

- The value that is specified in the RPL, if any.



- The value that is specified in JCL at the step level, if any.
- The value that is specified in the IGDSMSxx member of SYS1.PARMLIB, if any.

RLSTMOUT is valid a parameter for either VSAM RLS or DFSMStvs. If you specify RLSTMOUT but do not specify the TVSNAME parameter, the value is used only by RLS. For DFSMStvs, the first instance of DFSMStvs brought up within the sysplex determines the value. Subsequent DFSMStvs instances use the value established by the first system, regardless of what might be specified in their members of SYS1.PARMLIB.

RLSTMOUT can be specified only once in a sysplex and applies across all systems in the sysplex.

**Default:** 0

#### **RLSABOVETHEBARMAXPOOLSIZE({(ALL,size)})**

#### **RLSABOVETHEBARMAXPOOLSIZE({(sysname1,size1[...;sysname32,size32])})**

Specifies the total size of the buffer management facility (BMF) buffer pool that resides above the 2-gigabyte bar for either of the following environments:

- All systems
- Each system referenced of the following parameter

Valid values are between 500 MB and 2,000,000 MB (2 Terabytes).

**Default:** 0

#### **RLSFIXEDPOOLSIZE({(ALL,size)})**

#### **RLSFIXEDPOOLSIZE({(sysname1,size1[...;sysname32,size32])})**

Specifies the amount of the total real storage in megabytes, both above and below the 2 gigabyte bar, that are permanently fixed (pinned) on either of the following environments:

- All systems
- Each system referenced in the parameter

**Default:** 0

#### **SAM\_USE\_HPF({YES|NO})**

Specifies whether you want SAM (BSAM and QSAM) and PAM to use HPF when it is available. This has an effect only if you enable HPF by specifying ZHPF=YES on the ZHPF statement in the IECIOSxx parmlib member.

#### **NO**

Specifies that SAM and PAM should not use HPF. If you specify SAM\_USE\_HPF(NO) in either IGDSMSxx or on the SET SMS command, the DFASAMHPF bit in the DFA control block is set off. SAM and PAM do not use HPF

#### **YES**

Specifies that you want SAM and PAM to use HPF when it is available and enabled. If you specify or default to SAM\_USE\_HPF(YES) in either IGDSMSxx or on the SET SMS command, SMS sets on a bit in the DFA, DFASAMHPF.

Because YES is the default, you see SAM\_USE\_HPF=YES when you display SMS options for the system, even if it is not attached to an HPF-capable device.

The following list has cases in which BAM does not use HPF even though IOS allows it:

- In a partitioned concatenation one or more of the data sets is a PDS that resides on a device that does not support HPF.
- An I/O error occurred with HPF. BAM switches to CCW channel programs and does not resume HPF for the currently open DCB.
- Certain temporary conditions cause BAM to switch to CCWs temporarily but resume HPF for later channel programs.

**Default:** YES

**SELECT({event[,event][,...][ALL]})**

Specifies one or more events or services that SMS is to trace (if SMS tracing is active). See the description of the DESELECT parameter for a list of valid events.

**Default:** ALL

**Note:** DESELECT(ALL) must precede the SELECT parameter if only specific trace options are to be traced.

**SIZE(nnnnnnK|nnnM|nnnnnn|128K)**

Specifies the size of the SMS trace table in bytes. If you specify a value of 0, no tracing is performed.

*nnnnnnK* specifies the size in kilobytes; the value can range from 0 K to 255000 K (255,000 kilobytes), and it is rounded up to the nearest 4 K unit.

*nnnM* specifies the size in megabytes; the value can range from 0M to 255M (255 megabytes).

If you specify *nnnnnn* without a unit, the system assumes a unit of kilobytes.

**Default:** 128 K

**SMF\_TIME(YES|NO)**

SMF\_TIME specifies whether DFSMS is to use SMF timing; that is, whether SMF type 42 records are to be created at the expiration of the SMF interval period, synchronized with SMF and RMF data intervals.

The following SMF record 42 subtypes are affected when you specify SMF\_TIME(YES): 1, 2, 15, 16, 17, 18, 19. If you record these subtypes, you can use SMF\_TIME(YES) to synchronize SMF type 42 data with SMF and RMF data intervals.

Specifying SMF\_TIME(YES) overrides the following IGDSMSxx parameters: CACHETIME, CF\_TIME.

**Default:** YES

**STEPNAME(STEPNAME|\*)**

Limits the number of volume selection analysis messages activated by VOLSEGMSG(ON) for a certain stepname or for all stepnames. Specify asterisk (\*) to indicate *all* stepnames.

**Default:** \*.

**SUPPRESS\_DRMSGs (YES|NO)**

Specifies whether SMS suppresses DELETE/RENAME messages issued to the hardcopy log and job log.

**NO**

Does not suppress DELETE/RENAME messages to the hardcopy log and job log.

**YES**

Suppresses DELETE/RENAME messages to the hardcopy log and job log.

**Default:** NO

**SUPPRESS\_SMSMSG (YES|NO,IGD17002I,IGD17054I,IGD17227I,IGD17395I)**

Specifies whether one or all of the SMS messages IGD17002I, IGD17054I, IGD17227I, and IGD17395I are to be issued or suppressed. The user must specify one or more of the applicable messages in this parameter.

**NO,IGD17002I,IGD17054I,IGD17227I,IGD17395I**

Does not suppress the specified messages (IGD17002I, IGD17054I, IGD17227I, IGD17395I) if they are issued.

**Note:** IGD17002I is used to specify whether SMS suppresses or issues message IGD17002I on the console.

**YES**

The specified messages are suppressed.

**Default:** NO,IGD17002I,IGD17054I,IGD17227I,IGD17395I

**SYSNAME(sysname1[,sysname2[...[,sysname32]])**

Specifies the name of the system or systems on which DFSMStvs instances are to run. You can specify up to 32 system names, which must be in the same order as the DFSMStvs instance names. SMS examines the specified system names and compares them to the system names in the CVT. When it finds a match, SMS stores the value of the TVSNAMES parameter in the matching position as the DFSMStvs instance name for the system.

Use the combination of SYSNAME and TVSNAMES when the parmlib member is shared between systems. If no SYSNAME parameter is specified, the TVSNAMES parameter applies to the system on which the parmlib member is read.

If you specify the SYSNAME parameter, you must also specify the TVSNAMES(*nnn*) parameter. If you specify SYSNAME, but the system name is not specified, DFSMStvs is not started on the system.

**Default:** None.

**SYSTEMS({8|32})**

This keyword specifies whether the system is running in compatibility mode (8-name limit) or 32-name mode.

SYSTEMS(8) specifies that a maximum of 8 system names, system group names, or both, can be specified for the SMS configuration. This value indicates that the system is running in compatibility mode and can share configurations (SCDSs or ACDSs) and COMMDS with systems that are running previous releases of z/OS. Essentially, the system continues to operate as before DFSMS/MVS Version 1.3, whose date of general availability was in 1995.

SYSTEMS(32) specifies that a maximum of 32 system names, system group names, or both, can be specified for the SMS configuration. This value indicates that the system is not running in compatibility mode, and therefore the ACDS, SCDS, and COMMDS cannot be shared with any systems that are running in compatibility mode.

**Notes:**

1. When a system in an SMS complex begins running at a level with DFSMS/MVS Version 1.3 or later, the constructs in the SMS configuration are automatically expanded to prepare for the additional system information. This change occurs for all SMS configurations regardless of whether SMS 32-name support is used.
2. When you are using RESERVE or RELEASE on the volumes that contain shared SMS control data sets with other systems, the potential for deadlock increases dramatically. Even if the ACDS and COMMDS are allocated as the only data sets on separate volumes, deadlocks can occur. To avoid contention problems, you can use global resource serialization (GRS) to convert hardware reserves on the ACDS and COMMDS to SYSTEMS scope enqueues. Also, you should place resource name IGDSCSXS in the RESERVE conversion resource name list (RNL) as a generic entry. This can minimize contention delays and prevent deadlocks, which are sometimes associated with the VARY SMS command.
3. When you convert an SMS complex from compatibility mode to 32-name mode, the conversion is permanent. Be sure to copy your current SMS control data sets to data sets with different names before you begin the conversion.
4. You can do the conversion through the operator console or an ISMF panel. When you begin to convert, take the following steps:
  - a. Set a date and time for the conversion when the allocation activity on the systems is low.
  - b. Create an SCDS, ACDS, and COMMDS by copying existing SMS control data sets. Be sure to use the new formulas for data set space requirements. To provide for emergency fallback, do not convert your existing primary SCDS, ACDS, and COMMDS at the outset.
  - c. On each system in the SMS complex, create an IGDSMSxx member in SYS1.PARMLIB that points to the new ACDS and COMMDS and specifies SYSTEMS(32).
  - d. Immediately before conversion, issue SETSMS INTERVAL(999) on all systems that are involved in the conversion. This prevents a system from rereading the COMMDS and attempting to

activate the new configuration before you have an opportunity to change the mode of that system.

- e. On each system, issue SET SMS=xx to restart SMS or re-IPL the system using the new IGDSMSxx member of SYS1.PARMLIB. This restarts SMS in 32-name mode using the new ACDS and COMMDs.

Restarting SMS resets the INTERVAL parameter for the system. If INTERVAL is specified in the IGDSMSxx member of SYS1.PARMLIB, that value is used. Otherwise, the default value is 15.

**Default:** 8

#### **TRACE(ON|OFF)**

Specifies whether SMS tracing is to be on or off.

**Note:** Running SMS with the following options: TRACE=ON TYPE=ALL and SELECT(ALL) MAY result in an increase in CPU consumption because trace records are being written for ALL SMS activity. This includes not only error conditions but ALL NORMAL PROCESSING as well.

**Default:** ON

#### **TRACEEXIT(user-trace-exit)**

Defines an installation exit for SMS tracing. The name of the exit must be 1 to 8 alphanumeric characters and it must be a valid load module. There is no default. For more information about the SMS tracing exit, see [z/OS DFSMS Installation Exits](#).

#### **TVSAMCOM({minval|1},{maxval|0})**

Enables DFSMStvs automatic commit and specifies the minimum and the maximum for a range of number of update requests that are used by DFSMStvs to determine when and if to call RRS services to issue a commit point on behalf of the batch application. DFSMStvs adjusts the commit frequency to a number between these two values based on record lock analysis for the current unit of recovery.

Specify both values as a number of updates in the range of 0 to 99999. A value of 0 for both numbers means that no automatic commits are performed by DFSMStvs for the units of recovery using this value. Only one TVSAMCOM value can be specified. Each system has its own TVSAMCOM values as long as it is using a different **IGDSMSxx** PARMLIB member. If you specify the TVSAMCOM parameter, you must also specify the TVSNAME(*nnn*) parameter.

Defaults are:

- *minval* = 1, *maxval* = 0 if the TVSAMCOM keyword is specified
- *minval* = 0, *maxval* = 0 if the TVSAMCOM keyword is not specified.

For a particular DFSMStvs request, the value used for automatic commits is in the following order:

1. The value that is specified in JCL at the step level, if any.
2. The value that is specified in the IGDSMSxx member of SYS1.PARMLIB, if any.

#### **TVSNAME(nnn1[,nnn2[...nnn32]])**

Specifies the identifier or identifiers that uniquely identify DFSMStvs instances that run in the sysplex. You can specify up to 32 identifiers, each of which must be a numeric value from 0 to 255. Each identifier must be unique within the sysplex. DFSMStvs uses this identifier as the last byte of its instance name (although it displays as three bytes). If the TVSNAME parameter is specified without the SYSNAME parameter, only a single value can be specified, and the name applies to the system on which the parmlib member is read. The numeric digits are appended to the characters IGWTV to form the DFSMStvs instance name.

You can use the TVSNAME parameter without the SYSNAME parameter when the parmlib member is not shared between systems. If no TVSNAME parameter is found, DFSMStvs processing is not available on the system.

**Default:** None.

**TV\_START\_TYPE({WARM|COLD},{WARM|COLD}[...,{WARM|COLD}])**

Specifies the type of start that each instance of DFSMStvs is to perform. Up to 32 TV\_START\_TYPE values can be specified. TV\_START\_TYPE values must be specified in the same order as DFSMStvs instance names. If WARM is specified, DFSMStvs reads its undo log and processes the information found in accordance with the information that RRS has about any outstanding units of recovery. If COLD is specified, DFSMStvs deletes any information that is remaining in the undo log and starts as if the log were empty. Use COLD only when the DFSMStvs undo log has been damaged.

**Recommendation:** Do not cold start DFSMStvs unless the DFSMStvs system logs were damaged. After a cold start, data sets for which recovery was not completed might be left in a damaged state and must be recovered manually. If the data sets are forward recoverable, their forward recovery logs might also be damaged. Manually recover the data sets (without using forward recovery), take backups of them and any other data sets using the forward recovery log, then delete and redefine the forward recovery log.

You can allow some values to default and others to be specified. For example, specifying the keyword in the following way would cause the DFSMStvs instance in the second position to warm start, while the first and third DFSMStvs instances would cold start.

```
TV_START_TYPE(COLD, , COLD)
```

If both TVSNAM and SYSNAM parameters are also specified, TV\_START\_TYPE applies to the system specified on the SYSNAM parameter preceding or following it. If TV\_START\_TYPE is found with only the TVSNAM parameter, it applies to only the system on which the parmlib member is being read.

**Default:** WARM

**TYPE(ERROR ALL[(TRACE|T|VOLSELMSG|V)[,ALL|ERROR(TRACE|T|VOLSELMSG|V)])**

Specifies how you want to trace events (TRACE) and issue volume selection analysis messages (VOLSELMSG).

**ALL**

Specify ALL to trace all events and issue volume selection analysis messages (VOLSELMSG(ON)) for all allocations.

**ERROR**

Specify ERROR to trace error events and issue volume selection analysis messages (VOLSELMSG(ON)) for allocations that have failed.

**[(TRACE|T|VOLSELMSG|V)[,ALL|ERROR(TRACE|T|VOLSELMSG|V)])**

These are optional subparameters. TRACE|T or VOLSELMSG|V associated with the first subparameter specifies whether the required value, ALL or ERROR, specified in the first subparameter applies to the TRACE or VOLSELMSG facility. The second subparameter is optional and can be used to specify another value and facility after the first subparameter is specified.

When none of these optional subparameters are specified, the value that is specified in the first subparameter applies to both TRACE and VOLSELMSG. For example, if you want to set a TYPE value of ERROR for the SMS TRACE facility, and a TYPE value of ALL for the VOLSELMSG facility, you could code: TYPE(ERROR(TRACE) , ALL(VOLSELMSG) ).

If you specify VOLSELMSG(*nnnnn*), where *nnnnn* has a value greater than 0, with TYPE(ALL), you must also specify one of the following parameters to limit the number of detailed analysis messages:

- JOBNAME
- ASID
- STEPNAME
- DSNAM

**Default:** ERROR

**USEEAV({YES|NO})**

Specifies, at the system level, whether SMS can select an Extended Address Volume during volume selection processing. This check applies to new allocations and when data sets are extended to a new volume.

**NO**

SMS does not select any Extended Address Volumes during volume selection. Data sets might still exist on Extended Address Volumes in either the track-managed or cylinder-managed space of the volume. NO is the default.

**YES**

Extended Address Volumes can be used to allocate new data sets or to extend existing data sets to new volumes.

When SMS is not active in the system, USEEAV is not available and the installation must use alternate means to control the usage of Extended Address Volumes.

**Default:** NO

**USE\_MOST\_FREE\_SPACE({YES|NO})**

Specifies whether to allow SMS randomization technique to be used for volume selection. This allows SMS to select the volumes with the most free space, when more than one volume has been assigned the same weight. This parameter only applies to volumes that are on the secondary or tertiary list. Volumes on the primary list are passed to SRM. SRM will then determine which volume will be selected based on channel load balancing.

**NO**

SMS randomly selects a volume between volumes with the same weight, and does not consider volumes with the most free space.

**YES**

SMS randomly selects a volume with the same free space and the same weight.

**Default:** NO

**USE\_RESOWNER({YES|NO})**

Indicates whether construct authorization checking is done using the RESOWNER value, which is based on the high-level qualifier of the data set name, or using the allocating user ID for the data set. If you specify NO, the RESOWNER value is not extracted and the allocating user ID is used.

**Default:** YES

**USER\_ACSVAR([value1],[value2],[value3]))**

Specifies three positional values that SMS uses to initialize the ACS read-only variable &USER\_ACSVAR. The values can be accessed in ACS routines with the variables &USER\_ACSVAR(1), &USER\_ACSVAR(2), and &USER\_ACSVAR(3) respectively.

The values can be 1 - 8 alphanumeric or national characters (\$, #, @) or period (.) or dash (-).

Any positional value that is not specified is blank. For example, USER\_ACSVAR() or USER\_ACSVAR(,,) set all 3 positional values to blank. Specify a single dash (-) for any positional value to keep the current value as is. For example, specify USER\_ACSVAR(-,-,ABC) to keep the first and second values as they are but change the third value to be ABC.

**VOLSELMSG({ON|OFF,0|nnnnn|ALL})**

Controls messages about volume selection analysis that are issued when you create or extend an SMS-managed data set to a new volume. These analysis messages are written to the hardcopy log and the job log.

**ON|OFF**

Controls whether SMS volume selection analysis messages are to be issued.

**Default:** OFF

**0|nnnnn|ALL**

Controls whether SMS volume selection analysis messages are to be issued.

**Default:** 0

**0**

Indicates that only summarized analysis messages are to be issued.

**nnnnn**

The number of volumes to be included in the message with a range of 0 to 65535.

**ALL**

Indicates that all volumes used for volume selection is included in detailed analysis messages.

If you specify VOLSELMSG(*nnnnn*), where *nnnnn* has a value greater than 0, with TYPE(ALL), you must also specify one of the following parameters to limit the number of detailed analysis messages:

- ASID
- DSNAME
- JOBNAME
- STEPNAME

When all volumes are to be included, volumes are listed by storage group. If only a subset of volumes is to be included, volumes are listed in volume selection preference order without an association to storage group. The system can issue an excessive number of analysis messages to the spool for the following conditions:

- The job or address space creates or extends many SMS-managed data sets
- Many volumes are to be included in the analysis messages.

**Default:** OFF,0

**VSAM\_ZHYPERLINK(YES|NO)**

Specifies whether VSAM data sets are eligible to exploit zHyperLink on this system.

**NO**

Disables zHyperLink for all VSAM data sets on this system.

**Default:** NO

**YES**

Makes the VSAM data sets on this system eligible for zHyperLink.

**Note:** The 'YES' option makes the VSAM data sets on this system eligible for zHyperLink. There are other conditions that must be satisfied before an I/O is done with zHyperLink for the data sets. See [Working with data sets](#) for the complete list of conditions.

## Examples of the contents of IGDSMSxx

---

Assume that you want to define SMS with the following properties:

- An ACDS named SYS1.ACDS9.
- A COMMDS named SYS1.COMMDS.
- An interval of 15 seconds before synchronizing with any other SMS subsystems in the complex.
- SMF type 42 records are to be synchronized with the SMF and RMF intervals.

Figure 18 on page 561 shows the statement that you would code in IGDSMSxx to request that SMS have these properties:

```
SMS ACDS(SYS1.ACDS9) COMMDS(SYS1.COMMDS) INTERVAL(15)
SMF_TIME(YES)
```

Figure 18. Example: Contents of IGDSMSxx, example 1

---

The next example defines a parmlib member that is specific to one system and sets up the following properties:

- An ACDS of SYS1.ACDS9.
- A communications data set of SYS1.COMMDS.

- An interval of 10 seconds before synchronizing with any other SMS subsystems in the complex.
- A DFSMStvs name in the form of IGWTVnnn, for example, IGWTV001.
- A quiesce timeout value of 240.
- An activity keypoint (AKP) value of 2000.
- No log of logs.
- Requests DFSMStvs to perform a warm start.

Figure 19 on page 562 shows the statement that you would code in IGDSMSxx to request that SMS have these properties.

---

```
SMS ACDS(SYS1.ACDS9) COMMDS(SYS1.COMMDS) INTERVAL(10)
TVSNAME(1) QTIMEOUT(240) AKP(2000) TV_START_TYPE(WARM)
```

---

Figure 19. Example: Contents of IGDSMSxx, example 2

---

The next example defines a PARMLIB member that applies to multiple systems and sets up the following properties:

- An ACDS of SYS1.ACDS10.
- A communications data set of SYS1.COMMDS10.
- An interval of 20 seconds before synchronizing with any other SMS subsystems in the complex.
- Three instances of DFSMStvs name IGWTV001, IGWTV002, and IGWTV003 to be established on the systems named SYSTEM1, SYSTEM2, and SYSTEM3, respectively.
- The default quiesce timeout value (300).
- The default activity key point value (1000).
- A log of logs, using a log stream name IGWLOG.LOGLOGS.
- Requests that DFSMStvs perform a cold start on all systems.

Figure 20 on page 562 shows the statement that you would code in IGDSMSxx to request that SMS have these properties.

---

```
SMS ACDS(SYS1.ACDS10) COMMDS(SYS1.COMMDS10) INTERVAL(20)
LOG_OF_LOGS(IGWLOG.LOGLOGS)
SYSNAME (SYSTEM1,SYSTEM2,SYSTEM3)
TVSNAME( 1, 2, 3)
TV_START_TYPE(COLD,COLD,COLD)
```

---

Figure 20. Example: Contents of IGDSMSxx, example 3

---

### Restrictions:

1. The DFSMStvs instance names must be unique.
2. After a cold start, any data sets for which recovery was not completed, are most likely left in a damaged state and must be recovered manually. If the data sets are forward recoverable, their forward recovery logs might also be damaged. IBM suggests that you manually recover the data sets (without using forward recovery), take back ups of them and any other data sets using the forward recovery log, then delete and redefine the forward recovery log.

The next example defines a parmlib member that applies to multiple systems and sets up the following properties:

- An ACDS of SYS1.ACDS10.
- A communications data set of SYS1.COMMDS10.
- An interval of 20 seconds before synchronizing with any other SMS subsystems in the complex.
- RLSABOVETHEBARMAXPOOLSIZE value of 1024.



- RLSFIXEDPOOLSIZE value of 1050.

Figure 21 on page 563 shows the statement that you would code in IGDSMSxx to request that SMS have these properties.

```
SMS ACDS(SYS1.ACDS10) COMMDS(SYS1.COMMDS10) INTERVAL(20)
  RLSABOVETHEBARMAXPOOLSIZE(ALL,1024)
  RLSFIXEDPOOLSIZE(ALL,1050)
```

Figure 21. Example: Contents of IGDSMSxx, example 4

## Examples of specifying DFSMStvs parameters

Table 31 on page 563 shows examples of ways that TVS parameters might be specified.

| Table 31. Example: Specifying DFSMStvs parameters  |   |
|--|---|
| Example  | Valid or not valid  |
| TVSNAME(1)   | Valid. Applies only to one system. All other parameters are defaulted.  |
| TVSNAME(1) AKP(500)  | Valid. Applies only to one system. All parameters other than AKP are defaulted.   |
| TVSNAME(1) SYSNAME(SYS1) RLSTMOUT(15)  | Valid. Applies only to one system. All parameters except RLSTMOUT are defaulted.  |
| TVSNAME(1,2) SYSNAME(SYS1,SYS2) QTIMEOUT(500)  | Valid. Applies to two systems. All parameters except QTIMEOUT are defaulted.  |
| TVSNAME( 1, 2, 3) SYSNAME(SYS1,SYS2,SYS3)<br>TV_START_TYPE(WARM,COLD,WARM)<br>LOG_OF_LOGS(LOG.OF.LOGS) | Valid. Each parameter specifies the correct number of values.   |
| TVSNAME( 1, 2, 3) SYSNAME(SYS1,SYS2,SYS3)<br>TV_START_TYPE(COLD,,WARM) AKP(,700,900)                   | Valid. The second TV_START_TYPE value and the first AKP value are defaulted.  |
| TVSNAME( 1, 2, 3) SYSNAME(SYS1,SYS2,SYS3)<br>TV_START_TYPE(WARM,COLD,)                                 | Valid. The third TV_START_TYPE value is defaulted.  |
| QTIMEOUT(500) AKP(500,200)   | Not valid. The TVSNAME parameter is required when DFSMStvs parameters are specified.                                      |
| TVSNAME(1,2) AKP(500,200) QTIMEOUT(500)  | Not valid. The SYSNAME parameter is required when more than one TVSNAME value is specified.                               |
| TVSNAME( 1, 2, 3) SYSNAME(SYS1,SYS2,SYS3)<br>TV_START_TYPE(WARM,COLD)                                  | Not valid. TVSNAME and SYSNAME specify three values while TV_START_TYPE specifies only two.                               |
| TVSNAME(1) AKP(500,200)  | Not valid. The TVSNAME parameter specifies only one value while AKP specifies two.  |
| TVSNAME( 1, 2, 3) SYSNAME(SYS1,SYS2,SYS3)<br>TV_START_TYPE(WARM,COLD,WARME)                            | Not valid. The right number of values is specified on each parameter, but WARME is not a valid value for TV_START_TYPE.   |
| TVSNAME( 1, 2) SYSNAME(SYS1,SYS2) TVSAMCOM(10, 100)  | Valid. TVSAMCOM applies only to systems using this IGDSMSxx parmlib member. All parameters except TVSAMCOM are defaulted. |



## Chapter 63. IGGCATxx (DFSMS catalog configuration)

IGGCATxx allows you to define catalog system parameters and make permanent changes between IPLs. You can specify other catalog parameters in the LOADxx member of SYS1.PARMLIB and the SYSCATxx member of SYS1.NUCLEUS. The IGGCATxx parameters are processed both at IPL and when CAS is restarted. See [The intersection of SYSCATxx, LOADxx, IGGCATxx, and MODIFY CATALOG command in z/OS DFSMS Managing Catalogs](#).

Use the command DISPLAY IPLINFO,CATALOG to display the catalog system parameter members currently in effect at a given time.

### Parameter in IEASYSxx (or specified by the operator)

You must specify the current IGGCATxx member or members in the CATALOG=xx parameter in IEASYSxx parameter. The xx suffix can be any 2 alphanumeric characters or national characters (@,#,\$). The default is 00 (zeros).

- If the system finds no CATALOG parameter, it uses default IGGCAT00. If the system finds no IGGCAT00 default member, default values will be used.
- If you specify multiple IGGCATxx members in the CATALOG=xx parameter, the system processes them in the order specified. When the same parameter appears in multiple members, the value specified in the last member processed, becomes the value in effect.
- If the system does not find a IGGCATxx member matching the CATALOG=xx specification, the system issues a message for each missing IGGCATxx member.

### Syntax rules for IGGCATxx

Follow the rules in [“General syntax rules for the creation of members” on page 7](#). The following rules also apply to the creation of IGGCATxx parmlib members:

- Input ends with the end of file (EOF). No explicit continuation syntax is required.
- Blanks in any combination constitute a delimiter.
- Delimiters are not required between parameters with values; the right parenthesis after the specified parameter value is sufficient.
- Comments can appear in columns 1-71 and must begin with "/" and end with "/". Comments are allowed between parameters.
- If the parser finds an error in any parameter, the system issues message IEC386W to display the text in error up to column 71. The parser will continue to parse any parameters on the next line. If the same parameter that was found to be in error on any earlier line is found and valid, the system uses that value for the parameter.
- If the parser finds an error in any parameter on a line, parsing for that line stops and no parameters from that line are used. The parser continues to parse any parameters on the next line.
- All parameters should start and finish on the same line. For example the following is not a valid syntax:

```
VVDSSPACE( 10, 14
)
```

- The parameters do not have to start in column one, but they must fit entirely within columns 1 and 71. The parser ignores any text beyond column 71.
- You can specify any of the parameters multiple times, but the parser uses only occurrences of any parameters are allowed. The last valid value is used for the parameter. For example, the following is allowed; in this case, the system uses VVDSSPACE(14,14) as the final value for VVDSSPACE:

```
VVDSSPACE(10,10)
VVDSSPACE(14,14)
```

- You can use blanks between or before values in a parameter. For example:
  - A specification of VVDSSPACE( 10, 14) is valid, and the system interprets it as VVDSSPACE(10,14).
  - A specification of NOTIFYEXTENT( 55) is valid, and the system interprets it as NOTIFYEXTENT(55).
- Although you can have blanks between or before values in a parameter, you cannot have blanks between the digits in a single parameter value. For example:
  - If you intend a value of VVDSSPACE(10,14) but specify VVDSSPACE(1 0, 14) the parameter is not valid.
  - If you intend a value of NOTIFYEXTENT(66), but specify NOTIFYEXTENT(6 6), this parameter is not valid.
- If you specify one or more IGGCATxx suffixes, but the system cannot find all of the matching members, it issues a message for each member that is not found and processing continues with the members that the system did find. If the system does not find any IGGCATxx members, including the default IGGCAT00 member, it uses the default parameter values.
- When the same parameter appears in multiple IGGCATxx members, the value that is specified in the last member processed becomes the value in effect. The last valid specification in the last member is used for the particular parameter. If a particular parameter is not specified in any of the parmlib members, a default value will be used for the parameter
- If all instances of a specific parameter are invalid or the parameter is not specified at all in any of the IGGCATxx parmlib members during an IPL, then the default value is substituted for the parameter. During a restart of the Catalog address space, the value that existed before the restart is retained for the parameter.
- For readability, enter only one parameter per line.

## Syntax format of IGGCATxx

```
resource(minutes,action)
ALIASLEVEL(n)
AUTOADD(ON|OFF)
CATMAX(nnn)
DELFORCEWNG(YES|NO)
DELRECOVWNG(YES|NO)
DSNCHECK(YES|NO)
DUMP(ON|OFF)
DUMPON(rc,rsn,mod)
DUMPON(rc,rsn,mod,cnt)
EXTENDEDALIAS(YES|NO)
GDGEXTENDED(YES|NO)
GDGFIFOENABLE(YES|NO)
GDGLIMITMAX(nnn)
GDGPURGE(YES|NO)
GDGSCRATCH(YES|NO)
NOTIFYEXTENT(percent)
SMF16BYTETIMESTAMP(YES|NO)
SYMREC(YES|NO)
SYS%(ON|OFF)
TAPEHLQ(name)
TASKMAX(nn)
TASKMIN(nnn)
TASKTABLESIZE(nnn)
UPDTFAIL(YES|NO)
VVDSSPACE(primary,secondary)
VVRCHECK(YES|NO)
```

## Statements and parameters for IGGCATxx

### **resource(minutes,action)**

Specifies whether resource contention monitoring for a resource is active or inactive for catalog requests and, if active, how long the system should allow a catalog request to wait before notifying the operator and (optionally) redriving the request.

*resource* specifies the name of a resource and can be any of:

- ALLOCLCK, which is an internal CAS lock that serializes access to CAS allocation task responsible for most catalog allocation events.
- SYSIGGV2, which is used to serialize access to associated catalog records.
- SYSZTIOT, which is used to control access to task input/output table resources.
- SYSZVVDS, which is used to serialize access to associated VVDS records. The SYSZVVDS reserve, along with the SYSIGGV2 reserve, provide a mechanism to facilitate cross system sharing of catalogs.

*minutes* is the wait time in minutes. Valid values range from 0 minutes (minimum) to 65535 minutes (maximum). Specifying 0 (zero) for *minutes* makes resource contention monitoring inactive for that resource. Any value from 1 through 4 is reset to 5 minutes. Any value greater than 9999 is reset to 9999 minutes.

*action* is the action to be taken when the specified wait time is exceeded. *action* can be either N (for notify only) or R (for redrive and notify). When redrive is active, the first time a service task with an active resource passes the contention threshold, the service task is abended, and the request is resubmitted to catalog for processing.

The default for all resources is active with threshold at 10 minutes and an action of notify only. These values determine the default for contention resources at IPL and post CAS RESTART. When no parmlib values exist at IPL, the resource is set to active with threshold of 10 minutes and action of notify only. On CAS RESTART, in the absence of a parmlib value, the resource retains whatever values it had before restart.

### **ALIASLEVEL(n)**

Specifies the MLA search level. ALIASLEVEL has a default value of 1, with a minimum of 1 and a maximum of 4.

### **AUTOADD(ON|OFF)**

Specifies whether the autoadd function is enabled when the first connection is made to the coupling facility by the catalog address space.

**Default:** OFF

### **CATMAX(nnnn)**

Specifies the maximum number of catalogs that can be opened concurrently in CAS. When the limit is exceeded, the least recently accessed catalog is closed, freeing the CAS storage it had occupied. They remain allocated, but in restart status with no CAS storage. If the new limit is less than the previous limit, all currently open catalogs are closed.

The minimum value is 1 and the maximum value is 9999. The number that is specified for *nnnn* is in decimal.

While the maximum value of 9999 can be specified, it is highly recommended that the value does not exceed the number of open data sets for an address space as determined by the size of the TIOT specified in [Chapter 4, "ALLOCxx \(allocation system defaults\)," on page 67](#) for a description. For example, if a 32K TIOT is specified, then it is recommended that CATMAX be set to no higher than 1635. Similarly, for a 64K TIOT, the recommended maximum would be 3273.

### **DELFORCEWNG(YES|NO)**

Specifies whether you want the warning message IDC1997I or IDC1998I when attempting to use the DELETE VVDS RECOVERY or DELETE USERCATALOG FORCE command.

**Default:** YES

**DELRECOVWNG(YES|NO)**

Specifies whether you want the system to issue message IDC1999I if a DELETE UCAT RECOVERY command is attempted.

**Default:** NO

**DSNCHECK(YES|NO)**

Specifies if you want to enable syntax checking on names being added to a catalog.

**Default:** YES

**DUMP(ON|OFF)**

Specifies whether dynamic dumps are available. The default is OFF.

**DUMPON(*rc,rsn,mod[,cnt]*)**

Specifies the return (*rc*) and reason codes (*rsn*) to take a dump on if a match is found in a valid catalog module (*mod*). The optional *cnt* value specifies to capture a dump on the *n*th occurrence of the condition (one to three characters from 1 to 999). The default for *cnt* is 1.

**EXTENDEDALIAS(YES|NO)**

Specifies if you want to enable the ability to create extension records for user catalog aliases on the current system.

**Default:** NO

**GDGEXTENDED(YES|NO)**

Specifies whether to enable GDG extended support (YES) or not (NO). The default is NO.

Do not enable GDG extended support until you are confident that you remain on z/OS V2R2 or higher, and that all shared systems are z/OS V2R2 or higher.

**Default:** NO

**GDGFIFOENABLE(YES|NO)**

Specifies whether the GDG allocation order feature is enabled. The default is NO.

The GDG order feature allows the user to specify FIFO or LIFO (default) for the order in which the GDS list is returned for data set allocation when the GDG name is supplied on the DD statement.

**Default:** NO

**GDGLIMITMAX (*nnn*)**

Specifies the maximum number allowed for the LIMIT parameter on a DEFINE GDG.

The minimum value is 0 and the maximum value is 999. The number that is specified for *nnn* is in decimal.

A value of 0 means that there is no maximum value for LIMIT, and the value in the DEFINE GDG LIMIT is used.

**Note:** The GDGEXTENDED and GDGLIMITMAX parameters are not dependent on each other. Classic GDGs are limited to 255 generations, and a GDGLIMITMAX value greater than 255 does not apply to classic GDGs. If GDGEXTENDED is set to NO or is not specified, only classic GDGs can be defined, and a GDGLIMITMAX greater than 255 has no effect on limiting the number of generations.

**Default:** 0

**GDGPURGE(YES|NO)**

Specifies what the default for DEFINE GDG should be when neither the PURGE nor the NOPURGE parameter is specified.

**Default:** NO

**GDGSCRATCH(YES|NO)**

Specifies what the default for DEFINE GDG should be when neither the SCRATCH nor the NOSCRATCH parameter is specified.

**Default:** NO

**NOTIFYEXTENT(percent)**

The specified value is preserved across a CAS restart and is applied at IPL. You can also change this value with a CAS restart.

The default is NOTIFYEXTENT(80). A percentage value of zero indicates that the monitoring for extent usage is suppressed. If a catalog exceeds 90% utilization of the maximum extents, the system issues message IEC361I even if the threshold was set to zero.

**SMF16BYTETIMESTAMP(YES|NO)**

Specifies whether the SMF 16-byte timestamp for SMF record types 61, 65 and 65 should be appended to the record. YES indicates the timestamp is to be appended.

**Default:** NO

**SYMREC(YES|NO)**

Specifies if you want to enable SYMREC record creation.

**Default:** YES

**SYS%(ON|OFF)**

Specifies whether SYS% to SYS1% conversion is enabled.

**Default:** OFF

**TAPEHLQ(name)**

Specifies the high-level qualifier of a tape volume catalog. Valid characters are alphanumeric (A-Z and 0-9) and national (@, #, \$) characters.

**Default:** SYS1

**TASKMAX(tasks)**

Specifies the upper limit for the user service task used that is by the catalog address space (CAS), which is the maximum number of non-CAS concurrent service requests that can run at any given time.

- The value for TASKMAX cannot be higher than 90% of the CAS Service Task Table (TASKTABLESIZE) value that is specified in the SYS1.NUCLEUS(SYSCATxx) member or 90% of the TASKTABLESIZE value that is optionally specified in the IGGCATxx parmlib member. TASKMAX defaults to 90% of the TASKTABLESIZE value in effect, with a minimum of 24 and a maximum of 360.
- The value for TASKMAX cannot be lower than the lower limit of the service task used by the catalog address space that is specified in SYS1.NUCLEUS(SYSCATxx) or SYS1.PARMLIB(LOADxx) members. The default for the lower limit is 60.

You can display both the upper limit and the lower limit of the user service task by issuing the F CATALOG, REPORT catalog command. Use the MODIFY CATALOG command to decrease the TASKMAX value or restore it to 90% of the maximum number of concurrent catalog requests value that is specified in the SYSCATxx member or 90% of the value that is defined in IGGCATxx. The new value that is specified on MODIFY CATALOG is then in effect until the next IPL.

**Restriction:** If both TASKMAX and TASKTABLESIZE are included in IGGCATxx, TASKTABLESIZE must be specified first.

**TASKMIN(mintasks)**

Specifies the lower limit on the number of catalog service tasks that can be concurrently run. TASKMIN has a default value of 60, with a minimum of 24 and a maximum of 180.

**TASKTABLESIZE(maxtasks)**

Specifies the maximum number of possible tasks that are running at a particular time. The number includes both catalog and non-catalog tasks. TASKTABLESIZE is an IPL only parameter. TASKTABLESIZE is ignored on a CAS restart (no error message is issued). TASKTABLESIZE has a default value of 200, with a minimum of 200 and a maximum of 400.

**Restriction:** If both TASKMAX and TASKTABLESIZE are included in IGGCATxx, TASKTABLESIZE must be specified first.

**UPDTFAIL(YES|NO)**

Specifies whether you want the system to issue message IEC390I when a VSAM update request against a catalog was abnormally terminated. This message is intended to alert the installation that potential catalog damage might have resulted from the incomplete request.

**Default:** YES

**VVDSPACE(primary,secondary)**

Specifies the number of tracks for primary and secondary allocations that the catalog address space (CAS) should use for an implicitly defined VVDS. The specified values are preserved across a CAS restart and are applied at IPL. The maximum value for *primary* and *secondary* is 999.

If a zero secondary value is specified on a VVDSPACE(pri,sec) parameter and the primary value is valid, then on an IPL, a default of 10 tracks is substituted for the secondary. On a restart of the catalog address space, the value that existed before the CAS restart is retained.

**Default:** VVDSPACE(10,10)

**VVRCHECK(YES|NO)**

Specifies whether you want to enable enhanced VVR checking on VVDS I/O.

**Default:** NO



## Chapter 64. IKJTSoxx (TSO/E commands and programs)

You can use IKJTSoxx to identify the commands and programs the system is to use. The IKJTSoxx member allows you to identify:

- Authorized commands and programs.
- Commands that a user cannot issue in the background.
- APF-authorized programs that users may call through the TSO/E service facility.

If your installation is using the virtual lookaside facility (VLF) and plans to use the TSO/E VLFNOTE command, add VLFNOTE to this parmlib member as an authorized command, using the AUTHCMD NAME parameter. See *z/OS MVS Programming: Authorized Assembler Services Guide* for information about when to use the VLFNOTE command.

IKJTSoxx also allows you to specify the defaults for the TSO/E ALLOCATE, SEND, RECEIVE, TRANSMIT, CONSOLE, and TEST commands.

By defining the SHR option on the ALLOCATE parameter, you can change the system default for the disposition of data sets from OLD to SHARE (SHR).

The TRANSREC statement allows you to specify the characteristics for the data to be transmitted or received.

The TEST parameter allows you to specify the installation-written test subcommands and the names of TSO/E commands that are to be allowed to execute under the TEST command. These commands are in addition to those allowed by default. Through the SEND statement, you can specify the data set into which the SEND command is to store messages. The system checks that named data set when the user issues the LISTBC command to retrieve stored messages. The SEND statement, with the MSGPROTECT keyword, also allows you to protect mail from being seen by users who do not meet security criteria. By itself, setting MSGPROTECT(ON) causes mail to be stored in a mail log named 'logname.userid', rather than 'userid.logname'. By combining MSGPROTECT(ON) with RACF 1.9, you can request that the system compare the level of security of the mail received with the level of security of the recipient.

For information about setting up RACF 1.9 to work with MSGPROTECT(ON), see *z/OS Security Server RACF Security Administrator's Guide*.

To use IKJTSoxx, copy the default from SYS1.SAMPLIB(IKJTSo00) to SYS1.PARMLIB(IKJTSoxx). You can then update the member to meet the needs of your installation.

### Parameter in IEASYSxx (or specified by the operator)

IKJTSo=xx

The two-character identifier (xx) is appended to IKJTSo to identify the IKJTSoxx parmlib member. If you do not specify the IKJTSo=xx parameter, the system processes the IKJTSo00 parmlib member.

### Selecting the IKJTSoxx member

If present, IKJTSo00 is used automatically during IPL. A different IKJTSoxx member can be selected during IPL by specifying IKJTSo=xx for the IPL parameters.

To select another IKJTSoxx member after IPL, you can issue the TSO/E command PARMLIB UPDATE (xx) or the system command SET IKJTSo=xx, where xx is the alphanumeric value to be appended to IKJTSo.

To list the values in the active IKJTSOxx parmlib member, you can issue either of the following commands:

```
DISPLAY IKJTSO
PARMLIB LIST
```

For example,

```
DISPLAY IKJTSO,ALLOCATE
                ,CONSOLE
                ,HELP
                ,LOGON
                ,NOTBKGND
                ,SEND
                ,TEST
                ,TRANSREC
                ,ALL
```

```
PARMLIB LIST(ALLOCATE)
            (CONSOLE)
            (HELP)
            (LOGON)
            (NOTBKGND)
            (SEND)
            (TEST)
            (TRANSREC)
            (ALL)
```

For more information about the DISPLAY command, see *z/OS MVS System Commands*. For more information about the PARMLIB command, see *z/OS TSO/E System Programming Command Reference*.

## Syntax rules for IKJTSOxx

---

1. Comments may appear in columns 1-71 and must begin with a '/' and end with '\*/'.
2. Use a plus sign (+) or a dash (-) to continue a line. Any comments must appear to the left of the continuation character.
3. If the system encounters a syntax error in a IKJTSOxx statement, the default values are used for all the parameters on the statement. The system issues a message and processing continues.
4. Columns 1 through 72 may contain data.

## Syntax format of IKJTSOxx

```

ALLOCATE DEFAULT{(OLD)} | {(SHR)}

AUTHCMD NAMES(cmd1,cmd2...)

AUTHPGM NAMES(pgm1,pgm2...)

AUTHTSF NAMES(name1,name2...)

NOTBKGD NAMES(cmd1,cmd2...)

HELP language(dsname1[,dsname2,...])[,language(dsname1[,dsname2,...])]

LOGON
  LOGONHERE(ON|OFF)
  PASSWORDPREPROMPT(ON|OFF)
  PASSPHRASE(ON|OFF)
  TIMEOUT(n)
  USERIDMAX{(7)} | {(8)}
  VERIFYAPPL(ON|OFF)

CONSOLE
  INITUNUM(nnnn)
  INITSNUM(nnnn)
  MAXUNUM(nnnnn)
  MAXSNUM(nnnnn)

PLATCMD{NAMES(cmd1,cmd2...)} | {NONE}

PLATPGM{NAMES(pgm1,pgm2...)} | {NONE }

TEST TSOCMD(cmd1,cmd2,cmd3....)
  SUBCMD((scmd1,load1),(scmd2,load2)...)

TRANSREC
  NODESMF{((nodename1,smfid1),(nodename2,smfid2),...)}
    {((*,*))}
  SPOOLCL(spoolclass)
  CIPHER{(ALWAYS) | (YES) | (NO)}
  OUTWARN(n1,n2)
  OUTLIM(n1)
  VIO(unitname)
  LOGSEL(logselector)
  LOGNAME(lognamesuffix)
  USRCTL(name)
  SYSCTL(datasetsname)
  SYSOUT(sysoutclass | *)
  DAPREFIX(TUPREFIX | USERID)

SEND
  OPERSEND(ON | OFF),
  USERSEND(ON | OFF),
  SAVE(ON | OFF),
  USEBROD(ON | OFF)
  CHKBROD(ON | OFF)
  BROADCAST (DATASET(data-set-name) VOLUME(volume-name)
    TIMEOUT(time-out) switch-prompt)
  MSGPROTECT(ON|OFF)
  LOGNAME(data-set-name | *)
  SYSPLEXSHR(ON|OFF)
  USERLOGSIZE(primary-quantity,secondary-quantity,dir-block)
  OPERSEWAIT(ON|OFF)

```

## IBM-supplied default for IKJTSOxx

IKJTSO00 is supplied and used automatically during IPL. To use another IKJTSOxx member, issue the SET IKJTSO=xx command or the PARMLIB UPDATE(xx) command after IPL. Either command will replace the current IKJTSOxx with the member specified in the command.

## Statements and parameters for IKJTSOxx

### ALLOCATE DEFAULT{(OLD)} | {(SHR)}

Specifies the default value for the data sets required by a program. If you do not specify the ALLOCATE parameter, the system defaults to OLD.

**AUTHCMD NAMES(cmd1,cmd2...)**

Specifies the authorized TSO/E commands. *cmd1,cmd2* list the authorized commands. Each name can contain up to 8 characters. See SYS1.SAMPLIB for the current list of authorized commands. If you are using VLF and plan to use the TSO/E VLFNOTE command, include VLFNOTE in the active IKJTSOxx member.

For the latest information about the commands, see the list of parmlib members in *z/OS Program Directory* in the *z/OS Internet library* ([www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary)).

**AUTHPGM NAMES(pgm1,pgm2...)**

Specifies the authorized programs. *pgm1,pgm2* lists the authorized programs. Each program name can contain up to 8 characters.

For the latest information about the programs, see the list of parmlib members in *z/OS Program Directory* in the *z/OS Internet library* ([www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary)).

**AUTHTSF NAMES(name1,name2...)**

Specifies the APF-authorized programs that can be called through the TSO service facility. The *name1,name2* identify the names of the programs. Each name can contain up to 8 characters.

Do not place programs from any IBM products in this table unless the owning product documentation specifically instructs you to do so. For example, do not put IDCAMS in AUTHTSF.

For the latest information about the programs, see the list of parmlib members in *z/OS Program Directory* in the *z/OS Internet library* ([www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary)).

**CONSOLE**

Specifies the installation's defaults for the TSO/E CONSOLE command.

**INITSNUM(nnnn)**

Specifies the initial number of solicited messages that can be queued to the extended MCS console session (established through the CONSOLE command) at any time. This number does not include messages that are sent by the TPUT service. For information about the TPUT service, see *z/OS TSO/E Programming Services*.

When the actual number of queued messages reaches 80% of the specified number, installation exit IKJCNX50 is invoked. When the actual number of queued messages reaches the specified number, installation exit IKJCNX64 is invoked. For information about these installation exits, see *z/OS TSO/E Customization*.

**Default:** 1000 (decimal).

**INITUNUM(nnnn)**

Specifies the initial number of unsolicited messages that can be queued to the extended MCS console session (established through the CONSOLE command) at any time. This number does not include messages that are sent by the TPUT service. For information about the TPUT service, see *z/OS TSO/E Programming Services*.

When the actual number of queued messages reaches 80% of the specified number, installation exit IKJCNX50 is invoked. When the actual number of queued messages reaches the specified number, installation exit IKJCNX64 is invoked. For information about these installation exits, see *z/OS TSO/E Customization*.

**Default:** 1000 (decimal).

**MAXSNUM(nnnnn)**

Specifies the maximum number of solicited messages that can be queued to the extended MCS console session (established through the CONSOLE command) at any time. The system records this value at initialization time; this value can only be changed through the parmlib UPDATE command for active extended MCS console sessions. This number does not include messages that are sent by the TPUT service. For information about the TPUT service, see *z/OS TSO/E Programming Services*.

This value is used by console activation processing and is passed to the TSO/E message capacity exits (IKJCNX50 and IKJCNX64).

**Default:** 10000 (decimal).

#### **MAXUNUM(nnnnn)**

Specifies the maximum number of unsolicited messages that can be queued to the extended MCS console session (established through the CONSOLE command) at any time. The system records this value at initialization time; this value can only be changed through the parmlib UPDATE command for active extended MCS console sessions. This number does not include messages that are sent by the TPUT service. For information about the TPUT service, see [z/OS TSO/E Programming Services](#).

This value is used by console activation processing and is passed to the TSO/E message capacity exits (IKJCNX50 and IKJCNX64).

**Default:** 10000 (decimal).

#### **HELP language(dsname1[,dsname2,...])[,language(dsname1[,dsname2,...])]**

Specifies message help texts for the specified languages.

##### **language**

Specifies the three character language code. See [Table 54 on page 640](#) for the table of supported language codes.

##### **dsname**

Specifies the name of the data set that contains help text for the specified language. You can specify up to 255 help data sets for each language.

**Default:** ENU(SYS1.HELP)

#### **LOGON**

Specifies the system settings for the TSO/E LOGON command.

##### **LOGONHERE(ON|OFF)**

Specifies whether the RECONNECT option on the TSO/E LOGON panel is honored even when the system does not detect a disconnected state and the user appears to be logged on. Users can reconnect their session from a new terminal without canceling their previous session first, similar to how the LOGONHERE option works under z/VM.

**Default:** ON

##### **PASSWORDPREPROMPT(ON|OFF)**

Specifies whether the user is prompted to enter both the user ID and password before the presentation of any other information.



**Warning:** TSO/E logon exits might need to be updated before activating PASSWORDPREPROMPT. Exit processing that affects the TSO/E user ID or password might not work as expected.



**Warning:** Once activated, users that are defined to UADS and not RACF cannot log on unless RACF is not active.

**Default:** OFF

##### **PASSPHRASE(ON|OFF)**

Specifies whether the TSO/E logon panel allows users to enter up to 100 characters in the password field. If 8 characters or less are entered, the input is treated as a password. If more than 8 characters are entered, the input is treated as a passphrase. For more information about activating passphrase support, see [z/OS TSO/E Customization](#).

**Default:** OFF

##### **TIMEOUT(n)**

Specifies a value between 0 and 255 denoting how many minutes TSO LOGON prompting is allowed before the LOGON session is terminated. If 0 is specified, no timeout occurs. If not specified, 5 minutes is the default.

**Note:** If the TIMEOUT value is routed from a system that does not support TIMEOUT, the receiving system sets the default of 5 minutes.

### **USERIDMAX{(7)} | {(8)}**

Allows setting a longer user ID or prefix. When USERIDMAX is set to a value of 8, the following should be kept in mind:

- The SUBMIT command submits jobs for 8-character user IDs with job names equal to the user ID.
- If messages sent to 8-character user IDs by the SEND command are to be saved, they are only saved if user logs are enabled. Messages are delivered to the user if they are to be displayed in the user's session.
- Information Center Facility only allows users with IDs that are 7 characters or less to invoke Information Center Facility function.
- Users who share their IDs with z/OS V2R2 or lower systems and set 8 character prefix values should be made aware that the prefix value is not usable on those shared systems since the maximum length supported is 7.

When 8 character user IDs are enabled, note the following:

- Although UADS user can be at most 7-characters, you can use an 8-character prefix with a UADS user when 8-character user IDs are enabled. However, the 8-character prefix cannot be saved across sessions for a UADS user. NOPREFIX is the value that is saved when a UADS user with an 8-character prefix logs off.
- RACF defined users with a TSO segment can use and save 8-character prefix value across sessions.
- Any BATCH TSO TMP job running under a user ID with NOPREFIX as the prefix value saved in the UPT runs with the prefix defaulting to the user ID.
- Any TSO user who logs on as a foreground TSO user with NOPREFIX as the prefix value saved in the UPT runs with NOPREFIX, unless changed by a logon exit.

**Default:** 7

### **VERIFYAPPL(ON|OFF)**

Specifies whether TSO/E determines an APPLID for the system the user is logging on to and passes that APPLID to RACF for verification during TSO/E logon. This option can be used to limit access to different systems that share RACF database. For information about setting up APPLIDs in RACF and implementing APPLID verification, see [z/OS TSO/E Customization](#).

**Default:** OFF

### **NOTBKGD NAMES(cmd1,cmd2...)**

Specifies the commands that may **not** be issued in the background. **cmd1,cmd2** lists these commands. Each can contain up to 8 characters.

See SYS1.SAMPLIB for the current list of commands.

### **PLATCMD{NAMES(cmd1,cmd2...)} | {NONE}**

Specifies the commands (**cmd1, cmd2,...**) that are executed on the TSO/E command/program invocation platform. These commands do not require task termination processing to clean up for them. Each command can contain up to 8 characters.

See SYS1.SAMPLIB for the current list of commands. For more information about the TSO/E command or program invocation platform, see [z/OS TSO/E Customization](#).

**Default:** NONE. No commands are eligible to run on the TSO/E command or program invocation platform).

### **PLATPGM{NAMES(pgm1,pgm2...)} | {NONE }**

Specifies the programs (**pgm1, pgm2,...**) that are to be run on the TSO/E command/program invocation platform. These programs do not require task termination processing to clean up for them. Each program name can contain up to 8 characters.

See SYS1.SAMPLIB for the current list of commands. For more information about the TSO/E command/program invocation platform, see *z/OS TSO/E Customization*.

**Default:** NONE. No commands are eligible to run on the TSO/E command or program invocation platform.

#### **TEST TSOCMD(*cmd1,cmd2,cmd3,....*)**

#### **TEST SUBCMD((*scmd1,load1*),(*scmd2,load2*)...)**

The TEST parameter specifies that the following commands are authorized to be executed in a test environment. TSOCMD specifies that the following commands (*cmd1,cmd2...*) are installation-written TSO/E commands that are allowed to be executed under TEST. SUBCMD specifies that the following installation-written command can be invoked as a subcommand of TEST.

The value for *scmd1* is the command. The value for *load1* is the entry point for the program to be invoked as the subcommand. For each SUBCMD specified, you must include both the command and the program name for the command.

#### **TRANSREC**

TRANSREC allows you to specify the characteristics for the RECEIVE and TRANSMIT commands.

#### **CIPHER{(ALWAYS) | (YES) | (NO)}**

Specifies the choice for controlling data encryption.

##### **ALWAYS**

For every transmission, the data is automatically encrypted.

##### **NO**

Encryption is not allowed on any transmission. NO overrides the specification of the ENCRYPT operand on the TRANSMIT command and does not allow you to provide encryption through the TRANSMIT encryption exits, INMXZ03 or INMXZ03R.

##### **YES**

Encryption is a user option.

**Default:** YES

#### **DAPREFIX(TUPREFIX | USERID)**

DAPREFIX specifies how the control and log data sets are to be prefixed for messages that are written by utility programs, such as IEBCOPY.

##### **TUPREFIX**

The control and log data sets are prefixed with the PREFIX set in the User Profile Table. If the PROFILE NOPREFIX option is in effect, the log data set is LOG.MISC and the control data set is NAMES.TEXT.

##### **USERID**

The control and log data sets are prefixed with the user ID whenever the PROFILE NOPREFIX option is in effect. Users cannot log to LOG.MISC and reading NAMES.TEXT when PROFILE NOPREFIX is in effect.

**Default:** TUPREFIX

#### **LOGNAME(lognamesuffix)**

LOGNAME specifies the default suffix qualifier for the log data set name. The following values take precedence over this parameter:

- LOGNAME operand of the TRANSMIT command.
- :LOGNAME tag in the control section of the NAMES data set.
- :LOGNAME tag in a nickname definition.

The *lognamesuffix* is the name of the suffix qualifier and must be 1-8 alphanumeric characters that begin with an alphabetic or special (#, @, or \$) character. The names must be separated by a period.

In the absence of any explicit specification, the default log data set name is *userid.LOG.MISC*.



**Maximum length restriction:** TSO/E prefixes the name of the log data set with the user-specified *dsname-prefix* from the PROFILE command, so the name is equivalent to *prefix.logselector.logname-suffix*. The maximum length of the name is 44 characters, including the periods and the *prefix*.

### LOGSEL(*logselector*)

LOGSEL specifies the default middle qualifier for the log data set name. (The name in the :LOGSEL tag in the control section of the NAMES data set takes precedence.) The *logselector* is 1-8 alphanumeric name of the middle qualifier. The first character must be alphabetic or special (#, @, or \$). The names must be separated by a period.

### NODESMF{((*nodename1,smfid1*),(*nodename2,smfid2*),...)}{((\*,\*))}

NODESMF specifies the correspondence between the system identifiers and the network node names.

*nodename* specifies the name of the network node. *nodename* must be the name of a node that is defined on the NJERMT JES3 initialization statement or on the NODE(xxxxxxx) JES2 initialization statement.

The *smfid* specifies the system identifier for a particular processor, paired with a *node-name*. *smfid* must be specified for each *nodename*. *smfid* must match the system identifier that is defined for the processor on the SID parameter of the SMFPRMxx member.

*\**, *\** specifies that the *nodename* is to be retrieved dynamically from JES. This specification is recommended because it eliminates the need to specify static values for *nodename* and *smfid*.

**Default:** (NODENAME, SMF)

**Note:** If you omit the *smfid* for the host node, TSO/E uses a value of eight question marks (???????) for the *nodename* that is associated with the transmitted data.

### OUTLIM(*n1*)

OUTLIM specifies the maximum number of records a user can transmit before the transmission is terminated.

If *n1* is less than or equal to 16777215, the system passes the value to JES as the OUTLIM value. If *n1* is greater than 16777215, the system does not pass the value to JES. However, *n1* still serves as the limit for the TRANSMIT command. *n1* should be greater than zero.

**Note:** The TRANSMIT command continues to work when the OUTLIM value is exceeded when writing to an OUTDDN or OUTDSN. The NOWARN option in the TRANSMIT command can be used to skip related warning messages. For more information about the NOWARN option, see [z/OS TSO/E Customization](#) and [z/OS TSO/E Command Reference](#).

The TSO/E TRANSMIT command produces punched card output. Punched card output is limited by TSO/E or by JES, depending on which limit is lower. If the TSO/E limit is the lowest and is reached, the transmission is terminated and the following message is displayed at the user's terminal:

```
INMX032I  TRANSMIT command terminated.  Transmission limit of 'nn'
records exceeded.
```

If the JES limit is the lowest and is reached, the transmission is allowed to continue, abnormally ended, or abnormally ended with a dump.

**Tip:** Set the TSO/E limit lower than the JES limit to allow the TSO/E user to receive messages that indicate whether the system successfully transmitted the data set.

For more information about output limits, see:

- The OUTLIM DD statement in [z/OS MVS JCL Reference](#)
- The ESTPUN initialization statement in [z/OS JES2 Initialization and Tuning Guide](#)
- The dynamic allocation SYSOUT output limit specification DALOUTLM (key=X'001B') in [z/OS MVS Programming: Authorized Assembler Services Guide](#)



**Default:** 30000 (decimal).

### **OUTWARN(*n1*,*n2*)**

OUTWARN allows the installation to specify the intervals at which a warning message is issued to a user who is transmitting a large file.

#### ***n1***

Specifies the number of records to be transmitted before the first warning message is issued to the user. The default is 10000 (decimal).

#### ***n2***

Specifies the number of records to be transmitted before second and subsequent warning messages are issued. The subsequent warning messages are issued each time this number of records is transmitted. The default is 5000 (decimal).

If you specify only one value with OUTWARN, the system uses that value as the first interval and uses the default (5000) for the second and subsequent intervals.

### **SPOOLCL(*spoolclass*)**

Specifies the output class default. Use the SPOOLCL operand *class* to specify your installation's output class default.

This parameter applies to outgoing data only. Incoming data that is addressed to the issuer of RECEIVE or to the user ID specified on the RECEIVE command by an authorized issuer of RECEIVE is eligible to be received regardless of its sysout class.

**Value range:** A-Z, 0-9, or \*

**Default:** If you do not specify a different SPOOLCL operand, the default of B is used.

### **SYSCTL(*datasetname*)**

SYSCTL specifies the name of an alternate NAMES data set. You can use this parameter, with a routine you write, to provide a global standard set of nicknames within the installation. For example, the routine might manipulate the entries in a directory and store the resulting output (nicknames) in the SYSCTL data set. End users could then use the standard set of nicknames, instead of having to define their own nicknames on an individual basis.

The *datasetname* identifies the name of the data set and must be 1-8 alphanumeric characters that begin with an alphabetic or special (#, @, or \$) character. The names must be separated by periods. The total characters in the names, including the periods, cannot exceed 44 characters. TSO/E does not prefix the *datasetname*.

### **SYSOUT(*sysoutclass* | \*)**

SYSOUT specifies the default SYSOUT class for messages that are written from utility programs, such as IEBCOPY. *sysoutclass* identifies the sysout class and can be A-Z, 0-9, or asterisk (\*).

**Default:** SYSOUT(\*); the system writes the messages to the terminal.

### **USRCTL(*name*)**

USRCTL is the name for the NAMES data set. The *name* must be 1-8 alphanumeric characters that begin with an alphabetic or special (#, @, or \$) character. The names must be separated by a period.

In the absence of any explicit specification, the default NAMES data set name is *userid*.NAMES.TEXT.

**Maximum length restriction:** TSO/E prefixes the name of the NAMES data set with the user-specified *dsname-prefix* from the PROFILE command. The maximum length of the name is 44 characters, including the periods and the *prefix*.

### **VIO(*unitname*)**

VIO specifies the device type on which temporary space can be allocated for use by the TRANSMIT and RECEIVE commands. The *unitname* is the name of the device type and can be either an esoteric name (SYSDA) or a specific DASD device (for example, 3380).

If you do not specify VIO, the system defaults to the UNIT specification for the user in the UADS. If there is no UNIT specification, the system defaults to an installation-defined default or to the system default, SYSALLDA. (In each of the three preceding situations, IEBCOPY might fail.)

**Tip:** *unitname* should be a device type that you designated as VIO at IPL. The use of VIO ensures the integrity of sensitive data.

## SEND

Specifies the installation's defaults for the TSO/E SEND and LISTBC commands, and the OPERATOR SEND command.

### **BROADCAST** (*dataset*(*data-set-name*) *VOLUME*(*volume-name*)

### **BROADCAST TIMEOUT**(*time-out*) *switch-prompt*)

Identifies the broadcast data set and the processing options to use when switching between broadcast data sets.

#### ***data-set-name***

Specifies the fully qualified data set name. The use of quotation marks in the data set name is ignored; that is, 'SYS3.BROADCAST' is equal to SYS3.BROADCAST. DATASET is a required subkeyword.

#### ***switch-prompt***

Specifies whether TSO/E should prompt before switching the broadcast data set. Valid values for *switch-prompt* are PROMPT and NOPROMPT. *switch-prompt* is an optional subkeyword. The default value is PROMPT.

When a parmlib UPDATE ROUTE command is issued, the *switch-prompt* setting is valid only when a switch is detected on the system. If no switch is detected, no prompt occurs, regardless of whether the command causes a broadcast data set switch on any systems that the settings are specified. If a separate prompt for each system is needed, consider using the MVS ROUTE \*ALL,SET IKJTSO=xx command instead.

If the BROADCAST keyword is not specified, the default values are SYS1.BROADCAST for *data-set-name*, no volume, 5 second *time-out*, and PROMPT for *switch-prompt*.

The data set must be formatted with the TSO/E SYNC command and cataloged or the volume serial must be specified on the BROADCAST keyword.

**Note:** TSO/E uses the name that is specified in the BROADCAST keyword or its default. Any entries for the SYSLBC DD name in MSTJCLxx are disregarded by TSO/E.

#### ***time-out***

Specifies the number of seconds a switch request waits for resources before timing out. Valid values for TIMEOUT are integers in the range of 0 to 999, inclusive. TIMEOUT is an optional subkeyword. The default value is 5 seconds.

#### ***volume-name***

Specifies the volume serial on which the broadcast data set resides. VOLUME is an optional subkeyword.

### **CHKBROD**(**ON** | **OFF**)

CHKBROD indicates whether LISTBC processing is to check for messages in the broadcast data set and the user log and retrieve any messages found. LISTBC processing uses CHKBROD only when USEBROD is ON; that is, LISTBC processing ignores the broadcast data set when USEBROD is OFF.

#### **OFF**

LISTBC processing checks only the user log for messages.

#### **ON**

LISTBC processing checks both the broadcast data set and the user log.

**Default:** ON

**Notes:**

1. CHKBROD applies only if you use user logs to store messages. It does not apply if you use only the broadcast data set to store messages. For more information about user logs, see [z/OS TSO/E Customization](#).
2. If USEBROD is ON and the user log does not exist, LISTBC creates the user log and then checks SYS1.BROADCAST and retrieves any messages found. This checking and retrieval occur regardless of the CHKBROD setting.

LISTBC and SEND processing differ depending on the USEBROD and CHKBROD operands. If LOGNAME is set to 'SYS1.BROADCAST', the following conditions are true:

- The USEBROD and CHKBROD operands do not affect processing
- SEND and LISTBC use the broadcast data set for messages.

For the effects of USEBROD and CHKBROD on LISTBC and SEND processing when LOGNAME is not set to SYS1.BROADCAST, see [Table 32 on page 581](#), which assumes the installation is using individual user logs.

| <i>Table 32. LISTBC and SEND results based on CHKBROD and USEBROD settings when installation is using individual user logs</i> |  |  |
|--|--|--|
|  | USEBROD ON   | USEBROD OFF  |
| CHKBROD ON   | <ul style="list-style-type: none"> <li>• LISTBC: The broadcast data set is always checked for messages, even when a user log exists.</li> <li>• SEND: Messages are saved in the broadcast data set when no user log exists.</li> </ul>   | <ul style="list-style-type: none"> <li>• LISTBC: The broadcast data set is not checked for messages.</li> <li>• SEND: Messages are not saved in the broadcast data set when no user logs exists. Message IKJ55058I is issued instead.</li> </ul> |
| CHKBROD OFF  | <ul style="list-style-type: none"> <li>• LISTBC: The broadcast data set is not checked for messages, except when LISTBC creates a new user log or when an existing user log cannot be allocated.</li> <li>• SEND: Messages are saved in the broadcast data set when no user log exists.</li> </ul> | <ul style="list-style-type: none"> <li>• LISTBC: The broadcast data set is not checked for messages.</li> <li>• SEND: Messages are not saved in the broadcast data set when no user log exists. Message IKJ55058I is issued instead.</li> </ul>  |

### LOGNAME(*data-set-name* | \*)

LOGNAME identifies the log name of the data set where the system stores messages and notes.

To store messages (mail) in the broadcast data set, set LOGNAME to \*. \* is the preferred method to request that the mail be stored in the broadcast data set.

**Note:** For compatibility, the system accepts the specification of LOGNAME(SYS1.BROADCAST), and the user's mail is stored in the current broadcast data set. The BROADCAST keyword on the SEND statement is used to specify a broadcast data set name other than SYS1.BROADCAST.

To store messages in individual logs, set LOGNAME to the qualifier for the user log data set name. You can also specify a member name in parentheses.

The name of the user log data set depends on the setting of the MSGPROTECT parameter. If MSGPROTECT is off, the user log naming convention is as shown, where *userid* is the user's TSO/E user ID and LOGNAME is the qualifier that you specify on the SEND PARMLIB parameter.

```
userid.LOGNAME
```

If MSGPROTECT is ON, the user log naming convention is

```
LOGNAME.userid
```

For example, suppose that you set LOGNAME to *u log.data*. If MSGPROTECT is OFF, the user log data set name is as follows:

```
userid.u log.data
```

If MSGPROTECT is ON, the user log data set name is as follows:

```
u log.data.userid
```

For more information about user logs, see [z/OS TSO/E Customization](#).

### MSGPROTECT(ON | OFF)

If you use user logs, use the MSGPROTECT operand to indicate whether the individual user log data set is security protected from the user. Set MSGPROTECT to one of the following values. The default value is OFF.

#### OFF

Users can view their received mail without any security checking by the system. If MSGPROTECT is OFF, the user log data set name is `userid.logname`, where *userid* is the user's TSO/E user ID and *logname* is the data set name qualifier that you specify on the LOGNAME operand. This naming convention allows the user to access the user log data set. The mail in the user log is not security-protected from the user. The user can log on and get the messages by requesting MAIL or by issuing the LISTBC command.

#### ON

The individual user log is protected from the user and the messages (mail) within the individual user log can be viewed only if the user is logged on with the proper security label.

If the MSGPROTECT operand is ON, the user log data set name is `logname.userid`, where *logname* is the data set name qualifier that you specify on the LOGNAME operand of the SEND PARMLIB parameter and *userid* is the user's TSO/E user ID. This naming convention protects the user log data set from the user when an installation has defined the RACF profile for LOGNAME.\* UACC (NONE). Mail in the user log can be viewed by the user if the user is logged on at the proper security label by using the LISTBC command, or by requesting MAIL during LOGON.

If RACF 1.9 or later is installed and your installation has set up security labels for your users using RACF, and the MSGPROTECT operand is ON, the security label of the sender is stored with the message in the user log data set. When the receiving user issues the LISTBC command to view messages, the security label of the receiving user is checked with the security label that is stored with the message for each message in the user log. The result of that check determines whether LISTBC displays the messages. If LISTBC does not display a message and the user is authorized at the security label of the message but is not currently logged on at the security label of the message, then the message remains in the user log. The user can log on to TSO/E with the proper security label and view the message later. If LISTBC does not display a message and the user can never log on at the proper security label for the message (user is not authorized by RACF for that security label), the message gets deleted.

**Note:** Use of the MSGPROTECT operand is only used with RACF 1.9 or later. If a lower level of RACF is installed on your system, MSGPROTECT does not protect messages. If you plan to use the MSGPROTECT operand with a lower level of RACF installed, each user log must be allocated by the installation.

#### Default: OFF

If the MSGPROTECT value is switched from ON to OFF, messages that were left in the individual user logs on one setting cannot be retrieved until the settings are switched back.

**Tip:** To prevent the master catalog from filling up with catalog entries for the new user logs, create a user catalog and define an alias that is associated with the user catalog of LOGNAME.

### OPERSSEND(ON| OFF),

OPERSSEND specifies whether users who are authorized to use the OPERATOR command can issue the SEND subcommand to send messages or notes. For information about the OPERATOR and SEND commands, see [z/OS TSO/E Customization](#).

#### OFF

Users who are authorized to use the OPERATOR command cannot issue the SEND subcommand to send messages or notes.

**ON**

Users who are authorized to use the OPERATOR command can issue the SEND subcommand to send messages or notes.

**Default:** ON

**OPERSEWAIT(ON|OFF)**

Indicates whether WAIT or NOWAIT is requested when an OPERATOR SEND command is issued without an explicit WAIT/NOWAIT operand.

**OFF**

The OPERATOR SEND command is issued with NOWAIT. NOWAIT on OPERATOR SEND specifies that messages can be sent to any specified user whose terminal is not busy (output buffers not full).

**ON**

The OPERATOR SEND command is issued with WAIT. WAIT on OPERATOR SEND specifies that messages cannot be sent to any specified user until all users can receive them. That is, no user's terminal is busy (no user's output buffers are full).

**Default:** OFF

**SAVE(ON | OFF),**

SAVE specifies whether the SEND command processor and the OPERATOR SEND subcommand processor are to save messages in a log that the installation specifies.

**Default:** ON

**SYSPLEXSHR(ON | OFF)**

SYSPLEXSHR indicates whether the broadcast data set is shared outside systems in the sysplex.

**OFF**

The broadcast data set is shared with systems outside the sysplex

**ON**

The broadcast data set is shared only among systems in the sysplex.

**Default:** OFF

**Tip:** To avoid confusion in your installation when modifying the broadcast data set, give SYSPLEXSHR the same value in every system's IKJTSoxx member. A system with SYSPLEXSHR set to OFF does not communicate broadcast data set changes to systems with SYSPLEXSHR set to ON.

**USEBROD(ON | OFF)**

USEBROD indicates whether messages intended for users who do not have individual user logs are to be stored in the SYS1.BROADCAST data set. If the installation is not using individual user logs, the system ignores this operand.

**OFF**

Messages are not saved and the user does not receive the messages.

**ON**

Messages are stored in the SYS1.BROADCAST data set.

**Default:** ON

Table 32 on page 581 shows how LISTBC and SEND interpret the USEBROD and CHKBROD operands if the installation is using individual user logs. This figure applies to messages only; USEBROD and CHKBROD do not affect the processing of notices.

**Default:** ON

**USERLOGSIZE(primary-quantity,secondary-quantity,dir-block)**

USERLOGSIZE specifies the amount of space that is allocated for the USERLOG data set if user logs are used.

***dir-block***

An optional parameter that specifies the number of blocks that are requested for the directory if the user log is a partitioned data set. The default is 20 directory blocks.

***primary-quantity***

Specifies the number of tracks that are requested for the primary allocation of the user log data set. The default is one track.

***secondary-quantity***

Specifies the number of tracks that are requested for secondary allocations of the user log. The default is two tracks.

**USERSEND(ON | OFF),**

USERSEND specifies whether users can issue the SEND command to send messages or notes to other terminal users. USERSEND is not valid for the SEND subcommand of the OPERATOR command. Use the OPERSEND parameter to specify whether authorized users of the OPERATOR command can use the SEND subcommand.

**OFF**

Users cannot issue the SEND command to send messages or notes to other terminal users.

**ON**

Users can issue the SEND command to send messages or notes to other terminal users.

**Default:** ON

## Chapter 65. IOEPRMxx (z/OS File System parameters)

IOEPRMxx contains the configuration options that control the z/OS File System (zFS) environment and zFS aggregates to be attached at the start-up of zFS. The IOEPRMxx files are contained in the logical parmlib concatenation, which are defined on the PARMLIB parameter in the LOADxx member. Alternatively, you can specify the z/OS File System (zFS) configuration options in the IOEFSPRM file, which is pointed to by the IOEZPRM DD statement in the ZFS PROC.

This topic covers only concatenation and syntax rules. For information about parameters for the IOEPRMxx parmlib member and the IOEFSPRM file, see [IOEFSPRM](#) in *z/OS File System Administration*.

### Specifying the IOEPRMxx concatenation

To concatenate data sets to the IOEPRMxx concatenation, you specify the suffixes of the IOEPRMxx data sets on the PARM option of the FILESYSTYPE TYPE(ZFS) statement in the BPXPRMxx parmlib member (see [Chapter 13, “BPXPRMxx \(z/OS UNIX System Services parameters\),”](#) on page 123). The PARM parameter is case sensitive; you must enter the string of suffixes in upper case. [Figure 22 on page 585](#) shows an example of a FILESYSTYPE TYPE(ZFS) statement.

```
FILESYSTYPE TYPE(ZFS) ENTRYPOINT(IOEFSCM)
ASNAME(ZFS, 'SUB=MSTR')
PARM('PRM=(01,02,03)')
```

*Figure 22. Example: FILESYSTYPE TYPE(ZFS) statement*

You can specify any system symbol in the PARM parameter that resolves to two characters. For example, [Figure 23 on page 585](#) shows a FILESYSTYPE TYPE(ZFS) statement that uses system symbols.

```
FILESYSTYPE TYPE(ZFS) ENTRYPOINT(IOEFSCM)
ASNAME(ZFS, 'SUB=MSTR')
PARM('PRM=(01,&SYSCONE.)')
```

*Figure 23. Example: FILESYSTYPE TYPE(ZFS) statement using system symbols*

If symbol &SYSCONE is equal to AB, this statement specifies that the system should search parmlib member IOEPRM01 first and IOEPRMAB second. You might use this specification if, for example, parmlib member IOEPRM01 contains common configuration options and IOEPRMAB contains configuration options specific to system AB. If the system does not find a particular parmlib member, the search for the configuration option continues with the next parmlib member.

You can specify up to 32 IOEPRMxx member suffixes in the PARM parameter. To specify 32 members, type member suffixes up to column 71 and then continue them in column 1 on the next line. For example, [Figure 24 on page 585](#) shows an FILESYSTYPE TYPE(ZFS) statement that specifies 32 IOEPRMxx members.

```

col 72
|
V
FILESYSTYPE TYPE(ZFS) ENTRYPOINT(IOEFSCM) ASNAME(ZFS, 'SUB=MSTR')
      PARM('PRM=(00,01,02,03,04,05,06,07,08,09,10,11,12,13,14,
15,16,17,18,19,20,21,22,23,24,25,26,27,28,29,30,31)')
^
|
col 1
```

*Figure 24. Example: FILESYSTYPE TYPE(ZFS) statement specifying 32 IOEPRMxx members*

### Syntax rules for IOEPRMxx

The following syntax rules apply to IOEPRMxx:

- Columns 73-80 are ignored in the IOEPRMxx member.
- Any line beginning with # or \* is considered a comment.
- The text in the IOEFSPRM file is case insensitive. Any option or value can be upper or lower case.
- Blank lines are allowed.
- Do not have any sequence numbers in the IOEFSPRM file.
- If a configuration option is specified more than once, the first one found is taken.
- If a statement that has a default is omitted, the default is used.



## Chapter 66. IPCSPRnn (Interactive Problem Control System)

An IPCSPRnn member contains parameters used during an IPCS session. These session parameters allow an installation to tailor IPCS sessions to its particular requirements. The parameters define the names of various data sets and default values to be used throughout that IPCS session. When you execute the IPCS command, IPCS initialization processes these parameters. Thus, you cannot modify or respecify them during an IPCS session.

The installation can have several IPCSPRnn members. You then specify the member that suits your needs for a particular IPCS session. See [Chapter 11, “BLSCECT \(formatting exits for dump and trace analysis\),”](#) on page 109 for information about IPCS parmlib member allocation.

### Parameter in IEASYSxx (or specified by the operator)

None. The PARM(nn) keyword on the IPCS TSO command specifies the IPCSPRnn member that the system will use during that IPCS session.

### Syntax rules for IPCSPRnn

- IPCS processes each statement as lines of TSO/E Command Language. Comments follow the rules of TSO/E Command Language and can be used wherever a delimiter can appear. Comments begin with /\* and can end with \*/ on the same line. Additional options for ending comments are described within the TSO/E Command Language. For more details, see [z/OS TSO/E Command Reference](#) and [z/OS TSO/E User's Guide](#).
- The IPCSPRnn member's suffix identifier can consist of numerals only. For example, IPCSPR01 is permitted, but IPCSPR1A is not.
- IPCSPRnn supports system symbols.

### IBM-supplied default for IPCSPRnn

The IPCS installation package includes the default member IPCSPR00.

### Statements and parameters for IPCSPRnn

**Multiple keywords are no longer functional:** As of z/OS V1R11, the only functional keywords are LINELENGTH and PAGESIZE. The DSD, NODSD, PDR, NOPDR, PROBIDPREFIX, SYSTEM, GROUP, ADMINAUTHORITY, and DELETEAUTHORITY keywords continue to be parsed but are ignored by IPCS when IPCSPRnn is processed.

#### LINELENGTH(value)

Specifies the default record length (LRECL) for the IPCS print output data set. *value* is a two- or three-decimal digit from 83 through 255. This parameter is optional.

If you do not specify an LRECL for the print output data set and if it is not specified in the session parameters, the default is 137.

**Value range:** 83-255

**Default:** 137

#### PAGESIZE(value)

Specifies the default number of lines per page for the IPCS print output data set. *value* is a decimal number that ranges from 3 through  $2^{31}-1$ . This parameter is optional. If you do not specify it, the default is 60.

PAGESIZE values should correspond with the number of lines that will fit on the forms that are typically used at your installation.

**Default:** 60

## Chapter 67. IQPPRMxx (PCIE related parameters)

Use the IQPPRMxx parmlib member to specify parameters that are used for managing PCIE-related features, such as the zEDC Express feature.

Use the SET IQP command to change the parameters while the system is active.

**Note:** The IQPPRMxx will still be valid on IBM zEnterprise z15 and above processors, but the tunable options will no longer be available. Therefore, a message IQP062I REQUEST REJECTED - OPTIONS IGNORED will be displayed.

### Parameter in IEASYSxx (or specified by the operator)

```
IQP={aa
    {(aa,bb...)} }
```

This parameter identifies the IQPPRMxx parmlib member or members to be used for managing PCIE-related features, such as the zEDC Express feature. The two alphanumeric characters, represented by aa (or bb, and so on), are appended to IQPPRM to form the name of the IQPPRMxx member(s).

### Syntax rules for IQPPRMxx

- Data is specified in columns 1-71. Columns 72-80 are ignored.
- You can enter one or more statements on a line or use multiple lines for one statement.
- The same statement can appear multiple times in a parmlib member. For example, a ZEDC statement with the MAXSEGMENTS parameter may be specified one line and another ZEDC statement with the DEFMINREQSIZE parameter may be specified on another line.
- Use commas as delimiters. The system interprets multiple commas as a single comma. You can use commas between parameters and values. For example, the following parameter specification is valid:

```
ZEDC,
MAXSEGMENTS=4,
DEFMINREQSIZE=4,
INFMINREQSIZE=16
```

- Comments can start in any column and can span lines. Comments must start with /\* and end with \*/. Comments may appear in any place where a blank is accepted, except within quoted strings.
- Syntax errors cause the parameter to be ignored and processing to continue with the next parameter.
- If a parameter appears multiple times, the first valid instance is accepted, and subsequent occurrences are ignored.
- Enter values in uppercase, lowercase, or mixed case. The system converts the input to uppercase.

### Statements and parameters for IQPPRMxx

#### ZEDC

Use the ZEDC statement to specify parameters for managing application requests that use the zEDC Express feature.

Parameters for the ZEDC statement:

#### DEFMINREQSIZE=nnnn

Specifies the minimum size in kilobytes of the data to be compressed in order for the request to be eligible for compression.

**Value range:** 4-9999 (4 K to 9999 K). The request size must be greater than or equal to this size in order to be eligible for compression. Otherwise, software compression is used.

**Default:**

- 4 (4 K) for z14 processors and below
- 1 (1K) for z15 processors and above

**INFMINREQSIZE=nnnn**

Specifies the minimum size in kilobytes of the data to be decompressed in order for the request to be eligible for decompression.

**Value range:** 4-9999 (4 K to 9999 K). The request size must be greater than or equal to this size in order to be eligible for compression. Otherwise, software compression is used.

**Default:**

- 16 (16K) for z14 processors and below
- 1 (1K) for z15 processors and above

**MAXSEGMENTS=nnn**

Specifies the maximum number of 16 MB storage areas (segments) to allow for problem state compression (deflation) and decompression (inflation) requests.

**Value range:** 0, 4-64 (64 MB to 1 GB)

If zero is specified, problem state programs will not use the zEDC Express feature for compression and decompression requests.

If a nonzero value is specified, the system initially allocates and page fixes 4 segments for problem state requests. Additional segments are allocated and page fixed as needed up to the maximum number of segments. Segments that are no longer needed will be page freed and deallocated after a system determined amount of time.

If a SET IQP command is used to change the MAXSEGMENTS value to a lower value, the change is ignored and the original value remains in effect, because the maximum number of segments cannot be decreased dynamically. If a higher value is specified, the value is accepted.

**Default:** 4 (64 MB)

zlib is the problem state exploiter for zEDC. For more information about zlib, see [\*z/OS MVS Programming: Callable Services for High-Level Languages\*](#).

---

## Chapter 68. IRRPRMxx (RACF parameters)

The IRRPRMxx parmlib member contains data for the RACF data set name table, range table, and sysplex communications options. Use an IRRPRMxx member to specify statements that describe the RACF data set name table and the range table, that were previously defined by ICHRDSNT and ICHRRNG.

For the data set name table, the statements include the primary and backup data set name, update backup options, and resident index blocks.

Sysplex communication options can also be specified in the parmlib member.

Each individual section can be in its own parmlib member, however, no section can be split between multiple members. A maximum of 3 parmlib members can be specified.

For complete information about the IRRPRMxx parmlib member, including syntax and parameters, see [Specifying RACF database options in \*z/OS Security Server RACF System Programmer's Guide\*](#).

---

### IBM-supplied default for IRRPRMxx

There is no default IRRPRMxx parmlib member. SYS1.SAMPLIB provides a sample parmlib member, IRRPRMXX.



## Chapter 69. IVTPRM00 (Communication Storage Manager)

IVTPRM00 sets parameters for the Communication Storage Manager (CSM). IVTPRM00 is read during CSM initialization when the first IVTCSM REQUEST=CREATE\_POOL macro is issued. (VTAM issues this macro when started.) The parameters can be changed without a re-IPL by editing the IVTPRM00 member and issuing the MODIFY CSM command with no command parameters specified.

### Parameter in IEASYSxx (or supplied by the operator)

None.

### Syntax format of IVTPRM00

```
FIXED MAX(maxfix)
ECSA MAX(maxecsa)
HVCOMM MAX(maxhvcmm)
POOL(bufsize,bufsource,initbuf,minfree,expbuf)
```

**Restriction:** FIXED MAX, ECSA MAX, HVCOMM MAX, and POOL must begin in column 1.

Use one of the following rules for comments:

- A comment statement is indicated by placing an asterisk (\*) in column 1.
- A comment can be added by placing one or more blanks after the parameter on the statement.

### Syntax rules for IVTPRM00

System symbols can be used. For more information, see the section on using MVS system symbols in [z/OS Communications Server: SNA Network Implementation Guide](#).

### IBM-supplied defaults for IVTPRM00

The IBM-supplied defaults for the CSM ECSA and data space buffer pools are as follows.

| bufsize | 4 K | 16 K | 32 K | 60 K | 180 K |
|---------|-----|------|------|------|-------|
| initbuf | 64  | 32   | 16   | 16   | 2     |
| minfree | 8   | 4    | 2    | 2    | 1     |
| expbuf  | 16  | 8    | 4    | 4    | 2     |

The IBM-supplied defaults for the CSM HVCOMM buffer pools are as follows.

| bufsize | 4 K | 16 K | 32 K | 60 K | 180 K |
|---------|-----|------|------|------|-------|
| initbuf | 256 | 64   | 32   | 17   | 5     |
| minfree | 32  | 8    | 4    | 4    | 2     |
| expbuf  | 256 | 64   | 32   | 17   | 5     |

## Statements and parameters for IVTPRM00

---

### **ECSA MAX**

Defines the maximum amount of storage that is dedicated to ECSA CSM buffers.

#### **maxecsa**

A decimal integer that specifies the maximum bytes of ECSA storage that is dedicated to CSM use.

**Value range:** 1024 K to 2048 M

**Default:** The default value is 100 M

#### **Notes:**

1. K indicates kilobytes; M indicates megabytes.
2. You must code only one blank between the keywords ECSA and MAX. If more than one blank appears between these keywords, the system ignores the statement as a comment and no syntax error message is generated. In this case, the system uses the default value of 100 M.
3. The ECSA MAX statement must be completed on one line.
4. Do not code blanks between the keyword MAX and (.

### **FIXED MAX**

Defines the maximum amount of storage that is dedicated to fixed CSM buffers.

#### **maxfix**

A decimal integer that specifies the maximum bytes of fixed storage that is dedicated to CSM use.

**Value:** The value range is 1024 K to 30720 M.

**Default:** The default is 512 M.

#### **Notes:**

1. K indicates kilobytes; M indicates megabytes.
2. You must code only one blank between the keywords FIXED and MAX. If more than one blank appears between these keywords, the system ignores the statement as a comment and no syntax error message is generated. In this case, the system uses the default value of 100 M.
3. The FIXED MAX statement must be completed on one line.
4. Do not code blanks between the keyword MAX and (.
5. You might want to specify a higher value for the FIXED MAX parameter if you are using a very high amount of HVCOMM storage buffers.

### **HVCOMM MAX**

Defines the maximum amount of storage that is dedicated to High Virtual Common storage (Common storage above the bar) CSM buffers.

#### **maxhvcomm**

A decimal integer specifying the maximum bytes of High Virtual Common storage that is dedicated to CSM use.

**Value range:** 100 M to 999999 M

**Default value:** 2000 M

#### **Notes:**

- M indicates megabytes.
- Code only one blank between the keywords HVCOMM and MAX. If more than one blank appears between these keywords, the system ignores the statement as a comment and no syntax error message is generated. In this case, the system uses the default value of 2000 M.
- The HVCOMM MAX statement must be completed in one line.
- Do not code blanks between the keyword MAX and (.



**POOL**

One POOL definition can be specified for each CSM buffer pool of a particular *bufsize* and *bufsource* combination.

**bufsize**

The size of the buffers in the pool to be created.

**Value range:** 4 K, 16 K, 32 K, 60 K, 180 K

**Default:** None. A valid range value is required.

**bufsource**

The storage source from which buffers are allocated. The values are as follows:

**DSPACE**

Buffers are allocated from data space storage.

**ECSA**

Buffers are allocated from ECSA storage.

**HVCOMM**

Buffers are allocated from High Virtual Common storage (common storage above the bar).

**expbuf**

The number of free buffers by which the pool is expanded when the free buffers fall below the *minfree* value.

**Value range:** For ECSA and Data Space pools:

| Bufsize | Expbuf range |
|---------|--------------|
| 4K      | 1 - 256      |
| 16K     | 1 - 256      |
| 32K     | 1 - 128      |
| 60K     | 1 - 68       |
| 180K    | 1 - 22       |

For HVCOMM pools:

| Bufsize | Expbuf range |
|---------|--------------|
| 4K      | 1 - 1024     |
| 16K     | 1 - 512      |
| 32K     | 1 - 256      |
| 60K     | 1 - 136      |
| 180K    | 1 - 45       |

**Note:** CSM expands the HVCOMM buffer pool on a megabyte boundary. The above number is rounded to the number of buffers on the next megabyte of storage.

**Default:** None.

The IBM-supplied defaults for *expbuf* for all buffer pools are as follows:

| bufsize | 4 K | 16 K | 32 K | 60 K | 180 K |
|---------|-----|------|------|------|-------|
| ECSA    | 16  | 8    | 4    | 4    | 2     |
| DSPACE  | 16  | 8    | 4    | 4    | 2     |
| HVCOMM  | 256 | 64   | 32   | 17   | 5     |

**initbuf**

The initial number of buffers that are created in the pool when the first IVTCSM REQUEST=CREATE\_POOL macro is issued by an application. If zero is specified, only the base pool structure is created and the pool is expanded on the first IVTSCSM REQUEST=GET\_BUFFER based on the *expbuf* specification. The pool is not reduced below the level specified by either *initbuf* or *expbuf*, whichever is higher.

**Value range:** 0 - 9999

**Default value:** The IBM-supplied default value is used unless it is overridden by a CREATE\_POOL request.

**minfree**

The minimum number of free buffers that are allowed in the pool at any time. The storage pool is expanded the value that is specified in *expbuf* if the number of free buffers falls below this limit.

**Value range:** 0 - 9999

**Default:** The IBM-supplied default value is used unless it is overridden by a CREATE\_POOL request.

## Chapter 70. IXGCNFxx (system logger initialization parameters)

IXGCNFxx contains statements that can be used to control the following functions when z/OS system logger starts or is restarted on the initializing system within the sysplex.

1. Identify the tracing options when system logger initialized.
2. Specify the logger monitoring intervals for warning and action messages.
3. Specify the logger resource management policies on a system.
4. Specify the ZAI parameters for the z/OS IBM zAware log stream client socket communication and log data buffering details in order to send log stream data to the IBM zAware server.

### Specifying the IXGCNFxx members

The installation can optionally create one or more IXGCNFxx members and place them in SYS1.PARMLIB. The following methods can be used to specify the current IXGCNFxx members:

1. The operator can enter the SET IXGCNF=xx command at any time after IPL.
2. You can specify the IXGCNF=xx parameter in the IEASYSxx parmlib member during IPL, and then select IEASYSxx in the LOADxx parmlib member or specify SYSP=xx in response to the SPECIFY SYSTEM PARAMETERS system message.
3. You can specify IXGCNF=xx in response to the SPECIFY SYSTEM PARAMETERS system message.

You can specify one or more current IXGCNFxx parmlib members during IPL. For example, a IXGCNF=(00,01) system parameter informs the system to use IXGCNF00 and IXGCNF01 as current members. The system processes these members in the order they are specified. For all options, the last parmlib member specifying the option is honored.

If any errors are encountered for the specified IXGCNFxx parmlib members, logger will issue an error message and then attempt to process remaining parameters for syntax. For a SET IXGCNF command, parameter updates are not done. At IPL, default values are substituted for all parameters. For example, assume a shared IXGCNFxx parmlib includes the MONITOR LSPRIMARY,CONSUMPTIONALERT(*value*) specification. Also assume one release is at z/OS V1R13 and the other is at z/OS V2R1. The shared IXGCNFxx parmlib member will be honored on the z/OS V2R1 release. However, the z/OS V1R13 release processing will issue an unrecognized keyword type error message, and use the system defaults for all the IXGCNFxx options.

As part of the IXGCNF parmlib processing, logger might issue a TRACE CT or a DISPLAY LOGGER command. For information about required SAF authority, see the topic on defining authorization for the system logger address space in [z/OS MVS Setting Up a Sysplex](#).

Before changing options with SET IXGCNF=xx, consider issuing a D LOGGER,IXGCNF command to see what options are currently in affect. Combine the displayed options with any new request that shares the same option statement. Note, the SETLOGR system command can also be used to make changes to the system logger (IXGLOGR) address space processing, and can be used to dynamically change some of the options provided in parmlib.

The following restrictions apply to the IXGCNFxx parmlib parameters when attempted to be updated as part of the SET IXGCNF=xx command processing.

1. ZAI SERVER, PORT, and TPNAME changes are not honored if there are existing socket connections to the IBM zAware server. Disconnect the applicable log streams or quiesce any existing socket connection through the SETLOGR FORCE,ZAIQUIESCE command (use the ALL keyword or LSN= for each applicable log stream).

2. Reducing the LOGBUFMAX value below the current in-use storage buffers will cause system logger to put the LOGBUFFULL specification into effect.

## Related members in parmlib

1. COUPLExx as z/OS system logger requires at least a base sysplex configuration in order to function.
2. CTILOG00 for information pertaining to system logger CTRACE options (see Ctncccxx). Also see SYSLOGR component trace in *z/OS MVS Diagnosis: Tools and Service Aids*.

## Parameter in IEASYSxx (or supplied by the operator)

```
IXGCNF={aa
        {aa,bb...}}
```

This parameter identifies the IXGCNFxx parmlib member(s) to be used when system logger starts or is restarted on the initializing system within the sysplex. Syntax IXGCNF=aa specifies a single member and syntax IXGCNF=(aa,bb,...) identifies groups of system logger initialization statements across several IXGCNFxx members. The installation can optionally create one or more members and place them in SYS1.PARMLIB. When multiple IXGCNFxx members are concatenated, the individual system logger options are merged with the last parmlib member option taking precedence.

## Syntax rules for IXGCNFxx

The following syntax rules apply to IXGCNFxx:

1. Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
2. Comments may appear in columns 1-71 and must begin with "/" and end with "/". A comment can span lines and can appear anywhere except within a keyword or a specified value.
3. Blank lines are allowed anywhere in the member.
4. You can use both uppercase and lowercase letters; the system translates lowercase letters to uppercase letters before processing.
5. The system recognizes the end of a statement when it encounters either the beginning of the next valid statement or an end-of-file (EOF) indicator.
6. Use valid delimiters to separate keyword parameters. A valid delimiter is a blank. The system treats multiple blanks as one.
7. Blanks can appear between keyword parameters, between values, and between statements. Blanks cannot appear within a keyword value.
8. Delimiters are required between keywords.
9. If the system finds a syntax error in IXGCNFxx, the system issues an error message, and then attempts to continue processing the next keywords, statements, and parmlib members, for syntax only. No updates take place on error.

## IBM-supplied defaults for IXGCNFxx

There is no default IXGCNFxx parmlib member. SYS1.SAMPLIB provides a sample parmlib member IXGCNFXX.

## Syntax format of IXGCNFxx

```
[
CTRACE(parmlib_member_name)
MONITOR
OFFLOAD
    WARNALLOC(initial-delay-interval)
    ACTIONALLOC(secondary-delay-interval)
    WARNRECALL(initial-delay-interval)
    ACTIONRECALL(secondary-delay-interval)
LSPRIMARY
    CONSUMPTIONALERT(ALLOW | SUPPRESS)
MANAGE
OFFLOAD
    ALLOCAHEAD(YES | NO)
    USEOFFLOADADMIN(YES | NO)
    KEEPLOCALBUFFERS(NO | YES)
    LOCALBUFFERLIMIT(NO | YES)
STAGING
    USESTAGINGMIN(YES | NO)

LOGRCDS
    ALLOWACCESS(YES | NO)

HYPERWRITE
    ALLOWUSE(YES | NO)

. . .
ZAI
SERVER(NONE | host_name | IP_addr)
PORT(port_num)
TPNAME(NONE | transport_name)
LOGBUFMAX(value)
LOGBUFWARN(nn)
LOGBUFFULL(MSG | QUIESCE)
]
```

## Statements and parameters for IXGCNFxx

**CTRACE(*parmlib\_member\_name*)**

Specifies the member of SYS1.PARMLIB that contains the tracing options to be used when the z/OS system logger component is initialized (IXGLOGR address space starts) or when a SET IXGCNF command is entered. You can specify a CTnLOGxx parmlib member name.

This statement provides initial tracing options while system logger is starting and as an alternative approach to issuing a CTRACE command to specify tracing options other than those in default member CTILOG00. For information about coding the component trace member of SYS1.PARMLIB, see Chapter 26, “CTnccccx (component trace parameters),” on page 249.

Logger converts the input to a TRACE CT,ON,COMP=SYSLOGR,PARM=CTnLOGxx command. Look at the syslog for IEE538I or other error messages to verify the options that are specified in the *parmlib\_member\_name* are accepted. You can verify the logger tracing options in effect by using the D TRACE,COMP=SYSLOGR command.

For more information about viewing (D TRACE) the current system logger trace settings and specifying new options for the system logger (SYSLOGR) component trace, see [z/OS MVS System Commands](#) and [z/OS MVS Diagnosis: Tools and Service Aids](#), respectively.

**Value range:** The value range is the 8-character member name in the format CTnLOGxx where:

$$n$$

An alphanumeric character to specify the source of the member. IBM-supplied members use I.

**XX**

Any two characters.

**Default:** CTILOGOO

## MONITOR

Provides system logger monitoring specifications.

**OFFLOAD**

Specifies the initial and secondary delay intervals for monitoring system logger log stream offload activity. See [Offload and service task monitoring in z/OS MVS Setting Up a Sysplex](#) for more information about the logger offload monitoring.

**ACTIONALLOC(secondary-delay-interval)**

Specifies the amount of time, in seconds, allowed before the log stream offload monitor issues messages to allow possible action to be taken by the installation because of an offload being delayed waiting for a data set allocation or deletion request to complete.

If the data set allocation or deletion request does not complete within this interval, system logger issues messages IXG311I identifying the log stream and data set resources, and logger also issues WTOR message IXG312E to allow action to be taken if necessary.

D LOGGER,IXGCNF[,MONITOR] displays system logger monitoring settings

**Value range:** A decimal number 5 - 86400 seconds (meaning 5 seconds to 24 hours, respectively).

**Default:** 60 (60 seconds, 1 minute)

**ACTIONRECALL(secondary-delay-interval)**

Specifies the amount of time, in seconds, allowed before the log stream offload monitor issues messages to allow possible action to be taken by the installation because of an offload being delayed waiting for a migrated data set recall request to complete.

If the migrated data set recall request does not complete within this interval, system logger issues messages IXG311I identifying the log stream and data set resources, and logger also issues WTOR message IXG312E to allow action to be taken if necessary.

D LOGGER,IXGCNF[,MONITOR] displays system logger monitoring settings.

**Value range:** A decimal number from 5 to 86400 seconds (meaning 5 seconds to 24 hours, respectively)

**Default:** 120 (120 seconds, 2 minutes)

**CONSUMPTIONALERT(ALLOW | SUPPRESS)**

Specifies whether log streams defined with WARNPRIMARY(YES) issue log stream primary storage consumption alert messages on this system when the imminent threshold is exceeded or an entry threshold occurs, or for any log stream when a primary storage full consumption point is reached.

**ALLOW**

Issues the primary storage consumption and offload messages if the log stream is defined with the correct parameters.

**SUPPRESS**

Suppresses any alerts or messages, regardless of the log stream definition.

See [z/OS MVS Setting Up a Sysplex](#).

**Note:** Display LOGGER,IXGCNF[,MONITOR] system logger monitoring settings

**Default:** ALLOW

**LSPRIMARY**

Specify the log stream primary (interim) storage monitoring.

**WARNALLOC(initial-delay-interval)**

Specifies the amount of time, in seconds, allowed before the log stream offload monitor starts issuing a warning message indicating that an offload is delayed waiting for a data set allocation or deletion request to complete.

If the data set allocation or deletion request does not complete within this interval, system logger issues message IXG310I to warn the operator of the log stream offload being delayed. If this value is not less than the ACTIONALLOC secondary-delay-interval, then logger will not issue the IXG310I warning message as part of its log stream offload monitoring.

D LOGGER,IXGCNF[,MONITOR] displays system logger monitoring settings.

**Value range:** A decimal number 5 - 86400 seconds (meaning 5 seconds to 24 hours, respectively).

**Default:** 30 (30 seconds, 1/2 minute)

#### **WARNRECALL(initial-delay-interval)**

Specifies the amount of time, in seconds, allowed before the log stream offload monitor starts issuing a warning message. The message indicates that an offload is delayed waiting for a migrated data set recall request to complete.

If the migrated data set recall request does not complete within this interval, system logger issues message IXG310I to warn the operator of the log stream offload being delayed.

If this value is not less than the ACTIONRECALL secondary-delay-interval, then logger will not issue the IXG310I warning message as part of its log stream offload monitoring.

D LOGGER,IXGCNF[,MONITOR] displays system logger monitoring settings.

**Value range:** A decimal number from 5 to 86400 seconds (meaning 5 seconds to 24 hours, respectively).

**Default:** 60 (60 seconds, 1 minute)

### **MANAGE**

Provides the resource management policy for system logger.

#### **OFFLOAD**

Specifies the system logger policy on the system for managing log stream offload activity. See the section on offloading log data from interim storage by freeing or moving it to DASD in [z/OS MVS Setting Up a Sysplex](#) for more information about logger offload processing.

#### **ALLOCACHEAD(YES | NO)**

Specifies whether the system will proactively manage advanced-current offload data sets for log streams that are defined with a LS\_ALLOCACHEAD= value that is greater than zero. See the section on offloading log data from interim storage by freeing or moving it to DASD in [z/OS MVS Setting Up a Sysplex](#) for more information about logger behavior based on the ALLOCACHEAD and LS\_ALLOCACHEAD parameters.

##### **YES**

Indicates that the system will proactively manage advanced-current offload data sets for particular log streams in order to keep the log streams more readily available. Such log streams are defined with a LS\_ALLOCACHEAD= value that is greater than zero and are connected on the system.

##### **NO**

Indicates that the system will not proactively allocate and open advanced-current offload data sets for log streams that are connected on the system.

Access to any new or existing offload data sets that will move log data from the primary or interim storage to DASD is managed on the system only as needed and when requested. This means that the system will only allocate and open the actual current offload data set when it is explicitly needed for an offload activity to move log data to DASD on this system.

You can use the DISPLAY LOGGER,IXGCNF[,MANAGE] command to view the parameter settings for configuring the system logger.

**Default:** YES

#### **USEOFFLOADADMIN(YES | NO)**

Specifies whether the system ensures that log stream offload data sets are newly allocated on the system with a size of at least 1MB when the LS\_SIZE attribute is not specified for the log stream. For more information about planning for log stream offload data sets, see [Plan DASD space for system logger in z/OS MVS Setting Up a Sysplex](#).

**YES**

Indicates that the system ensures that log stream offload data sets are allocated on the system with a base minimum size of at least 1MB. If a log stream offload data set is newly allocated with a size smaller than 1MB, the logger deletes the data set and allocates a new one with a size of at least 1MB.

The message IXG256I is issued if this occurs. For more information, see *z/OS MVS System Messages, Vol 10 (IXC-IZP)*.

**NO**

Indicates that the system does not ensure the use of the 1MB offload data set size as a base minimum.

It is recommended that offload data sets are to be sized no smaller than 1MB, unless the log stream exploiter specifically recommends a size below this amount.

To view the parameter settings for configuring the system logger, use the DISPLAY LOGGER,IXGCNF[,MANAGE] command.

**Default:** YES

**KEEPLOCALBUFFERS(NO | YES)**

Specifies whether the system will request to keep the real frames backing the local buffers used as interim storage when it is freed. Keeping the real frames reduces page faults that will occur when the local buffers are reused during subsequent IXGWRITE requests.

**Note:** Local buffers are high virtual private areas associated with the system logger address space, IXGLOGR. Specifying KEEPLOCALBUFFERS(YES) may result in systems experiencing increased paging.

Evaluate your real memory requirements to ensure unacceptable paging does not occur by reviewing the amount of real memory consumed by the system logger address space, IXGLOGR.

The following options are possible:

**NO**

Indicates that the system will not keep the real frame used to back local buffers when the buffer storage is freed.

**YES**

Indicates that the system will request to keep the real frame used to back local buffers when the buffer storage is freed.

You can use the DISPLAY LOGGER,IXGCNF,MANAGE command to view the parameter settings for configuring the system logger.

**Default:** NO

**LOCALBUFFERLIMIT(NO | YES)**

Specifies whether the system will initiate offloads before local buffers become full.

This setting should be used only after all tuning options are exhausted, as it increases the number of offloads across all log streams connected on the system where it is enabled and supersede normal offload processing triggers. For CF structure log streams, it may also drive offload processing and local buffer cleanup processing on other systems in the sysplex.

It can be used as a temporary circumvention until a configuration tuning change is implemented, as the setting can be enabled and disabled dynamically using just the SETLOGR system command.

The following options are possible:

**NO**

Indicates that the system will not initiate offloads before local buffers become full. Events that typically trigger offloads will continue to occur.



**YES**

Indicates that the system will initiate offloads before local buffers become full.

You can use the DISPLAY LOGGER,IXGCF,MANAGE command to view the parameter settings for configuring the System Logger.

**Default:** NO

**STAGING**

Specifies the system logger policy on the system for managing log stream staging data sets.

**USESTAGINGMIN(YES | NO)**

Specifies whether the system ensures that log stream staging data sets are newly allocated on the system with a size of at least 10MB when the STG\_SIZE attribute is not specified for the log stream. For more information about planning for staging data set use, see [Plan space for staging data sets in z/OS MVS Setting Up a Sysplex](#).

**YES**

Indicates that the system ensures that log stream staging data sets are allocated on the system with a base minimum size of at least 10MB. If a log stream staging data set is newly allocated with a size smaller than 10MB, the logger deletes the data set and allocates a new one with a size of at least 10MB.

The message IXG256I is issued if this occurs. For more information, see [z/OS MVS System Messages, Vol 10 \(IXC-IZP\)](#).

**NO**

Indicates that the system does not ensure the use of the 10MB staging data set size as a base minimum.

It is recommended that staging data sets are to be sized no smaller than 10MB, unless the log stream exploiter specifically recommends a size below this amount.

To view the parameter settings for configuring the system logger, use the DISPLAY LOGGER,IXGCF[,MANAGE] command.

**Default:** YES

**HYPERWRITE**

Specifies the system logger policy on the system for IBM zHyperWrite data replication use for log stream data sets.

**ALLOWUSE(YES|NO)****YES**

Indicates that use of IBM zHyperWrite data replication is allowed as system logger writes to certain log stream data sets on the particular system as follows:

- staging data sets for DASDONLY type log streams,
- offload data sets for both the DASDONLY type only and Coupling Facility structure-based type log streams.

**Note:** System Logger does not support IBM zHyperWrite data replication for staging data sets for Coupling Facility structure-based type log streams.

Refer to the [“HYPERWRITE” on page 497 specification in Chapter 57, “IECIOSxx \(I/O related parameters\),” on page 483](#) for details, requirements, and enablement related to the IBM zHyperWrite data replication.

**NO**

Indicates that use of IBM zHyperWrite data replication is not allowed for any system logger log stream data sets on the particular system with this specification.

**Default:** NO

**LOGRCDS**

Specifies the system logger policy on the system that manages access to the sysplex scope LOGR couple data set (CDS). See "Prevent a z/OS image from accessing LOGR couple data sets" in [z/OS MVS Setting Up a Sysplex](#) for more information about LOGR CDS management.

**ALLOWACCESS(YES | NO)**

Specifies whether the particular system will make use of the sysplex scope LOGR couple data sets when they are presented to system logger by the Cross-system Coupling Facility (XCF) component. System logger requires the use of at least a primary couple data set to perform its operations. However, some z/OS images within the sysplex should not have any access to these couple data sets. See the allowable couple data set (CDS) data types for system logger's use under the USECDSTYPE option.

**YES**

Indicates that system logger should not inhibit attempts to make use of the sysplex scope LOGR couple data sets when they are presented by XCF on the z/OS image.

**NO**

Indicates that system logger will not attempt to make use of the sysplex scope LOGR couple data sets that are presented by XCF on the z/OS image. Because system logger requires the use of one or more couple data sets to perform its operations, do not specify this option unless it is clearly understood and intended. See "Prevent a z/OS image from accessing LOGR couple data sets" in [z/OS MVS Setting Up a Sysplex](#) before using this option.

**Warning:**

Do not use the MANAGE LOGRCDS ALLOWACCESS(NO) specification in a shared IXGCNFxx member among multiple z/OS images unless explicitly intended.

Using the NO option will result in XCF error messages such as IXC255I when LOGR CDSs are processed within the sysplex, for example when restarting a system or when processing subsequent SETXCF COUPLE,TYPE=LOGR,... commands.

The following list of restrictions apply to specifying the NO option:

- The NO option is not allowed on the SET IXGCNF and SETLOGR MANAGE commands.
- The NO option is not allowed when the IXGLOGR address space is restarted and the original system restart option defaulted to YES or was specified as YES.
- If the original system restart option was specified as NO and then changed through a command to YES, and if the IXGLOGR address space is later restarted, then the YES specification remains in effect.
- If the USECDSTYPE keyword is specified with an option other than LOGR, then specifying ALLOWACCESS(NO) during the IPL cannot be changed to YES on SET IXGCNF and SETLOGR MANAGE commands or if the IXGLOGR address space is later restarted.

You can use the DISPLAY LOGGER,IXGCNF[,MANAGE] command to view the system logger configuration parameter settings.

**Default:** YES

**USECDSTYPE(LOGR | LOGRY | LOGRZ)**

Specifies the couple data set data type to be used by system logger on the z/OS image. The default CDS data type is LOGR, which refers to the sysplex scope primary and alternate couple data sets.

When either LOGRZ or LOGRY is specified, then system logger will make use of the single-system scope primary and alternate couple data sets of that specified CDS data type.

These two options can only be specified when ALLOWACCESS(NO) is specified. For these specifications, system logger will not attempt to make use of the sysplex scope LOGR couple data sets, however, system logger services will be available on that single-system with an isolated system view within the sysplex.

For more information about the system logger management of these unique single-system scope CDS types, see [Using LOGRZ or LOGRY couple data sets for a single system scope within a sysplex in z/OS MVS Setting Up a Sysplex](#). Only one z/OS in a sysplex may make use of CDS datatype LOGRx at one time.

### **LOGR**

Indicates that system logger, on the z/OS image using this SYS1.PARMLIB IXGCNFxx member, will make use of the sysplex scope couple data sets for CDS data type LOGR, unless ALLOWACCESS(NO) is specified.

### **LOGRY**

Can only be specified with ALLOWACCESS(NO). Indicates that system logger, on the z/OS image using this SYS1.PARMLIB IXGCNFxx member, will make use of the single scope couple data sets for CDS data type LOGRY.

### **LOGRZ**

Can only be specified with ALLOWACCESS(NO). Indicates that system logger, on the z/OS image using this SYS1.PARMLIB IXGCNFxx member, will make use of the single scope couple data sets for CDS data type LOGRZ.

The following list of restrictions apply to specifying the USECDSTYPE option:

- If LOGRY or LOGRZ is specified for USECDSTYPE along with ALLOWACCESS(YES), then error message IXG734I will be issued indicating the inconsistent specifications. Parmlib processing will continue, and system logger will use the sysplex scope LOGR CDS type on this system.
- The USECDSTYPE option is not allowed to be changed on SET IXGCNF and SETLOGR MANAGE commands or if the IXGLOGR address space is later restarted. If a change is intended, then a re-IPL of the system is needed using the new options.

You can use the DISPLAY LOGGER,IXGCNF[,MANAGE] command to view the system logger configuration parameter settings.

**Default:** LOGR

## **ZAI**

Specify the definitions for the z/OS IBM zAware log stream client socket communication and log data buffering details in order to send log stream data to the IBM zAware server.

By default, no communication with the IBM zAware server will occur unless it is explicitly requested and the z/OS IBM zAware log stream client requirements are established.

See [Preparing for z/OS IBM zAware log stream client usage in z/OS MVS Setting Up a Sysplex](#) for more details on establishing and using z/OS IBM zAware log stream clients.

### **LOGBUFMAX(value)**

Identifies the maximum number of storage buffers (in gigabytes) to be used by system logger for managing z/OS IBM zAware log stream client data being sent to the IBM zAware server. Allows clients ability to set a threshold (for their environment) on the amount of (pageable, above the 2 GB bar) storage that could be utilized on their z/OS system in the case of spiking or inhibited data flow to the IBM zAware server.

If the maximum for these storage buffers are used, then any new log stream data needing to be sent to the IBM zAware server is lost. See LOGBUFFULL specification on how system logger handles the z/OS IBM zAware log stream client data when a storage buffer full condition occurs.

D LOGGER,IXGCNF[,ZAI] and D LOGGER,STatus,ZAI commands display the details on the system logger z/OS IBM zAware log stream client buffer usage.

**Value range:** 1-99 (in gigabytes)

**Default:** 2 (2 GB)

### **LOGBUFWARN(nn)**

Specifies the z/OS IBM zAware log stream client manager buffer warning level percentage when system logger starts issuing message IXG375E.

When the z/OS IBM zAware log stream client manager is using this percent of overall buffer space (see LOGBUFMAX), message IXG375E is issued. As the buffer pool is expanded/extended by the next incremental amount, system logger issues an updated instance of IXG375E with the new buffer storage percent in use indication. As in-use system logger z/OS IBM zAware log stream client buffers are no longer needed. The buffers are released, and message IXG375E is issued for the new percent in use.

When the overall percentage of buffers in use is at least 5% below the LOGBUFWARN value, system logger will DOM message IXG375E.

D LOGGER,IXGCNF[,ZAI] and D LOGGER,STatus,ZAI commands display the details on the system logger z/OS IBM zAware log stream client buffer usage.

**Value range:** 10-90 (10% to 90%)

**Default:** 75 (75% of LOGBUFMAX value)

### **LOGBUFFULL({MSG | QUIESCE})**

Specifies the action to be taken by system logger when the z/OS IBM zAware log stream client manager buffers become full (see LOGBUFMAX).

MSG indicates that system logger should continue attempting to send log data to the IBM zAware server and keep a count of the number of log blocks that could not be buffered and were lost. When buffers become available, then message IXG383I is issued. It indicates that not all the log data was sent to the IBM zAware server.

QUIESCE indicates that when system logger reaches the full amount of buffers then disconnect the socket connection to the IBM zAware server. The socket connection remains disconnected until either a SETLOGR command (for example, SETLOGR FORCE,ZAICONNECT,ALL) or SET IXGCNF command that has specifications to connect to the IBM zAware server. No z/OS IBM zAware log stream client data is maintained while in the quiesced state, meaning the buffers holding the log data for this purpose is released (freed). Logger issues message IXG382I for each log stream that is quiesced.

D LOGGER,IXGCNF[,ZAI] and D LOGGER,STatus,ZAI commands display the details on the system logger z/OS IBM zAware log stream client buffer usage.

**Default:** MSG

### **PORT(port\_num)**

Identifies the port number that is associated with the SERVER specification for the IBM zAware server, as shown in the following examples:

- PORT(3801)
- PORT(10120)

D LOGGER,IXGCNF[,ZAI] and D LOGGER,STatus,ZAI commands display the details on the system logger z/OS IBM zAware log stream client information.

**Value range:** 1 - 65535 (up to 5 digits)

**Default:** 2001

### **SERVER({NONE | host\_name | IP\_addr})**

Specifies the host name (as defined by domain name system, DNS) or TCP/IP location where the z/OS IBM zAware server is running and will receive the z/OS IBM zAware log stream client data.

#### **NONE**

Indicates no IBM zAware server is desired and does not indicate a server name. Therefore, no z/OS IBM zAware log stream client is to be established by system logger.

#### **host\_name**

Specifies the canonical host name, as defined by DNS, where the IBM zAware server is located:

- Consist of alphabetic letters (A-Z), numeric digits (0-9), hyphens(-), and periods (.),

- Consist of 1 to multiple sections (labels) of 1-63 characters that are separated by a period (.),
- Alphabetic characters are case insensitive,
- Each section must start and end with either an alphabetic character (A-Z) or numeric digit (0-9). For example: WWW.IBM.COM

**Note:** The DNS server does not need to be up and running when the IXGCFxx parmlib member is processed as the *host\_name* and is resolved when the z/OS IBM zAware log stream client needs to make a connection to the IBM zAware server.)

### ***IP\_addr***

Specifies an IP address for the IBM zAware server location. Can be either IPv4 or IPv6 address format.

The IPv4\_address must be specified as a dotted decimal quad: *ddd.ddd.ddd.ddd* format.

- It must have three dots (.) and the rest of the characters must be decimal numbers (0-9),
- It must consist of four sections of 1-3 decimal digits that are separated by dots (.),
- The decimal digits must represent numbers 0 - 255.
- The leading (non-significant) zeros for each number can either be specified or suppressed.
- The minimum length is 7 characters, and the maximum length is 15 characters.

For example: 192.0.2.255

The IPv6\_address must be specified with colons as delimiters.

- It must have 2 - 7 colons (:) and contain hexadecimal numbers (0-9, A-F, a-f),
- It must consist of up to 8 sections of 0-4 hexadecimal numbers that are separated by a colon (:).
- Leading (non-significant) zeros for each number can either be specified or suppressed.
- When all 8 sections are not specified, then zero compression via double colons must be used and can only appear once to designate the zero compression range.
- The IP address cannot start or end with a colon unless part of a double-colon (zero compression range).
- The section that is specified before a double colon (zero compression range) correspond to left-aligned sections 1 through nth specified section. Sections that are specified after the double colon correspond to right-aligned sections 8 down to number of sections after the double colon.
- The minimum length is 2 characters, maximum length is 39 characters.

For example:

#### **SERVER(2001:db8:85a3::8a2e:370:7334)**

Has three sections before and three sections after the double colon, so it would yield 16 byte (4-word) value of 20010DB8 85A30000 00008A2E 03707334.

#### **SERVER(2001:db8:85a3::8a2e:370)**

Has three sections before and two sections after the double colon, so it would yield 16 byte (4-word) value of 20010DB8 85A30000 00000000 8A2E0370.

**Note:** When you specify an IPv6\_address, all the routers in the path of the socket connection between the z/OS IBM zAware client and IBM zAware server must also support IPv6 format addresses. Otherwise the socket connection might fail when attempted.

When a value other than NONE is provided, the z/OS system logger component establishes a socket connection for communication with the IBM zAware server on behalf of a z/OS IBM zAware log stream client. By default, no communication with the IBM zAware server occurs unless it is explicitly requested and the z/OS IBM zAware log stream client requirements are established.

D LOGGER,IXGCNF[,ZAI] and D LOGGER,STatus,ZAI commands display the details on the system logger z/OS IBM zAware log stream client information.

**Value range:** Up to 64 characters, consisting of alphabetic characters (A-Z), numeric digits (0-9), periods (.), colons (:), and hyphens (-).

- Considered an IPv6 address if there are colons (:).
- Considered and IPv4 address if there are numeric digits (0-9) and periods(.), but no alphabetic characters (A-Z) or hyphens(-).
- Otherwise is considered a host\_name, unless NONE meaning no IBM zAware server.

**Default:**

#### **TPNAME(NONE | *transport\_name*)**

An optional parameter that specifies whether a transport provider name will be used by system logger to set the transport affinity, also called TCP/IP stack affinity, meaning that sockets are restricted to only one transport provider for communications from the IBM zAware log stream client to the IBM zAware server.

When the value NONE is specified for the TPNAME parameter, no affinity to a specific transport provider will be used for establishing the sockets.

When specified, the *transport\_name* value must match a transport provider specified on the NAME parameter for a SUBFILESYSTYPE statement in BPXPRMxx or specified with the SETOMVS command. Note that the transport provider name in this context refers to the TCP/IP address space name, which provides the functions also referred to as the TCP/IP stack. See [Chapter 13, “BPXPRMxx \(z/OS UNIX System Services parameters\),” on page 123](#) and *z/OS UNIX System Services Planning* for details about transport providers.

The D LOGGER,IXGCNF,ZAI and D LOGGER,STatus,ZAI commands display the details about the system logger IBM zAware log stream client information.

**Value range:** Up to 8 alphanumeric or national (\$, #, @) characters with the first character non-numeric; the system converts any lowercase alphabetic characters to uppercase.

**Default:** NONE

## Examples of IXGCNFxx member

The following example shows a IXGCNFxx parmlib member that requests that up to one z/OS IBM zAware log stream client can be established (for example, for SYSPLEX.OPERLOG) to communicate with a IBM zAware server at host domain name system "plpsc.pok.ibm.com" via port # 10120. System logger will manage up to 1 gigabytes as the log stream data buffering limit with warning messages to occur when 80% in use and to issue a different message if all the log data buffers become full.

```
ZAI      SERVER(plpsc.pok.ibm.com) PORT(10120)
         LOGBUFMAX(1) LOGBUFWARN(80) LOGBUFFULL(MSG)
```

---

## Chapter 71. IZUPRMxx (configure IBM z/OS Management Facility)

You do not have to create an IZUPRMxx parmlib member to get IBM z/OS Management Facility (z/OSMF) up and running. Instead, you might find that the z/OSMF configuration defaults are sufficient for your environment. If so, use the defaults for a quick-start experience with z/OSMF. If your z/OSMF set-up requires customization, you can provide a customized member, IZUPRMxx, with installation-specific values for your configuration.

For more information about the IZUPRMxx parmlib member, including syntax and parameters, see [\*IBM z/OS Management Facility Configuration Guide\*](#).





## Chapter 72. LNKLSTxx (LNKLST concatenation)

Use the LNKLSTxx member of parmlib to specify the program libraries that are to be concatenated to SYS1.LINKLIB to form the LNKLST concatenation. In addition to the data sets you specify in LNKLSTxx, the system automatically concatenates data sets SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE and SYS1.SIEAMIGE to SYS1.LINKLIB. You can create any number of LNKLSTxx members.

### Using PROGxx to define LNKLST concatenations

Instead of using LNKLSTxx to specify the LNKLST concatenation, consider using PROGxx.

If you specify both PROG=xx for a member with a LNKLST ACTIVATE statement and LNK=xx, the system ignores LNK=xx at IPL and issues message CSV487I LNK IPL PARAMETER HAS BEEN IGNORED. LNKLST SET *lnklstname* IS BEING USED. The LNKLST set refers to the data sets that are defined to the LNKLST concatenation through LNKLST statements in PROGxx. See [“Using the LNKLST statement” on page 688](#).

### Using LNKLSTxx

If you use LNKLSTxx instead of PROGxx, during IPL, the system opens and concatenates each data set in the order it was listed, starting with the first-specified LNKLSTxx member. The system creates a data extent block (DEB) that describes the data sets concatenated to SYS1.LINKLIB and their extents. The extents remain in effect for the duration of the IPL.

After this processing completes, library lookaside (LLA) is started. LLA manages the LNKLST data sets and can be used to control updates to them. For more information about SYS1.LINKLIB and other data set concatenations, see:

- [“Concatenating data sets to the LNKLST concatenation” on page 690](#)
- [“APF authorization for LNKLST data sets” on page 691](#)
- [“Cataloging LNKLST data sets” on page 691](#)
- [“Modifying the contents of LNKLST data sets” on page 691](#).

There are LNKLST considerations that pertain to the use of the IEFOPZxx parmlib member, described in Chapter 58, [“IEFOPZxx \(data set optimization configuration\),” on page 507](#).

### Parameter in IEASYSxx (or supplied by the operator)

```
LNK={aa
    {aa,bb,...[,L]}
    [,L]}
```

The two characters (A-Z, 0-9, @, #, or \$), represented by aa (or bb, and so forth.), are appended to LNKLST to identify one or more LNKLSTxx members of parmlib.

If the L option is specified, the names of the data sets that are concatenated to SYS1.LINKLIB are displayed at the operator's console as the data sets are opened. The list is preceded by message: IEA331I LINK LIBRARY CONCATENATION SYS1.LINKLIB

### Syntax rules for LNKLSTxx

The following rules apply to the creation of LNKLSTxx:

- On each record, use commas to separate the names of data sets.

- To indicate that a record is to be continued, place a comma followed by at least one blank after the last data set name on a record.
- If a data set is cataloged in a user catalog, but not in the system master catalog, you must also specify the volume serial (VOLSER) of the volume on which the data set resides. Specify the VOLSER in parentheses, immediately after the data set name.
- If you do not use the corresponding SYSLIB statement in PROGxx and you specify SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, or SYS1.SIEAMIGE in LNKLSTxx (perhaps to change the system's default processing), you must also specify the VOLSER of the volume on which the data set resides. Otherwise, the system ignores the specification.
- On a line, data entered after the last data set name and the optional comma continuation character is treated as a comment and ignored.
- Data records entered after the last data line are ignored as if they are comments.

## Syntax format of LNKLSTxx

```
IEASYSxx: ...,LNK=(nn,nn,nn,...)
LNKLSTxx: {data-set-name}, {data-set-name},...
           {data-set-name(volser)} {data-set-name(volser)}
```

## Syntax example of LNKLSTxx

```
IEASYSxx: ...,LNK=(00,01,02,03)
LNKLST00: SYS1.CMDLIB,SYS1.TSORTNS,SYS1.BTAMLIB,
LNKLST01: SYS1.LINKLIB,DBLUE.U30LIB(U30PAK),SYS2.U30LIB
LNKLST02: SYS1.AUXLIB,SYS1.JES3
LNKLST03: SYS1.TEST
```

As a result of these specifications, the following data sets, in the order specified, are concatenated to SYS1.LINKLIB (after SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE and SYS1.SIEAMIGE):

- SYS1.CMDLIB,SYS1.TSORTNS,SYS1.BTAMLIB,DBLUE.U30LIB,
- SYS2.U30LIB,SYS1.AUXLIB,SYS1.JES3,SYS1.TEST

In the LNKLST01 parmlib member in this example, note the following:

- The specification of SYS1.LINKLIB is ignored.
- DBLUE.U30LIB is a user-cataloged data set on VOLSER U30PAK.

## IBM-supplied default for LNKLSTxx

IBM does not supply a default LNKLSTxx member. By default, the system concatenates data sets SYS1.MIGLIB and SYS1.CSSLIB to SYS1.LINKLIB.

## IBM-supplied sample for LNKLSTxx

IBM provides a sample LNKLSTxx member in SYS1.SAMPLIB. The sample member is named LNKLST00.

## Chapter 73. LOADxx (system configuration data sets)

The LOADxx member specifies:

- Information about your I/O configuration.
- An alternate nucleus ID.
- The architecture level of the nucleus.
- The NUCLSTxx member that you use to add and delete modules from the nucleus region at IPL-time.
- Information about the master catalog.
- Information about the parmlib concatenation.
- The name of the sysplex (systems complex) that a system is participating in; it is also the substitution text for the &SYSPLEX system symbol.
- The IEASYMxx and IEASYSxx parmlib members that the system is to use.
- Additional parmlib data sets that the system will use to IPL. These data sets are concatenated ahead of SYS1.PARMLIB to make up the parmlib concatenation.
- Filtering keywords so you can use a single LOADxx member to define IPL parameters for multiple systems. The initial values of the filter keywords (HWNAME, LPARNAME and VMUSERID) are set at IPL to match the actual values of the system that is being IPLed. The LOADxx member can be segmented by these keywords.
- Facilities that are not to be used at this time because migration to another processor, z/OS release, or both is underway.

The LOADxx member is selected through the use of the LOAD parameter on the system control (SYSCTL) frame of the system console. For information about specifying the LOAD parameter, see *z/OS MVS System Commands*. If the operator does not select a LOADxx member on the system console, the system uses LOAD00.

**Note:** The system must have access to a LOADxx member.

### Placement of LOADxx

You can place the LOADxx member in one of the following system data sets:

- SYSn.IPLPARM
- SYS1.PARMLIB

Consider placing LOADxx in the SYSn.IPLPARM data set. During IPL, the system looks for LOADxx in the following order:

1. SYS0.IPLPARM through SYS9.IPLPARM on the IODF volume.
2. SYS1.PARMLIB on the IODF volume.
3. SYS1.PARMLIB on the sysres volume.

**Note:** The IODF volume must be in the same subchannel set as the IPL device.

Do not create a SYSn.IPLPARM data set unless it contains the LOADxx member that is used to configure your system. When the system finds either SYSn.IPLPARM or SYS1.PARMLIB, it expects to find a LOADxx member in the data set. The search will stop with the first SYSn.IPLPARM or SYS1.PARMLIB data set found. The system will use the LOADxx it finds within that data set as designated by the LOAD parameter. If the LOADxx member specified on the LOAD parameter is not in the data set, the system loads a wait state.

**Note:** Because the system data sets are searched in ordered sequence, use SYS0.IPLPARM for best IPL performance.

## Copying LOADxx members

To copy LOADxx members to a backup volume, use either DFDSS (for SMS-managed volumes) or IEBCOPY. To ensure that the system will associate the copied LOADxx member with the proper IODF on a SYSn.IPLPARM volume, do not specify the IODF prefix in the LOADxx member. The system then will default the prefix of the IODF data set to the prefix of the SYSn.IPLPARM data set that contains the LOADxx member.

## Filtering with LOADxx

The LOADxx filter keywords HWNAME, LPARNAME, and VMUSERID allow you to use a single LOADxx member to define IPL parameters for multiple systems. At IPL, the initial values of the keywords are set to match the actual values of the system being IPLed. The filter keywords are used to optionally change the IPL parameters.

**Note:** If a filter keyword is not applicable to a particular system, it is initialized to blanks at IPL. Subsequent specification of this filter keyword within LOADxx resets it.

The keywords control filtering in a hierarchy with HWNAME on the top and VMUSERID on the bottom. Figure 25 on page 614 shows this hierarchical relationship. The HWNAME parameter is used to specify the Control Processing Complex (CPC) name. HWNAME also sets LPARNAME and VMUSERID to their default values. The LPARNAME parameter, the next level in the hierarchy, is used to set the Logical Partition name. LPARNAME also sets VMUSERID to the default value. The value of HWNAME is unchanged. The lowest level of the hierarchy, the VMUSERID parameter, specifies the user ID of a z/VM system under which a z/OS image is running as a guest. Due to the hierarchical relationship of these keywords, the following rules apply to the specifications in your LOADxx member:

1. Keyword HWNAME is in effect from its occurrence to the next HWNAME statement in the member or to the end of the LOADxx member.
2. Keyword LPARNAME is in effect from its occurrence to the next HWNAME or LPARNAME statement or to the end of the LOADxx member.
3. Keyword VMUSERID is in effect from its occurrence to the next HWNAME, LPARNAME, or VMUSERID statement or to the end of the LOADxx member.

There is no way to explicitly indicate that you want the LPARNAME parameter or the VMUSERID parameter reset to their default values. If the system that is being IPLed is not running as LPAR mode or on VM, LPARNAME and VMUSERID might not be meaningful. This is a case when you might want to reset these values. As previously discussed, specifying the HWNAME parameter resets the LPARNAME and VMUSERID parameters to their default values. You can also reset just the VMUSERID parameter to its default value by specifying the LPARNAME parameter.

See “Filtering example” on page 615 for examples of how to set the keywords.




Figure 25. LOADxx filtering hierarchy

When another LOADxx statement (such as SYSCAT or IODF) is specified, the current HWNAME, LPARNAME, and VMUSERID filters are compared to the actual system values. If they all match, that LOADxx statement is accepted as applicable to the system that is being IPLed. See [“Statements and parameters for LOADxx”](#) on page 618 for specifics about each keyword.

## Filtering example

The following example illustrates uses of the HWNAME, VMUSERID, and LPARNAME filter parameters to segment LOADxx statements for various configurations. The contents of the LOADxx member are shown and then the IPL results are given.

```
*-----1-----2-----3-----4-----5-----6-----7--
NUCLEUS  1
NUCLST   00

*This segment applies to any machine in any logical partition (or
*not in LPAR mode).

*-----1-----2-----3-----4-----5-----6-----7--
SYSPARM  01
PARMLIB  ALLSYS.PARMLIB

*This segment applies to an IPL on VM user ID V1 on any LPAR (or not
*in LPAR mode), and on any hardware.
*Note that at this point neither HWNAME
*nor LPARNAME have been specified in the LOADxx member, so they
*will automatically match those of the system being IPLed.

*-----1-----2-----3-----4-----5-----6-----7--
VMUSERID V1
IEASYM   V1
SYSPARM  V1

*This segment applies to any IPL on VM user ID V2 on any LPAR (or not
*in LPAR mode), and on any hardware.
*Note that at this point neither HWNAME
*nor LPARNAME have been specified in the LOADxx member, so they
*will automatically match those of the system being IPLed.
*-----1-----2-----3-----4-----5-----6-----7--
LPARNAME
IEASYM   DD
PARMLIB  NOT.LPAR.PARMLIB

*This segment applies to an IPL on machine H2 in any logical partition
*(or not in LPAR mode), under any VM user ID (or not under VM).
*The specification of HWNAME causes the LPARNAME
*and VMUSERID filters to be reset.

*-----1-----2-----3-----4-----5-----6-----7--
HWNAME   H2
SYSPARM  H2
PARMLIB  H2.PARMLIB

*This is only *one* LOADxx.

*-----1-----2-----3-----4-----5-----6-----7--
HWNAME   H1
SYSPARM  H1
PARMLIB  H1.PARMLIB

*This segment applies to an IPL on machine H1 in logical partition L2
*not under any VM user ID (or not under VM).
*-----1-----2-----3-----4-----5-----6-----7--
VMUSERID
IEASYM   CC
PARMLIB  NOT.VM.PARMLIB

*This segment applies to an IPL on machine H1 running in non-LPAR mode
*under any VM user ID (or not under VM). The specification of
*LPARNAME causes the VMUSERID filter to be reset to match the system
*being IPLed.

*-----1-----2-----3-----4-----5-----6-----7--
LPARNAME
IEASYM   DD
PARMLIB  NOT.LPAR.PARMLIB
```

\*This segment applies to an IPL on machine H2 in any logical partition  
 \*(or not in LPAR mode), under any VM user ID (or not under VM).  
 \*The specification of HWNAME causes the LPARNAME  
 \*and VMUSERID filters to be reset.

```
*-----1-----2-----3-----4-----5-----6-----7--
HWNAME    H2
SYSPARM   H2
PARMLIB   H2.PARMLIB
```

\*This is only \*one\* LOADxx.

```
*-----1-----2-----3-----4-----5-----6-----7--
HWNAME    H1
SYSPARM   H1
PARMLIB   H1.PARMLIB
```

\*This segment applies to an IPL on machine H1 in logical partition L2  
 \*not under any VM user ID (or not under VM).

Table 33 on page 616 summarizes some of the IPL results produced by the previous example. Using a second PARMLIB statement adds to the list of parmlibs. For any other statement, the previous value is replaced.

| Table 33. IPL results  |   |
|--|---|
| IPL  | LOADxx members  |
| IPL on hardware H1 with logical partition L0 not under z/VM.     | SYSPARM H1<br>IEASYM not used<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H1.PARMLIB<br>PARMLIB SYS1.PARMLIB   |
| IPL on hardware H1 with logical partition L1 under VMUSERID V1.  | SYSPARM H1<br>IEASYM L1<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H1.PARMLIB<br>PARMLIB SYS1.PARMLIB   |
| IPL on hardware H1 with logical partition L2 under VMUSERID V0.  | SYSPARM H1<br>IEASYM BB<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H1.PARMLIB<br>PARMLIB L2.PARMLIB<br>PARMLIB SYS1.PARMLIB                           |
| IPL on hardware H1 with logical partition L2 not under z/VM.     | SYSPARM H1<br>IEASYM CC<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H1.PARMLIB<br>PARMLIB L2.PARMLIB<br>PARMLIB NOT.VM.PARMLIB<br>PARMLIB SYS1.PARMLIB |
| IPL on hardware H1, not in LPAR mode, and not under VMUSERID V2. | SYSPARM H1<br>IEASYM DD<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H1.PARMLIB<br>PARMLIB NOT.LPAR.PARMLIB<br>PARMLIB SYS1.PARMLIB                     |

Table 33. IPL results (continued)

| IPL  | LOADxx members  |
|--|---|
| IPL on hardware H2, not in LPAR mode, and not under VMUSERID V1 or V2.         | SYSPARM H2<br>IEASYM not used<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB H2.PARMLIB<br>PARMLIB SYS1.PARMLIB                 |
| IPL on hardware H2 under VMUSERID V2 in logical partition L0.                  | SYSPARM H2<br>IEASYM V2<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB V2.PARMLIB<br>PARMLIB H2.PARMLIB<br>PARMLIB SYS1.PARMLIB |
| IPL on unnamed hardware with logical partition L1 not under VMUSERID V1 or V2. | SYSPARM L1<br>IEASYM L1<br>PARMLIB ALLSYS.PARMLIB<br>PARMLIB SYS1.PARMLIB   |

## Parameter in IEASYSxx (or supplied by the operator)

None.

## Support for system symbols

You can use LOADxx to define substitution text for the &SYSPLEX system symbol and point to other parmlib members that define system symbols. However, do not use those system symbols or any others in LOADxx. The system must complete processing of LOADxx to define substitution texts to the system symbols. Therefore, the system might not substitute text for system symbols that you use in LOADxx.

## Syntax rules for LOADxx

The following syntax rules apply to LOADxx:

- Each record consists of 80 columns, although columns 73 through 80 are ignored.
- The fields are column-dependent as shown in “Statements and parameters for LOADxx” on page 618. Columns not shown to contain data must contain blanks. All data must be left-justified within the column ranges.
- Lines that begin with an asterisk in column 1 are comments.
- Blank lines are ignored.

## Syntax format of LOADxx

LOADxx is a column-dependent parmlib member. An asterisk in column 1 denotes a comment. Parameters begin in column 1. Data begins in column 10. Columns 73-80 are ignored.

In the following syntax diagram, column grids are included as comments to help you place parameters and data in the correct columns.

```
*-----1-----2-----3-----4-----5-----6-----7
HWNAME      h1
LPARNAME    l1
VMUSERID    v1

*-----1-----2-----3-----4-----5-----6-----7
ARCHLVL     a
DYNCPADD    { nnnn | ENABLE | DISABLE}

IEASYM      [xx]
            [(xx,yy,zz,...,L)]
INITSQA     xxxK yyyyK
            xxxM yyyyM
IODF        xx hiqualif configid id y s
MACHMIG     x1,x2,...,xn
MTLSHARE    {Y | N}
NUCLEUS     n
NUCLST      nn y
PARMLIB     dsn                                [valid]
                                                [*****]
                                                [*MCAT*]

PROCVIEW    {CORE | CPU | CORE,CPU_OK}
SYSCAT      volserxycsdsname                    hlqtcv
SYSPARM     [xx]
            [(xx,yy,zz,...,L)]
SYSPLEX     plexname
```

IBM-supplied default for LOADxx

Although IBM provides no default member in SYS1.PARMLIB, you can create a sample LOADxx member using the JCL in the IPXLOADX member of SYS1.SAMPLIB. You can also use the SPPINST member of SYS1.SAMPLIB to create, update or list LOADxx members through an ISPF application.

For detailed information about setting up and using these tools, see the prolog of the IPXLOADX and Appendix B, “Symbolic Parmlib Parser,” on page 793 at the end of this information.

Statements and parameters for LOADxx

ARCHLVL

The ARCHLVL statement specifies the mode in which the operating system will run. In z/OS, the processor determines the appropriate z/OS architecture mode, and you do not need to specify the ARCHLVL parameter. It is recommended that you do not specify the ARCHLVL statement.

Specifying the ARCHLVL parameter explicitly identifies the nucleus extension, IEANUCax, for the architecture level of your system. The system uses this extension along with the common base, IEANUC0x, to build the nucleus.

Table 34 on page 618 summarizes the contents of the columns.

Table 34. ARCHLVL statement

| Column | Contents  |
|--------|---|
| 1-7    | ARCHLVL   |
| 10     | A one-digit value to specify the architecture level for the nucleus extension.<br><br>The default is 2 (run in z/Architecture mode).<br><br>If you specify a value for ARCHLVL that is not the default for the processor, message IEA368I is issued during the IPL process, and the value you specified is ignored. |

DYNCPADD

Indicates if z/OS support for dynamic CPU/core addition is enabled. Table 35 on page 619 summarizes the contents of the columns.



Table 35. DYNCPADD statement

| Column | Contents  |
|--------|---|
| 1-8    | DYNCPADD  |
| 10-16  | <p>{<i>nnnn</i>   ENABLE   DISABLE}</p> <p><b><i>nnnn</i></b></p> <p>Specifies whether dynamic CPU/core addition functionality should be enabled such that <i>nnnn</i> CPUs/cores can be dynamically added to the image for the life of the IPL. <i>nnnn</i> must be a left-justified value without any leading zeros. Specifying 8 or 16 is acceptable syntax for <i>nnnn</i>; 16 is the default.</p> <p>The number of CPUs/cores that can be dynamically added is the minimum between:</p> <ul style="list-style-type: none"> <li>• <i>nnnn</i> plus the highest CPU/core ID defined at IPL</li> <li>• Highest CPU/core ID that the machine supports</li> <li>• Highest CPU/core ID the z/OS release supports</li> </ul> <p>If you specify <i>nnnn</i>, choose a value that is large enough to be able to dynamically add more CPUs/cores than you could envision for the life of the IPL, then add some extra and set that value in <i>nnnn</i>.</p> <p><b>DISABLE</b></p> <p>Specifies if dynamic CPU/core addition functionality should be disabled. If either the hardware or the z/OS release does not support dynamic CPU/core addition, dynamic CPU/core addition is disabled.</p> <p><b>ENABLE</b></p> <p>Specifies if dynamic CPU/core addition functionality should be enabled. The hardware and the z/OS release must support dynamic CPU/core addition to be able to dynamically add a CPU/core after IPL. When you specify ENABLE, z/OS prepares to dynamically add the smaller of the following:</p> <ul style="list-style-type: none"> <li>• Highest CPU/core ID the hardware supports</li> <li>• Highest CPU/core ID the z/OS release supports.</li> </ul> <p>IBM recommends specifying <i>nnnn</i> to avoid allocating CPU/core-related storage for CPUs/cores that will never be dynamically added for the life of the IPL.</p> <p>The default is 16.</p> |

**Note:** When PROCVIEW CPU is in effect, DYNCPADD applies to CPUs. When PROCVIEW CORE is in effect, DYNCPADD applies to cores.

## HWNAME

Specifies the name of a central processor complex (CPC), as defined in the hardware configuration definition (HCD) in the **Processor ID** field. The HWNAME parameter is used as a filter to define value parameters for a specified processor.

This optional filter parameter identifies a segment of LOADxx that can contain LOADxx statements that are used if the specified HWNAME matches the name of the processor where the LOADxx statement is running. When HWNAME is specified, it resets the LPARNAME and VMUSERID to their default values.

**Note:** Before the specification of this keyword, all statements up to this keyword pertain to any CPC. This keyword cannot be reset, and all subsequent statements pertain to the last specified HWNAME.

[Table 36 on page 620](#) summarizes the contents of the column.

Table 36. HWNAME statement

| Column | Contents  |
|--------|---|
| 1-6    | HWNAME  |
| 10-17  | A required hardware processor name as defined in the IODF. There is no default value. |

IEASYM

The IEASYM statement identifies one or more suffixes of IEASYMxx members of SYS1.PARMLIB that takes the following steps for one or more systems:

- Define static system symbols.
- Specify the IEASYSxx parmlib members that the system is to use.

To specify one IEASYMxx parmlib member, code IEASYM as shown in [Table 37 on page 620](#):

Table 37. Specifying one IEASYMxx member

| Column | Contents  |
|--------|---|
| 1-6    | IEASYM  |
| 10-11  | A 2-character suffix that is appended to IEASYM to select the member. |

This example shows an IEASYM statement that tells the system to use the IEASYM01 parmlib member:

```
*
*-----1-----2-----3-----4-----5-----6-----7--
IEASYM   01
*
```

To specify one IEASYMxx parmlib member and display a list of member names in message IEA009I, code IEASYM as shown in [Table 38 on page 620](#):

Table 38. Specifying one IEASYMxx parmlib member and displaying a list of member names

| Column | Contents  |
|--------|---|
| 1-6    | IEASYM  |
| 10     | A left parenthesis.   |
| 11-12  | A 2-character suffix that is appended to IEASYM to select the member. |
| 13-14  | The following characters:   |
|        | ,L  |
| 15     | A right parenthesis.  |

This example shows an IEASYM statement that tells the system to use the IEASYM01 parmlib member and display the names of those members in message IEA009I.

```
*
*-----1-----2-----3-----4-----5-----6-----7--
IEASYM   (01,L)
*
```

To specify more than one IEASYMxx parmlib member, code IEASYM as shown in [Table 39 on page 621](#):

Table 39. Specifying more than one IEASYMxx parmlib member

| Column | Contents  |
|--------|---|
| 1-6    | IEASYM  |
| 10     | A left parenthesis.   |
| 11-71  | A list of 2-character suffixes appended to IEASYM to select the members. To display a list of member names in message IEA009I, specify ,L anywhere after the first suffix and enclose the values in parentheses, as shown in the following example. |

This example shows an IEASYM statement that tells the system to use the IEASYM01 and IEASYM02 parmlib members and display the names of those members in message IEA009I.

```
*
*-----1-----2-----3-----4-----5-----6-----7--
IEASYM  (01,02,L)
*
```

If you specify a list of IEASYMxx suffixes, the system processes them from left to right. The system uses the definitions in all IEASYMxx members for which suffixes are specified. If the system finds duplicate definitions, the last definition overrides any previous definitions.

There is no default. If you do not specify an IEASYM statement, the system does not process IEASYMxx during initialization.

## INITSQA

The INITSQA statement allows more SQA and ESQA storage to be reserved for IPL and NIP processing when the default amount is not sufficient. Increasing the minimum below the line SQA allocation must be done with caution to ensure that it does not affect the lower boundary of CSA storage. If a syntax error exists, the entire statement is ignored and message IEA368I is issued.

Table 40 on page 621 summarizes the contents of the columns.

Table 40. INITSQA statement

| Column | Contents  |
|--------|---|
| 1-7    | INITSQA   |
| 10-14  | <p>The amount of SQA to be added to the default initial amount. If blank, no SQA is added. If non-blank, a 4-digit numeric value followed by a multiplier of K or M must be specified.</p> <p>The value range is 0000 K to 2048 K or 0000 M to 0002 M.</p> <p>The default is 0000 K.</p>  |
| 16-20  | <p>The amount of ESQA to be added to the default initial amount. If blank, no ESQA is added. If nonblank, a 4-digit numeric value followed by a multiplier of K or M must be specified.</p> <p>The value range is 0000 K to 8192 K or 0000 M to 0016 M.</p> <p>The default is 0000 K.</p> |

## IODF

The IODF statement identifies the I/O definition file that contains information about the I/O configuration that is defined to your system through the hardware configuration definition (HCD). To change the I/O configuration definition when the system is running, use the activate process. For information about the ACTIVATE command, see *z/OS MVS System Commands*. For information about using the HCD to change the I/O configuration definition, see *z/OS HCD User's Guide*.

Table 41 on page 622 summarizes the contents of the columns.

Table 41. IODF statement

| Column | Contents  |
|--------|---|
| 1-4    | IODF  |
| 10-11  | <p>IODF suffix. This suffix is appended to <i>nnnnnnnn.IODF</i> to form the name of the <i>nnnnnnnn.IODFxx</i> data set.</p> <p>The value range is a two-digit hexadecimal number (X'00-FF'), asterisks (**), pluses (++), minuses (--), or equals (==).</p> <ul style="list-style-type: none"> <li>• If you used HCD to create your I/O Configuration data set (IOCDS), you can specify asterisks, pluses, minuses, or equals for the IODF suffix.</li> <li>• If you specify asterisks, pluses, minuses, or equals, z/OS uses the IODF name found in the hardware configuration token. This IODF represents the last I/O configuration in the channel subsystem which you activated during the last Power® On Reset (POR) or dynamic I/O configuration change.</li> <li>• If you override descriptor fields 1 and 2 in the HCD panel with an invalid IODF name, z/OS treats IODF suffixes ** and ++ as if no IODF suffix was specified in LOADxx (z/OS searches from X'00' to X'FF' for a production IODF).</li> <li>• If ** was specified and the Hardware Configuration Token in the Processor System area (as written by the IOCDS and reflected in D IOS,CONFIG output) does NOT match the PROCESSOR Token in the IODF data set, then z/OS will continue looking for a valid IODF from IODF suffix '00' to 'FF'. If there is no IODF with a matching TOKEN then the IODF with a matching OS Config will be used to IPL.</li> <li>• If a valid IODF is not found and you specified --, z/OS searches for a production IODF starting with a suffix of X'FF' and searches backwards to X'00'.</li> <li>• If a valid IODF is not found and you specified ++, z/OS searches for a production IODF with a suffix of '00' to 'FF'.</li> <li>• If an invalid IODF name is found and == is specified, z/OS loads wait state X'0B1' reason code X'00B'.</li> </ul> <p>If pluses (++) are specified and a valid IODF name is found in the hardware token, but is not found in the search or cannot be used, IODF selection is made in the following order:</p> <ul style="list-style-type: none"> <li>• Search for the next available IODF starting with the current IODF suffix number plus one and search up to X'FF'. If none is found, the search continues from X'00' up to the current IODF number minus one.</li> <li>• Select the first IODF that has both a processor definition in the IODF that matches the currently active hardware definition, and a matching operating system configuration identifier.</li> <li>• If no matching IODF token is found, select the first IODF that has a matching operating system configuration identifier.</li> <li>• If no matching operating system configuration identifier is found, a wait state is loaded.</li> </ul> |

Table 41. IODF statement (continued)


| Column | Contents  |
|--------|---|
|        | <p>If minuses (--) are specified and a valid IODF name is found in the hardware token, but is not found in the search or cannot be used, IODF selection is made in the following order:</p> <ul style="list-style-type: none"> <li>• Search for the next available IODF starting with the current IODF suffix number minus one and search down to X'00'. If none is found, the search continues from X'FF' down to the current number plus one.</li> <li>• Select the first IODF that has both a processor definition in the IODF that matches the currently active hardware definition, and a matching operating system configuration identifier.</li> <li>• If no matching IODF token is found, select the first IODF that has a matching operating system configuration identifier.</li> <li>• If no matching operating system configuration identifier is found, a wait state is loaded.</li> </ul> <p>If equals (==) are specified and a valid IODF name is found in the hardware token, but is not found in the search or cannot be used, the result is the same as if you specified a specific number for the IODF suffix (hilevqu.IODF01).</p> <p>If not specified, all possible IODFs (00-FF) are searched. The IODF selection is made in the following order:</p> <ul style="list-style-type: none"> <li>• If no matching IODF token is found, select the first IODF that has a matching operating system configuration identifier.</li> <li>• If no matching operating system configuration identifier is found, a wait state is loaded.</li> </ul> <p> <b>Attention:</b> If you specify asterisks (**), pluses ('++'), minuses (--), or equals (==) for an IODF that does not reside on the IODF volume, or if you omit the IODF parameter altogether, the resulting search can substantially increase the time that it takes to IPL the system, especially if the IODF volume has a large VTOC. In this situation, the system enters an X'073' wait state, indicating that the IPL is waiting for an I/O interrupt. To correct the problem, either specify the correct IODF suffix in LOADxx, or move the required IODF to the IODF volume, then reIPL.</p> |
| 13-20  | <p>High-level qualifier for the IODF data set name. This qualifier is added to IODFxx to form the name of the nnnnnnnn.IODFxx data set.</p> <p>If equals (====) are specified, z/OS attempts to extract the high-level qualifier from the hardware configuration token. If the token is not available, a wait state is loaded. Otherwise, z/OS uses this high-level qualifier for the IODF name. If the first character of the high-level qualifier that is found in the hardware configuration token is blanks, a wait state is loaded.</p> <p>The value range is 1 - 8 alphameric characters or =====.</p> <p>If LOADxx resides in a SYSn.IPLPARM data set, and there is no high-level qualifier specified, the high-level qualifier defaults to the high-level qualifier of the SYSn.IPLPARM data set. If LOADxx resides in a SYS1.PARMLIB data set, and there is no high-level qualifier specified, a wait state is loaded.</p>   |

Table 41. IODF statement (continued)

| Column | Contents   |
|--------|--|
| 22-29  | <p>Operating system configuration identifier. This eight-character identifier is used to select the appropriate configuration from those configurations defined in the IODF. For a list of eligible operating system configurations, select the “Define Operating System Configurations” option on the primary HCD panel.</p> <p>If there is only one operating system configuration identifier in nnnnnnnn.IODFxx, then that one is used. If there is more than one identifier and the identifier is not specified, a wait state is loaded.</p> |
| 31-32  | <p>Eligible device table identifier</p> <p>The default is 00.</p>  |
| 34     | <p>To indicate that the system should load all of the device support modules for the devices that are defined in the IODF and all the device types that support dynamic processing, specify either Y or blank. To indicate that the system should load only the modules that are required for the devices that are defined in your IODF, specify any non-blank character other than Y.</p> <p>The default is Y.</p>  |

Table 41. IODF statement (continued)

| Column | Contents  |
|--------|---|
| 36     | <p>Subchannel set indicator. Indicates the subchannel set IOS uses for normal base devices that have a special secondary device with the same address. The following values can be specified:</p> <p><b>0</b></p> <p>Indicates the normal base devices in subchannel set 0 are used for the IPL.</p> <p><b>n</b></p> <p>Indicates that the special secondary devices in this subchannel set are used for the IPL.</p> <p><b>*</b></p> <p>Indicates the subchannel set of the IPL device is used for the IPL.</p> <p>If you are using a product to manage disk replication with HyperSwap capability (for example, GDPS or TPC-R), it is possible to have secondary devices attached to a subchannel set other than 0. Using such a configuration creates "special" pairs of devices consisting of one device in subchannel set 0 and a second device in an alternate subchannel set. Attaching secondary devices in an alternate subchannel set allows you to better utilize subchannel set 0 for devices that must be online and available for allocation.</p> <p>You must provide direction when an IPL is required so that z/OS brings the correct devices online when HyperSwap occurs (that is, when secondary devices become the devices in use, or in other words, the active subchannel set for a special pair of devices becomes the subchannel set to which the secondary devices are attached). On systems where special secondary devices are connected, if this value is not specified or is not valid (for example, not a 0, 1, 2, or *), the system will prompt the operator with message IEA111D to determine what subchannel set should be used.</p> <p>Specifying * allows z/OS to inherit the active subchannel set from the IPL devices (for IBM zEnterprise 196 (z196) or later processors). Specifying a number indicates that a specific subchannel set is to be used as the active subchannel set. Consult the documentation for your disk replication manager to determine whether special pairs are supported and if any restrictions exist before specifying this parameter.</p> <p>There is no default.</p> |

**LPARNAME**

Specifies the name of a logical partition that is defined to a processor, which is one of the following:

- The partition name that is specified on the Add Partition panel in HCD (see [z/OS HCD User's Guide](#) for more information).
- The partition name that is specified on the RESOURCE or CHPID statement that is input to the I/O configuration program (IOCP).

This optional filter parameter identifies a segment of LOADxx that might contain LOADxx statements that are used if the specified HWNAME matches the name of the processor and the specified LPARNAME matches the actual LPAR logical partition in which z/OS is executing. When LPARNAME is specified, it resets VMUSERID to its default value. The LPARNAME parameter is used as a filter to define value parameters for a specified partition of a processor.

**Note:** When z/OS is running under any virtual machine (z/VM or an alternate virtual machine), there is considered to be no LPAR name.

Table 42 on page 626 summarizes the contents of the columns.

Table 42. LPARNAME statement

| Column | Contents  |
|--------|---|
| 1-8    | LPARNAME  |
| 10-17  | A required logical partition name as defined to LPAR. A blank entry indicates a z/OS image not running in LPAR mode. The default of matching the system being IPLed is set indirectly by specifying the HWNAME parameter. |

## MACHMIG

Identifies one or more facilities that you do not want z/OS to use at this time because migration to another processor, z/OS release, or both is underway. Code the MACHMIG statement as described in Table 43 on page 626.

Table 43. MACHMIG statement

| Column | Contents  |
|--------|---|
| 1-7    | MACHMIG   |
| 10-72  | <p>A list of facilities not to use. When more than one facility is listed, separate each from the previous by one or more blanks or commas. The following facilities can be specified in upper, lower, or mixed case:</p> <ul style="list-style-type: none"> <li>• EDAT2 (the hardware-based enhanced-DAT facility 2)</li> <li>• TX (the hardware-based transactional-execution facility) This option is ignored as of z/OS V2R4. The facility will be used even if this is specified. z/OS V2R4 requires availability of the transactional-execution facility.</li> <li>• RI (a hardware-based facility that is reserved for IBM use only)</li> <li>• VEF (the hardware-based vector extension facility) This option is ignored as of z/OS V2R5. The facility will be used even if this is specified. z/OS V2R5 requires availability of the vector extension facility.</li> <li>• GSF (the hardware-based Guarded Storage Facility)</li> <li>• CRYPTRS (the hardware-based crypto counter facility). This option also implies that the hardware-based NNPI counter facility will not be used.</li> <li>• NNPICTRS (the hardware-based NNPI counter facility)</li> </ul> |

This example shows a MACHMIG statement that tells the system not to use the enhanced DAT facility 2.

```
*
*-----1-----2-----3-----4-----5-----6-----7--
MACHMIG  EDAT2
*
```

There is no default. If you do not specify a MACHMIG statement, the system does not limit its exploitation of machine facilities.

## MTLSHARE

The MTLSHARE statement enables a full-support MTL system to treat manual tape library defined devices as stand-alone devices when the Y(es) parameter is specified. Specifying Y also implies that the cartridge loader on MTL defined devices should not be indexed. For complete details, see [z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries](#).

Table 44 on page 627 summarizes the contents of the columns.



Table 44. MTLSHARE statement

| Column | Contents  |
|--------|---|
| 1-8    | MTLSHARE  |
| 10     | <p>Y indicates that the system is to run in its coexistence mode, that is, treat MTL defined tape drives as stand-alone drives, and do not index the cartridge loaders on such drives.</p> <p>N indicates that the system is to run in its full function mode. MTL defined drives are treated as MTL resident drives, and cartridge loaders on such drives are indexed per MTL rules.</p> |

The default is N.

## NUCLEUS

The NUCLEUS statement identifies the IEANUC0x member of SYS1.NUCLEUS that your system is to use. If the operator specified a nucleus identifier on the LOAD parameter, z/OS ignores the NUCLEUS statement.

Table 45 on page 627 summarizes the contents of the columns.

Table 45. NUCLEUS statement

| Column | Contents  |
|--------|---|
| 1-7    | NUCLEUS   |
| 10     | <p>A one-digit suffix that is appended to “IEANUC0” to select a member of SYS1.NUCLEUS.</p> <p>The default is 1.</p> <p><b>Note:</b> When you specify an alternate nucleus, the proper architectural extension of the nucleus must also exist. See <a href="#">ARCHLVL</a> for information about architectural extensions to the nucleus.</p> |

## NUCLST

The NUCLST statement:

- Identifies the NUCLSTxx parmlib member that your system is to use.
- Specifies whether the system is to load a wait state if any of the INCLUDE statements in the NUCLSTxx member specify a member that cannot be found in SYS1.NUCLEUS.

The NUCLSTxx member must reside in the same data set as the LOADxx member. For information about coding the NUCLSTxx member, see [Chapter 79, “NUCLSTxx \(customizing the nucleus region\),” on page 677.](#)

Table 45 on page 627 summarizes the contents of the columns.

| Column | Contents  |
|--------|---|
| 1-6    | NUCLST  |
| 10-11  | <p>A two-character suffix that is appended to “NUCLST” to select a NUCLST member.</p> <p>There is no default.</p> |

| Column | Contents  |
|--------|---|
| 13     | <p>The character Y indicates that a wait state is to be loaded if any of the INCLUDE statements in the NUCLSTxx member specify a member that cannot be found in SYS1.NUCLEUS. If any other character is specified, the system does not load a wait state.</p> <p><b>Note:</b> Uppercase Y is required. Lowercase y indicates that a wait state is not to be loaded.</p> <p>Default: Do not load a wait state.</p> |

PARMLIB

Specifies a data set that is included in the logical parmlib concatenation. The parmlib concatenation consists of up to 16 PARMLIB data sets and SYS1.PARMLIB. When there is more than one parmlib statement, the statements are concatenated and SYS1.PARMLIB, as cataloged in the Master Catalog, is added at the end of the concatenation, unless it was specified in a parmlib. See “Restrictions” on page 57 for restrictions on cataloging parmlib data sets when a system symbol is used. The parmlib concatenation is established during IPL and is used by Master Scheduler Initialization. Programs can access members in the logical parmlib concatenation using the IEFPRMLB macro (see *z/OS MVS Programming: Assembler Services Reference IAR-XCT*). Each additional PARMLIB statement adds another data set to the logical parmlib concatenation.

Table 46 on page 628 summarizes the contents of the columns.

Table 46. PARMLIB statement

| Column | Contents   |
|--------|--|
| 1-7    | PARMLIB  |
| 10-53  | A required valid data set name. There is no default value.   |
| 55-60  | <p>A optional valid volume name.</p> <p>If a volume name is specified, IPL processing will attempt to locate the specified data set on the specified volume.</p> <p>If ***** or &amp;SYSR1 is specified, IPL processing attempts to locate the specified data set on the system residence volume.</p> <p>If *MCAT* is specified, IPL processing attempts to locate the specified data set on the IPL-time master catalog volume.</p> <p>If nothing is specified, IPL processing attempts to locate the specified data set first in the master catalog and, if it is not located there, on the system residence volume.</p> |

**Note:** &SYSR1 is the only system symbol that can be specified in the logical parmlib concatenation.

Default: If you do not specify at least 1 parmlib statement, the parmlib concatenation consists of only SYS1.PARMLIB and Master Scheduler processing uses the IEFPARM DD statement, if there is one in the Master JCL. If there are no parmlib statements in the parmlib concatenation and there is no IEFPARM DD statement, Master Scheduler processing will use SYS1.PARMLIB.

Example 1 shows the definition of a parmlib concatenation consisting of MYDSN1.PARMLIB, MYDSN2.PARMLIB, MYDSN3.PARMLIB. SYS1.PARMLIB, as cataloged in the master catalog, will automatically be concatenated as the last data set in the parmlib concatenation.

```
-----1-----2-----3-----4-----5-----6-----7--
PARMLIB MYDSN1.PARMLIB
PARMLIB MYDSN2.PARMLIB
PARMLIB MYDSN3.PARMLIB
```

VOL123  
VOL456

Example 2 shows the definition of a parmlib concatenation consisting of MYDSN1.PARMLIB, MYDSN2.PARMLIB, SYS1.PARMLIB on volume VOL234, MYDSN3.PARMLIB and, additionally, SYS1.PARMLIB, as cataloged in the master catalog, which will be concatenated as the last data set in the parmlib concatenation.

```
-----1-----2-----3-----4-----5-----6-----7--
PARMLIB MYDSN1.PARMLIB
PARMLIB MYDSN2.PARMLIB                                VOL123
PARMLIB SYS1.PARMLIB                                  VOL234
PARMLIB MYDSN3.PARMLIB                                VOL456
```

Example 3 shows the definition of a parmlib concatenation consisting of MYDSN1.PARMLIB, MYDSN2.PARMLIB, SYS1.PARMLIB as cataloged in the master catalog and MYDSN3.PARMLIB. SYS1.PARMLIB is not concatenated as the last data set in this case since it was already specified on a PARMLIB statement without a volume serial number and is, thus, the SYS1.PARMLIB cataloged in the master catalog.

```
-----1-----2-----3-----4-----5-----6-----7--
PARMLIB MYDSN1.PARMLIB
PARMLIB MYDSN2.PARMLIB                                VOL123
PARMLIB SYS1.PARMLIB
PARMLIB MYDSN3.PARMLIB                                VOL456
```

In all of the above examples, if none of the data sets specified on the parmlib statements could be located, the parmlib concatenation would consist of only SYS1.PARMLIB.

**PROCVIEW**

Indicates the processor view for the duration of the IPL. [Table 47 on page 629](#) summarizes the contents of the columns.

*Table 47. PROCVIEW statement*

| Column | Contents |
|--------|----------|
| 1-8    | PROCVIEW |

Table 47. PROCVIEW statement (continued)

| Column | Contents  |
|--------|---|
| 10-21  | <p>{CORE   CPU   CORE,CPU_OK}</p> <p><b>CORE</b></p> <p>Specifies a processor view of core, where a core can have 1-n threads. A thread is comparable to the definition of a CPU in a pre-multithreading environment. The number of usable threads per core is limited by what is supported by the underlying hardware, the current z/OS release, and the MT_CP_MODE and MT_ZIIP_MODE settings “Statements and parameters for IEAOPTxx” on page 388. If the underlying hardware does not support MT, a core is limited to one thread.</p> <p>With PROCVIEW CORE, the system:</p> <ul style="list-style-type: none"> <li>• Interprets the LOADxx DYNCPADD value as the number of cores that can be dynamically added. For more information, see the DYNCPADD parameter described previously in this section.</li> <li>• Rejects DISPLAY MATRIX=CPU commands and requires issuing DISPLAY MATRIX=CORE commands to display the core state. For more information, see the description of the DISPLAY M=CORE command in <a href="#">z/OS MVS System Commands</a>.</li> <li>• Rejects CONFIG CPU commands and requires issuing CONFIG CORE commands to configure an entire core. For more information, see the description of the CONFIG CORE command in <a href="#">z/OS MVS System Commands</a>.</li> <li>• Rejects MODE commands AD, CC, IV, PD, PS, PT, SD, SL, and TC that provide a machine check threshold. For more information, see the description of the DISPLAY M=CORE command in <a href="#">z/OS MVS System Commands</a>.</li> </ul> <p>For purposes of migration and coexistence, you can specify PROCVIEW CORE on systems that do not specifically support multithreading. For more information about the MT Facility, see <a href="#">z/Architecture Principles of Operations</a>.</p> <p><b>CPU</b></p> <p>Specifies a traditional processor view of CPU and does not exploit the MT Facility.</p> <p><b>CORE,CPU_OK</b></p> <p>Behaves like PROCVIEW CORE but in some case also accepts "CPU" (for which it treats "CPU" as "CORE"). Specifically:</p> <ul style="list-style-type: none"> <li>• The system accepts CONFIG CPU commands and processes them as if CONFIG CORE commands were specified.</li> <li>• The system accepts DISPLAY MATRIX=CPU commands and processes them as if DISPLAY MATRIX=CORE commands were specified.</li> </ul> <p><b>Note:</b> When PROCVIEW CORE or PROCVIEW CORE,CPU_OK is requested and the underlying hardware supports MT, partitions are forced to run with IEAOPTxx HIPERDISPATCH=YES and are unable to switch into HIPERDISPATCH=NO.</p> <p><b>Default:</b> CPU</p> |
|        | <p><b>SYSCAT</b></p> <p>Identifies the master catalog. The operator can override the value that is specified on this parameter, using the LOAD parameter on the system console with an appropriate initialization message</p>   |

suppression indicator (IMSI). For more information, see the topic on loading the system software in *z/OS MVS System Commands*.

Table 48 on page 631 summarizes the contents of the columns.

Table 48. SYSCAT parameter

| Column | Contents  |
|--------|---|
| 1-6    | SYSCAT  |
| 10-15  | The volume serial of the device that contains the master catalog.   |
| 16     | The character 1, unless SYS% to SYS1 conversion is active, in which case it is a 2.   |
| 17     | Alias name level of qualification.<br>The value range is 1 - 4.<br>The default is 1.  |
| 18-19  | CAS service task lower limit.<br>The value range is X'18' - X'B4'.<br>The default is X'3C'.<br>If you want to specify the C®AS service task lower limit, specify the value with EBCDIC characters, for instance, hexadecimal B4 is specified as C'B4' or X'C2F4'. |
| 20-63  | The 44-byte data set name of the master catalog.  |
| 64-71  | The 1 - 8 character high-level qualifier of the tape volume catalog.<br><b>Default:</b> SYS1.   |
| 72     | Specify Y to enable AUTOADD when the catalog address space (CAS) makes the first connection to the coupling facility. The AUTOADD function enables coupling facility support of enhanced catalog sharing (ECS) for eligible catalogs.                             |

If you do not specify a SYSCAT statement, the system prompts the operator to specify the SYSCATxx member of SYS1.NUCLEUS.

## SYSPARM

The SYSPARM statement identifies one or more IEASYSxx members of the parmlib concatenation that the system is to use (in addition to IEASYS00). To display the contents of IEASYSxx at the operator console when the system processes each member, specify , L anywhere after the first suffix and enclose the values in parentheses. For example, specify (01 , L) on SYSPARM to tell the system to process IEASYS01 and display the contents of that member at the operator console. The system ignores the SYSPARM statement if the operator specifies on the LOAD parameter that the system should prompt for system information. The operator can accomplish this by specifying an A, P, S, or T IMSI character on the LOAD parameter on the system console. For details about IMSI characters, see the topic on loading the system software in *z/OS MVS System Commands*.

**Note:** The suffixes of IEASYSxx members can also be specified:

- On the SYSPARM parameter in the IEASYMxx parmlib member.
- By the operator, in response to message IEA101A SPECIFY SYSTEM PARAMETERS.

See “Step 2. Determine where to specify system parameters” on page 39 for more information.

During system initialization, NIP first processes the IEASYS00 parmlib member to establish parameters. Then it determines, from the suffixes that are specified on the SYSPARM statement in LOADxx, the SYSPARM parameter in IEASYMxx, or by the operator, which IEASYSxx members are to

be used. See “[Step 2. Determine where to specify system parameters](#)” on [page 39](#) for a description of how the system determines which IEASYSxx members are to be used.

To specify one IEASYSxx parmlib member, code SYSPARM as described in [Table 49 on page 632](#).

*Table 49. SYSPARM statement (specifying one IEASYSxx parmlib member)*

| Column | Contents  |
|--------|---|
| 1-7    | SYSPARM   |
| 10-11  | A 2-character suffix that is appended to IEASYS to select the member. |

The following example shows a SYSPARM statement that tells the system to use the IEASYS01 parmlib member:

```
*
*-----1-----2-----3-----4-----5-----6-----7--
SYSPARM  01
*
```

To specify one IEASYSxx parmlib member and display the contents of IEASYSxx at the operator console, code SYSPARM as described in [Table 50 on page 632](#).

*Table 50. SYSPARM statement (specifying one IEASYSxx parmlib member and displaying the contents)*

| Column | Contents  |
|--------|---|
| 1-7    | SYSPARM   |
| 10     | A left parenthesis.   |
| 11-12  | A 2-character suffix that is appended to IEASYS to select the member. |
| 13-14  | The following characters: , L   |
| 15     | A right parenthesis.  |

The following example shows a SYSPARM statement that tells the system to use the IEASYS01 parmlib member and display the contents at the operator console:

```
*
*-----1-----2-----3-----4-----5-----6-----7--
SYSPARM  (01,L)
*
```

To specify more than one IEASYSxx parmlib member, code SYSPARM as described in [Table 51 on page 632](#).

*Table 51. SYSPARM statement (specifying one or more IEASYSxx parmlib members)*

| Column | Contents  |
|--------|---|
| 1-7    | SYSPARM   |
| 10     | A left parenthesis.   |
| 11-71  | A list of 2-character suffixes appended to IEASYS to select members of SYS1.PARMLIB. To display the contents of IEASYSxx at the operator console when the system processes each member, specify , L anywhere after the first suffix and enclose the values in parentheses, as shown in the following example. |

The following example shows a SYSPARM statement that tells the system to use IEASYSxx members IEASYS01 and IEASYS02 and display their contents at the operator console:

```
*
*-----1-----2-----3-----4-----5-----6-----7--
```

```
SYSPARM (01,02,L)
*
```

If you do not specify a SYSPARM statement, the system prompts the operator to specify the IEASYSxx members of SYS1.PARMLIB.

**SYSPLEX**

The SYSPLEX statement specifies the name of the sysplex in which the system participates. It is also the substitution text for the &SYSPLEX system symbol. Specify a sysplex name that is different from the names of all the systems that participate in the sysplex.

**Note:** The sysplex name must match the name that is specified in both of the following places:

- The SYSPLEX parameter of the XCF couple data set format utility. See [z/OS MVS Setting Up a Sysplex](#) for information about the data set format utility.
- The SYSPLEX parameter in the COUPLExx parmlib member. LOADxx defines the substitution text for &SYSPLEX early in system initialization so other parmlib members can use it. Therefore, if you plan to use the &SYSPLEX system symbol in parmlib, specify the sysplex name in LOADxx. To ensure that the name in COUPLExx matches the one in LOADxx, specify the &SYSPLEX system symbol on the SYSPLEX parameter in COUPLExx. (See Chapter 24, “COUPLExx (cross-system coupling facility (XCF) parameters),” on page 229 for more information.)

The value range is as described in [Table 52 on page 633](#):

Table 52. SYSPLEX statement

| Column | Contents  |
|--------|---|
| 1-7    | SYSPLEX   |
| 10-17  | The sysplex name. It can consist of 1 to 8 characters, left-aligned in the column. Valid characters are alphanumeric (A-Z and 0-9) and national (@,#,\$). |

If you do not specify a SYSPLEX statement, the system uses the value LOCAL until it processes the COUPLExx parmlib member. Then it uses the name that is specified in COUPLExx. In this case, the system substitutes LOCAL for the &SYSPLEX system symbol in all parmlib members that are processed before COUPLExx.

This example specifies that OURWORLD is the sysplex name.

```
*
*-----1-----2-----3-----4-----5-----6-----7--
SYSPLEX  OURWORLD
*
```

**VMUSERID**

Specifies the user ID of a z/VM system under which a z/OS image is running as a guest. This optional filter parameter identifies a segment of LOADxx that might contain LOADxx statements that are used if the specified HWNAME matches the name of the processor, the specified LPARNAME matches the actual LPAR logical partition in which z/OS is executing, and the specified VMUSERID matches the actual user ID of the z/VM guest machine in which z/OS is executing.

The value range is as described in [Table 53 on page 633](#):

Table 53. VMUSERID statement

| Column | Contents   |
|--------|--|
| 1-8    | VMUSERID   |
| 10-17  | A required user ID name as defined to z/VM. A blank indicates an image not running under VM. The default of matching the system that being IPLed is set indirectly by specifying the HWNAME or LPARNAME parameter. |

## Example of parmlib concatenation

The example in [Figure 26](#) on [page 634](#) creates a parmlib concatenation with five data sets.

- The first PARMLIB statement indicates that data set dsn1 is included in the parmlib concatenation.
- The second PARMLIB statement indicates that data set dsn2, residing on volume vol2, is included in the parmlib concatenation.
- The third PARMLIB statement indicates that data set dsn3, residing on the sysres volume, is included in the parmlib concatenation.
- The fourth PARMLIB statement indicates that data set dsn4, residing on the master catalog volume, is included in the parmlib concatenation.
- SYS1.PARMLIB is automatically added to the bottom of the parmlib concatenation.

```

*
*
*-----1-----2-----3-----4-----5-----6-----7--
PARMLIB  dsn1
PARMLIB  dsn2                      vol2
PARMLIB  dsn3                      *****
PARMLIB  dsn4                      *MCAT*
*
*
SYSCAT   volserxycdsname
*
* The first SYSPARM parameter specifies one IEASYSxx parmlib member.
* The second SYSPARM parameter specifies multiple IEASYSxx parmlib
* members. xx, yy, and zz are suffixes for IEASYS.
*
SYSPARM  xx
SYSPARM  (xx[,yy,zz...,L])
*
* In the SYSplex parameter, plexname is the sysplex name.
*
*-----1-----2-----3-----4-----5-----6-----7--
SYSplex  plexname
*
*
* VMUSERID v1 specifies that the LOADxx statements that follow the
* VMUSERID statement are used only if the vm user ID being used is v1.
*
*-----1-----2-----3-----4-----5-----6-----7--
VMUSERID v1
*
*****

```

Figure 26. Example of parmlib concatenation (LOADxx)



## Chapter 74. LPALSTxx (LPA library list)

Use the LPALSTxx member to add your installation's read-only reenterable user programs to the pageable link pack area (PLPA). Placing programs in the PLPA allows them to be shared among users of the system.

Use one or more LPALSTxx members to concatenate your installation's program library data sets to SYS1.LPALIB. The system uses this concatenation, which is referred to as the LPALST concatenation, to build the PLPA.

The modules in the data sets that you define in LPALSTxx must meet the same requirements as the modules defined in SYS1.LPALIB. For example, these modules must be reentrant and executable.

During NIP, the system opens and concatenates each data set specified in LPALSTxx in the order in which the data set names are listed, starting with the first-specified LPALSTxx member.

The LPALST concatenation can have up to 255 extents. If you specify more data sets than the concatenation can contain, the system truncates the LPALST concatenation and issues messages that indicate which data sets were not included in the concatenation.

If one or more LPALSTxx members exist, and the system can open the specified data sets successfully, the system uses the LPALST concatenation to build the PLPA (during cold starts and IPLs that include the CLPA option). If a library named in LPALSTxx cannot be opened, message IEA712I is issued for that library and the system continues to build the LPA list concatenation with the other libraries named in LPALSTxx. If no LPALSTxx members exist, or none of the libraries named in LPALSTxx can be opened, the system builds the PLPA from only the modules named in SYS1.LPALIB.

The data sets in the LPALST do not have to be APF-authorized. However, any module in the pageable link pack area is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected any data set in the LPALST to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

Data sets to be concatenated to SYS1.LPALIB must be cataloged in the system master catalog or a user catalog identified in the LPALSTxx member. (The system does not check OS CVOLs and only checks user catalogs when a data set name and pack VOLSER are listed in LPALSTxx.)

You cannot use PDSEs in the LPALST concatenation.

To identify which LPALSTxx members the system is to use, specify the member suffixes on the LPA parameter in IEASYSxx or as a parameter entered during IPL.

### Parameter in IEASYSxx (or supplied by the operator)

```
LPA=      {aa
           {(aa,bb,...[,L])}}
```

The two characters (A-Z, 0-9, @, #, or \$), represented by aa (or bb, and so forth), are appended to LPALST to form the name of the LPALSTxx parmlib member(s). If the L option is specified, the system displays (at the operator's console) the names of the data sets successfully concatenated to SYS1.LPALIB.

The LPA parameter is only effective during cold starts, or during IPLs in which you specify the CLPA option. The LPA parameter does not apply to modules requested through the MLPA option.

### Syntax rules for LPALSTxx

The following rules apply to the creation of LPALSTxx:

- On each record, place a string of data set names separated by commas.

- If a data set is not cataloged in the system master catalog but is cataloged in a user catalog, specify in parentheses immediately following the data set name the one to six-character VOLSER of the pack on which the data set resides.
- Indicate continuation by placing a comma followed by at least one blank after the last data set name on a record.
- Be careful not to specify the same data set name more than once in the LPALSTxx members. This applies to data sets with and without a VOLSER specified. The same data set name is concatenated as many times as it appears in all specified LPALSTxx members. Specifying the data set name more than once can cause additional processing during IPL, when the CLPA processes.
- If a module exists in more than one library in the concatenation, the first occurrence of the module is placed in the PLPA. Later occurrences are ignored.
- The LPALIB data set is always the first data set in the concatenation (see [“Using the SYSLIB statement” on page 687](#)). Unless overridden by a SYSLIB statement in PROGxx, the LPALST concatenation begins with SYS1.LPALIB. If you do not use SYSLIB and place the LPALIB data set name on any record in any LPALSTxx member, the name is ignored.
- Lines that begin with an asterisk in column 1 are comments.
- On a line, data entered after the last data set name and the optional comma continuation character are treated as a comment and ignored.

## Syntax format of LPALSTxx

```
IEASYSxx: ...,LPA=(nn,nn,nn,...)
LPALSTxx: {data-set-name},{data-set-name},...
          {data-set-name(volser)} {data-set-name(volser)}
```

## Syntax example of LPALSTxx

In both examples, DBLUE.U30LIB is a user-cataloged data set on VOLSER U30PAK. All other data sets are cataloged in the system master catalog.

```
IEASYSxx: ...,LPA=(00,01,02,03)
LPALST00: SYS1.CMDLIB,SYS1.TSORTNS,SYS1.BTAMLIB
LPALST01: SYS1.U30LIB,SYS2.U30LIB,DBLUE.U30LIB(U30PAK),SYS1.LPALIB
LPALST02: SYS1.AUXLIB,SYS1.JES3
LPALST03: SYS1.TEST
```

**Example 1:** PROGxx does not include a SYSLIB LPALIB statement. The following data sets are concatenated to SYS1.LPALIB:

- SYS1.CMDLIB
- SYS1.TSORTNS
- SYS1.BTAMLIB
- SYS1.U30LIB
- SYS2.U30LIB
- DBLUE.U30LIB
- SYS1.AUXLIB
- SYS1.JES3
- SYS1.TEST

Because the SYSLIB statement with the LPALIB option was not used in PROGxx, the specification of SYS1.LPALIB (in LPALST01) is ignored.

**Example 2:** PROGxx includes the following:

```
SYSLIB LPALIB(SYS2.LPALIB)
```

The following data sets are concatenated to SYS2.LPALIB:

- SYS1.CMDLIB
- SYS1.TSORTNS
- SYS1.BTAMLIB
- SYS1.U30LIB
- SYS2.U30LIB
- DBLUE.U30LIB
- SYS1.LPALIB
- SYS1.AUXLIB
- SYS1.JES3
- SYS1.TEST

## IBM-supplied default for LPALSTxx

---

There is no default LPALSTxx member. If the installation does not create an LPALSTxx member (and therefore no data sets are concatenated to SYS1.LPALIB), the system uses only SYS1.LPALIB to build the PLPA.

## Statements and parameters for LPALSTxx

---

Not applicable.



## Chapter 75. MMSLSTxx (MVS message service list)

MMSLSTxx contains information that the MVS message service (MMS) uses to define the languages that are available for message translation at your installation. Through the use of the LANGUAGE, DEFAULTS, and EXIT statements, you:

- Identify the languages available into which U.S. English messages can be translated.
- Specify the default language into which U.S. English messages can be translated.
- Specify the installation exits that get control either before or after the translation occurs.

### Selecting an MMSLSTxx member

You can select a particular MMSLSTxx parmlib member in one of the following ways:

- Specifying the MMS keyword on the INIT statement in the CONSOLxx parmlib member. CONSOLxx is used at system initialization.
- Issuing the SET MMS command after system initialization.

Two alphanumeric characters are appended to MMSLST to form the name of the MMSLSTxx parmlib member. After initialization, you can issue the SET MMS command to change the MMSLSTxx member; however, this change is temporary. At the next IPL, the system uses the MMSLSTxx member specified in the CONSOLxx. For information about CONSOLxx, see Chapter 23, “[CONSOLxx \(console configuration definition\)](#),” on page 201. For descriptions of the SET command, see [z/OS MVS System Commands](#).

### Parameter in IEASYSxx

None.

### Sample MMSLSTxx member

IBM provides a sample MMS member, CNLLSTXX, in SYS1.SAMPLIB.

### Syntax rules for MMSLSTxx

These rules apply to the creation of MMSLSTxx:

- Each record is 80 characters long. The system ignores columns 72 through 80 and leading blanks.
- Begin comments with /\* in any column. It is best to end the comment with a \*/. If, however, you do not include the end delimiter, the system recognizes the next statement.
- Specify one DEFAULTS statement only.
- Specify one or more LANGUAGE statements including U.S. English.
- Optionally, specify one or two EXIT statements.

### Syntax format of MMSLSTxx

```
DEFAULTS  LANGCODE(langcode)
LANGUAGE  LANGCODE(langcode) DSN(langdsn) CONFIG(membername) [NAME(langname)]
[EXIT  NUMBER(exitnum)  ROUTINE(exitname)]
```

## Syntax example for MMSLSTxx

```

DEFAULTS  LANGCODE (FRC)
LANGUAGE  LANGCODE (ENU) DSN(SYS1.MSG.NLSMSENU) CONFIG(CNLENU01) NAME (AMERICAN)
LANGUAGE  LANGCODE (ENG) DSN(SYS1.MSG.NLSMSENG) CONFIG(CNLENG01)
LANGUAGE  LANGCODE (FRC) DSN(SYS1.MSG.NLSMSFRC) CONFIG(CNLFRC01)
          NAME (FRENCH) NAME (FRANCAIS)
LANGUAGE  LANGCODE (ESP) DSN(SYS1.MSG.NLSMSESP) CONFIG(CNLESP01)
EXIT  NUMBER(1) ROUTINE(NLSEXIT1)
EXIT  NUMBER(2) ROUTINE(NLSEXIT2)

```

## IBM-supplied default for MMSLSTxx

None.

## Statements and parameters for MMSLSTxx

### DEFAULTS

Specifies the default language your installation uses for translation. If MVS system messages or application-generated messages are available in this language, the messages are displayed to the operator in this specified language.

#### LANGCODE(*langname*)

Specifies the three-character code for the default system language. You must code a LANGUAGE statement corresponding to the default language specified here. For a list of valid language codes see [Table 54 on page 640](#).

### EXIT

Specifies an installation exit that is to get control either before or after the translation occurs. See [z/OS MVS Installation Exits](#) for more information about the MMS pre-processing and post-processing exits.

#### NUMBER(*exitnum*)

Specifies the number of the exit to get control. The possible values are 1 and 2. Exit 1 gets control before message translation occurs and exit 2 gets control after translation.

#### ROUTINE(*exitname*)

Specifies the 1 - 8 character name of the MMS preprocessing or postprocessing installation exit.

Table 54. Language codes

| Code | Language name           | Country or region |
|------|-------------------------|-------------------|
| CHS  | Simplified Chinese      | China (PRC)       |
| CHT  | Traditional Chinese     | Taiwan            |
| DAN  | Danish                  | Denmark           |
| DEU  | German                  | Germany           |
| DES  | Swiss German            | Switzerland       |
| ELL  | Greek                   | Greece            |
| ENG  | UK English              | United Kingdom    |
| ENP  | US English (uppercase)  | United States     |
| ENU  | US English (mixed case) | United States     |
| ESP  | Spanish                 | Spain             |
| FIN  | Finnish                 | Finland           |
| FRA  | French                  | France            |

| Table 54. Language codes (continued) |                   |                   |
|--------------------------------------|-------------------|-------------------|
| Code                                 | Language name     | Country or region |
| FRB                                  | Belgian French    | Belgium           |
| FRC                                  | Canadian French   | Canada            |
| FRS                                  | Swiss French      | Switzerland       |
| ISL                                  | Icelandic         | Iceland           |
| ITA                                  | Italian           | Italy             |
| ITS                                  | Swiss Italian     | Switzerland       |
| JPN                                  | Japanese          | Japan             |
| KOR                                  | Korean            | Korea             |
| NLD                                  | Dutch             | Netherlands       |
| NLB                                  | Belgian Dutch     | Belgium           |
| NOR                                  | Norwegian         | Norway            |
| PTG                                  | Portuguese        | Portugal          |
| PTB                                  | Brazil Portuguese | Brazil            |
| RMS                                  | Rhaeto-Romanic    | Switzerland       |
| RUS                                  | Russian           | Russia            |
| SVE                                  | Swedish           | Sweden            |
| THA                                  | Thai              | Thailand          |
| TRK                                  | Turkish           | Turkey            |

## LANGUAGE

Specifies information pertaining to all languages your installation uses for translation, including the language that is specified on the DEFAULTS statement. You must code one language statement per language that is supported at your installation.

### LANGCODE(*langcode*)

Specifies the three-character code for the language whose message skeletons are contained in the runtime message file that is identified by DSN(*langdsn*).

At least one LANGUAGE statement must have a LANGCODE(*langcode*) of ENU for US English. For a list of valid language codes see [Table 54 on page 640](#).

### DSN(*langdsn*)

Specifies the data set name of the runtime message file that contains the message skeletons for the specified language. See *z/OS MVS Programming: Assembler Services Guide* for information about creating runtime message files.

### CONFIG(*membername*)

Specifies the member of SYS1.PARMLIB that contains information about the date and time formats of messages that are translated into the specified language. The name of the member must be in the form of CNLcccxx, where:

#### ccc

The appropriate three-character language code.

#### xx

Any two characters that uniquely identify the member.

See Chapter 18, “CNLcccxx (time and date format for translated messages),” on page 179 for information about coding the CNLcccxx parmlib member.

**NAME(*langname*)**

Specifies a 1-24 byte name by which the installation can optionally refer to the language specified through the LANGCODE parameter. Language names must be unique within any one MMSLSTxx member. You can specify more than one NAME parameter on a LANGUAGE statement.

The language can be a quoted string that contains mixed case characters as well as shift-in and shift-out characters to delineate double-byte character set (DBCS) characters.



## Chapter 76. MPFLSTxx (message processing facility list)

MPFLSTxx contains information that the message processing facility (MPF) uses to control:

- Message presentation

On certain devices, messages can appear with highlighting, in color, or with added intensity.

- Message management

Message management refers to message suppression, message retention, and message processing.

- Message suppression

A suppressed message does not appear at a console but is written to the hard-copy log.

- Message retention

The action message retention facility (AMRF) keeps action messages in a buffer area, allowing the operator to request that any action message not acted on be recalled to the screen. In MPFLSTxx, you can identify certain action messages that AMRF is not to retain.

- Message processing

Use MPFLSTxx to identify messages to be processed either using a message automation subsystem (for example, NetView or using installation-written exits).

- Command Processing

You can specify installation exits that will get control each time a command is issued.

This description of the MPFLSTxx parmlib member has the following order:

- General information including syntax rules and selecting MPFLSTxx members.
- Controlling message presentation using MPFLSTxx, in [“Controlling message presentation through MPFLSTxx”](#) on page 644.
- Controlling message management using MPFLSTxx, in [“Controlling message management”](#) on page 647.
- Controlling command processing using MPFLSTxx, in [“Controlling command processing using MPFLSTxx”](#) on page 657.

### Parameter in IEASYSxx

None.

### Syntax rules for MPFLSTxx

These rules apply to the creation of MPFLSTxx:

- Each record is 80 characters long. The system ignores columns 72 through 80 and leading blanks.
- Each message processing record can contain only one message identifier.
- The message processing record for msgid, .DEFAULT, or MPFHCF cannot have embedded blanks.
- The message processing record for .MSGCOLR and .MSGIDS must have a single blank between the statement and the operand. Embedded blanks are not allowed anywhere else on the message processing record.
- Begin comments with /\* in any column. It is best to end the comment with a \*/. If, however, you do not include the end delimiter, the system recognizes the next statement.

## Selecting MPFLSTxx members

You can select a particular MPFLSTxx parmlib member, or a concatenation of MPFLSTxx members (up to 39), in the following ways:

- Specifying the INIT statement with the MPF keyword in the CONSOLxx parmlib member. CONSOLxx is used at system initialization.
- Including the SET MPF command in the COMMNDxx parmlib used at system initialization.
- Issuing the SET MPF command after system initialization.

Two alphanumeric characters are appended to MPFLST to form the name of the MPFLSTxx parmlib member. Multiple members can be specified.

**Note:** Specify one or more MPFLSTxx parmlib members in **either** the CONSOLxx member **or** in the COMMNDxx member. Do not maintain this selection in both members. After initialization, you can issue the SET MPF command to change one or more MPFLSTxx members; however, this change is temporary. At the next IPL, the system uses the MPFLSTxx members specified in the CONSOLxx or COMMNDxx member. See the information about the CONSOLxx and COMMNDxx parmlib members.

If you issue the SET MPF=NO command, the system uses the IBM-supplied defaults for message presentation and for message management. For descriptions of the SET command, see [z/OS MVS System Commands](#).

## IBM-supplied MPFLSTxx member

None.

## Controlling message presentation through MPFLSTxx

Message presentation refers to color, highlighting, and intensity attributes that the system uses when displaying messages on different areas of an operator console. You can specify these attributes on the .MSGCOLR statement in the MPFLSTxx member; however, the console must support the attributes you specify. On the .MSGCOLR statement, you can indicate the display attributes that the system is to use in one of the following ways:

- IBM-supplied defaults (DEFAULT).
- Attributes specified in the previously used MPFLSTxx member or concatenation of MPFLSTxx members (NOCHANGE).
- Color (c), highlighting (h), and intensity (i) attributes specified within MPFLSTxx for a message area (msgarea).

For more information about these definitions, see [Table 55 on page 645](#).

## Syntax for controlling message presentation

The syntax for the .MSGCOLR statement is:

```
.MSGCOLR {DEFAULT} [/*comments*/]
          {NOCHANGE}
          {msgarea(c,h[,i])[,msgarea(c,h[,i])]}...
```

## IBM-supplied defaults for .MSGCOLR

If you do not specify a .MSGCOLR statement, the system uses IBM-supplied defaults. See the following description on the .MSGCOLR statement for these defaults.

If you specify a .MSGCOLR statement with no operands, the system defaults to NOCHANGE. NOCHANGE indicates that the color, highlighting, and intensity attributes are to be the same as those specified in the previously used MPFLSTxx member (or concatenation of MPFLSTxx members).

## Displaying the message presentation attributes for the current MPFLSTxx

You can use the DISPLAY MPF command to list the current color intensity and highlighting specifications for a specific console or for all consoles. For a description of the DISPLAY MPF command, see [z/OS MVS System Commands](#).

## MPFLSTxx parameters for controlling message presentation

### .MSGCOLR

.MSGCOLR indicates the beginning of a statement that defines the display attributes for messages.

#### DEFAULT

DEFAULT causes the system to use the IBM-supplied color, highlighting, and intensity defaults. See the following description on *msgarea*. (Table 56 on page 646 lists the defaults.) If you need to specify a .MSGCOLR DEFAULT statement, specify only one.

If the first .MSGCOLR statement in the MPFLSTxx concatenation specifies DEFAULT, the system ignores any later .MSGCOLR statements, issues an error message, and continues processing any remaining statements.

#### NOCHANGE

NOCHANGE indicates that the color, highlighting, and intensity attributes are to be the same as those specified in the previously used concatenation of MPFLSTxx members. If you need to specify a .MSGCOLR NOCHANGE statement, specify only one. If the MPFLSTxx concatenation does not contain a .MSGCOLR statement, the system defaults to NOCHANGE.

If the first .MSGCOLR statement specifies NOCHANGE, the system ignores any later .MSGCOLR statements, issues an error message, and continues processing any remaining statements. The system uses the color, highlighting, and intensity attributes specified in the previously used concatenation of MPFLSTxx members.

### *msgarea(c,h[,i])*

*msgarea* specifies the message area (message type or field) and contains the accepted values and the defaults for *msgarea*. This operand allows you to specify the color (*c*), highlighting (*h*), and intensity (*i*) attributes for a message area. Table 55 on page 645 summarizes the supported attributes.

| Table 55. Attributes to specify for a message area   |   |  |
|--|---|--|
| Color attributes (c)   | Highlighting attributes (h)   | Intensity attributes (i)   |
| <ul style="list-style-type: none"> <li>• R-Red</li> <li>• W-White</li> <li>• G-Green</li> <li>• B-Blue</li> <li>• P-Pink</li> <li>• Y-Yellow</li> <li>• T-Turquoise</li> </ul> | <ul style="list-style-type: none"> <li>• N-Normal (colored characters on a black background)</li> <li>• B-Blinking</li> <li>• R-Reverse video (black characters on a colored background)</li> <li>• U-Underscored characters</li> </ul> | <ul style="list-style-type: none"> <li>• N-Normal intensity</li> <li>• H-High intensity</li> </ul> |

If you specify a *msgarea*, you must specify the color and highlighting attributes. If you do not, or if the system detects an error in any specified value, it issues an error message, stops checking the statement in error, and continues processing any later statements. The intensity attribute, however, is optional. If you do not specify the intensity attribute, the system uses the IBM-supplied defaults.

If you specify multiple .MSGCOLR statements for the same *msgarea*, the system uses the last valid statements.

These attributes can be overridden by the extended message highlighting options in IEAVMXIT or the MPF exit routines. For more information about coding these exit routines, see [z/OS MVS Installation Exits](#).

Table 56. Values for msgarea

| msgarea Value   | Meaning and Use   | Defaults (c,h,i) |
|---|---|------------------|
| AUTOR   | Specifies attributes for write-to-operator with reply (WTOR) messages that are being monitored by auto-reply processing.  | (W,N,H)          |
| ENTRYARA  | Specifies attributes for the entry area.  | (G,N,N)          |
| EVETACTN  | Specifies attributes for eventual action messages (issued with a descriptor code of 3).   | (G,N,N)          |
| GENMSG  | Specifies attributes for general system messages (issued with a descriptor code other than 1, 2, 3 or 11).  | (G,N,N)          |
| IMEDACTN  | Specifies attributes for immediate action messages (issued with a descriptor code of 2 or WTOR messages).<br><br><b>Note:</b> For a device with limited image capability (such as the 3290), the reverse video highlighting attribute applies only to the action characters (* or @) that precede the message identifier.                                       | (W,N,H)          |
| INSTRERR  | Specifies attributes for error messages that appear in the instruction line.  | (W,N,H)          |
| OOLCNTL   | Specifies attributes for the control line text of an out-of-line status display, not including the selector pen detectable fields on the control line.  | (T,N,N)          |
| OOLDATA   | Specifies attributes for the data lines of an out-of-line status display.   | (G,N,N)          |
| OOLLABEL  | Specifies attributes for the label lines of an out-of-line status display.  | (T,N,N)          |
| PPMSG   | Specifies attributes for non-action messages issued by a problem program (issued with a descriptor code other than 1, 2, 3, or 11).   | (G,N,N)          |
| SELPEN  | Specifies attributes for fields that are selector pen detectable, such as: <ul style="list-style-type: none"> <li>in the control line of an out-of-line display - <ul style="list-style-type: none"> <li>F</li> <li>E</li> </ul> </li> <li>in the control line of an in-line display - <ul style="list-style-type: none"> <li>C</li> </ul> </li> </ul>          | (B,N,N)          |
| URGATTN   | Specifies attributes for urgent attention messages (issued with a descriptor code of 1 for system failure or 11 for critical eventual action).<br><br><b>Note:</b> For a device with limited image capability (such as the 3290), the reverse video highlighting attribute applies only to the action characters (* or @) that precedes the message identifier. | (R,N,H)          |
| WARNLGEN  | Specifies attributes for the left half of the warning line for general messages such as: <ul style="list-style-type: none"> <li>IEE163I MODE=R</li> <li>IEE163I MODE=RD</li> <li>IEE161I WARNING-CON=N, DEL=Y</li> </ul>  | (B,N,N)          |
| WARNRGEN  | Specifies attributes for the right half of the warning line for general messages such as: <ul style="list-style-type: none"> <li>IEE160I UNVIEWABLE MESSAGE</li> </ul>  | (B,N,N)          |
| WARNRURG  | Specifies attributes for the right half of the warning line for urgent attention messages such as: <ul style="list-style-type: none"> <li>IEE159E MESSAGE WAITING</li> </ul>  | (R,B,H)          |
| <b>Note:</b> If you specify EVETACTN, GENMSG, OOLDATA, OOLLABEL, or PPMSG for a device with limited image capability (such as the 3290), the system ignores the reverse video highlighting attribute. |   |                  |

## Controlling message management

MPFLSTxx allows you to specify how you want to process WTO/WTOR messages. *Message management* refers to message suppression, message retention, message automation eligibility, and the use of installation-supplied WTO/WTOR exit routines.

Message suppression means that the message is logged in the hardcopy log, but it does not appear at an MVS operator's console.

Message retention means that action messages are saved by the action message retention facility (AMRF) on the action message retention queue. Retention allows the operator to view the message later. If you choose not to retain a message, the system will not add it to the action message retention queue.

Message automation eligibility means that you are using an automation subsystem to process particular WTO/WTOR messages in a pre-determined way. The automation subsystem (such as Tivoli NetView for z/OS) allows the installation to program the processing for a particular message. For example, your installation might be using an automation subsystem to do the following tasks:

- Modify the text of a message.
- Reroute a message to a different operator's console or to a different system for processing.
- Record some information that is contained in the message text for future use.
- Respond to the message.

An automation subsystem can look at the message text and the message attributes and perform the programmed action. You can use MPFLSTxx to identify whether you want a message to be eligible for automation processing. The automation subsystem must then select and process the messages. You can also use MPFLSTxx to indicate information to pass to an automation subsystem. Messages that are eligible for automation processing can also be suppressed or retained. Message suppression and retention are functions separate from automation. The Tivoli NetView for z/OS subsystem recognizes the message automation eligibility specifications in MPFLSTxx.

Your installation might have installation-written exit routines to handle WTO/WTOR messages. Through MPFLSTxx, you can specify which messages are to go to which exit routine. The exit routine can examine the message text and the message attributes and decide whether to suppress, retain, or take other actions on the message. The exit routine can also examine and modify the token.

## Specifying message management

For the messages that you specify in MPFLSTxx, you can indicate that the system is to:

- Suppress specific messages or all messages that begin with a particular prefix. SUP(YES/NO) provides this option.
- Retain action messages (descriptor codes 1, 2, 3, 11) using the action message retention facility (AMRF). The RETAIN parameter allows you to selectively retain certain types of action messages (immediate, eventual, or critical eventual).
- Allow an automation subsystem, such as NetView, to respond to the WTO/WTOR message(s) that you specify. AUTO(YES/NO/token) allows you to identify whether a message is eligible for automation processing and to pass information (a token) to the automation subsystem.
- Pass control to an installation-supplied WTO/WTOR exit routine to process the message(s). The USEREXIT option allows you to identify the exit routine.
- Assign installation-supplied defaults for specific messages that are identified in the MPFLSTxx member. The .DEFAULT statement allows you to change the system-assigned message processing defaults for any message you specify.
- Assign installation-supplied defaults for messages that are not identified in the MPFLSTxx member. The .NO\_ENTRY statement allows you to indicate how the system is to handle messages that are not specified in the MPFLSTxx member.
- Indicate or flag the beginning of particular messages that are written to the JES3 hard-copy log. The MPFHCF statement allows you to specify the character you want to use as an indicator.

## Syntax for controlling message management

To control message management, MPFLSTxx recognizes one parameter, **msgid**, and four statements: (.DEFAULT, .NO\_ENTRY, MPFHCF, and .MSGIDS)

- **msgid** allows you to specify a particular message id or prefix. This specification is also called the message processing record.
- .DEFAULT allows you to specify the defaults for groups of messages listed in the MPFLSTxx parmlib member.
- .NO\_ENTRY allows you to specify the default processing you want for messages that are not identified in any of the active MPFLSTxx parmlib members. (Note that you must code the underscore (\_) in the statement.)
- MPFHCF allows you to indicate or flag messages that JES3 writes to the hardcopy log. Note that this statement does not begin with a period (.).
- .MSGIDS NOCHANGE allows you to specify that the messages identifiers and the message processing are to be the same as those specified in the previously used concatenation of MPFLSTxx members.

The syntax of the message processing record (msgid) is:

```
msgid      [,AUTO  [(YES)  ] ,RETAIN [(YES)  ] ,SUP [(YES)]]
           [      [(NO)   ]          [(NO)   ]          [(ALL)]]
           [      [(TOKEN)]          [(I,E,CE)]          [(NO)  ]]
           [      [ ,USEREXIT(exitname)] [/*comments*/] ]
```

The syntax of the .DEFAULT statement is:

```
.DEFAULT   [,AUTO  [(YES)  ] ,RETAIN [(YES)  ] ,SUP [(YES)]]
           [      [(NO)   ]          [(NO)   ]          [(ALL)]]
           [      [(TOKEN)]          [(I,E,CE)]          [(NO)  ]]
           [      [ ,USEREXIT(exitname)] [/*comments*/] ]
```

The syntax of the MPFHCF statement is:

```
MPFHCF=[x/&]
```

The syntax for the .MSGIDS statement is:

```
.MSGIDS NOCHANGE
```

The syntax of the .NO\_ENTRY statement is:

```
.NO_ENTRY  [,AUTO  [(YES)  ] ,RETAIN [(YES)  ] ,SUP [(YES)]]
           [      [(NO)   ]          [(NO)   ]          [(ALL)]]
           [      [(TOKEN)]          [(I,E,CE)]          [(NO)  ]]
           [      [/*comments*/] ]
```

For descriptions of these statements and parameters, see [“Statements and parameters for MPFLSTxx”](#) on page 651.

## IBM-supplied defaults for message management

- If you have msgid (message processing) statements in the MPFLSTxx member, the defaults vary and are described in the syntax and parameter descriptions for the msgid , .DEFAULT, and .NO\_ENTRY statements.
- If you do not specify an MPFLSTxx member, the defaults are AUTO(YES), RETAIN(YES), and SUP(NO). The system considers all messages eligible for automation processing, it retains action messages, and displays all messages.

## Listing the message processing attributes for the current MPFLSTxx

You can use the DISPLAY MPF command to list the results of the current MPFLSTxx member. The DISPLAY MPF command displays:

- The messages being suppressed by MPF.
- The action messages that are **not** being retained by the action message retention facility.
- The installation exits that receive control for selected messages.
- The status of the general-use WTO installation exit, IEAVMXIT.

For descriptions of the DISPLAY command, see [z/OS MVS System Commands](#).

**Note:** The DISPLAY MPF command will not display if a message is eligible for automation processing. The hard-copy log, however, will contain the automation tracking indicator.

To diagnose MPF processing, you can also use the hard-copy log to determine the message processing options used for a message.

## Using other methods to suppress messages

WTO/WTOR messages can be suppressed through an MPFLSTxx member and by other methods. When an installation uses more than one method, message suppression is performed in the following order:

1. The message processing facility (MPF) itself suppresses messages.
2. An installation-supplied WTO/WTOR installation exit (either IEAVMXIT or an exit routine you name on the USEREXIT parameter in MPFLSTxx) can suppress messages. (Note that the exit routine can also override MPF suppression. That is, the exit can prevent MPF from suppressing a message.)
3. An active subsystem (such as JES2, JES3, or NetView) can suppress messages.
4. CONTROL V command can suppress messages by specifying only the message levels that are to be displayed at a console. The LEVEL keyword on the CONSOLE statement in the CONSOLxx member of SYS1.PARMLIB controls the message levels for the console.

## Controlling foreign message management

A foreign message is one that is received from another system. MPFLSTxx allows you to specify whether you want subsystems on your system to receive these messages. Many subsystems do not need to see foreign messages. You can reduce the amount of CPU utilized in the CONSOLE address space for foreign message processing by limiting the number of subsystems that receive foreign messages.

## Syntax for controlling message management

To control the management of foreign messages, MPFLSTxx recognizes one statement type .FORNSSI. It specifies whether foreign messages (both WTOs and DOMs) are to be presented to any or all subsystem interface (SSI) exits listening to the WTO and DOM broadcast function codes. The .FORNSSI statement has the following syntax.

```
.FORNSSI  *ALL
          *NONE
          NOCHANGE
          (list of subsystems)
```

## Syntax rules for the .FORNSSI statement

These rules apply specifically to the .FORNSSI statement in addition to the general rules listed in [“General syntax rules for the creation of members”](#) on page 7.

- Only one .FORNSSI statement is allowed. The system rejects any additional .FORNSSI statement and issues message IEF760I.
- A .FORNSSI statement without any operand is treated as a syntax error and the system issues message IEF760I.
- Subsystem names must be separated by a comma and must be enclosed in parentheses, even if the list is composed of only one subsystem name.
- The .FORNSSI statement cannot span to the next record.

## IBM-supplied defaults for foreign message management

If no MPFLSTxx member has ever been set or SET MPF=NO is issued, the system defaults to the \*ALL state.

## Displaying the foreign message processing attributes for the current MPFLSTxx

You can use the DISPLAY MPF command to list the current installation options for handling foreign messages. For a description of the DISPLAY MPF command, see [z/OS MVS System Commands](#).

## MPFLSTxx parameters for managing foreign messages

### .FORNSSI

**.FORNSSI** indicates the beginning of a statement that defines the attributes for handling foreign messages.

### \*ALL

Indicates that all subsystems are to receive foreign messages and DOMs.

### \*NONE

Indicates that no subsystems are to receive foreign messages and DOMs.

### NOCHANGE

Indicates that the system are to retain the previous .FORNSSI statement.

### (list of subsystems)

Indicates one or more subsystems that are to receive foreign messages and DOMs. Subsystems not in this list do not receive foreign messages and DOMs.

## Controlling verbose message production

A *verbose message* is a multi-line message that contains additional lines of explanation. MPFLSTxx allows you to specify whether you want components of your system that support verbose messages to produce verbose messages or not. If you request that verbose messages be produced, they will be included in their entirety in the JOBLOG but the extra lines of explanation will not be included in the SYSLOG or OPERLOG and will not be queued to any consoles.



## Syntax for controlling the production of verbose messages

To control the production of verbose messages, MPFLSTxx recognizes the statement type `.MSGOPTION`. It specifies whether verbose messages are to be produced by the components of your system. The syntax of the `.MSGOPTION` statement is as follows.

```
.MSGOPTION VERBOSE[(Y)]
                  [(N)]
```

## Syntax rules for the `.MSGOPTION` statement

These rules apply specifically to the `.MSGOPTION` statement in addition to the general rules listed in “General syntax rules for the creation of members” on page 7.

- Only one `.MSGOPTION` statement is allowed. The system rejects any additional `.MSGOPTION` statement and issues message IEF760I.
- A `.MSGOPTION` statement without any operand is treated as a syntax error and the system issues message IEF760I.

## IBM-supplied default for verbose message production

If no MPFLSTxx member has ever been set or `SET MPF=NO` is issued, the system defaults to the `VERBOSE(N)` state.

## Displaying the verbose message production setting for the current MPFLSTxx

You can use the `DISPLAY MPF` command to display the current verbose message production setting. For a description of the `DISPLAY MPF` command, see [z/OS MVS System Commands](#).

## MPFLSTxx parameters for managing verbose message production

### **.MSGOPTION**

Indicates the beginning of a statement that defines message processing options.

### **VERBOSE(N)**

Indicates that verbose messages are not to be produced.

### **VERBOSE(Y)**

Indicates that verbose messages are to be produced.

## Statements and parameters for MPFLSTxx

### ***msgid***

Identifies a message or group of messages to be processed. The *msgid* consists of:

- A complete message identifier of one to ten characters. This is known as a *specific* message identifier.
- A message prefix, which is a portion of the message identifier, followed by an asterisk (\*). This is known as a *generic* message identifier.
- A single quotation mark (') is not a valid character in a message identifier.

A message identifier begins with the first nonblank character of the message text and continues until the next blank.

**Note:** The system might insert a character, such as a + or \*, preceding the message identifier. This character is not a part of the message identifier. Do not add it to the *msgid* specification.

You can specify only one *msgid* per record. If a *msgid* is repeated within an MPFLSTxx member, the system uses the options that are specified on the first record and ignores the duplicates.

If you want MPF to process a specific message, you must specify the complete message ID, for example, IEF124I.

If you want MPF to process all messages that begin with a specific prefix, you can specify the prefix and an asterisk, for example, IEF24\*. Use the message prefix with an asterisk carefully. Too wide a suppression, such as IEF\*, could suppress many messages that you need for effective system operation.

With one exception, specific message definitions take precedence over generic message definitions. For example, if you specify both a specific entry for IEF638I, and a generic entry that includes IEF638I (such as IEF63\*), the system uses the specific entry to process IEF638I.

In situations where a message is included by more than one generic message definition, such as IEF6\* and IEF63\*, the most specific definition takes precedence. In this example, the system uses the entry for IEF63\* for message IEF638I, if no specific entry exists.

**Note:** A *msgid* that consists of only a single asterisk (\*) does not mean “all messages,” but rather messages that have a single asterisk as their message identifier.

#### **,AUTO(YES|NO|token)**

Specifies whether the message (*msgid*) is eligible for processing by an automation subsystem, such as Tivoli NetView for z/OS.

##### **NO**

Makes the message ineligible for automation processing.

##### **YES**

Makes the message eligible for automation processing.

##### **token**

The *token* value is available for MPF installation exit processing and for processing by an automation subsystem. Specifying a token indicates that the message is eligible for processing by the automation subsystem. The token value must be 1 to 8 alphanumeric characters. Do not use a left parenthesis as part of the token value. Embedded blanks are allowed in the token value. For example, if you code an ‘N,O, and a blank’, AUTO(NO ), the system takes the “NO” as a token value.

If you specify *msgid* and do not specify the AUTO option, the system defaults to NO. If you do not specify any message processing statements for a message, the system considers the message eligible for automation processing AUTO(YES). To change the system default, use the .DEFAULT or the .NO\_ENTRY statement.

**Note:** A message might loop repetitively to an extended MCS console if all of the following conditions are true:

- AUTO(YES) is specified, and
- The RACF OPERPARM segment specifies AUTO YES for the extended MCS console, and
- The console profile, as defined through TSO/E CONSPROF, specifies YES for the UNSOLDISP parameter or for the SOLDISP parameter or for both.

**Default:** NO

#### **,RETAIN(YES|I,E,CE|NO)**

If the message identified by the *msgid* is an action message (immediate, eventual, or critical eventual), RETAIN specifies whether the message is to be retained by the action message retention facility (AMRF). AMRF retains action messages only (not WTORs).

##### **CE**

Critical eventual action messages are retained.

##### **E**

Eventual action messages are retained.

**I**

Immediate action messages are retained.

**NO**

No action messages are retained.

**YES**

All action messages are retained. YES is the default.

You can specify any combination of I, E, or CE.

To view a retained message, use the DISPLAY R command.

**Default:** YES. You can use the .DEFAULT statement followed by a msgids to change the system default for the list of messages.

**,SUP(YES|ALL|NO)**

Specifies whether MPF is to suppress the message that is identified by *msgid*.

**ALL**

Suppresses all messages that are identified by *msgid*, without exception.

**NO**

Messages that are identified by *msgid* are not suppressed.

**YES**

Suppresses messages that are identified by *msgid*, with the following exceptions:

- Command responses where MCSFLAG=RESP was specified on the WTO or WTOR macro.
- Command responses with descriptor code 5 (immediate command response).

**Note:** This exception does not apply to command responses with descriptor code 5 that are generated in response to the MONITOR command. SUP(YES) suppresses such responses.

If you specify a *msgid* without SUP, the system uses the default, SUP(YES), and does not display the message. If, however, you do not specify any message processing statements for a message, the system displays the message. To change the system defaults, use the .DEFAULT or the .NO\_ENTRY statement.

**Default:** YES

**,USEREXIT(exitname)**

Specifies the name of an installation-supplied WTO/WTOR installation exit routine that is to get control each time the system issues the messages. This routine can process the messages; it can suppress, retain, or respond to a message. It can make the message eligible for automation processing, and take other actions on the message. The exit should be link-edited into an APF-authorized library that is part of the LNKLIST concatenation.

The *exitname* can be from one to eight alphanumeric (A-Z, 0-9) and national characters (&, \*, \$). The first character must be alphabetic or numeric. If you do not specify an exitname, the system uses IEAVMXIT, if it exists. To change the system default, use the .DEFAULT statement.

For more information about the WTO/WTOR installation exits, see Chapter 23, “CONSOLxx (console configuration definition),” on page 201 and [z/OS MVS Installation Exits](#).

**.DEFAULT**

.DEFAULT allows you to specify the defaults that you want for the message processing records (msgids) that follow .DEFAULT. The options you specify on the .DEFAULT statement override the system defaults for messages that you list. On the .DEFAULT statement, you can specify that the message is eligible for automation processing, retention, or suppression, and the installation exit that is to process the message. Through AUTO(token), you can also specify information to be passed to the automation subsystem. .DEFAULT with no options, results in the message being ineligible for automation processing, and indicates that the system is to suppress and retain any listed action messages. IEAVMXIT, if it exists, receives that message.

You can use the .DEFAULT statement multiple times within an MPFLSTxx member. Each group of messages following a .DEFAULT statement should have common option values. This allows you to

control attributes assigned by default to each message ID without having to change every message processing record.

On a particular message record (msgid statement) that follows a .DEFAULT statement, you can specify specific operand values that override, for that message, the .DEFAULT values.

If there are multiple occurrences of a message ID that is listed under one .DEFAULT statement, the system uses the options for the first occurrence and ignores the others.

If an MPFLSTxx member contains multiple .DEFAULT statements, the system uses the values on the .DEFAULT statement that precedes the first message record (msgid statement) in that group.

#### **,AUTO(YES|NO|token)**

Specifies whether a message or a list of messages following the .DEFAULT statement is eligible for processing by an automation subsystem, such as Tivoli NetView for z/OS.

##### **NO**

Subsequent messages are not eligible for automation processing. AUTO(NO) is the system default for the .DEFAULT statement.

##### **YES**

Messages are eligible for automation processing.

##### **token**

The *token* value is available for MPF installation exit processing and for processing by an automation subsystem. Specifying a token indicates that the message is eligible for processing by the automation subsystem. The token value must be 1 to 8 alphanumeric characters. You cannot use a left parenthesis "(" as part of the token value. Embedded blanks are allowed in the token value. For example, if you code an 'N,O, and a blank', AUTO(NO ), the system uses the "NO" as a token value.

#### **Notes:**

1. If you specify a .DEFAULT and omit the AUTO option, the system will not consider the messages eligible for automation processing. If, however, you do not specify any message processing statements for a message, the system considers the message eligible for automation processing.
2. A message might loop repetitively to an extended MCS console if all of the following are true:
  - AUTO(YES) is specified, and
  - The RACF OPERPARM segment specifies AUTO YES for the extended MCS console, and
  - The console profile, as defined through TSO/E CONSPROF, specifies YES for the UNSOLDISP parameter or for the SOLDISP parameter or for both.

**Default:** NO

#### **,RETAIN(YES|I,E,CE|NO)**

RETAIN specifies which subsequent action messages are to be retained by the action message retention facility (AMRF).

##### **E**

Eventual action messages are retained.

##### **CE**

Critical eventual action messages are retained.

##### **I**

Immediate action messages are retained.

##### **NO**

Action messages are not retained.

##### **YES**

All action messages are retained. YES is the default.

You can specify any combination of I, E, or CE. To view a retained message, use the DISPLAY R command.

**Default:** YES

**,SUP(YES|ALL|NO)**

Specifies whether MPF is to suppress subsequent messages.

**ALL**

Suppresses all subsequent messages, without exception.

**NO**

Subsequent messages are not suppressed.

**YES**

Suppresses subsequent messages, with the following exceptions:

- Command responses where MCSFLAG=RESP was specified on the WTO or WTOR macro.
- Command responses with descriptor code 5 (immediate command response).

**Note:** This exception does not apply to command responses with descriptor code 5 that are generated in response to the MONITOR command. SUP(YES) suppresses such responses.

If you specify a .DEFAULT statement without SUP, the system uses the default, SUP(YES), and suppresses subsequent messages.

If you specify a .DEFAULT statement with one of the SUP options, and then specify SUP on a subsequent message record, the system uses the SUP value that is specified on that particular message record.

If you do not specify any message processing statements for a message, the system displays the message, regardless of any SUP value that might have been specified on a preceding .DEFAULT statement.

**Default:** YES

**,USEREXIT(exitname)**

Specifies the name of an installation-supplied WTO/WTOR installation exit routine that is to get control each time the system issues one of the indicated messages. This routine then processes the messages. The exit should be link-edited into an APF-authorized library that is part of the LNKLIST concatenation.

The *exitname* can be from one to eight alphanumeric (A-Z, 0-9) or national characters (@, \$, \*). The first character must be alphabetic or numeric. If you do not specify an *exitname* the system defaults to IEAVMXIT, if it exists.

For more information about the WTO/WTOR installation exits, see [Chapter 23, “CONSOLxx \(console configuration definition\),” on page 201](#), and [z/OS MVS Installation Exits](#).

**MPFHCF=[x/]&**

If JES3 writes the messages to the hardcopy log, this statement specifies the indicator (x) used to identify suppressed messages in the hardcopy log. (JES2 ignores this statement.) The indicator can be any character, including a blank. If x specifies an indicator that is not a printable character, the indicator is translated to a blank.

**Note:** This statement does not begin with a period (.).

**Default:** When MPFHCF is not specified, the default character is an ampersand (&).

**.MSGIDS**

**NOCHANGE**

.MSGIDS NOCHANGE specifies that the message identifiers are to be the same as those specified in the previously used concatenation of MPFLSTxx members (the one the system was previously using). Use this statement with the .MSGCOLR statement.

The .MSGIDS NOCHANGE statement should not be specified in an MPFLSTxx member or a concatenation of MPFLSTxx members that includes message identifiers. If syntactically correct message identifiers (msgid statements) precede the .MSGIDS NOCHANGE statement, the system

ignores the statement, issues an IEF760I error message, and continues processing the remaining statements. If a valid .MSGIDS NOCHANGE statement precedes message identifiers, the system ignores the message identifiers, issues an IEF760I error message, and continues processing the remaining statements.

If multiple .MSGIDS NOCHANGE statements occur in one MPFLSTxx member, or a concatenation of MPFLSTxx members, the system processes each statement as though it were the first statement.

### **.NO\_ENTRY**

.NO\_ENTRY specifies the message processing options for all messages that are not specified in MPFLSTxx members. The options that you specify on the .NO\_ENTRY statement override the system defaults for messages that are not specified in this member. On the .NO\_ENTRY statement, you can specify whether all messages not specified in the MPFLSTxx member are to be considered eligible for automation processing, retained, and suppressed.

.NO\_ENTRY is a very powerful statement and should be used with care.

**Note:** .NO\_ENTRY requires the underscore (\_) in the syntax. You might not, however, be able to print the underscore character on your printer.

If you specify a .NO\_ENTRY statement with no options, the system considers the messages that are not specified in the MPFLSTxx member to be eligible for automation processing, it retains action and WTOR messages, and it displays all messages (AUTO(YES) RETAIN(YES) SUP(NO)). These options are the same defaults that the system uses when no message processing record is specified in an MPFLSTxx member for a particular message.

.NO\_ENTRY checks the syntax and then ignores the USEREXIT(exitname) statement. IEAVMXIT receives control, if it exists.

Specify only one .NO\_ENTRY statement in an MPFLSTxx member. If there is more than one occurrence of a .NO\_ENTRY statement in an MPFLSTxx member, the system checks the syntax of the duplicate and uses the options on the first .NO\_ENTRY statement. If there is more than one occurrence of a .NO\_ENTRY statement in a concatenation of MPFLSTxx members, the system uses the options on the first valid .NO\_ENTRY statement in the concatenation.

### **,AUTO(YES|NO|token)**

For messages that are not identified in MPFLSTxx, AUTO indicates whether the message is eligible for processing by an automation subsystem, such as Tivoli NetView for z/OS. Specifying AUTO without either YES or NO results in a syntax error.

#### **YES**

Messages are eligible for automation processing.

#### **NO**

Messages are not eligible for automation processing.

#### **token**

The *token* value is available for MPF installation exit processing and for processing by an automation subsystem. Specifying a token indicates that the message is eligible for processing by the automation subsystem. The token value must be 1 to 8 alphanumeric characters. You cannot use a left parenthesis, "(", as part of the token value. Embedded blanks are allowed in the token value. For example, if you code an 'N,O, and a blank', AUTO(NO ), the system uses the "NO" as a token value.

#### **Notes:**

1. IEAVMXIT, if it exists, gets control for all messages whose message ids are not specified in the MPFLSTxx member.
2. A message might loop repetitively to an extended MCS console if all of the following are true:
  - AUTO(YES) is specified, and
  - The RACF OPERPARM segment specifies AUTO YES for the extended MCS console, and

- The console profile, as defined through TSO/E CONSPROF, specifies YES for the UNSOLDISP parameter or for the SOLDISP parameter or for both.

**Default:** YES

### **,RETAIN(YES|I,E,CE|NO)**

For all action messages (immediate, eventual, or critical eventual) not identified in MPFLSTxx, RETAIN specifies which messages are to be retained by the action message retention facility (AMRF).

#### **E**

Eventual action messages are retained.

#### **CE**

Critical eventual action messages are retained.

#### **I**

Immediate action messages are retained.

#### **NO**

Action messages are not retained.

#### **YES**

All action messages are retained. YES is the default.

You can specify any combination of I, E, or CE. To view a retained message, use the DISPLAY R command.

**Default:** YES

### **,SUP(YES|ALL|NO)**

Specifies whether MPF is to suppress messages that are not specified in MPFLSTxx members.

#### **ALL**

Suppresses all messages, without exception. SUP(ALL) causes the system to suppress all messages that are not identified in the active MPFLSTxx member. This setting might result in most or all messages being suppressed from the MCS console. Suppression of all messages is useful in certain situations, such as a remote system, but it can be detrimental if an operator is expecting these messages.

#### **NO**

Messages are not suppressed.

#### **YES**

Suppresses messages, with the following exceptions:

- Command responses where MCSFLAG=RESP was specified on the WTO or WTOR macro.
- Command responses with descriptor code 5 (immediate command response).

**Note:** This exception does not apply to command responses with descriptor code 5 that are generated in response to the MONITOR command. SUP(YES) suppresses such responses.

**Default:** NO

## Controlling command processing using MPFLSTxx

---

Besides message management, MPFLSTxx allows you to specify up to six names of command installation exits that let you modify commands to be processed. You can take the following steps in the command installation exits:

- Change the text of commands.
- In a sysplex, change the destination of commands by routing them to a different system for execution.
- Modify a console's authority to use a particular command. That is, you can use the exit to:
  - Authorize the command from a console that normally would not have the authority to issue the command.

- Reject the command from a console that normally would not have the authority to issue the command.
- Execute commands.
- Suppress commands.

The command exits receive control every time a command is issued. For more information about the command installation exit, see [z/OS MVS Installation Exits](#).

## MPFLSTxx parameters for controlling command processing

---

### **.CMD**

.CMD allows you to specify the installation exit(s) that modifies a command issued in a system or sysplex. These installation exits allow you to modify how commands are issued, the command text, or the MCS command authority of the console that is to issue the command.

You can have only one .CMD statement in an MPFLSTxx member. If more than one .CMD statement appears in an MPFLSTxx member (or a concatenation of MPFLSTxx members), the system uses the first occurrence of the .CMD statement.

For more information about the command installation exit, see [z/OS MVS Installation Exits](#).

### **USEREXIT(exitnam1,exitnam2,...)**

USEREXIT specifies the names of one or more command installation exits. Each name can be from one to eight alphanumeric characters. The command installation exit specified by *exitname* receives control when an MVS command is issued. Each installation exit is invoked in the order specified on this statement. You can code up to six unique 8-character command installation exit names on a statement, separating the names with one or more commas or blanks.

### **NOCHANGE**

NOCHANGE specifies that the command installation exits are to be the same as those specified in the previously used concatenation of MPFLSTxx members. NOCHANGE is the default.

The system processes either the .CMD NOCHANGE statement or the installation command exit names (.CMD USEREXIT) depending on which is coded first in MPFLSTxx. The system ignores the second one.

If comments are used on the .CMD statement, at least one blank must separate them from the rest of the data on the statement.

## Deactivating a command exit

There are times when you might want to deactivate a command exit routine, perhaps because its function is not required at particular times or because you want to modify the routine. You can deactivate a command exit routine in either of two ways:

- Specify, on the .CMD statement of the appropriate MPFLSTxx member, the name of a command exit that does not exist in SYS1.LINKLIB, such as 'USEREXIT(NONE)'. Enter the SET MPF=xx command to refresh the MPFLSTxx member.

This action effectively deactivates any command exits that were enabled during the prior MPFLSTxx activation. The system issues an informational message that can be ignored in this case.

- Enter the SET MPF=NO command to disable all active MPFLSTxx members. Remove the exit name from the .CMD statement of the appropriate MPFLSTxx member and enter the SET MPF=xx command to resume MPF processing.

Entering the SET MPF=NO command causes all installation-specified MPF options to be deactivated. IBM-supplied defaults are used until the installation re-activates its MPFLSTxx members.



## Approaches to message suppression using MPFLSTxx

You can use MPFLSTxx for message suppression conservatively or aggressively. In a *conservative* environment, you would suppress messages by identifying the complete ids. You would suppress, however, only messages that are regarded from an operator's perspective as useless.

In an *aggressive* environment, you would suppress messages through the conservative approach and you would possibly choose to suppress all messages from certain components. If you decide to suppress all of the messages from a specific component, make sure that none of the messages have any vital importance to the operator. (Suppressing a message does not affect processing by the Tivoli NetView for z/OS subsystem.) In an aggressive approach, you could also choose to suppress messages that rarely are important to the operator.

There are five lists of suppressible messages. They are examples that you should review according to the environment in which you might use them. Make sure that you review each message and determine whether your installation should suppress it or not. Notice that the list of messages that are considered suppressible in a conservative environment are identified by the full message identifier. In the list of the 'more aggressive' approach to message suppression, the messages are identified by the message prefix followed by an asterisk. The five lists are as follows:

- Conservative set of non-JES or system messages.
- Aggressive set of non-JES or system messages.
- Conservative set of JES2 messages.
- Aggressive set of JES2 messages.
- Conservative set of JES3 messages.

The decision to designate a message eligible for automation processing is independent of the decision to suppress the message. You might want the message suppressed but not processed by automation. The two processes occur independently according to their individual specifications.

The following lists are concerned with suppression, not automation processing.

### Conservative list of suppressible non-JES messages

This section shows example messages. Review each message according to the environment in which it might be used. Make sure that you review each message and determine whether your installation should suppress it or not.

```

ARC0100I SETSYS COMMAND COMPLETED          HSM
ARC0200I TRAP IN MODULE XXX
ARC0208I TRAP FOR ERROR CODE XX
ARC0503I ALLOCATION ERROR, RETURN CODE=XX
ARC0728I VTOC FOR VOLUME XX COPIED TO DATA SET
ARC0734I ACTION=MIGRATE FRVOL=XX TOVOL=XX TRACKS
CSV003I  MODULE NOT FOUND
CSV011I  FETCH FAILED
CSV300I  PROBABLE INVALID RECORD COUNT
DFS035I  BATCH INITIALIZATION COMPLETE
DFS092I  IMS/VS LOG TERMINATED
DFS627I  IMS/VS RESOURCE CLEANUP COMPLETED OR FAILED FOR JOB
DFS629I  IMS TCB ABEND IMS|SYS
DFS2207I IMS/VS LOG(S) BLOCKSIZE=XXX,BUFNO=YYY
DFS2208I XXXX LOGGING IN EFFECT ON IMS/VS ZZZZ
DFS2500I *MDA00 DATABASE/DATASET ALLOCATED/UNALLOCATED
DSI090I  NCCF LOAD FAILED MSG DURING STARTUP
IAT480I  JOB JJJ EXPRESS CANCELLED BY INTERPRETER DSP
ICB402I  VOLUME XXX NOT FOUND IN MSVC INVENTORY
ICB411I  UNABLE TO RESTORE BASE VOLUME XX RECORD
ICH70001I LAST ACCESS AT HH.MM.SS ON YY.DDD
IEA848I  NO DUMP PRODUCED FOR THIS ABEND ...
IEA989I  SLIP TRAP MATCHED
IEA995I  SYMPTOM DUMP OUTPUTIEC070I (VSAM EOB ERROR)
IEC130I  DD STATEMENT MISSING
IEC141I  013-RC (open error)
IEC331I  ABEND MESSAGES
IEC161I  VSAM OPEN ERROR MESSAGES.
IEC705I  TAPE ON device IS label_type

```

```

IEC801I  LNA THRESHOLD TRANS= ...
IEC999I  IFG0TC0A...
IEE043I  SYSTEM LOG DATA SET HAS BEEN QUEUED
IEE400I  THESE MESSAGES CANCELLED - XX
IEF097I  USERID ASSIGNED
IEF125I  LOGGED ON
IEF126I  LOGGED OFF
IEF170I  (53 BYTES OF WTP TEXT)
IEF176I  WTR DDD WAITING FOR WORK
IEF188I  PROBLEM PROGRAM ATTRIBUTES ASSIGNED
IEF196I  ALLOCATION
IEF202I  STEP sss WAS NOT RUN BECAUSE OF cde
IEF236I  ALLOCATION FOR job
IEF237I  ALLOCATED TO
IEF287I  DSN DISP VOL SER NOS =
IEF288I  dsn SYSOUTIEF403I  job STARTED
IEF404I  job ENDED
IEF450I  JOB ABEND
IEF452I  JOB NOT RUN JCL ERROR
IEF453I  JOB FAILED JCL ERROR
IEF677I  WARNING MESSAGE(S) FOR JOB JOBNAME ISSUED
IEF722I  JOB FAILED - SECURITY REASON
IEF861I  FOLLOWING RESERVED DATA SET NAMES UNAVAILABLE TO JOB
IEF863I  DSN=DSNAME
IKJ144I  UNDEFINED USER(S) XXX
IKJ572I  USER(S) XXX NOT LOGGED ON
IKJ605I  USER(S) XXX NOT LOGGED ON
IKJ606I  USERID ALREADY LOGGED ON
IKT100I  USERID CANCELLED DUE TO UNCONDITIONAL LOGOFF
IKT108I  USERID RECEIVE ERROR,RPLRTNCD=XX ETC.
IOS050I  CHANNEL DETECTED ERROR
IOS071I  (MIH message)
IST234I  I/O ERROR ON TERMINAL XXX
IST259I  INOP RECEIVED FOR NODENAME
IST521I  GBIND QUEUED FOR COS ETC
IST522I  ERNN ACTIVATION FAILED ...
IST523I  REASON =
IST530I  GBIND PENDING MESSAGE
IST532I  EVENT ID MESSAGE
IST619I  ID FAILED - RECOVERY IN PROGRESS
IST621I  RECOVERY SUCCESSFUL FOR NETWORK NODE

```

## Aggressive list of suppressible non-JES messages

For a more aggressive approach to message suppression of non-JES messages, you might choose to add the message prefixes in this section to the conservative list in [“Conservative list of suppressible non-JES messages”](#) on page 659. The following are examples. Review each message according to the environment in which it might be used. Make sure that you review each message and determine whether your installation should suppress it or not.

```

ADM*      ALL ADMPRINT MSGS
AHL*      ALL GTF MESSAGES
DFH1500    CICS INITIALIZATION MESSAGES
DFS0433    NUMBER OF BUFFERS FOR SUBPOOL SIZE NNN INCREASED
DFS0435    NUMBER OF BUFFERS INVALID ON CARD N
DFS0540    DFSZDC00 PROGRAM=, CKPTID=,
DFS0730    UNABLE TO OPEN/CLOSE DATASET WITH DDNAME ...
DFS391I    (Variable message from utility)
DFS826I    BLDL FAILED FOR FOLLOWING DBDs
DFS830I    BLDL FAILED FOR FOLLOWING PSBS;
DFS840I    INDEX ERROR ...
IAT7903    JOB JJJ HELD OUTPUT PURGED
IKF*      ALL COBOL MESSAGESERB*      RMF MESSAGES
IBM*      ALL PLI MESSAGES TO PROGRAMMER
IEC03*     B37-D37-E37 ETC. ABENDS
IEF251I    JOB CANCELLED
IFO*      ALL ASSEMBLER F MESSAGES
IFY*      ALL VS FORTRAN MESSAGES
VPW004*    VPW CLASS DEST STATUS      VIRTUAL PAPER WRITER
VPW012*    VPW IO ERROR(READ) INPUTDCB
VPW016*    VPW NO CATALOG POINTER

```

## Conservative list of suppressible JES2 messages

To suppress JES2 messages through MPF processing, you must specify the \$ prefix and the appropriate message identifier. If you have more than one JES2 subsystem, you must specify the message to be suppressed by MPF for each subsystem. This section shows examples. Review each message according to the environment in which it might be used. Make sure that you review each message and determine whether your installation should suppress it or not.

```
$HASP001 R,TEXT VIA $DM
$HASP002 AUTOMATIC COMMANDS HALTED
$HASP100 ON TSORDR/INTRDR/ETC..... RDR
$HASP101 jobname HELD
$HASP110 jobname -- ILLEGAL JOB STATEMENT
$HASP111 jobname -- INVALID /*ROUTE CARD
$HASP112 jobname -- INVALID /*JOBPARM CARD
$HASP113 jobname -- INVALID /*OUTPUT CARD
$HASP114 jobname -- INVALID EXECUTION MODE
$HASP115 jobname -- INVALID /*NETACCT CARD
$HASP116 jobname -- INVALID /*NOTIFY CARD
$HASP117 jobname -- INVALID /*XMIT CARD
$HASP118 jobname -- INVALID /*CONTROL STATEMENT
$HASP120 DEVNAME COMMAND (e.g. INTRDR $VS,'CMD')
$HASP125 SKIPPING FOR JOBCARD
$HASP160 devname - INACTIVE
$HASP165 ENDED ...
$HASP200 XX STARTED ON LINEX
$HASP203 XX DISCONNECTED FROM LINEX
$HASP208 xxx SCHEDULED FOR yyy SNA,VTAM,...
$HASP210 SESSION zzzz LOGGED OFF LINElna
$HASP240 MESSAGES TO INACTIVE SPOOL MEMBER DISCARDED
$HASP244 XX INVALID COMMAND
$HASP249 NX command-text
$HASP250 JOB XXXXXXXXX IS PURGED
$HASP301 JOBNAM - DUPLICATE JOB NAME - JOB DELAYED
$HASP309 INIT XX INACTIVE
$HASP310 XXX TERMINATED AT END OF MEMORY
$HASP395 JOBNAM ENDED
$HASP396 XXX TERMINATED
$HASP503 ERROR PROCESSING NCC RECORD RECEIVED
$HASP520 XXX ON devname
$HASP524 devname INACTIVE
$HASP530 XXX jobname on devname
$HASP532 jobname devname RESTARTED
$HASP534 devname INACTIVE
$HASP540 jobname ON devname
$HASP543 jobname devname DELETED
```

## Aggressive list of suppressible JES2 messages

For a more aggressive approach to message suppression of JES2 messages, you might chose to add the messages in this section to the preceding conservative list. These messages are examples. Review each message according to the environment in which it might be used. Make sure that you review each message and determine whether your installation should suppress it or not.

```
$HASP150 OUTGRP ON device
$HASP308 jobname - ESTIMATED TIME EXCEEDED
$HASP373 jobname STARTED - INIT xx
$HASP375 jobname ESTIMATE EXCEEDED BY
$HASP406 jobname WAS EXECUTING
```

## Conservative list of suppressible JES3 messages

With JES3, there is no particular category of messages that are generally suppressible. Therefore, the list contains only specific messages identified by complete message identifiers. This section shows examples. Review each message according to the environment in which it might be used. Make sure that you review each message and determine whether your installation should suppress it or not.

```
IAT1600 LINES EXCEEDED
IAT2000 JOB SELECTED
IAT2002 LSTOR= ALLOC= ...
IAT2003 MPAINIT= DI= ...
```

```

IAT2006    PREMATURE JOB TERM
IAT2007    GMS CONNECT - JOB JOBNO ...
IAT5200    JOB IN SETUP ON MAIN
IAT5918    MAIN JES3 V (VERIFY DESCRIPTION)
IAT6101    JOB IS PRTY (job read in)
IAT6108    JOB (NOTIFY TEXT)
IAT6118    CARDS FLUSHED
IAT6160    JOB NET DJNET NOW ENTERING SYSTEM
IAT6201    JOB JOBNO=JJJ JOBS ...
IAT6306    JOB IS DSPNAME
IAT7001    JOB IS ON WRITER
IAT7007    JOB IS ON WRITER, PURGED
IAT7100    (INTERCOM cmd from dsp)
IAT7120    IO ERROR ON CONSOLE
IAT7310    NEW DJNET HAS COMPLETED
IAT7450    JOB PURGED
IAT7530    IO ERROR ON LINE
IAT9123    DATA RECEPTION ACTIVE ON LINE
IAT9124    JOB RECEPTION ACTIVE ON LINE
IAT9127    JOB IS FROM NODENAME
IAT9190    JOB IS BEING SENT ON LINE
IAT9191    JOB SENT TO NODE

```

## Examples of MPFLSTxx members

The contents of MPFLSTxx depend on the goals of your specific installation. The following five examples show possible contents of MPFLSTxx.

**Example 1:** Figure 27 on page 662 assumes that you want to create a parmlib member named MPFLST7C to accomplish the following tasks:

- Suppress some frequently issued JES2, MONITOR, and general messages that are of no interest to the operator or to automation processing.
- Set the color and highlighting attributes of messages to display eventual action messages in pink and non-action messages issued by problem programs in yellow.

The SET MPF=7C command establishes this list of messages as those that are to be suppressed and ignored by an automation subsystem, and also sets the color and highlighting attributes for eventual action and non-action messages. The system uses the IBM-supplied defaults for all other message types or console fields.

```

$HASP100
$HASP101
$HASP150
$HASP165
$HASP200
$HASP250
$HASP309
$HASP373
$HASP375
$HASP395
IEC130I
IEC705I
IEF125I
IEF126I
IEF165I
IEF170I
IEF236I
IEF237I
IEF403I
IEF404I
.MSGCOLR EVETACTN(P,N),PPMSG(Y,N)

```

Figure 27. Example: Creating parmlib member MPFLST7C

**Example 2:** Figure 28 on page 663 assumes that you want to create a parmlib member named MPFLSTDF to accomplish the following tasks:

- Reset the color, highlighting, and intensity attributes to the IBM-supplied default values.

- Suppress, retain, and mark eligible for automation processing the same messages as specified in the previously active concatenation of MPFLSTxx parmlib members.

```
.MSGCOLR DEFAULT
.MSGIDS NOCHANGE
```

Figure 28. Example: Creating parmlib member MPFLSTDF

**Example 3:** Figure 29 on page 663 assumes that you want to create a parmlib member named MPFLSTRV to accomplish the following tasks:

- Display all messages in reverse video (that is, the characters are to appear in black on a colored background).
- Display eventual action messages in pink and non-action messages that are issued by problem programs in yellow.
- Suppress, retain, and mark eligible for automation processing the same messages as specified in the previously active concatenation of MPFLSTxx parmlib members.

```
.MSGCOLR URGATTN(R,R),IMEDACTN(W,R),EVETACTN(P,R)
.MSGCOLR GENMSG(G,R),PPMSG(Y,R),SELPEN(B,R)
.MSGCOLR INSTRERR(W,R),ENTRYARA(G,R),WARNLGEN(B,R)
.MSGCOLR WARNRGEN(B,R),WARNRURG(R,R),OOLCNTL(T,R)
.MSGCOLR OOLLABEL(T,R),OOLDATA(G,R)
.MSGIDS NOCHANGE
```

Figure 29. Example: Creating parmlib member MPFLSTRV

**Example 4:** Figure 30 on page 663 shows how to create a parmlib member named MPFLST18 to:

- Display all messages of the form IECxxxx and have control pass to an installation-supplied WTO/WTOR installation exit routine each time the system prepares to issue such a message.
- Suppress certain IEFxxxx messages and have control pass to an installation-supplied WTO/WTOR installation exit routine each time the system prepares to issue one of the messages.
- Allow action message IEE601E to be displayed at the operator console but not be retained by the action message retention facility.

```
IEC*,SUP(NO),USEREXIT(usrexit1) /*usrexit1 handles IEC messages*/
IEF170I,SUP(YES),USEREXIT(usrexit2)
IEF236I,SUP(YES),USEREXIT(usrexit2)
IEF237I,SUP(YES),USEREXIT(usrexit2)
IEF403I,SUP(YES),USEREXIT(usrexit2)
IEE601E,SUP(NO),RETAIN(NO) /*display only*/
```

Figure 30. Example: Creating parmlib member MPFLST18

**Example 5:** Figure 31 on page 664 shows how to create a parmlib member named MPFLST02 to:

- Specify that messages not identified in this member are not eligible for automation processing.
- Establish the default for specific messages so that they are eligible for automation processing, suppressed, retained, and passed to an installation exit. Override this default for one particular message and have it displayed.
- Establish the default for specific messages so that they are eligible for automation processing, suppressed and retained. Display one specific message.
- Establish the default for specific messages so they are not retained. They are displayed and passed to an installation exit for processing. The installation exit must turn off automation processing and use the token to select a console to reroute the message to.

- The last .DEFAULT statement with no options specified sets the defaults for the subsequent list of messages to AUTO(NO) RETAIN(YES) and SUP(YES) and the messages are passed to IEAVMXIT, if it exists.

```

/*
/* DO NOT AUTOMATE THOSE MESSAGES NOT SPECIFIED IN MPFLST
/*
.NO_ENTRY,AUTO(NO)
/*
/* AUTOMATE CONSOLE BUFFERS AND USE MPF EXIT
/*
.DEFAULT,AUTO(YES),USEREXIT(COMMTASK)
IEA405E                /*WTO BUFFER SHORTAGE - 80% FULL*/
IEA404A,SUP(NO)        /*SEVERE WTO BUFFER SHORTAGE - 100% FULL
                        ALSO TELL OPER WHY JOBS IN WAIT*/
IEA406I                /*TO BUFFER SHORTAGE RELIEVED*/
/*
/* AUTOMATE PRODUCTION JOB STATUS MESSAGES
.DEFAULT,AUTO(YES)
IEF402I,SUP(NO)        /*JJJ FAILED IN ADDRESS SPACE X
                        SYSTEM ABEND SXXX REASON - RC
                        NOTIFY OPER OF FAILURE */
IEF403I                /*JJJ-STARTED */
IEF404I                /*JJJ-ENDED */
/*
/* REROUTE THE TAPE MESSAGES
/*
/* - AUTO TOKEN USED BY EXIT TO SELECT CONSOLE FOR MESSAGE
/* - EXIT MUST TURN OFF AUTOMATION (IMPLIED BY TOKEN USE)
/* - REROUTE EXIT WILL SEND MESSAGE TO PROPER CONSOLE
/*
.DEFAULT,RETAIN(NO),USEREXIT(REROUTE),AUTO(TAPEPOOL),SUP(NO)
IEF233*                /* M DDD,SER,LABEL,JJJ,SSS,DSN */
IEF234E                /* K/D/R DDD,SER PVT/PUB/DTR, JJJ,SSS,SPACE*/
IEC400A                /* M DDD,SER/DSN*/
IEC401A                /* F DDD,SER/DSN*/
IEC402D                /* F DDD,SER/DSN*/
IEC403A                /* M DDD,SER*/
IEC501*                /* M DDD,SER,LABEL,DENSITY,JJJ,SSS,DSN*/
IEC507D                /* E DDD,SER,JJJ,SSS,DSN*/
IEC509A                /* F DDD,SER,JJJ,SSS,DSN*/
/*
/*      RESET DEFAULT FOR OLD LIST
/*      (FROM A DIFFERENT MPFLSTxx MEMBER)
.DEFAULT
IEC*
IEF170I
IEF236I
IEF237I
IEF403I
IEE601E

```

Figure 31. Example: Creating parmlib member MPFLST02

## Chapter 77. MSGFLDxx (message flood automation parameters)

Use the MSGFLDxx member to define your installation policy for controlling message flooding situations, where xx should be alphabetic, numeric, or national characters. Special characters are not supported.

The following statements are provided:

- The comment statement indicates commentary information.
- The msgtype statement indicates the type of message that the parameters apply to.
- The DEFAULT statement specifies the default action to be taken for a specific address space that exceeds the job threshold message rate (JOBTHRESH / INTVLTIME) or a specific message that exceeds the message threshold message rate (MSGLIMIT / INTVLTIME). The built-in defaults apply otherwise.
- The DEFAULTCMD statement specifies the default command that will be issued if a CMD action has been specified for the address space.
- The JOB statement identifies up to 64 specific jobs for which specific actions are to be taken if REGULAR or ACTION messages from the job are involved in a message flooding situation. During intensive mode processing, if the specified job requires action to be taken against it, the actions will be taken from those specified on the JOB statement. You can use the JOB statement to override the DEFAULT (or built-in) actions for this specific job.
- The MSG statement defines up to 1024 specific messages for which specific actions are to be taken if the message is involved in a message flooding situation.

### Parameter in IEASYSxx (or issued by the operator)

There is no IEASYSxx parameter to set MSGFLD=xx, but the MSGFLDxx suffix can be specified in CONSOLxx. It can also be set at any time using the SET MSGFLD= command.

When MSTRJCL=(xx[,L]) is specified on IEASYSxx, JCL messages issued for master scheduler processing are routed to consoles that receive operator information (routing code 2) or system/error maintenance (routing code 10) messages. Use MSTRJCL=(xx[,L]) only for debugging purposes. See [Chapter 56](#), “IEASYSxx (system parameter list),” on page 421.

#### SET MSGFLD=xx

The two characters xx indicate the MSGFLDxx member that contains the parameters and actions for message flood automation processing. You can use alphabetic, numeric, or national characters to specify the two characters xx. Do not use special characters.

### Syntax rules for MSGFLDxx

The following syntax rules apply to MSGFLDxx:

- All statements must begin in column 1 or they are ignored. (Statements with a blank in column 1 are ignored.)
- Statements are 80 columns in length, but only the first 71 columns are processed. Columns 72-80 are ignored. Specifications extending beyond column 71 are truncated without detection or warning.
- Any statement may be repeated if all of its parameters will not fit on a single statement.
  - If a parameter is specified on more than one statement, the specification on the last statement is the one that is used.
  - If a parameter is specified more than once on a statement, the rightmost specification is the one that is used.

- If mutually-exclusive parameters (such as LOG/NOLOG) are specified on more than one statement, the parameter specified on the last statement is the one that is used.
- If mutually-exclusive parameters are specified on a single statement, the rightmost specification is the one that is used.
- An asterisk \* in column 1 indicates that the rest of the record is a comment.
- The /\* characters in column 1 and 2 also indicate that the rest of the record is a comment. You do not need to supply the \*/ characters but, if you supply them, they will be accepted. The comment is considered ended at the end of the record; it does not extend to the next record.

## IBM-supplied default for MSGFLDxx

---

If message flood automation is enabled by either:

- Specifying MSGFLD=(NONE,(ON)) on a CONSOLxx INIT statement, or
- Issuing a SETMF ON command before a MSGFLDxx parmlib member has been read using a SET MSGFLD=xx command,

the following built-in defaults are used :

- REGULAR parameters:

```
REGULAR MSGTHRESH=50
REGULAR JOBTHRESH=20
REGULAR INTVLTIME=1
REGULAR SYSIMTIME=2
REGULAR JOBIMTIME=2
```

REGULAR actions: LOG, AUTO, NODISPLAY, NOCMD

- ACTION parameters:

```
ACTION MSGTHRESH=50
ACTION JOBTHRESH=20
ACTION INTVLTIME=1
ACTION SYSIMTIME=2
ACTION JOBIMTIME=2
```

ACTION actions: LOG, AUTO, NODISPLAY, NOCMD, NORETAIN

- SPECIFIC parameters:

```
SPECIFIC MSGTHRESH=50
SPECIFIC MSGLIMIT=20
SPECIFIC INTVLTIME=1
SPECIFIC SYSIMTIME=2
SPECIFIC MSGIMTIME=2
```

SPECIFIC actions: LOG, AUTO, NODISPLAY, NORETAIN, NOIGNORE

- SPECIFIC message set:

```
IOS000I NOLOG,NOAUTO,NODISPLAY
IOS002A NOLOG,NOAUTO,NODISPLAY
IOS017I NOLOG,NOAUTO,NODISPLAY
IOS107I NOLOG,NOAUTO,NODISPLAY
IOS109E NOLOG,NOAUTO,NODISPLAY
IOS251I NOLOG,NOAUTO,NODISPLAY
IOS291I NOLOG,NOAUTO,NODISPLAY
IOS444I NOLOG,NOAUTO,NODISPLAY
IOS450E NOLOG,NOAUTO,NODISPLAY
IEA476E NOLOG,NOAUTO,NODISPLAY
IEA491E NOLOG,NOAUTO,NODISPLAY
IEA494I NOLOG,NOAUTO,NODISPLAY
IEA497I NOLOG,NOAUTO,NODISPLAY
```

This message set was chosen to handle message floods that can occur during the GDPS HyperSwap IPL processing. Note that the IEA497I message has continuation messages that are issued as separate single line messages, without message IDs. These separate messages are not handled.



When a MSGFLDxx parmlib member is read, message flood automation first replaces any parameters that it was using with the built-in default values. It then replaces those values with any values specified in the parmlib member. This ensures that message flood automation always has valid policy values that it can use. The exception to this are the built-in SPECIFIC messages which are automatically deleted by the first MSGFLDxx PARMLIB member read.

## Statements and parameters for MSGFLDxx

MSGFLDxx provides the following statement types:

- comment statement
- msgtype statement
- DEFAULT statement
- DEFAULTCMD statement
- JOB statement
- MSG statement

### Syntax of the comment statement

A comment statement is indicated by placing an asterisk (\*) in column 1 or by placing an open comment specification (/\*) in columns 1 and 2. There is no need to place a closing comment specification on the statement although it is good practice to do so.

### Syntax and parameters of the msgtype statement

A msgtype statement identifies the type of message that any following DEFAULT, DEFAULTCMD, JOB, and MSG statements apply to. The msgtype statement has the following syntax form.

```
msgtype keyword=value[,keyword=value]
```

#### **msgtype**

The message type, which is one of the following specifications:

- REGULAR
- ACTION
- SPECIFIC

#### **keyword**

The parameter name, which is one of the following specifications:

- INTVLTIME
- JOBIMTIME (not supported for msgtype SPECIFIC)
- JOBTHRESH (not supported for msgtype SPECIFIC)
- MSGIMTIME (not supported for msgtype REGULAR and ACTION)
- MSGLIMIT (not supported for msgtype REGULAR and ACTION)
- MSGTHRESH
- SYSIMTIME

#### **value**

The parameter value.

- For JOBTHRESH, MSGLIMIT and MSGTHRESH: a positive, nonzero integer count of messages in the range 1 to 999999999
- for INTVLTIME: a positive, nonzero integer time in seconds in the range 1 to 999999999

- For SYSIMTIME, JOBIMTIME and MSGIMTIME: a positive, nonzero floating point time in seconds in the range 0.000001 to 16777215.0

**Notes:**

1. Floating point fractions such as 0.1 might not be stored exactly because of limitations of the floating point format.
2. For msgtype REGULAR and ACTION, the JOBTHRESH value must be less than the MSGTHRESH value.
3. For msgtype SPECIFIC, the MSGLIMIT value must be less than the MSGTHRESH value.

**Syntax rules:** Syntax rules:

- The *msgtype* specification must begin in column 1 and must be separated from the first keyword by a single blank character.
- The *keyword* and the value are separated by an equal (=) character. There must be no blank characters on either side of the equal character.
- *keyword=value* pairs are separated by a comma. There must be no blank characters on either side of the comma.
- If *value* is a floating point number, it does not need to contain a decimal point unless a fractional value is being specified. The specifications 1.0 and 1. and 1 are equivalent as are 0.25 and .25.
- Comment text follows the last *keyword=value* pair. There must be at least one blank character between the value and the beginning of the comment text. There is no need to preface the comment text with either an asterisk (\*) or open comment specification (/ \*).

**Example :**

```
REGULAR MSGTHRESH=50, JOBTHRESH=20, INTVLTIME=1 comment
REGULAR SYSIMTIME=0.125, JOBIMTIME=0.25
```

## Syntax and parameters of the DEFAULT statement

The DEFAULT statement specifies the default action to be taken for a specific address space that exceeds the job threshold message rate (JOBTHRESH / INTVLTIME) or a specific message that exceeds the message threshold message rate (MSGLIMIT / INTVLTIME). The built-in defaults apply otherwise. The DEFAULT statement has the following syntax form.

```
DEFAULT action[,action]
```

The DEFAULT statement applies to the previously specified *msgtype*. Zero or more DEFAULT statements should follow each *msgtype* statement.

**action**

The default action to be taken. It can be one of the following specifications:

**AUTO | NOAUTO**

Determines whether the message is queued to an EMCS console for automation.

**CMD | NOCMD**

Determines whether the command that is defined by the DEFAULTCMD statement is issued. Not valid for *msgtype* SPECIFIC.

**DISPLAY | NODISPLAY**

Determines whether the message is queued to a console for display.

**IGNORE | NOIGNORE**

Determines whether message flood automation is to process the message. Not valid for *msgtype* ACTION or REGULAR.

**LOG | NOLOG**

Determines whether the message is written to the SYSLOG or OPERLOG.

**RETAIN | NORETAIN**

Determines whether the message is retained by the action message retention facility (AMRF). Not valid for *msgtype* REGULAR.

**Note:** Specifying NOLOG, NODISPLAY, and NOAUTO together results in the message being deleted. Deleted messages are not sent to the console address space or to other systems in the sysplex.

**Syntax rules:** Syntax rules:

- The DEFAULT specification must begin in column 1 and must be separated from the first action by a single blank character.
- The *action* parameter specifications are separated by a comma. There must be no blank characters on either side of the comma.
- Comment text can follow the last action. There must be at least one blank character between the action and the beginning of the comment text. You do not have to preface the comment text with either an asterisk (\*) or open comment specification (/).

**Example:**

```
DEFAULT LOG,NOAUTO,NODISPLAY,NOCMD
```

**Syntax and parameters of the DEFAULTCMD statement**

The DEFAULTCMD statement specifies the default command that is issued if a CMD action was specified for the address space. The DEFAULTCMD statement has the following syntax form.

```
DEFAULTCMD 'cmdchr[ASIDchar],cmdtext'
```

The DEFAULTCMD statement applies to the previously specified *msgtype*. Although more than one DEFAULTCMD statement can be supplied, only the last statement specified is actually configured for the message type.

**ASIDchar**

An optional single character that can be used later in the *cmdtext* to indicate where an address space identifier (ASID) should be substituted. *ASIDchar* must be different than the *cmdchr*. Only a single substitution is performed. The ASID is provided in printable hexadecimal, suitable for use in the CANCEL command.

**cmdchr**

A single character that can be used later in the *cmdtext* to indicate where the jobname should be substituted. Only a single substitution is performed.

**cmdtext**

Any valid z/OS or subsystem command. The maximum length is limited to 56 characters.

**Notes:**

1. The DEFAULTCMD specification does not apply to *msgtype* SPECIFIC.
2. Your security product might prevent you from issuing the command that you specified on the DEFAULTCMD statement. Because the command is issued from the address space that is causing the flood, the address space causing the flood must be authorized to issue the command. In terms of RACF, this means that the address space must have sufficient access authority. For example, to issue the MVS CANCEL command, UPDATE access authority is required.

**Syntax rules:**

- The DEFAULTCMD specification must begin in column 1 and must be separated from the opening quotation mark character of the command specification by a single blank character.
- The *cmdchr* character should be chosen so that it does not conflict with any special characters or punctuation characters that are used in the *cmdtext*.

- The *cmdchr* character must not have blank characters either before it or after it.
- The *cmdchr* is separated from the *cmdtext* by a comma. There must be no blank characters on either side of the comma. Message flood automation treats whatever follows the comma as the *cmdtext*.
- The *cmdtext* is any valid z/OS or subsystem command. There is no practical way for message flood automation to check the correctness of this command, so it is important that the command be specified correctly. An improperly specified command results in an error when message flood automation attempts to issue it.

The *cmdtext* can include special characters and punctuation characters. If single-quoted characters are used as part of the *cmdtext* specification, two single-quoted characters must be specified for each desired single-quoted character in the command text that will be used.

- Comment text can follow the closing quotation mark character. There must be at least one blank character between the quotation mark and the beginning of the comment text. There is no need to preface the comment text with either an asterisk (\*) or open comment specification (/).

**Example: :**

```
DEFAULTCMD '#,CANCEL #' z/OS cancel job
DEFAULTCMD '#,*CANCEL,SY1,#' JES3 cancel job
DEFAULTCMD '#,SEND '#' is issuing a lot of messages',BRDCST'
DEFAULTCMD '&%,CANCEL &,A=%'
```

## Syntax and parameters of the JOB statement

JOB statements identify up to 64 specific jobs for which specific actions are to be taken if REGULAR or ACTION messages from the job are involved in a message flooding situation. During intensive mode processing, if the specified job requires action to be taken against it, the actions are taken from those specified on the JOB statement. You can use the JOB statement to override the DEFAULT (or built-in) actions for this specific job. The JOB statement has the following syntax form.

```
JOB jobname [action][,action]
```

The JOB statement applies to the previously specified REGULAR or ACTION *msgtype* statements. Zero to 64 JOB statements should follow each REGULAR or ACTION *msgtype* statement.

### **action**

If specified, is one or more of the actions as defined for the DEFAULT statement. If an action is not specified, the DEFAULT or built-in default actions are used.

### **jobname**

The job name, which is 1 to 8 characters in length. You can use wildcard characters \* and % when you specify a job name:

- An asterisk (\*) matches a substring of any characters for any length (0 to n).
- A percent sign (%) matches a single character.

**Note:** Message flood automation assigns the job name NONAME to operating system services that issue messages that are not attributable to a particular job. The system assigns the name IEESYSAS to system services that occupy their own address spaces. Message flood automation cannot distinguish the difference between started tasks running in different address spaces with the same name.

### **Syntax rules:**

- The JOB specification must begin in column 1 and must be separated from the *jobname* by a single blank character.
- The *jobname* is separated from the first *action*, if specified, by a single blank character. More than one blank character causes any following string to be treated as comment text.
- The *action* parameter specifications are separated by a comma. There must be no blank characters on either side of the comma.

- Comment text can follow the last action. There must be at least one blank character between the action and the beginning of the comment text. If *action* is not specified, there must be at least two blank characters. There is no need to preface the comment text with either an asterisk (\*) or open comment specification (/).

**Example:**

```
JOB PROD1001
JOB PROD1002  comment: note >1 blank required before comment
JOB PROD1003 LOG,NOAUTO
JOB PROD1004 LOG,NOAUTO comment: note only 1 blank required
JOB AOC%NV* LOG,AUTO,RETAIN
JOB LLA* LOG,AUTO
```

## Syntax and parameters of the MSG statement

MSG statements define up to 1024 specific messages for which specific actions are to be taken if the message is involved in a message flooding situation. The MSG statement has the following syntax form.

```
MSG msgid [action][,action]
```

The MSG statement applies to the previously specified SPECIFIC *msgtype* statement. One to 1024 MSG statements should follow the SPECIFIC *msgtype* statement.

**action**

If specified, is one or more of the actions as defined for the DEFAULT statement. CMD is not supported. If an action is not specified, the DEFAULT or built-in actions are taken for the message. You can use an MSG statement to override the DEFAULT or built-in actions to be taken for a specific message. If IGNORE is specified, the message is ignored by message flood automation and no action is taken for the message even if the message threshold is exceeded and other actions are specified.

**msgid**

A 1-to-10 character message identifier. Up to the first 10 characters of the first blank-delimited token in the message is treated as the message identifier.

Message flood automation treats everything in the message up to the first blank as the message ID. If the message ID in the message is followed immediately by a special character before the first blank, the special character is treated as part of the message ID and must be specified for a match to occur. Also, message flood automation can handle message IDs with embedded special characters without problem, for example, message IDs that include embedded "-" characters.

**Note:** The *msgid* identifier does not support wildcard specifications.

**Syntax rules:**

- The MSG specification must begin in column 1 and must be separated from the *msgid* by a single blank character.
- The *msgid* is separated from the first action, if specified, by a single blank character. More than one blank character causes any following string to be treated as comment text.
- *action* specifications are separated by a comma. There must be no blank characters on either side of the comma.
- Comment text may follow the last action. There must be at least one blank character between the action and the beginning of the comment text. If *action* is not specified, there must be at least two blank characters. There is no need to preface the comment text with either an asterisk (\*) or open comment specification (/).

**Example:**

```
MSG IAT1001
MSG IAT1002  comment: note >1 blank required before comment
MSG IAT1003 LOG,NOAUTO
MSG IAT1004 LOG,NOAUTO comment: note only 1 blank required
```

```
MSG IOS000I NOLOG,NODISPLAY
MSG DSI064A NOLOG,NODISPLAY,NORETAIN
```

### Suggested MSG specifications to handle specific conditions:

Provide MSG specifications for the following messages that can be produced if an ESCON Director or FICON switch fails:

```
IOS001E
IOS050I
IOS051I
IOS071I
IOS251I
IOS444I
IOS450E
```

Provide MSG specifications for the following messages that might be produced if a device fails:

```
IOS003A
```

Provide MSG specifications for the following messages if you perform HyperSwaps or are in a GDPS environment:

```
IOS000I NOLOG,NOAUTO,NODISPLAY
IOS002A NOLOG,NOAUTO,NODISPLAY
IOS017I NOLOG,NOAUTO,NODISPLAY
IOS107I NOLOG,NOAUTO,NODISPLAY
IOS109E NOLOG,NOAUTO,NODISPLAY
IOS251I NOLOG,NOAUTO,NODISPLAY
IOS291I NOLOG,NOAUTO,NODISPLAY
IOS444I NOLOG,NOAUTO,NODISPLAY
IOS450E NOLOG,NOAUTO,NODISPLAY
IEA476E NOLOG,NOAUTO,NODISPLAY
IEA491E NOLOG,NOAUTO,NODISPLAY
IEA494I NOLOG,NOAUTO,NODISPLAY
IEA497I NOLOG,NOAUTO,NODISPLAY
```

### Notes:

1. Specifying NOLOG, NOAUTO and NODISPLAY together causes the message to be completely deleted.
2. While NOAUTO was chosen as the default to prevent message floods from overwhelming automation, if your automation has dependencies on any of these messages during a HyperSwap (including HyperSwaps in a GDPS environment), you might consider specifying AUTO for the message so that it can be detected by your automation. Refer to the GDPS documentation for further suggestions on use of Message Flood Automation in that environment.
3. If your automation has dependencies on any of these messages during a HyperSwap, you should specify AUTO for the message so that it can be seen by your automation.

## Syntax example

The values in the following MSGFLDxx parmlib member are for illustration purposes only. You should determine the values that are appropriate for your system. A sample MSGFLDxx parmlib member (named CNZZMFXX) is provided as an example in SYS1.SAMPLIB.

```

/*-----*/
/* Sample MSGFLDxx PARMLIB member. */
/*-----*/
/* REGULAR message specifications. */
/*-----*/
REGULAR MSGTHRESH=50,JOBTHRESH=20,INTVLTIME=1
REGULAR SYSIMTIME=2,JOBIMTIME=2
DEFAULT LOG,NOAUTO,NODISPLAY,NOCMD
DEFAULTCMD '&,CANCEL & -- cancelled by Message Flood Automation'
JOB AOC%NV* AUTO
JOB LLA* AUTO
JOB ZAP1 CMD
/*-----*/
/* ACTION message specifications. */
/*-----*/
ACTION MSGTHRESH=50,JOBTHRESH=20,INTVLTIME=1
ACTION SYSIMTIME=2,JOBIMTIME=2
DEFAULT LOG,NOAUTO,NODISPLAY,NOCMD,NORETAIN
DEFAULTCMD '&,CANCEL & -- cancelled by Message Flood Automation'
JOB AOC%NV* AUTO,RETAIN
JOB LLA* AUTO
JOB ZAP2 CMD
/*-----*/
/* SPECIFIC message specifications. */
/*-----*/
SPECIFIC MSGTHRESH=50,INTVLTIME=1
SPECIFIC SYSIMTIME=2
SPECIFIC MSGIMTIME=2
SPECIFIC MSGLIMIT=20
DEFAULT LOG,NOAUTO,NODISPLAY,NORETAIN
MSG IOS001E
MSG IOS003A
MSG IOS050I
MSG IOS051I
MSG IOS071I
MSG IOS251I
MSG IOS444I
MSG IOS450E
*****
***** end of member *****
*****

```

## Exempting messages from processing by message flood automation

If you have automation that assumes that suppression (NODISPLAY) implies no automation (NOAUTO), and the automation is critically dependent on specific messages (for example to signal that a program is UP or DOWN), you may want to code a SPECIFIC message entry for those messages. Specify an action of IGNORE which will cause Message Flood Automation to ignore the message even if the specific message threshold is exceeded and other actions have been specified (or defaulted) for the message. Providing a SPECIFIC message entry keeps the message out of both ACTION message and REGULAR message processing.





## Chapter 78. MSTJCLxx (master scheduler JCL)

The MSTJCLxx parmlib member contains the master scheduler job control language (JCL) that controls system initialization and processing. You can place the master scheduler JCL in MSTJCLxx as an alternative to keeping it in the MSTJCLxx module in SYS1.LINKLIB.

The advantage to placing the master JCL in the MSTJCLxx parmlib member is that it is easier to make changes to the master JCL. If you specify the master JCL in the MSTJCLxx module in linklib, you must reassemble the module and link-edit it into the system each time a change is made. Specifying the master JCL in parmlib eliminates the need to reassemble and link-edit the module.

If the system finds a MSTJCLxx parmlib member, it uses the JCL in that member to start the master scheduler address space. If the system does not find a MSTJCLxx parmlib member, it uses the JCL in the MSTJCLxx module in linklib.

For more information about how to change the master JCL or specify alternate versions of the master JCL data set, see [“Understanding the master scheduler job control language”](#) on page 9.

### Parameter in IEASYSxx (or supplied by the operator)

```
MSTRJCL=(xx[,L])
```

The two characters (A-Z, 0-9, @, #, or \$), represented by xx, are appended to MSTJCL to identify one of the following:

- The MSTJCLxx member of SYS1.PARMLIB.
- The MSTJCLxx module in SYS1.LINKLIB.

If the MSTRJCL parameter is not specified, the system uses the MSTJCL00 parmlib member. If the system does not find the MSTJCL00 parmlib member, it uses the default master JCL in the MSTJCL00 module in SYS1.LINKLIB.

### Performance implications

None.

### Support for system symbols

You can specify symbols in MSTJCLxx. Keep in mind that the system does not process symbols in MSTJCLxx in the same way that it processes symbols in parmlib members. Because MSTJCLxx contains JCL, the system processes symbols in MSTJCLxx during JCL processing. The results of symbolic substitution reflect the substitution rules that are in effect during JCL processing.

For details about using system symbols and JCL symbols in JCL, see [z/OS MVS JCL Reference](#).

### Syntax rules for MSTJCLxx

The syntax rules for the MSTJCLxx parmlib member are the same as for the master JCL in the MSTJCLxx module in linklib. For details about the syntax of the master JCL, see [“Writing your own master scheduler JCL”](#) on page 12.

The following example shows how the IBM-supplied IEESMJCL member of SYS1.SAMPLIB might appear in the MSTJCLxx module in linklib.

```

MSTJCL05 CSECT
DC      CL80'//MSTJCL05 JOB MSGLEVEL=(1,1),TIME=1440'
DC      CL80'//      EXEC PGM=IEEMB860'
DC      CL80'//STCINRDR DD SYSOUT=(A,INTRDR)'
DC      CL80'//TSOINRDR DD SYSOUT=(A,INTRDR)'
DC      CL80'//IEFPDSI DD DSN=SYS1.PROCLIB,DISP=SHR'
DC      CL80'//IEFPARM DD DSN=SYS1.PARMLIB,DISP=SHR'
DC      CL80'//SYSUADS DD DSN=SYS1.UADS,DISP=SHR'
DC      CL80'//SYSLBC DD DSN=SYS1.BROADCAST,DISP=SHR'
DC      CL80'/*'
END

```

The following example shows how IEESMJCL might appear in the MSTJCLxx parmlib member.

```

//MSTJCL05 JOB MSGLEVEL=(1,1),TIME=1440
//      EXEC PGM=IEEMB860
//STCINRDR DD SYSOUT=(A,INTRDR)
//TSOINRDR DD SYSOUT=(A,INTRDR)
//IEFPDSI DD DSN=SYS1.PROCLIB,DISP=SHR
//IEFPARM DD DSN=SYS1.PARMLIB,DISP=SHR
//SYSUADS DD DSN=SYS1.UADS,DISP=SHR
//SYSLBC DD DSN=SYS1.BROADCAST,DISP=SHR

```

**Note:** The only Broadcast data set name that TSO/E recognizes on the SYSLBC DD statement is SYS1.BROADCAST.

Comments are indicated by characters "/\*" in columns 1, 2, and 3. Code the comments in columns 4 through 80. Do not continue a comment statement using continuation conventions. Instead, code additional comment statements. The following example shows how a comment is coded:.

```

/* THE COMMENT STATEMENT CANNOT BE CONTINUED.
/* BUT IF YOU HAVE A LOT TO SAY, YOU CAN FOLLOW
/* A COMMENT STATEMENT WITH MORE COMMENT STATEMENTS.

```

## IBM-supplied default for MSTJCLxx

There is no default MSTJCLxx parmlib member. The default master JCL resides in the IBM-supplied MSTJCL00 module in SYS1.LINKLIB.

## Statements and parameters for MSTJCLxx

The JCL statements in MSTJCLxx are described in [“Writing your own master scheduler JCL”](#) on page 12.

## Chapter 79. NUCLSTxx (customizing the nucleus region)

The NUCLSTxx member allows you to load installation-supplied modules into the system's DAT-ON nucleus region at IPL-time. You can use NUCLSTxx to:

- Add your installation's modules to the nucleus region.
- Delete nucleus-resident modules and replace them with alternate versions of the modules.

NUCLSTxx saves you from having to link-edit your installation's nucleus-resident routines (such as installation-written SVCs) into the IEANUC0x member of SYS1.NUCLEUS.

### Adding and deleting modules

The modules to be added to the nucleus region, or deleted from it, must reside in members of SYS1.NUCLEUS. To add or delete modules, simply specify the members on INCLUDE or EXCLUDE statements in NUCLSTxx.

On each INCLUDE statement, specify one member of SYS1.NUCLEUS to be included in the nucleus region at IPL-time. Use INCLUDE for code that needs to reside in the nucleus region, such as device support routines, and installation-defined SVCs.

On each EXCLUDE statement, specify one member of SYS1.NUCLEUS to be excluded from the nucleus region at IPL-time. Use EXCLUDE statements to exclude members that you are replacing with INCLUDE statements. You can also use the EXCLUDE statement to exclude modules specified in nucleus module lists (NMLs) or module list tables (MLTs).

You cannot specify more than one member name for each INCLUDE or EXCLUDE statement. However, you can specify multiple INCLUDEs and EXCLUDEs in NUCLSTxx, in any order.

If you use INCLUDE and EXCLUDE statements to replace a member of SYS1.NUCLEUS in the nucleus region with another member, the new member must have a unique name.

### Contradictory specifications

If you specify for the same member name both an INCLUDE and an EXCLUDE statement, the system uses the EXCLUDE statement.

### Restrictions

Note the following restrictions when using NUCLSTxx:

- Multiple CSECT load modules must be link-edited with the scatter (SCTR) attribute of the linkage editor before they can be added to the nucleus region. If this is not done, the system enters a non-restartable wait state at system initialization.
- Do not use NUCLSTxx to load or delete an alternate nucleus (IEANUC0x). You can select an alternate nucleus member by specifying the suffix identifier of the alternate IEANUC0x member on either the NUCLEUS statement in the LOADxx member of SYS1.PARMLIB, or on the LOAD parameter during system initialization. For more information, see [“Specifying an alternate nucleus” on page 8](#).

### NUCLSTxx compared with NMLDEF

NUCLSTxx is provided as an alternative to the NMLDEF macro. With NMLDEF, you identify modules to be added to the nucleus by creating a set of tables, called nucleus module lists (NMLs). You can use either NUCLSTxx or NMLDEF to customize the nucleus. However, you might prefer to use NUCLSTxx for the following reasons:

- NUCLSTxx is easier to code than NMLDEF.
- NUCLSTxx resides in SYS1.PARMLIB (or SYSn.IPLPARM — wherever LOADxx resides). NMLs must reside in SYS1.NUCLEUS.
- You can use different NUCLSTxx members to load different SYS1.NUCLEUS members into the nucleus region. Therefore, NUCLSTxx provides you with greater flexibility than NMLDEF in customizing the nucleus.

For information about the NMLDEF macro, see [z/OS MVS Programming: Authorized Assembler Services Guide](#).

## Relationship to the LOADxx member

---

The NUCLSTxx member must reside in the same data set as the LOADxx member. This member can reside in either SYS1.PARMLIB or SYSn.IPLPARM, depending on how the installation defined its I/O configuration.

In LOADxx, code a NUCLST statement to specify the NUCLSTxx member to be used. On the NUCLST statement, you can optionally specify whether the system loads a wait state if any of the INCLUDE statements in the NUCLSTxx member specify a member that cannot be found in SYS1.NUCLEUS. The system does not load a wait state by default and continues to IPL.

For information about installing LOADxx, and on specifying the NUCLST statement in LOADxx, see [Chapter 73, “LOADxx \(system configuration data sets\),”](#) on page 613.

## Placement of NUCLSTxx

The NUCLSTxx member must reside in the same data set as the LOADxx member. This member can reside in either SYS1.PARMLIB or SYSn.IPLPARM, depending on how the installation defined its I/O configuration.

## NUCLSTxx specification in LOADxx member

In LOADxx, code a NUCLST statement to specify the NUCLSTxx member to be used. On the NUCLST statement, you can optionally specify whether the system loads a wait state if any of the INCLUDE statements in the NUCLSTxx member specify a member that cannot be found in SYS1.NUCLEUS. The system does not load a wait state by default and continues to IPL.

For information about installing LOADxx, and on specifying the NUCLST statement in LOADxx, see [Chapter 73, “LOADxx \(system configuration data sets\),”](#) on page 613.

## Parameter in IEASYSxx (or supplied by the operator)

---

None.

## Syntax rules for NUCLSTxx

---

The following syntax rules apply to NUCLSTxx:

- Each record consists of 80 columns, although columns 73 through 80 are ignored.
- The fields are column-dependent. Columns that are not shown to contain data must contain blanks.
- Comments must be preceded by an asterisk in column 1.
- Blank lines are ignored.

## Syntax format of NUCLSTxx

|                    |
|--------------------|
| INCLUDE<br>EXCLUDE |
|--------------------|

## IBM-supplied default for NUCLSTxx

None.

## Statements and parameters for NUCLSTxx

### EXCLUDE

The EXCLUDE statement specifies the name of a member of SYS1.NUCLEUS that is to be excluded from the nucleus region at IPL-time.

Informational messages are issued for all members that are excluded. You might want to review these messages to ensure that you have not excluded any members that are needed. Although the messages are not displayed on any console, you can read them by checking the IPL WTO buffer.

You can use the EXCLUDE statement to override INCLUDE statements provided through NMLs and MLTs. The EXCLUDE statement must name a member of SYS1.NUCLEUS; otherwise, the EXCLUDE statement is ignored.

You cannot use the EXCLUDE statement to exclude a CSECT that was previously linked into IEANUC01 by the linkage editor. You must use the linkage editor to replace or remove the CSECT by relinking IEANUC01, using the REPLACE keyword and the SCTR attribute.

#### Column

##### Contents

#### 1-7

EXCLUDE

#### 10-17

The name of a member of SYS1.NUCLEUS to be excluded from the nucleus region at IPL-time.

There is no default.

### INCLUDE

The INCLUDE statement specifies the name of a member of SYS1.NUCLEUS that is to be loaded into the nucleus region at IPL-time.

INCLUDE statements for members that are already included in the nucleus region through other means, such as via NMLs, are ignored.

#### Column

##### Contents

#### 1-7

INCLUDE

#### 10-17

The name of a member of SYS1.NUCLEUS to be loaded into the nucleus region at IPL-time.

There is no default.

## Example of replacing modules

You can replace nucleus members by using a combination of INCLUDE and EXCLUDE statements. To replace one member with another, take the following steps:

1. In NUCLSTxx, code an INCLUDE statement for the SYS1.NUCLEUS member to be used, and an EXCLUDE statement for the member to be replaced, as shown:

```
EXCLUDE oldmod  
INCLUDE newmod
```

The *oldmod* is a member of SYS1.NUCLEUS that was to be included through either an MLT or an NML, and *newmod* is a modified copy of *oldmod* and also is a member of SYS1.NUCLEUS. Note that a different member name is used for the modified copy specified on the INCLUDE statement.

2. IPL the system.

## Chapter 80. PFKTABxx (program function key table definition)

The PFKTABxx is an installation-created member of Parmlib. In this member, you define one or more program function key (PFK) tables. In another installation-created member of parmllib, CONSOLxx, you define the console configuration for the installation and specify which PFK member is to be used with that configuration. By using the CONSOLxx and PFKTABxx members together, the system can automatically initialize the console configuration with the related PFK table(s) during IPL. This processing reduces the number of operator responses, and eliminates the need to define manually the PF key settings.

### Parameter in IEASYSxx (or entered by the operator)

None.

### Syntax rules for PFKTABxx

Notes when creating PFKTABxx:

- You can define multiple PFK tables in a member.
- Data must be contained in columns 1-71; the system ignores columns 72-80.
- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.
- The first statement type in a member must be PFKTAB TABLE(tablename).
- Code the statement type as the first data item on a record.
- For each PFK table, define each program function key only once.
- One or more blanks must follow the statement types; you must code at least one blank between the statement type and the keyword.
- Keyword values must be set off by parentheses. If you code multiple values on a keyword, separate the values with a blank or a comma.
- Do not use blanks, commas, or comments in the middle of a keyword, between the keyword and the left parenthesis before the value, or in the middle of a value.
- A statement type continues to the next statement type in the member or until the end of the member. Therefore, there is no continuation character (except for CMD text).
- CMD text that spans more than one parmllib record line and specifies a system symbolic requires all lines to be enclosed with single quotation marks (') or double quotation marks (") and to be connected with a comma (,).

A syntax example:

```
PFKTAB TABLE(nnnnnnnn)

[ {CMD({ "cccccc[;cccccc]..."} ) } ]
[ { "cccccc" [, "cccccc"]... } ]
[ { 'cccccc' [, 'cccccc']... } ]
[ PFK(xx) [ { 'cccccc[;cccccc]... ' } ] [CON({Y})] ]
[ {KEY(kk[,kk]...) } ]
```

### Using the display command

Once the PFKTABxx member has been invoked through the SET PFK command, you may use the DISPLAY command to view the contents of that specific PFKTABxx member. For the correct syntax, see [z/OS MVS System Commands](#).

## IBM-supplied default for PFKTABxx

The IBM-supplied default member of SYS1.PARMLIB is PFKTAB00.

## Statements and parameters for PFKTABxx

**PFKTAB**

## TABLE (tablename)

PFKTAB indicates that a new PFK table is being defined. PFKTAB must be the first definition in a PFKTABxx member. The *tablname* indicates the name that is associated with this PFK table and must be 1-8 alphanumeric characters. The value that you specify for *tablname* here is the value that you specify for PFKTAB(*tablname*) in the CONSOLxx parmlib member.

**PFK(xx)**

Indicates the program function key that is being defined. (xx) is a decimal value from 1 through 24. Each xx value must be unique within a table.

```
CMD      {('command[;command]...')}
          {('command[:command]...')}
```

CMD indicates that the PFK is to have a command or commands that are associated with it. *command* specifies the command. Multiple commands on a CMD line must be separated with a semicolon. The maximum length of the commands including the single quotation marks is 126 characters. If a command contains a single quotation mark, surround the command with double quotation marks. If the commands contains double quotation marks, surround the command with single quotation marks. If a command contains an underscore, define the key as conversational CON(Y). When the system displays the command, the cursor is under the character immediately to the right of the underscore. The system will not display the underscore. Specify the complete command rather than take any parameter defaults, since the defaults might change. See [z/OS MVS System Commands](#) for details. JES3 commands must have an asterisk (\*) for a prefix or an alternate prefix as specified on the CONSTD statement of the JES3 initialization deck.

If you want an underscore to appear in the command, use two underscores. They are treated as one underscore, and are not used for cursor placement.

**KEY**      { (xx) }  
             { (xx,xx,...) }

KEY indicates that the PFK being defined is to be associated with another key or a list of PF keys. xx indicates the PFK to be processed when the PFK being defined is pressed. xx is a decimal number between 1-24 and cannot be the same value as on the PFK(xx). For example, do not define PFK(10) KEY(10). You can code a maximum of 62 keys in a key list.

CON      { (Y) }  
          { (N) }

Specifies whether the PFK being defined is to be conversational or nonconversational. If the PFK is conversational, CON(Y), the system displays the command so you can modify it before executing it. If the PFK being defined is associated with a list of keys, and the PFK is conversational, the system displays the command that is associated with each key in the key list so you can make modifications. If a PFK is nonconversational, the system automatically executes the command when the PFK is pressed. If you do not specify CON, the default is nonconversational; the command is not displayed before executing.



**Rule:** If a command contains a single underscore used to place the cursor, you must specify CON(Y).



## Chapter 81. PROGxx (authorized program list, exits, LNKLST sets and LPA)

The PROGxx parmlib member contains the following optional statement types:

- APF, which defines the format and contents of the APF-authorized program library list. (See [“Using the APF statement”](#) on page 685.)
- EXIT, which controls the use of exits and exit routines. (See [“Using the EXIT statement”](#) on page 686.)
- SYSLIB, which allows for the definition of alternate data sets for the system defaults (SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, SYS1.SIEAMIGE, and SYS1.LPALIB) at the beginning of the LNKLST and the LPALST concatenations. (See [“Using the SYSLIB statement”](#) on page 687.)
- LNKLST, which controls the definition and activation of a LNKLST set of data sets for the LNKLST concatenation. (See [“Using the LNKLST statement”](#) on page 688.)
- LPA, which defines the modules to be added to, or deleted from, LPA after IPL. (See [“Using the LPA statement”](#) on page 693.)
- REFRPROT, which indicates that REFR programs are protected. (See [“Using the REFRPROT statement”](#) on page 694.)
- NOREFRPROT, which indicates that REFR programs are not protected. (See [“Using the NOREFRPROT statement”](#) on page 694.)
- TRACKDIRLOAD, which enables system-wide tracking of directed load modules. (See [“Using the TRACKDIRLOAD statement”](#) on page 694.)
- NOTRACKDIRLOAD, which disables system-wide tracking of directed load modules. (See [“Using the NOTRACKDIRLOAD statement”](#) on page 694.)

### Using the APF statement

Use the APF statement to specify the following:

- The format (dynamic or static) of the APF-authorized library list.
- Program libraries to be added to the APF list.
- Program libraries to be deleted from the APF list.

The system automatically adds SYS1.LINKLIB and SYS1.SVCLIB to the APF list at IPL. In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) will be treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

If you specify a *dynamic* APF list format in PROGxx, you can update the APF list at any time during normal processing or at initial program load (IPL). You can also enter an unlimited number of libraries in the APF list.

If you specify a *static* APF list format in PROGxx, you can define the list only at IPL, and are limited to defining a maximum of 255 library names (SYS1.LINKLIB and SYS1.SVCLIB, which are automatically placed in the list at IPL, and up to 253 libraries specified by your installation).

#### Note:

1. If you currently specify APF-authorized libraries in the IEAAPFxx parmlib member, you can convert the format of IEAAPFxx to PROGxx using the IEAAPFPR REXX exec provided by IBM. For information about how to perform this conversion, see [“Using the IEAAPFPR exec”](#) on page 686.
2. Except for concatenations opened during system initialization, an unauthorized library concatenated to any authorized libraries will cause the system to consider all the concatenated libraries unauthorized.

3. If you allow storage management subsystem (SMS) to manage a library, the system may move the library to a different volume during normal SMS processing. To ensure that the library retains authorization, specify SMS on its APF statement.
4. When LNKAUTH=APFTAB is specified, the system considers SYS1.MIGLIB and SYS1.CSSLIB to be APF-authorized when they are accessed as part of the concatenation (even when they are not included in the APF list).

## Defining aliases in the APF list

Do not define aliases in the APF list because IBM's data management services (for example, OPEN processing) map an alias to its actual library name and query the APF list by the actual library name. An alias in the APF list does not authorize anything.

## Using the IEAAPFPR exec

If you haven't yet converted IEAAPFxx parmlib members to PROGxx parmlib members, you can do it using the following procedure:

Place the IEAAPFPR exec in a data set that is accessible to ISPF and PDF edit macros. If you specify the EXECUTIL SEARCHDD(YES) command, or if you have modified the TSO/E installation parameters to search SYSEXEC automatically, place IEAAPFPR in a data set allocated to SYSEXEC. Otherwise, place IEAAPFPR in a data set allocated to SYSPROC.

To invoke IEAAPFPR:

1. Make sure that the IEAAPFxx member to be converted is valid and syntactically correct.
2. Edit a PROGxx parmlib member.
3. Copy the IEAAPFxx member into the PROGxx member.
4. Enter the following on the edit command line and press ENTER. The system places the modified member in the edit buffer.

```
IEAAPFPR
```

5. Save the new PROGxx member.

**Note:** After you add PROG=xx to IEASYSxx, remove APF=xx from IEASYSxx and IEASYS00 to avoid duplication of processing.

## Using the EXIT statement

Use the EXIT statement type to specify statements that:

- Add exit routines to an exit.
- Replace exit routines for an exit.
- Modify exit routines for an exit.
- Delete exit routines from an exit.
- Undefine implicitly defined exits.
- Change the attributes of an exit.

You can use the PROGxx EXIT statement to define exits to the dynamic exits facility at IPL. You can use multiple ADD statements to add more than one exit routine to a particular exit.

Previously defined exit definitions can be modified with the PROGxx EXIT statement, the SET PROG=xx operator command, or the SETPROG EXIT operator command through the following methods:

- The EXIT statement of the PROGxx parmlib member. The PROGxx EXIT statement interacts with the PROG=xx parameter of IEASYSxx and the SET PROG=xx command. At IPL, operators can use PROG=xx to specify the particular PROGxx parmlib member the system is to use. During normal processing, operators can use the SET PROG=xx command to set a current PROGxx parmlib member.

- The SETPROG EXIT operator command. This command performs the same functions as the EXIT statement of the PROGxx parmlib member. See *z/OS MVS System Commands* for information about the SETPROG EXIT command.
- The CSVDYNEX macro. The CSVDYNEX macro can be used to define exits to the dynamic exits facility, control their use within a program, and associate one or more exit routines with those exits. It can also be used to associate exit routines with the existing SMF and allocation exits, which have been defined to the dynamic exits facility.

An installation can use any of these methods to control dynamic exits. For example, an exit routine can be associated with an exit using the CSVDYNEX ADD request, the SETPROG EXIT,ADD operator command, or the EXIT statement of PROGxx.

#### Notes:

1. If you currently specify exits in the EXITxx parmlib member, IBM suggests that you convert the format of EXITxx to PROGxx using the IEFEXPR REXX exec provided by IBM.
2. Exits that are currently specified in the SMFPRMxx parmlib member can also be specified in the PROGxx parmlib member. See “Specifying SMF exits to the dynamic exits facility” on page 767 for an example of how to use the EXIT ADD statement to specify SMF exits in PROGxx parmlib members.
3. Exit definitions are not replaced by the SET PROG=xx or SETPROG EXIT commands. They are modified as specified in the command.
4. The SET PROG=xx command may need authorization to define a dynamic exit via the REQUEST=DEFINE option of the CSVDYNEX macro. See *z/OS MVS Planning: Operations* for instructions.
5. All abbreviations that are listed for the DISPLAY PROG,EXIT command in *z/OS MVS System Commands* are valid when used on the EXIT statement. For example, EX is an abbreviation for EXITNAME and DSN is an abbreviation for DSNAME.

## Using the SYSLIB statement

Use the SYSLIB statement at IPL when you want to change the default system data sets that are placed at the beginning of the LNKST concatenation or LPALST concatenation. The system recognizes the following:

- LINKLIB data set (which defaults to SYS1.LINKLIB)
- MIGLIB data set (which defaults to SYS1.MIGLIB)
- CSSLIB data set (which defaults to SYS1.CSSLIB)
- LINKLIBE data set (which defaults to SYS1.SIEALNKE)
- MIGLIBE data set (which defaults to SYS1.SIEAMIGE)
- LPALIB data set (which defaults to SYS1.LPALIB)

The system always places the LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE data sets at the beginning of the LNKST concatenation and the LPALIB data set at the beginning of the LPALST concatenation. SYSLIB can be used only at IPL.

Use the SYSLIB LINKLIB statement to change the LINKLIB data set. Use the SYSLIB MIGLIB statement to change the MIGLIB data set. Use the SYSLIB CSSLIB statement to change the CSSLIB data set. Use the SYSLIB LINKLIBE statement to change the LINKLIBE data set. Use the SYSLIB MIGLIBE statement to change the MIGLIBE data set. Use the SYSLIB LPALIB statement to change the LPALIB data set.

When you use SYSLIB statements to change the defaults, you must ensure that SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, and SYS1.SIEAMIGE are defined to the LNKST concatenation and that SYS1.LPALIB is defined to the LPALST concatenation for the system.

You can use SYSLIB statements in PROGxx when you want to override system code, either for testing or as part of customization. Use the LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE options of the SYSLIB statement to place the data sets you define at the beginning of the LNKST concatenation. Use the LPALIB option of the SYSLIB statement to place the alternate data set you define at the beginning of

the LPALST concatenation. Using these alternate system data sets, you can override system code supplied in LINKLIB, MIGLIB, CSSLIB, LINKLIBE, MIGLIBE, and LPALIB to test fixes or make exits or other vendors code available to the system without having to modify the system code itself.

If you use SYSLIB statements for testing, you can re-IPL after testing with the regular system libraries appearing first in the link list and LPA list concatenations. You can specify SYSLIB statements in PROGxx and use either PROGxx with LNKST statements or LNKSTxx members to define and activate the remainder of the LNKST concatenation.

Some system exits and tables reside in their own load modules and, for some of them, default exits are supplied in LPALIB and LINKLIB by IBM. Some products, from IBM and other vendors, supply exits meant to replace IBM's default exits. Some vendors ship replacement modules meant to replace IBM-supplied modules. Your installation might have exits and tables that replace LINKLIB and LPALIB at the beginning of the link and LPA lists. This allows you to override these modules rather than replacing them, while keeping the IBM-supplied default modules available for recovery and for use on different system images, and keeping other vendors code separated from IBM's code. This makes it easier to share software among images with different requirements or software licenses and can reduce the time that is required to install new levels of software.

For examples of specifying SYSLIB statements, see [“Example of the SYSLIB statement” on page 702](#) and [“Examples of the LNKST statement” on page 707](#).

## Using the LNKST statement

---

A LNKST set consists of an ordered list of data sets for processing as the LNKST concatenation. Every LNKST set contains the LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE data sets as the first data sets in the LNKST concatenation. Unless overridden by SYSLIB statements, every LNKST set begins with one of the following datasets:

- SYS1.LINKLIB
- SYS1.MIGLIB
- SYS1.CSSLIB
- SYS1.SIEALNKE
- SYS1.SIEAMIGE

The system automatically adds these data sets to the beginning of the LNKST set that you define. If these data sets are not available to the system at IPL, a wait state occurs.

Use the LNKST statement:

- To define the LNKST set.
- To add a data set to the LNKST set.
- To delete a data set from the LNKST set.
- To remove the definition of a LNKST set from PROGxx (valid only after IPL).
- To test for the location of a routine associated with one of the data sets in the LNKST set (valid only after IPL).
- To associate a job or address space with the current LNKST set (valid only after IPL).
- To indicate that a LNKST set is to be activated.

**Note:** You must enter parameters on the LNKST statement in the order that is shown in the syntax diagrams. See [“Syntax format of the LNKST statements” on page 702](#)

You can add a data set to any LNKST set that you define and specify the position of the data set in the list, however an alias cannot be added for the LNKST created at IPL. You cannot add the data set before any of the system default data sets in the concatenation. That is, you can only concatenate the data set after the CSSLIB data set in the LNKST set. To change the system default data sets placed at the beginning of the LNKST concatenation, see [“Using the SYSLIB statement” on page 687](#).



**CAUTION:** When using the SETPROG LNKLIST command, be aware that some actions, such as ADD and ACTIVATE, might temporarily allocate all of the data sets in the LNKLIST concatenation to the master scheduler address space. The master scheduler address space has a TIOT size of 12 K, which allows for approximately 600 unit allocations. For data sets in the LNKLIST concatenation that have an SMS data class that is assigned with a Dynamic Volume Count greater than 1 specified, additional TIOT space might be required, reducing the number of data sets that might be allocated within the master scheduler address space. Multi-volume data sets are not supported in the LNKLIST concatenation. For this reason, IBM recommends that you not assign a data class that specifies a Dynamic Volume Count greater than 1 to a data set in the LNKLIST concatenation.

## Using PROGxx instead of LNKLISTxx

You can use LNKLIST statements in PROGxx instead of using LNKLISTxx to define the LNKLIST concatenation. At IPL, ensure that you have a LNKLIST ACTIVATE statement for the LNKLIST set that you have defined, and specify PROG=xx instead of LNK=xx.

## Converting a LNKLISTxx member to PROGxx using the CSVLNKPR exec

To convert a LNKLISTxx member to PROGxx format, use the CSVLNKPR REXX exec in SYS1.SAMPLIB. To install CSVLNKPR, place the exec in a data set that is accessible to ISPF and PDF edit macros. If you specify EXECUTIL SEARCHDD(YES) command, or if you have modified the TSO/E installation parameters to search SYSEXEC automatically, place CSVLNKPR in a data set allocated to SYSEXEC. Otherwise, place CSVLNKPR in a data set allocated to SYSPROC.

To invoke CSVLNKPR:

1. Make sure that the LNKLISTxx member to be converted is valid and syntactically correct.
2. Create a new, empty PROGxx parmlib member. It should be empty until you copy the LNKLISTxx member into it, because CSVLNKPR comments out any statement not in LNKLISTxx format.
3. Copy the LNKLIST statements from the old LNKLISTxx member into the empty PROGxx member.

Because the system automatically places the LINKLIB, MIGLIB, or CSSLIB data sets into the LNKLIST set, you do not need to specify them in the new PROGxx member. The data set names for the LINKLIB, MIGLIB, and CSSLIB default to SYS1.xxxxLIB, but you can change the data set names, if desired, using the SYSLIB statement in PROGxx. If you specify the LINKLIB, MIGLIB, or CSSLIB data set in the LNKLISTxx member, and you convert the member to PROGxx format and IPL with that PROGxx member, the system will issue message CSV532I to indicate the presence of a superfluous LNKLIST statement in that PROGxx member.

4. Enter CSVLNKPR on the edit command line. The system places the modified member in the edit buffer. If you enter CSVLNKPR without a name, the name of the LNKLIST set in PROGxx defaults to LNKLISTXX. If you specify CSVLNKPR(*name*), the system uses *name* as the name of the LNKLIST set in PROGxx.
5. Save the new PROGxx member.
6. After you have saved the new PROGxx member, remove the LNK=xx system parameter from IEASYSxx and from IEASYS00. Then activate PROGxx by specifying the PROG=xx system parameter at the next IPL. You can place PROG=xx in IEASYSxx and IEASYS00.

## Using LNKLIST processing

You can define multiple LNKLIST sets, but only one LNKLIST set is current in the system at any time. Any job or address space that is started after the current LNKLIST set is activated is associated with the current LNKLIST set. The job or address space continues to use the current LNKLIST set until the LNKLIST set for the job or address space is updated. (See the parameter description for LNKLIST UPDATE.)

## Changing the current LNKLIST set

You can change the current LNKLIST set dynamically through the SET PROG=xx and SETPROG LNKLIST commands.

A LNKLST set remains allocated until there are no longer any jobs or address spaces associated with it. If the current LNKLST set is dynamically changed, any job or address space associated with the previous LNKLST set continues to use the data sets until the job or address space finishes processing. Thus, a previously current LNKLST set might be active or in use by a job or address space even though a new current LNKLST set has been activated. Jobs or address spaces that are started after the new current LNKLST set is activated use the new current LNKLST set.

An active LNKLST set **cannot** be modified. Once the last job or address space associated with a LNKLST set terminates, the LNKLST set is no longer active. The only other way to deactivate a LNKLST set is with LNKLST UPDATE. See [“Removing or compressing a data set in an active LNKLST set” on page 692](#) for more information about LNKLST UPDATE.

Through SET PROG=xx and SETPROG LNKLST, you can also remove the definition of a LNKLST set from the system, associate a job or address space with the current LNKLST set, or locate a specific module associated with a data set in the LNKLST set. See [z/OS MVS System Commands](#).

## Concatenating data sets to the LNKLST concatenation

The number of data sets you can concatenate to form the LNKLST concatenation is limited by the total number of DASD extents the data sets will occupy. The total number of extents must not exceed 255. A partitioned data set extended (PDSE) counts as one extent.

The system concatenates as many of the data sets as possible until the limit of 255 extents is reached. The system ignores the remaining data sets. When the limit has been exceeded, the system writes error message IEA328E to the operator's console. This message is issued whether the concatenation is defined by LNKLSTxx or by PROGxx.

## Allocating a PDS or PDSE for use with LNKLST

When using PDSs and PDSEs, you can allocate LNKLST data sets with secondary extents. However, IBM suggests that PDSs in the LNKLST be allocated with only primary extents, for two reasons. First, this makes it easier to stay within the 255-extent limit for an active LNKLST concatenation without having to reallocate data sets in fewer extents initially. Second, if a PDS is updated while in the link list, it can be extended if it has been allocated using secondary space. This can cause members to be placed in extents that did not exist when the LNKLST concatenation was opened. Any attempt to access a member in a new extent causes the requesting program to abend with a logical I/O error. This recommendation does not apply to PDSEs.

If an LNKLST PDS has expanded into a secondary extent since the most recent IPL, a program can use either of the following methods to access a member in the secondary extent:

- Accessing the member as part of a joblib, steplib, or tasklib. This method causes the data set to lose its authorized program facility (APF) authorization for the duration of the job, step, or task, unless the data set is specified in the APF list (through the PROGxx or IEAAPFxx member). Note that SETPROG APF or SET PROG can be used to dynamically update the APF table.
- OR
- Dynamic LNKLST processing can be used to define a new current LNKLST. The following is one way this could be accomplished:
    1. Define a new LNKLST set with the same data sets (including the one that has gone into a new extend) as are in the current LNKLST set.

```
SETPROG LNKLST,DEFINE,NAME=new,COPYFROM=CURRENT
```

2. Activate the new LNKLST set, making it the current LNKLST.

```
SETPROG LNKLST,ACTIVATE,NAME=new
```

Now all address spaces that start while this new LNKLST set is current can able to access modules in the new extent. Address spaces that existed prior to this new LNKLST set becoming current will still not be able to access modules in the new extent.



3. The SETPROG LNKLIST,UPDATE option may be used to force pre-existing address spaces to use the new current LNKLIST.

```
SETPROG LNKLIST,UPDATE,JOB=*
```

There is some risk associated with this command (ABEND106 errors could result) and therefore it is recommended that this command be used only when necessary to prevent an IPL. Please see the SETPROG command in [z/OS MVS System Commands](#) for more important information about this option.

## APF authorization for LNKLIST data sets

SYS1.LINKLIB in the LNKLIST concatenation is APF-authorized by default. And, if you accept the default for the LNKAUTH system parameter (LNKAUTH=LNKLIST) or specify this value through an IEASYSxx member or as a response to the 'SPECIFY SYSTEM PARAMETERS' message at IPL time, data sets that are concatenated to SYS1.LINKLIB by default (like SYS1.MIGLIB and SYS1.CSSLIB) are automatically APF-authorized when accessed as part of the LNKLIST concatenation.

For more information, see the description of the LNKAUTH parameter in [Chapter 56, "IEASYSxx \(system parameter list\),"](#) on page 421.

## Cataloging LNKLIST data sets

Data sets in the LNKLIST concatenation must be cataloged in either the system master catalog or in a user catalog.

Cataloged data sets must be defined using the standard search order for requests as outlined in [z/OS DFSMS Managing Catalogs](#). Variations in the standard search order can result in data sets not being found during LNKLIST processing.

LNKLIST data sets processed during IPL must be either cataloged in the master catalog or have their volume serials specified.

**Note:** The volume specification is not intended to get LNKLIST to manage a data set that is not cataloged. It is designed to let the user put a user-cataloged data set in the LNKLIST. Since user catalog support is not available when IPL is processing LNKLIST, the volume must be specified to let LNKLIST processing know where the data set resides. If a volume is specified, LNKLIST processing will not try to locate the data set in the Master Catalog.

If you catalog a LNKLIST data set in the system master catalog, the system will find the data set automatically during IPL.

If you plan to use a user catalog, you should be aware that the system will not find the data set unless you specify both the name of the data set and the volume serial number (VOLSER) of the DASD volume on which the data set resides. (This restriction also applies if you are defining the LNKLIST concatenation in LNKLISTxx.)

## Modifying the contents of LNKLIST data sets

If you update members in LNKLIST data sets:

- Be sure to refresh LLA's directory table after completing the updates if you want to have the changes take effect immediately. You can refresh LLA in the following ways:
  - To update specific entries in LLA's directory table, enter the MODIFY LLA UPDATE command.
  - To refresh all entries in LLA's directory table, enter the MODIFY LLA REFRESH command.
  - Recycle (stop and restart) LLA.

For more information about these commands, see [z/OS MVS System Commands](#).

- Do not remove the LNKLIST data sets from LLA during the update, to avoid performance problems.

## Removing an XCFAS ENQ

The XCFAS address space has an ENQ on each LNKST data set. These ENQs provide serialization on the LNKST data sets. An ENQ on a LNKST data set prevents that data set from being altered as long as it is a member of an active LNKST. There is no connection between sysplex processing and LNKST processing.

There are times when you may want to remove the XCFAS ENQ; for example, when you want to update a data set of the same name on a different volume. Use the LNKST UNALLOCATE statement, described in [“Syntax format of the LNKST statements” on page 702](#), or the SETPROG LNKST,UNALLOCATE system command, described in [z/OS MVS System Commands](#), to remove the ENQ.

LLA also holds an ENQ on each LNKST data set. You can remove this ENQ by using the GET\_LIB\_ENQ(NO) option of the CSVLLAxx parmlib member, by updating LLA to REMOVE the data set from LLA management, or by stopping LLA. See [Chapter 25, “CSVLLAxx \(library lookaside \(LLA\) list\),” on page 243](#). For more information about an LLA-managed data set, see [Removing libraries from LLA management in the z/OS MVS Initialization and Tuning Guide](#).

After it is again OK for the system to have the ENQ, restore the previous system behavior, such as with:

- The LNKST ALLOCATE statement or the SETPROG LNKST,ALLOCATE command.
- The GET\_LIB\_ENQ(YES) option of the CSVLLAxx parmlib member.

## Removing or compressing a data set in an active LNKST set

It is sometimes necessary to remove a data set from the active LNKST set. Perhaps the data set is no longer needed, is causing a problem, or needs to be compressed. Use LNKST DELETE to remove a data set. The data set cannot be removed while a LNKST set is active (in use by at least one active address space). Use the following procedure to assure the data set being removed is not part of an active LNKST set:

1. Define a new LNKST set identical to the one from which the data set is to be removed.
2. Remove the appropriate data set from the new LNKST set.
3. Activate the new LNKST set. This makes the new LNKST set CURRENT on the system.
4. Update all currently running jobs to use the current LNKST set.

The following example shows how to remove a data set from an active LNKST set:

```
SETPROG LNKST DEFINE NAME(NEWLLSET) COPYFROM(OLDLLSET)
SETPROG LNKST DELETE NAME(NEWLLSET) DSNAME(data set.to.be.removed)
SETPROG LNKST ACTIVATE NAME(NEWLLSET)
SETPROG LNKST UPDATE JOB(*)
```

**Note:** Using UPDATE to switch LNKST sets for an active job could result in fetch failures. IBM suggests that you do this only when necessary.

When a new LNKST set is made current, data sets that are no longer part of an active LNKST continue to be managed by LLA. If you want LLA to no longer manage and to drop its allocation of a data set you have dynamically removed for all LNKST sets, you must issue a MODIFY LLA,UPDATE=xx pointing to a CSVLLAxx member specifying the REMOVE keyword for the library removed from the LNKST. Although stopping and starting LLA after the dynamic LNKST removal of the data set causes LLA to drop its management and allocation of the data set, this also slows system performance. To avoid slowing system performance, use the MODIFY LLA command to change the library indexes.

When compressing non-LNKST libraries, see the REMOVE statement in [“Statements and parameters for CSVLLAxx” on page 244](#).

## Placement of SYSLIB and LNKST statements in PROGxx

You can place LNKST statements for a LNKST set in different PROGxx members. For example, you can specify PROG=(01,02,03) and place the LNKST DEFINE statement in PROG01, LNKST ADD statements in PROG02, and the LNKST ACTIVATE statement in PROG03.

SYSLIB statements must always appear before any LNKST statements in PROGxx. If you specify multiple PROG=xx members, define any SYSLIB statements ahead of LNKST statements. For example, if you specify PROG=(01,02) during IPL, consider the following:

- If PROG01 has a LNKST statement, ensure that no SYSLIB statement appears after a LNKST statement, or in PROG02.
- If only PROG02 has a LNKST statement, ensure that no SYSLIB statement appears after a LNKST statement in PROG02.

## Using the LPA statement

---

Use the LPA statement to specify:

- Modules that are to be added to the LPA at the end of the IPL. This is needed only for program objects within PDSEs but can be used for load modules within PDSs.
- Modules that are to be added to the LPA following IPL.
- Modules that are to be deleted from the LPA following IPL.
- Threshold values for minimum amounts of CSA storage that must be available after an ADD operation.

You can also initiate a change to LPA from a program via the CSVDYLPA macro, or by an operator using the SETPROG command. The PROG system parameter can be used to specify CSA threshold values, but not to request ADD or DELETE operations.

You can exercise certain controls over the modules to be loaded:

- You specify a data set from which the system is to load the modules. You must be authorized to make the request.
- You can request that the modules be placed into fixed common storage.
- You can request that only the full pages within a load module be page-protected. This does leave the likelihood of the either the beginning or end, or both, of a load module not being page protected. By default, each module is individually page-protected. This is, however, wasteful of common storage, as each module needs then to occupy a whole number of 4096-byte pages. In all cases the module will be in key 0 storage.
- You can indicate that the module being replaced is the routine for a specific SVC. In this case, the system updates the SVC table for the specified SVC with the new entry point address.

By default, LPA module alias names are not automatically handled. By default, if a module has aliases, the module name and all associated aliases must be specified within the same request. Otherwise, one of the following outcomes could occur, depending upon the initial state of the system:

- The module name or alias is not found
- A duplicate copy of the same module is loaded
- A previous copy of the module is used.

You can use the ADDALIAS option to indicate that the system is to process aliases of the specified modules.

LPA modules are considered as coming from an authorized library. As part of its LPA search, the system finds modules that were added dynamically. A module added dynamically is found before one of the same name added during IPL.

The LPA statement is intended to replace modules only in cases where the owning product verifies the replacement. Otherwise, replacement could result in partial updates, or if the module address has already been saved by its owning product, an LPA search will not be done and the updated module will not be found.

It is sometimes necessary to re-IPL to replace LPA modules. For example, many service updates of LPA modules will require a re-IPL.

**Note:** If an application uses the CHKPT macro and dynamic LPA modules are in use at the time the checkpoint is taken, dynamic LPA must not be altered until you no longer intend to attempt a restart from the identified checkpoint. When a dynamic LPA module is detected on the load list, the CHKPT macro returns RC=16, RSN=64. If dynamic LPA was altered and the module has a different entry point address in dynamic LPA at deferred checkpoint restart, the restart fails with ABEND S13F. For more information about checkpoint/restart facilities, see *z/OS DFSMSdfp Checkpoint/Restart*.

## Using the REFRPROT statement

---

Use the REFRPROT statement type to specify that REFR programs are protected from modification by placing them in key 0, non-fetch protected storage, and page protecting the full pages. Therefore, any parts of the program that are on partial pages are not page-protected. For more information on protection of REFR programs, see *z/OS MVS Program Management: User's Guide and Reference*.

Note that the specification of REFRPROT will cause modules link-edited with the REFR attribute to be placed into key0, non-fetch protected, page-protected storage, regardless of their APF authorization.

## Using the NOREFRPROT statement

---

Use the NOREFRPROT statement type to specify that REFR programs are not protected from modification.

## Using the TRACKDIRLOAD statement

---

Use the SETPROG TRACKDIRLOAD statement to enable system-wide tracking of directed load modules. A directed load module is a module that is directly loaded to a specified storage address. When enabled, mapping information about directed load modules is included in the maps produced by hardware instrumentation services (HIS). Directed load tracking is enabled by default.

## Using the NOTRACKDIRLOAD statement

---

Use the SETPROG NOTRACKDIRLOAD statement to disable system-wide tracking of directed load modules.

## Using the DEFAULTS statement

---

Use the DEFAULTS statement type to set defaults that the system is to use when processing LPA and LNKST statements in PROGxx and the SETPROG LPA, SETPROG LNKST, and DISPLAY PROG,EXIT commands.

## Parameter in IEASYSxx (or specified by the operator)

---

### **PROG=xx**

The two-character identifier xx is appended to PROG to identify the PROGxx parmlib member. xx can be any two alphanumeric characters (A-Z, 0-9) or (@, #, or \$).

You can also specify multiple PROGxx members on this parameter. For example, you can specify two active members using the form PROG=(01,02).

Regardless of whether you specify the PROG=xx parameter, the system always places the following libraries in the APF list:

- SYS1.LINKLIB and SYS1.SVCLIB
- If the APF=xx system parameter is specified, the libraries that are contained in IEAAPFxx.

**Note:** In addition, any module in the link pack area (pageable LPA, modified LPA, fixed LPA, or dynamic LPA) is treated by the system as though it came from an APF-authorized library. Ensure that you have properly protected SYS1.LPALIB and any other library that contributes modules to the link pack area to avoid system security and integrity exposures, just as you would protect any APF-authorized library.

## PROG=xx and APF=xx

If you specify both the PROG=xx and the APF=xx parameters, then the system places into the APF list the libraries listed in IEAAPFxx, followed by the libraries listed in the PROGxx member or members.

The system will process IEAAPFxx and PROGxx parameters if both are specified. If you decide to use PROGxx **only**, convert the format of IEAAPFxx to PROGxx and then remove APF=xx system parameters from IEASYSxx and IEASYS00.

## PROG=xx and EXIT=xx

The system will process first PROGxx and then EXITxx parameters if both are specified. If you decide to use PROGxx only, convert the format of EXITxx to PROGxx and then remove EXIT=xx system parameters from IEASYSxx and IEASYS00.

## PROG=xx and LNK=xx

You can specify PROG=xx instead of LNK=xx for the LNKLIST concatenation. Whether you use PROGxx or LNKLISTxx to define the LNKLIST concatenation, the system always places the LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE data sets (either the system defaults or the data sets specified on SYSLIB statements) first in the concatenation.

If you use PROGxx and do not use LNKLIST statements, the system uses LNKLISTxx, if specified, on LNK=xx to define the LNKLIST concatenation.

If you define a LNKLIST set to be activated through PROGxx and specify both PROG=xx and LNK=xx, the system uses the definitions in PROGxx and issues message CSV487I:

```
LNK IPL PARAMETER HAS BEEN IGNORED.  LNKLIST SET lnklistname IS BEING USED
```

## IBM-supplied default

None.

## Syntax rules for PROGxx

These rules apply to the creation of PROGxx:

- Enter data only in columns 1 through 71. Do not enter data in columns 72 through 80; the system ignores these columns.
- Comments may appear in columns 1-71 and must begin with “/\*” and end with “\*/”.

## Syntax format of the APF statement

```
APF FORMAT(DYNAMIC|STATIC)
APF ADD | DELETE
   DSNAME(dsname)
   SMS | VOLUME(volname)
```

### APF

Statement type indicating that an action is to be performed on the APF list.

### FORMAT(DYNAMIC|STATIC)

Specifies that the format of the APF list is dynamic or static. Before you change the format of the APF list to dynamic, validate programs and vendor products are converted to use dynamic APF services (see [Chapter 43, “IEAAPFxx \(authorized program facility list\),” on page 361](#)), and that the proper program products are installed (see [z/OS Planning for Installation](#)).

**Example:** FORMAT(DYNAMIC)

**Default:** None

#### **ADD|DELETE**

Indicates whether you want to add or delete a library from the APF list.

**Default:** None

#### **DSNAME(dsname)**

The 44-character name of a library that you want to add or delete from the APF list. DSN, LIB, and LIBRARY are accepted synonyms for this parameter.

**Example:** DSNAME(SYSTEM.ACCT.DATA)

**Default:** None

#### **SMS|VOLUME(volname)**

The identifier for the volume containing the library specified on the DSNAME parameter, which is one of the following:

- SMS, which indicates that the library is SMS-managed.
- A six character identifier for the volume
- \*\*\*\*\*, which indicates that the library is located on the current SYSRES volume
- \*MCAT\*, which indicates that the library is located on the volume containing the IPL-time master catalog.

VOL is an accepted abbreviation for the VOLUME parameter.

**Example:** VOLUME(874932) or VOLUME(&SYSRx).

**Default:** None

## **Example of the APF statement**

The following example shows a PROGxx parmlib member that sets the format of the APF list to dynamic, and adds the following libraries to the APF list:

- SYS1.SUPER.UTILS on volume 614703
- SYS1.ACCTG.RECRDS on the current SYSRES volume
- SYS1.COMPU.DATA, an SMS-managed library.

```
APF FORMAT(DYNAMIC)
APF ADD
  DSNAME(SYS1.SUPER.UTILS)
  VOLUME(614703)
APF ADD /* Accounting records */
  DSNAME(SYS1.ACCTG.RECRDS)
  VOLUME(*****)
APF ADD
  DSNAME(SYS1.COMPU.DATA)
  SMS
```

## **Syntax format of the EXIT statements**

### **Syntax format of EXIT ADD:**

```

EXIT ADD
  EXITNAME(ex)
  MODNAME(mmmm)
  [STATE({ACTIVE|INACTIVE})]
  [DSNAME(dd)]
  [JOBNAME(jjj|*)]
  [ABENDNUM(n[,CONSEC])]
  [FIRST|LAST]
  [PARAM(param)]
  [DELETEFORCE({NO|YES})]
  [SERVICEMASK(servicemask)]

```

**Syntax format of EXIT REPLACE:**

```

EXIT REPLACE
  EXITNAME(ex)
  MODNAME(mmmm)
  [STATE({ACTIVE|INACTIVE})]
  [DSNAME(dsn)]
  [SERVICEMASK(servicemask)]

```

**Syntax format of EXIT MODIFY:**

```

EXIT MODIFY
  EXITNAME(ex)
  MODNAME(mmmm)
  [STATE({ACTIVE|INACTIVE})]
  [JOBNAME(jjj|*)]

```

**Syntax format of EXIT DELETE:**

```

EXIT DELETE
  EXITNAME(ex)
  MODNAME(mmmm)
  [FORCE({YES|NO})]

```

**Syntax format of EXIT UNDEFINE:**

```

EXIT UNDEFINE
  EXITNAME(ex)

```

**Syntax format of EXIT ATTRIB:**

```

EXIT ATTRIB
  EXITNAME(ex)
  KEEPRC(compare, kk)

```

**EXIT**

Statement type indicating that an action is to be performed on an exit or an exit routine.

**ADD**

Specifies that an exit routine is to be added to an exit.

**Default value:** None

**REPLACE**

Replaces an exit routine for an exit.

**MODIFY**

Specifies that the state of an exit routine is to be changed to active or inactive, and sets the conditions under which the exit routine is to be given control.

**Default value:** None

**DELETE**

Specifies that an exit routine is to be deleted from an exit.

**Default value:** None

**UNDEFINE**

Specifies that an implicitly defined exit is to be undefined. You define an exit implicitly if you add exit routines to it before it has been defined, or if you set attributes for it using the ATTRIB parameter before it has been defined. You can determine which exits have been implicitly defined by using the DISPLAY PROG,EXIT,ALL,IMPLICIT command.

**Default value:** None

**ATTRIB**

Specifies that the attributes of an exit are to be changed.

**Default value:** None

**EXITNAME(ex)**

The 1-16 character name of the exit. Names must be unique within the system. You can use alphanumerics, underscores, periods, and #, \$, or @. (but never with the character string "SYS").

**Default value:** None

**MODNAME(mmmm)**

The 1-8 character name of the exit routine. You can use alphanumerics and #, \$, and @.

If the DSNNAME parameter is not specified, the system tries to locate the exit routine using the LPA, the LNKST concatenation, and the nucleus. The MODNAME parameter is required for the ADD, DELETE, and MODIFY requests.

**Default value:** None

**[STATE({ACTIVE|INACTIVE})]**

Indicates the state of the exit routine. ACTIVE indicates that the exit routine is to be given control when the exit is called. INACTIVE indicates that the exit routine is not to be given control when the exit is called.

**Default value:** The default for the ADD parameter is ACTIVE. The default for the MODIFY parameter is to leave the current state of the exit routine unchanged.

**[DSNAME(dd)]**

The 1-44 character data set name of a load library in which the exit routine resides. The data set must be cataloged.

If the data set has been migrated, the issuer of the command that references PROGxx waits until the data set has been retrieved before continuing.

If the PROGxx member is specified in the IEASYSxx member, an exit routine fetched from the data set specified in a DSNNAME parameter cannot be given control until the master scheduler is initialized. In contrast, an exit routine not fetched from the DSNNAME-specified data set can be given control once the LNKST is opened.

**Default value:** If the DSNNAME parameter is not specified, the system tries to locate the exit routine using the LPA, the LNKST concatenation, and the nucleus.

**[JOBNAME(jjj)\*]**

The 1-8 character name of the job or jobs for which this exit routine is to be given control. You can only specify the JOBNAME parameter for an active exit routine. If the exit is called from another job, this exit routine is not given control. Use the JOBNAME parameter to restrict the processing of an exit routine to a particular job. To indicate the name of more than one job, use an asterisk for the last character. A matching job name is one that matches all the characters that precede the asterisk.

If you specify JOBNAME=\*, you are requesting that the system not check for the job name.



**Default value:** The default for the ADD parameter is JOBNAME=\*, which indicates that the exit routine is to be given control when any job calls the exit. The default for the MODIFY parameter is to use the job name or job names as specified on the ADD request.

#### [ABENDNUM(*n*[,CONSEC])]

Indicates when the system should stop giving control to the exit routine in case of abends. ABENDNUM(*n*) indicates that the exit routine is not to be given control after the *n*th abend. ABENDNUM=(*n*,CONSEC) indicates that there must be *n* consecutive abends before the system stops giving control to the exit routine. CONSEC is not supported if this exit has FASTPATH processing in effect and either a PSW key 8 to 15 or ANYKEY processing in effect.

**Default value:** The default is to use the ABENDNUM characteristics that were specified (or defaulted) when the exit was defined, or, if the exit is implicitly defined, the ABENDNUM characteristics that are specified when the exit is subsequently defined. The ABENDNUM value must not exceed 8 decimal digits.

#### [FIRST]

Specifies that the system is to call the exit routine before all other exit routines associated with this exit, unless another routine, added after it, also specifies the FIRST parameter.

**Default value:** If neither the FIRST parameter nor the LAST parameter is specified, the system can call the exit routine in any order relative to other exit routines associated with this exit.

#### [LAST]

Specifies that the system is to call the exit routine after all other exit routines associated with this exit, unless other routines are added after it.

**Default value:** If neither the FIRST parameter nor the LAST parameter is specified, the system can call the exit routine in any order relative to other exit routines associated with this exit.

#### PARAM=param

The 1 - 8 character parameter that is passed to the exit routine. If this parameter is less than 8 bytes, it is padded with blanks until it is 8 bytes. The first 4 bytes are passed to the exit routine in access register 0. The second 4 bytes are passed to the exit routine in access register 1. If you specify characters other than the following characters within the PARAM string, you must enclose the parameter string within single quotation marks:

- Uppercase alphabetic characters A - Z
- Numerics 0 - 9
- Special characters @, \$, #
- Period, asterisk, question mark, underscore, hyphen

#### [DELETEFORCE({NO or YES})]

Specifies whether any deletion of the exit routine (by CSVDYNEX, SETPROG, or an EXIT DELETE statement in PROGxx) must specify FORCE=YES:

- DELETEFORCE(NO), the default, specifies that exit routine deletion does not require FORCE=YES.
- DELETEFORCE(YES) specifies that exit routine deletion does require FORCE=YES. If the deletion request does not specify FORCE=YES, the request is rejected.

DELETEFORCE can be abbreviated as DELFORCE.

#### [SERVICEMASK(servicemask)]

Specifies a service mask for the exit routine that is used to determine whether the exit routine will be called for a given caller.

Specify *servicemask* as one of:

- *x1*
- *x1,x2*

where each *x1* and *x2* is a one to eight-digit hexadecimal number. *x1* and *x2* are padded on the left with zeros to a length of 8 and thus each identifies 4 bytes of the service mask. *x1* represents

bytes 0 to 3 of the mask, x2 represents bytes 4 to 7 of the mask (when no x2 is specified, those bytes are zeros). For example, `SERVICEMASK=(1,4003)` will produce a mask of (hexadecimal) 0000000100004003.

The service mask is applied to the service ID of the exit caller. Only if the ANDed value of the service mask and the service ID is nonzero for a given call and a given exit routine will that exit routine be called.

### **[FORCE({YES|NO})]**

Indicates that the system is to delete the exit routine. The exit routine will no longer be given control. Specify `FORCE(YES)` for an exit with FASTPATH processing in effect, and either a PSW key 8 to 15, or ANYKEY processing in effect. Assuming the exit has FASTPATH processing in effect, and the PSW key is 8 to 15, or ANYKEY processing is in effect:

- `FORCE(NO)` changes the state of the exit routine to inactive. The system does not free the storage.
- `FORCE(YES)` frees the storage of the exit routine immediately. Use `FORCE(YES)` only if you are sure that no exit is running that exit routine.

For exits that are non-FASTPATH or whose PSW key is 0 to 7, and not ANYKEY, the system frees the storage when it determines that no other exits are using the exit routine.

**Default value:** `FORCE(NO)`

### **KEEPRC(compare,kk)**

Specifies a comparison and a return code which, if true, cause the return information that is produced by this exit routine to be returned to the exit caller. The valid choices for *compare* are EQ, NE, GT, LT, GE, and LE. For example, with `KEEPRC(GT,4)`, if the exit routine produces a return code of 8, the compare for greater than with 4 is true, and `KEEPRC` processing causes the information that is produced by this exit routine to be returned to the exit caller.

If return codes from more than one exit routine match the conditions that are specified, the system returns information from the exit routine that finishes first.

**Default value:** The default is not to perform `KEEPRC` processing. Do not enter more than 8 decimal digits when specifying a value for *kk*. Refer to [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#) for information about using the `KEEPRC` parameter.

## **Examples of EXIT statements**

The following example shows a `PROGxx` parmlib member that does the following:

- Adds exit routine R1 to exit SYS.IEFUJI.
- Modifies exit routine R2 for exit SYS.IEFUSI to be inactive.
- Deletes exit routine R3 from exit SYS.IEFACTRT.
- Defines exit SYS.IEFUTL so that the system will “keep” information for return code 4 should any exit routine return with that return code.

```
EXIT ADD EXITNAME(SYS.IEFUJI) MODNAME(R1)
EXIT MODIFY EXITNAME(SYSSTC.IEFUSI) MODNAME(R2) STATE(INACTIVE)
EXIT DELETE EXITNAME(SYSJES3.IEFACTRT) MODNAME(R3)
EXIT ATTRIB EXITNAME(SYSTSO.IEFUTL) KEEPRC(EQ,4)
```

## Syntax format of the SYSLIB statement

```

SYSLIB LINKLIB(name)      [ {VOLUME|VOLSER|VOL} (volser) ]
SYSLIB MIGLIB(name)      [ {VOLUME|VOLSER|VOL} (volser) ]
SYSLIB CSSLIB(name)      [ {VOLUME|VOLSER|VOL} (volser) ]
SYSLIB LINKLIBE(name)    [ {VOLUME|VOLSER|VOL} (volser) ]
SYSLIB MIGLIBE(name)     [ {VOLUME|VOLSER|VOL} (volser) ]
SYSLIB LPALIB(name)      [ {VOLUME|VOLSER|VOL} (volser) ]

```

### SYSLIB

Statement type indicating that an alternate data set is to be defined for SYS1.LINKLIB, SYS1.MIGLIB, SYS1.SIEALNKE, SYS1.SIEAMIGE and SYS1.CSSLIB in the LNKST concatenation, and for SYS1.LPALIB in the LPALST concatenation.

IBM suggests that you use different data set names for LINKLIB, MIGLIB, CSSLIB, LINKLIBE on all SYSLIB statements. If the same data set name is used more than once, LLA will not manage the entire LNKST set.

### LINKLIB(name)

Specifies the name of the LINKLIB data set. If you specify a library other than SYS1.LINKLIB, you must ensure that SYS1.LINKLIB occurs within the LNKST concatenation. The system places the LINKLIB data set first in the LNKST concatenation.

**Default:** If you do not specify LINKLIB, the system uses SYS1.LINKLIB as the LINKLIB data set.

### MIGLIB(name)

Specifies the name of the MIGLIB data set. If you specify a library other than SYS1.MIGLIB, you must ensure that SYS1.MIGLIB occurs within the LNKST concatenation. The system places the MIGLIB data set after the LINKLIB data set in the LNKST concatenation.

**Default:** If you do not specify MIGLIB, the system uses SYS1.MIGLIB as the MIGLIB data set.

### CSSLIB(name)

Specifies the name of the CSSLIB data set. If you specify a library other than SYS1.CSSLIB, you must ensure that SYS1.CSSLIB occurs within the LNKST concatenation. The system places the CSSLIB data set after the MIGLIB data set in the LNKST concatenation.

**Default:** If you do not specify CSSLIB, the system uses SYS1.CSSLIB as the CSSLIB data set.

### LINKLIBE(name)

Specifies the name of the LINKLIBE data set. If you specify a library other than SYS1.SIEALNKE, you must ensure that SYS1.SIEALNKE occurs within the LNKST concatenation. The system places the LINKLIBE data set after the CSSLIB data set in the LNKST concatenation.

**Default:** If you do not specify LINKLIBE, the system uses SYS1.SIEALNKE as the LINKLIBE data set.

### MIGLIBE(name)

Specifies the name of the MIGLIBE data set. If you specify a library other than SYS1.SIEAMIGE, you must ensure that SYS1.SIEAMIGE occurs within the LNKST concatenation. The system places the MIGLIBE data set after the LINKLIBE data set in the LNKST concatenation.

**Default:** If you do not specify MIGLIBE, the system uses SYS1.SIEAMIGE as the MIGLIBE data set.

### LPALIB(name)

Specifies the name of the LPALIB data set. If you specify a library other than SYS1.LPALIB, you must ensure that SYS1.LPALIB occurs within the LPALST concatenation. The system places the LPALIB data set first in the LPALST concatenation.

**Default:** If you do not specify LPALIB, the system uses SYS1.LPALIB as the LPALIB data set.

**[ {VOLUME|VOLSER|VOL} (volser) ]**

Specifies the name of the volume on which the data set resides. The name can be from 1 to 6 characters.

This parameter is optional when the data set is cataloged in the system master catalog; the parameter is required when the data set is cataloged in a user catalog or if the data set is the LPALIB data set and it is not cataloged. You can use a value of \*\*\*\*\* to indicate that the data set is located on the current SYSRES volume, or use a value of "MCAT\*" to indicate that the data set is located on the volume containing the IPL-time master catalog.

For information other than that about the LPALIB data set, see [“Cataloging LNKLST data sets” on page 691.](#)

**Note:** If you do not specify [ {VOLUME|VOLSER|VOL} (volser) ], the system uses the volume indicated in the system master catalog.

## Example of the SYSLIB statement

The following example shows a PROGxx parmlib member to be IPLed in a test environment that is applying code fixes for the system. The libraries that are specified on these SYSLIB statements contain no data set members. Whether you use PROGxx or LNKLSTxx to activate the LNKLST concatenation, the system places SYS2.LINKLIB, SYS2.MIGLIB, SYS2.CSSLIB, SYS2.SIEALNKE, and SYS2.SIEAMIGE at the start of the LNKLST concatenation. The system places SYS2.LPALIB at the beginning of the LPALST concatenation. (You must ensure that SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE and SYS1.SIEAMIGE appear somewhere in the LNKLST concatenation and SYS1.LPALIB appears somewhere in the LPALST concatenation.)

```
SYSLIB LINKLIB(SYS2.LINKLIB)
SYSLIB MIGLIB(SYS2.MIGLIB)
SYSLIB CSSLIB(SYS2.CSSLIB)
SYSLIB LINKLIB(SYS2.SIEALNKE)
SYSLIB MIGLIB(SYS2.SIEAMIGE)
SYSLIB LPALIB(SYS2.LPALIB)
```

## Syntax format of the LNKLST statements

**Rule:** You must enter parameters on the LNKLST statement in the order shown in the syntax diagrams.

### Syntax Format of LNKLST DEFINE:

```
LNKLST DEFINE NAME(name)
        [COPYFROM(name)]
        [NOCHECK]
```

### Syntax Format of LNKLST ADD:

```
LNKLST ADD NAME(name) DSNAME(dsname)
        [{VOLUME|VOLSER|VOL}(name)]
        [{ATBOTTOM|ATTOP|AFTER(dsname)}]
        [CONCAT(NOCHECK|CHECK)]
```

### Syntax Format of LNKLST DELETE:

```
LNKLST DELETE NAME(name) DSNAME(dsname)
```

### Syntax Format of LNKLST UNDEFINE:

```
LNKLST UNDEFINE NAME(name)
```

**Syntax Format of LNKLIST TEST:**

```
LNKLST TEST NAME(name) MODNAME(modname)
```

**Syntax Format of LNKLIST ACTIVATE:**

```
LNKLST ACTIVATE NAME(name)
```

**Syntax Format of LNKLIST UPDATE:**

```
LNKLST UPDATE {JOB(jobname)}
               {ASID(asid)}
               [DELAY(delay)]
```

**Syntax Format of UNALLOCATE:**

```
LNKLST UNALLOCATE
```

**Syntax Format of ALLOCATE:**

```
LNKLST ALLOCATE
```

**LNKLST**

Statement type indicating that an action is to be performed for a LNKLIST set. LINKLIST, LINKLST, LNK, or LNKLIST can be specified as an alternative to LNKLIST.

**DEFINE**

Specifies the definition of a LNKLIST set (a set of ordered data sets for the LNKLIST concatenation).

**Default:** None

**ADD**

Indicates that you want to add a data set to the specified LNKLIST set.

IBM suggests using the COPYFROM parameter, when feasible, to define a LNKLIST set instead of defining the set and then using LNKLIST ADD statements to add individual data sets. The use of COPYFROM reduces system processing time. Use the LNKLIST ADD statement to add a new data set to a specific LNKLIST set.

You cannot add a data set to the current or active LNKLIST set. If a data set has been migrated, the request waits until the data set is available. For information about the maximum number of data sets you can define to a LNKLIST set, see [“Concatenating data sets to the LNKLIST concatenation” on page 690](#).

**Default:** None.

**DELETE**

Indicates that you want to delete a data set from the specified LNKLIST set. You cannot delete a data set from the current or active LNKLIST set.

**Default:** None.

## UNDEFINE

Indicates that you want to remove the definition of the LNKLST set from the system. You cannot remove the definition of the current LNKLST set, another LNKLST set that is being actively used by a job or address space, or the LNKLST defined at IPL through LNKLSTxx and the LNK parameter of IEASYSxx.

**Note:** You cannot specify this parameter at IPL. It is valid only when you specify SET PROG=xx.

See [“Removing or compressing a data set in an active LNKLST set”](#) on page 692 for information about LLA management of LNKLST sets.

**Default:** None.

## TEST

Indicates that you want to locate a specific routine associated with a data set in the LNKLST set. If the system locates the data set, the system indicates the name of the data set. If a data set has been migrated, the request waits until the data set is available.

**Note:** You cannot specify this parameter at IPL. It is valid only when you specify SET PROG=xx.

## ACTIVATE

Indicates that you want to activate the specified LNKLST set as the LNKLST concatenation. If you use SETPROG LNKLST or SET PROG=xx to activate another LNKLST set after IPL, jobs or address spaces that are still active continue to use the previous current LNKLST set. To associate a job or an address space with the current LNKLST set after IPL, you can use the UPDATE option on the SETPROG LNKLST command or the LNKLST UPDATE statement specified in the member for SET PROG=xx.

If a data set in the LNKLST set has been migrated before the LNKLST set is activated, the request waits until the data set is available.

When the ACTIVATE request completes, the system issues an event (ENF) signal (event code 52). Depending on the options specified in SMFPRMxx, whenever a LNKLST set is activated, the system records SMF record type 90 subtype 29. See [Chapter 84, “SMFPRMxx \(system management facilities \(SMF\) parameters\)”](#), on page 735.

You must have a LNKLST ACTIVATE statement defined in PROGxx when you use PROG=xx to activate the LNKLST set at IPL.

See [“Removing or compressing a data set in an active LNKLST set”](#) on page 692 for information about LLA management of LNKLST sets.

## UPDATE

Indicates that the system is to update an address space or the specified job or jobs to use the current LNKLST set. Otherwise, if the job is using another LNKLST set when the current LNKLST set is activated, it will continue to use the previous LNKLST set until it completes operations. When the job completes and restarts, the job then uses the data sets defined in the new currently active LNKLST set.

See [“Removing or compressing a data set in an active LNKLST set”](#) on page 692 for information about LLA management of LNKLST sets.

### **Note:**

1. You cannot specify this parameter at IPL. It is valid only when you specify SET PROG=xx.
2. Be careful when you use UPDATE. Updating jobs in an address space while it is fetching a module can cause the fetch to fail or result in fetching a copy that is not up-to-date. The system does not attempt to verify the validity of the data for the update function.

## UNALLOCATE

Indicates that you want to undo all existing allocations obtained while processing active LNKLST sets. This also releases the SYSDSN ENQ.

**Note:**

1. Make sure that you do not delete or move the LNKST data sets while the allocations are not in effect (from the time that you use the UNALLOCATE request until the time that you use the ALLOCATE request).
2. Once you have completed everything associated with the UNALLOCATE, you must specify LNKST ALLOCATE to re-obtain the remaining ENQs.

**ALLOCATE**

Indicates that you want to re-obtain the allocation (and SYSDSN ENQ) for every data set in every active LNKST.

**NAME(name)**

The name of the LNKST set that you want to specify. Naming conventions are as follows:

- You can specify from 1 to 16 characters for name.
- You can use alphanumerics, underscores, periods, and #, \$, or @.
- Do not use imbedded blanks.
- Do not use the names CURRENT or IPL. The system uses CURRENT to mean the current LNKST set and IPL to mean LNKST information specified in SYS1.PARMLIB member LNKSTxx.
- Do not begin the name with SYS. SYS is reserved for IBM use.

**Example:** NAME(MY.LNKST.SET)

**[COPYFROM(name)]**

The name of an existing LNKST set from which to initialize the LNKST set you are defining. If you specify CURRENT for the name, the system uses the current LNKST set.

**Example:**

```
LNKST DEFINE NAME(MY.LNKST.SET)
COPYFROM(SYSTEM.ACCT.DATA)
```

**Example:** If you omit this parameter, the system initializes the LNKST set with the LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE data sets in that order.

**[NOCHECK]**

Indicates that the system does not check to determine if the specified LNKST set contains SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, SYS1.SIEAMIGE before allocating the LNKST concatenation.

**Note:** Use NOCHECK with caution. NOCHECK is available ONLY to allow the creation of a LNKST without SYS1.LINKLIB/MIGLIB/CSSLIB/LINKLIBE/MIGLIBE. NOCHECK should be used ONLY when needed (such as if the pack has a problem).

For the following code to work, you must IPL using the SYSLIB statement to define an alternate LINKLIB data set. The LINKLIB, MIGLIB, CSSLIB, LINKLIBE, and MIGLIBE data sets are all determined during IPL and can never be changed or removed from the LNKST. To create a LNKST without those data sets, IPL specifying other data sets (empty PDSs can be used) with the PROGxx SYSLIB statement. The PROGxx statement would contain the following:

```
SYSLIB LINKLIB(SYS2.LINKLIB)
SYSLIB MIGLIB(SYS2.MIGLIB)
SYSLIB CSSLIB(SYS2.CSSLIB)
SYSLIB LINKLIBE(SYS2.SIEALNKE)
SYSLIB MIGLIBE(SYS2.SIEAMIGE)
```

Then IPL with prog=(xx) or prog=(xx,00).

You might use NOCHECK after you have modified SYS1.LINKLIB and want to compress SYS1.LINKLIB. The following procedure is an example:

1. Create a data set that contains a copy of SYS1.LINKLIB.
2. Define a LNKST set that has the same name as the current LNKST set but includes the replacement for SYS1.LINKLIB. Specify NOCHECK when defining this LNKST.
3. Activate the LNKST set you have defined with the replacement copy of SYS1.LINKLIB.
4. Stop the library lookaside (LLA) procedure. (See "Starting LLA" and "Modifying LLA" in [z/OS MVS Initialization and Tuning Guide](#).)
5. Use SET PROG=xx with LNKST UPDATE or SETPROG LNKST UPDATE to specify that jobs use the LNKST set. At this point, SYS1.LINKLIB is not active.
6. Compress SYS1.LINKLIB.
7. Use SET PROG=xx with LNKST ACTIVATE or SETPROG LNKST ACTIVATE to activate the original LNKST set that includes SYS1.LINKLIB.
8. Use SET PROG=xx with LNKST UPDATE or SETPROG LNKST UPDATE to specify that jobs use the original LNKST set and SYS1.LINKLIB.

### **DSNAME(dsname)**

The 44-character name of a data set or library that you want to add to the specified LNKST set or delete from the specified LNKST set. DSN, LIB, LIBRARY are accepted synonyms for this parameter.

The data set can be a PDS or a PDSE. (IBM suggests that you use PDSEs because of the limitations on the number of extents for a LNKST concatenation. See "Concatenating data sets to the LNKST concatenation" on page 690.) For the LNKST created at IPL, the *dsname* cannot be an alias.

Data sets to be added can be SMS-managed or non SMS-managed. After the system determines the volume and the SMS status of the data set, the following actions result in an error when the system tries to allocate the LNKST set:

- If the data set in the LNKST set changes status from SMS-managed to non SMS-managed, or from non-SMS managed to SMS-managed.
- If a non SMS-managed data set in the LNKST set is deleted and moved to another volume.

In either case, to add the data set after the change has occurred, you must first delete the data set from the LNKST set and add it again.

### **[{VOLUME|VOLSER|VOL}(name)]**

The name of the volume on which the data set resides. The data set must be cataloged. If the volume does not match the name in the catalog, the ADD request fails. The name can be from 1 to 6 characters.

You can use a value of \*\*\*\*\* to indicate that the data set is located on the current SYSRES volume. You can use a value of "MCAT\*" to indicate that the data set is located on the volume containing the IPL-time master catalog.

When the data set is cataloged in a user catalog instead of the master catalog, you can use this parameter. If a data set is cataloged in a user catalog, but not in the system master catalog, you must specify the VOLSER of the volume on which the data set resides. See "Cataloging LNKST data sets" on page 691.

**Default:** If you omit this parameter, the system uses the volume indicated in the catalog.

### **[{ATBOTTOM|ATTOP|AFTER}(dsname)]**

Indicates where in the LNKST set you want to place the data set.

ATBOTTOM indicates that you want to place the data set specified on the DSNAME parameter at the bottom of the list of data sets in the LNKST set.

ATTOP indicates that you want the data set specified on the DSNAME parameter to be added to the beginning of the LNKST set. The system always places the LINKLIB, MIGLIB, CSSLIB LINKLIB, and



MIGLIB data sets in that order at the beginning of every LNKLIST set in the LNKLIST concatenation. If you use ATTOP, the system always places the data set after the MIGLIB data set.

AFTER(*dsname*) indicates that the system places the data set specified on the DSNAME parameter after the data set specified by *dsname*. You cannot use this parameter to place a data set after the LINKLIB, MIGLIB, CSSLIB LINKLIB, or MIGLIB data set in the LNKLIST set. Instead, use ATTOP if you want to place the data set immediately after the MIGLIB data set.

**Default:** If you omit ATBOTTOM, ATTOP, or AFTER, the system adds the data set to the bottom of the LNKLIST set.

### [CONCAT(NOCHECK|CHECK)]

Indicates whether to check to see if the concatenation defined by the LNKLIST set is full.

NOCHECK indicates that you do not want to check to see if the concatenation is full. If the concatenation is full, it will be detected when the LNKLIST set is activated.

CHECK indicates that you want to check to see if the concatenation is full. This implies that all the data sets in the LNKLIST set must be concatenated. Specification of CHECK causes system processing to take longer.

**Default:** NOCHECK

### MODNAME(name)

MODNAME specifies the name of a routine or module to be located in the LNKLIST set. MODULE and MOD can be used as synonyms for MODNAME.

```
LNKLST TEST NAME(MY.LNKLIST.SET) MODNAME(MYMODULE)
```

### {JOB(jobname)|ASID(asid)}

Specifies the name of the job or address space.

JOB specifies the name of the job or jobs specified by *jobname*. You can use wildcard characters (?) or \*) for *jobname*. LNKLIST UPDATE updates any job whose name matches the specified criteria. The system compares *jobname* to the name of any initiated job or jobs that match, or to the name of the address space.

ASID specifies the address space ID for the job.

```
LNKLST UPDATE JOB(MYJOB)
```

### DELAY(delay)

Indicates the number of seconds to delay the completion of the UPDATE operation. The number of seconds can be from 0 - 255.

The LNKLIST statement is updated immediately, but the processing for closing and unallocating LNKLIST data sets that are no longer in use is delayed by the specified amount of time.

## Examples of the LNKLIST statement

This example shows how to define LNKLIST set MY.LINKLIST and indicate that MY.LINKLIST is to be activated at IPL. The resulting LNKLIST concatenation consists of the LINKLIB, MIGLIB, CSSLIB LINKLIB, and MIGLIB data sets in that order:

```
LNKLST DEFINE NAME(MY.LINKLIST)
LNKLST ACTIVATE NAME(MY.LINKLIST)
```

This next example shows how to add data sets to the LNKLIST set:

```
LNKLST DEFINE NAME(NEWLLSET) COPYFROM(OLDLLSET)
LNKLST ADD NAME(NEWLLSET) DSNAME(dataset.to.be.added)
LNKLST ACTIVATE NAME(NEWLLSET)
```

This example shows how the concatenation of data sets for LNKLIST1 is defined.

```

SYSLIB LINKLIB(SYS2.LINKLIB)
SYSLIB MIGLIB(SYS2.MIGLIB)
SYSLIB CSSLIB(SYS2.CSSLIB)
SYSLIB LINKLIB(SYS2.SIEALNKE)
SYSLIB MIGLIB(SYS2.SIEAMIGE)
SYSLIB LPALIB(SYS2.LPALIB)
LNKLST DEFINE NAME(LNKLIST1)
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.LINKLIB) ATTOP
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.MIGLIB)
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.CSSLIB)
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.SIEALNKE)
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.SIEAMIGE)
LNKLST ADD NAME(LNKLIST1) DSNAME(SYS1.AUXLIB) VOLUME(U32PAK)
LNKLST ACTIVATE NAME(LNKLIST1)

```

As a result of these PROGxx specifications, the following data sets, in the order specified, are concatenated at IPL:

```

SYS2.LINKLIB,SYS2.MIGLIB,SYS2.CSSLIB,SYS2.SIEALNKE,SYS2.SIEAMIGE,SYS1.LINKLIB,
SYS1.MIGLIB,SYS1.CSSLIB, SYS1.AUXLIB

```

In the example of the LNKLIST1 concatenation, note the following:

- The SYSLIB statements specify that SYS2.LINKLIB, SYS2.MIGLIB, SYS2.CSSLIB, SYS2.SIEALNKE, and SYS2.SIEAMIGE replace the system defaults at the beginning of the LNKLIST concatenation.
- SYS2.LPALIB is to appear first in the LPALST concatenation.
- SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, and SYS1.SIEAMIGE must be defined in the LNKLIST concatenation. SYS1.LINKLIB, SYS1.MIGLIB, SYS1.CSSLIB, SYS1.SIEALNKE, and SYS1.SIEAMIGE are specified, in that order, after SYS2.LINKLIB, SYS2.MIGLIB, SYS2.CSSLIB, SYS2.SIEALNKE and SYS2.SIEAMIGE.
- SYS1.AUXLIB is specified at the end of the LNKLIST1. VOLUME indicates that SYS1.AUXLIB is cataloged on VOLSER U32PAK.
- The LNKLIST ACTIVATE statement activates LNKLIST1 at IPL.

## Syntax format of the LPA statements

### Syntax format of LPA ADD:

```

LPA ADD
  MODNAME(modname,...) | MASK(mask)
  DSNAME(dsname | LNKLIST)
  [{VOLUME|VOLSER|VOL}(name)]
  [PAGEABLE | FIXED]
  [PAGEPROTALL | PAGEPROTPAGE]
  [SVCNUMDEC(svcnum) | SVCNUMDEC(svcnum,routcode)]
  [ADDALIAS | NOADDALIAS]
  [NOAPFREQ | APFREQ]

```

### Syntax format of LPA DELETE:

```

LPA DELETE
  MODNAME(modname,...)
  FORCE(YES)
  [CURRENT|OLDEST]

```

### Syntax format of LPA CSAMIN:

```

LPA CSAMIN
  (below,above)

```

**ADD**

Specifies that one or more modules is to be added to LPA.

**Default:** None

**CSAMIN**

Specifies the minimum amount of CSA and ECSA that must remain after a module is added to LPA. If the requested ADD operation would reduce the CSA or ECSA below the defined minimum, the system rejects the operation.

Modules added to the system via dynamic LPA processing are placed into CSA or ECSA storage. Therefore, it is important to ensure that the system CSA and ECSA sizes are adequately defined to handle the additional consumption of CSA storage resulting from the issuance of the dynamic LPA request. Further protection can be gained by using the CSADMIN parameter.

**Default:** (0,0)

**DELETE**

Specifies that one or more modules is to be deleted from LPA. Only modules added to LPA after an IPL are eligible for dynamic deletion.

**Default:** None

**LPA**

Statement type indicating that an action may be performed on LPA.

***below***

The minimum amount of below-16M CSA storage that must remain after the ADD operation, expressed in the format  $n|nK|nM$ , where  $n$  is a decimal number,  $nK$  is  $n*1024$ , and  $nM$  is  $n*1024*1024$ ,

***above***

The minimum amount of above-16M CSA storage that must remain after the ADD operation, expressed in the format  $n|nK|nM$ , where  $n$  is a decimal number,  $nK$  is  $n*1024$ , and  $nM$  is  $n*1024*1024$ ,

**MODNAME(modname,...,modname)**

*modname* is the 1-8 character LPA module name or alias. If the last character of the *modname* is "\*", it will be treated as X'C0'. This lets you directly specify the name of a load module that ends with that nonprintable character. Wildcard characters are not supported within *modname*. A maximum of 128 module names can be provided. MOD and MODULE can be used as synonyms of MODNAME.

If MODNAME is not specified, MASK must be specified.

**MASK(mask)**

*mask* is the 1-8 character mask that is to be applied to all the members of the specified data set. It can contain wildcard characters "\*" and "?" and all members that match will be processed.

If MASK is not specified, MODNAME must be specified.

**DSNAME(dsname)**

*dsname* is the 1-44 character data set name that contains the modules or aliases. When MODNAME is specified, you can specify DSNAME(LNKLIST) if you want the system to search the linklist instead of a particular data set. LNK, LNKLIST, LINKLIST or LINKLIST can be specified as an alternative to LNKLIST. The data set must be cataloged. It can be allocated as a PDS or PDSE program library.

The attribute of the CSA for each module is assigned as OWNER=SYSTEM. DSN, LIB, and LIBRARY can be used as synonyms of DSNAME.

**Default:** None

**VOLUME|VOLSER|VOL(name)**

*name* is the name of the volume on which the data set resides. The name can be from 1 to 6 characters.

You can use a value of `*****` or `&SYSR1` to indicate that the data set is located on the current SYSRES volume. You can use a value of `"*MCAT"` to indicate that the data set is located on the volume containing the IPL-time master catalog.

**Default:** None

#### **PAGEABLE | FIXED**

Indicates whether the modules are to be placed in fixed or pageable storage. PAGE can be used as a synonym of PAGEABLE.

**Default:** PAGEABLE

#### **PAGEPROTALL | PAGEPROTPAGE**

Indicates whether to page protect the modules entirely. The default is to page protect the entire module (PAGEPROTALL). When that default is taken, storage utilization for the modules increases, as each module gets allocated a number of whole pages (so that they can be page protected), rather than just the amount of storage that is truly necessary to load the module.

PPALL and PPA can be used as synonyms for PAGEPROTALL.

When PAGEPROTPAGE is requested, however, only the whole pages within each load module are page protected, which keeps the storage use to the minimum amount but which makes it possible that a storage overlay of the beginning or end of the load module can occur.

PPPAGE and PPP can be used as synonyms for PAGEPROTPAGE.

**Default:** PAGEPROTALL

#### **SVCNUMDEC=svcnun | SVCNUMDEC=(svcnun,route)**

SVCNUMDEC, or SVCDEC, identifies the entry within the SVC Table to update. The SVC number, *svcnun*, can be from 0 - 255. For an extended SVC (109, 116, 122, 137), you must specify the *route*, which is the extended SVC routing code. The *route* must be within the range that is supported by the SVC. For example, for SVC 109, the *route* must be from 0 - 255. The *route* for other extended SVC number depends on the release of z/OS. Use the SVCNUMDEC function for updating already-defined SVC Table entries. Do not use it to create new entries, as you might not get all of the attributes that you need. NOADDALIAS, or the value set by DEFAULTS LPA ADDALIAS | NOADDALIAS.

**Default:** This is not an SVC routine. The SVC table is not updated.

#### **ADDALIAS | NOADDALIAS**

ADDALIAS, or ALIAS, indicates to process provided names and aliases of the provided names. NOADDALIAS, or NOALIAS, indicates to process only the names provided. You can use NOADDALIAS to override the default values set by DEFAULTS LPA ADDALIAS.

**Default:** NOADDALIAS, or the value set by DEFAULTS LPA ADDALIAS | NOADDALIAS.

#### **NOAPFREQ | APFREQ**

APFREQ indicates that the specified data set must be APF-authorized. APFREQ does not apply if the data set is specified as LNKST which indicates that the LNKST concatenation is to be used. NOAPFREQ indicates that the data set need not be APF-authorized.

APFREQ indicates that, by default, the data set specified for LPA ADD must be APF-authorized. APFREQ does not apply if the data set is specified as LNKST which indicates that the LNKST concatenation is to be used. NOAPFREQ indicates that, by default, the data set need not be APF-authorized.

**Default:** The default for LPA ADD depends on the PROGxx DEFAULTS LPA and the SETPROG DEFAULTS LPA command specification. The default default is NOAPFREQ. If DEFAULTS LPA APFREQ is in effect, the default for LPA ADD is APFREQ.

#### **FORCE(YES)**

Confirms that the delete requester understands the ramifications of deleting a module from LPA, when the system can have no knowledge of whether any code is executing within the specified module.

**Default:** None. FORCE is a required parameter.

#### **CURRENT | OLDEST**

CURRENT specifies that the current copy is to be deleted. OLDEST specifies that the oldest dynamic copy other than the current one is to be deleted. CUR can be used as a synonym of CURRENT. OLD can be used as a synonym of OLDEST.

**Default:** CURRENT

## Syntax format of the REFRPROT statement

```
REFRPROT
```

#### **REFRPROT**

Statement type indicating that REFR modules are protected from modification.

## Syntax format of the NOREFRPROT statement

```
NOREFRPROT
```

#### **NOREFRPROT**

Statement type indicating that REFR modules are not protected from modification. NOREFRPROT is the default.

## Syntax format of the TRACKDIRLOAD statement

```
TRACKDIRLOAD
```

#### **TRACKDIRLOAD**

Statement type that enables system-wide tracking of directed load modules. TRACKDIRLOAD is the default.

## Syntax format of the NOTRACKDIRLOAD statement

```
NOTRACKDIRLOAD
```

#### **NOTRACKDIRLOAD**

Statement type that disables system-wide tracking of directed load modules.

## Syntax format of the DEFAULTS statements

```
DEFAULTS LNKLST [REQCOPYFROM | NOREQCOPYFROM] [COPYFROMCUR | NOCOPYFROMCUR]
DEFAULTS LPA [ADDALIAS | NOADDALIAS] [NOAPFREQ | APFREQ]
DEFAULTS EXIT [EXITTYPE({ALL | INSTALLATION | NOTPROGRAM}) ]
```

#### **ADDALIAS | NOADDALIAS**

ADDALIAS, or ALIAS, indicates to process provided names and aliases of the provided names. NOADDALIAS, or NOALIAS, indicates to process only the names provided.

**Default:** NOADDALIAS.

### **ALL | INSTALLATION | NOTPROGRAM**

Indicates that a DISPLAY PROG,EXIT command uses either ALL, INSTALLATION, or NOTPROGRAM if none of the following exit types are specified:

- ALL, which applies to exits that are either classified or not classified.
- INSTALLATION, or INSTALL, which applies to exits that are classified as installation exits.
- NOTPROGRAM, which applies to exits that are classified as program exits. PROGRAM cannot be specified as a default.
- PROGRAM, or NOTPROG, which applies to exits that are either classified or not classified as an exit that is not an installation exit.

If one of these exit types is specified, the default is not used.

**Note:** Some exits are not classified as installation or program exits.

**Default:** ALL

### **COPYFROMCUR | NOCOPYFROMCUR**

Indicates that a LNKST DEFINE statement, or SETPROG LNKST,DEFINE command must specify, or must not specify COPYFROM(CURRENT).

If DEFAULTS LNKST COPYFROMCUR is specified and LNKST DEFAULTS REQCOPYFROM is specified, the COPYFROM keyword does not have to be specified with the LNKST DEFINE statement.

COPYFROMCUR, or CFCUR, indicates that the COPYFROM(CURRENT) keyword must be specified.

NOCOPYFROMCUR, or NOCFCUR, indicates that the COPYFROM(CURRENT) keyword must not be specified.

**Default:** NOCOPYFROMCUR

### **DEFAULTS**

Statement type indicating to set defaults that are applied on LNKST and LPA statements in PROGxx and also applied on the SETPROG LNKST, SETPROG LPA, and DISPLAY PROG,EXIT commands.

### **EXIT**

Indicates that this default applies to the DISPLAY PROG,EXIT command.

### **LNKST**

Indicates that this default applies to LNKST statements in PROGxx and SETPROG LNKST commands.

### **LPA**

Indicates that this default applies to LPA statements in PROGxx and SETPROG LPA commands.

### **APFREQ | NOAPFREQ**

APFREQ indicates that, by default, the data set specified for LPA ADD must be APF-authorized.

APFREQ does not apply if the data set is specified as LNKST which indicates that the LNKST concatenation is to be used. NOAPFREQ indicates that, by default, the data set need not be APF-authorized.

**Default:** NOAPFREQ.

### **REQCOPYFROM | NOREQCOPYFROM**

Indicates that a LNKST DEFINE statement, or SETPROG LNKST,DEFINE command must specify, or must not specify the COPYFROM or NOCOPYFROM keyword.

REQCOPYFROM, or REQCF, indicates that the COPYFROM keyword must be specified.

NOREQCOPYFROM, or NOREQCF, indicates that the NOCOPYFROM keyword must be specified.

**Default:** NOREQCOPYFROM

# Chapter 82. SCHEDxx (PPT, master trace table, and abend codes for automatic restart)

Use the SCHEDxx member of parmlib to specify the following:

- Size of the master trace table.
- Abend codes that are eligible for automatic restart.
- Programs that are to be included in the program properties table (PPT) and thus receive special attributes.

**Note:** In previous releases of MVS, SCHEDxx allowed you to define attributes for the eligible device table (EDT) through the EDT statement. As of MVS/SP 5.1, the EDT statement is no longer valid. Instead, use HCD to define attributes for the EDT in the input/output definition file (IODF). For more information about defining the EDT, see *z/OS HCD Planning*.

You can use the following statement types in SCHEDxx:

## MT

Defines the size of the master trace table if one exists.

## NORESTART

Allows you to delete system and user abend codes from the list of abend codes that are eligible for automatic restart.

## PPT

Allows the installation to specify a list of programs that require special attributes or to change the attributes of the IBM-supplied default entries in the PPT (see Table 58 on page 720). The system scans this PPT to determine which, if any, special attributes apply to the program it is initiating.

**Note:** Usually, you should not add or change programs in the program properties table (PPT) unless the instructions for installing a program direct you to do so. If you do add a program to the PPT, or change an existing entry's properties, ensure that the program can function with the properties you have assigned to it. For example, a program designed to run in program protect key 8 might not be able to run in key 10 because of hardcoded key specifications in the program. If you were to specify KEY(10) in this case, the program will not function correctly.

## RESTART

Allows you to add user abend codes to the list of abend codes that are eligible for automatic restart.

## Parameter in IEASYSxx (or specified by the operator)

```
SCH={aa
      (aa,L)
      (aa,bb,...[,L])
      (,L)}
```

The two characters (A-Z, 0-9, @, #, or \$), represented by aa (or bb, etc.), are appended to SCHED to identify one or more SCHEDxx members of parmlib.

If the L option is specified, either on the SCH= keyword in the IEASYSxx parmlib member or in response to the 'SPECIFY SYSTEM PARAMETERS' prompt, the system displays the contents of SCHEDxx on the operator's console during IPL.

## Modifying the PPT between IPLs

You can use the SET SCH command to dynamically modify the contents of the PPT. The SET SCH command causes the system to replace the current PPT definitions with the IBM-supplied default PPT definitions, and the PPT definitions from one or more SCHEDxx members that you specify on the command. The new PPT definitions take effect immediately (that is, without requiring a reIPL of the system).

**Note:** Using the SET SCH command to change the properties of a program from NOCRITICALPAGING to CRITICALPAGING does not result in the system paging in any storage associated with this program that is currently paged out. It only guarantees that storage associated with the program that is currently paged in will not be paged out. To ensure that the associated storage of a program is all paged in after dynamically changing the properties of the program, end and restart the program.

For more information about the SET SCH command, see [z/OS MVS System Commands](#).

## Syntax rules for SCHEDxx

The following rules apply to the creation of SCHEDxx:

- Use columns 1 through 71. Do not use columns 72-80, because the system ignores these columns.
- Comments may appear in columns 1-71 and must begin with “/\*” and end with “\*/”.
- A statement type consists of 1-10 characters.
- A statement must begin with a valid statement type followed by at least one blank.
- A statement ends with the beginning of the next valid statement type or EOF.
- A statement can be continued even though there is no explicit continuation character.
- Multiple statement types are accepted.
- Operands must be 60 characters or less and may not span multiple records.
- Operands must be separated by valid delimiters. Valid delimiters are a comma, a blank, or column 71. If the operand contains parenthesis, then the right parenthesis is accepted as a valid delimiter.
- Multiple occurrences of a delimiter are accepted but treated as one.

## IBM-supplied default for SCHEDxx

None.

## IBM-supplied sample member SCHEDxx

IBM provides a sample member, named SCHED00, in SYS1.SAMPLIB. SCHED00 contains sample statements for various programs; these statements are not necessarily the IBM-supplied values.

To create a SCHEDxx member for your installation, you can copy SCHED00 to a SCHEDxx member and modify it according to your needs.

## Statements and parameters for SCHEDxx

The SCHED statements are described as follows:

```
MT SIZE{ (nnnK) }
      { (NONE) }
      { (24K) }
```



## MT

Specifies the size (in kilobytes) of the master trace table, which is used by the TRACE command. The system creates the master trace table during master scheduler initialization. By default, the master trace table is 24 kilobytes in size.

To specify a different size for the master trace table, specify MT SIZE(nnnK), where *nnn* is any value from 16 to 999. You must add the letter K for the increments (kilobytes), and enclose the entire value in parentheses.

For example, to have the system create a master trace table of 50 kilobytes, specify the following MT statement in SCHEDxx:

```
MT SIZE(50K)
```

If you do not want a master trace table to be created, specify MT SIZE as (NONE), as follows:

```
MT SIZE(NONE)
```

No table is created.

If you specify more than one MT statement in a SCHEDxx member, the system uses the first occurrence and ignores any subsequent MT statements.

**Default:** MT SIZE(24K)

## NORESTART CODES(code,code...)

Specifies which system and user abend codes are to be deleted from the table of abend codes that are eligible for automatic restart.

RESTART and NORESTART allows the installation to customize the list of abend codes that are eligible for automatic restart. This list is created by merging the user abend codes that are specified on the RESTART statement with the list of IBM-supplied system abend codes. A user abend code cannot have the same number as a system abend code. The system ignores a user abend code that is a duplicate of a system abend code. The IBM-supplied system abend codes are listed in [Table 57 on page 715](#).

*Table 57. IBM-supplied system abend codes*

| Code | Code | Code | Code |
|------|------|------|------|
| 001  | 20A  | 422  | 813  |
| 031  | 213  | 513  | 837  |
| 033  | 214  | 514  | 906  |
| 03A  | 217  | 613  | 913  |
| 0A3  | 2F3  | 614  | 926  |
| 0B0  | 313  | 626  | 937  |
| 0F3  | 314  | 637  | A14  |
| 100  | 317  | 700  | B14  |
| 106  | 32D  | 714  | B37  |
| 113  | 413  | 717  | C13  |
| 117  | 414  | 737  | E1F  |
| 137  | 417  | 806  | E37  |

The value range is 0-FFF (Hex).

## RESTART CODES(code,code...)

Specifies the user abend codes that are to be eligible for automatic restart. These are to be added to the system abend codes that are supplied by IBM.

**Value range:** 0-FFF (Hex)

## PPT

Allows the installation to specify a list of programs that require special attributes. Sometimes, your application programs need to possess special properties to run as efficiently and securely as possible. For example, an application that requires access to fetch-protected system data needs a system key (0-7) instead of the usual problem program key of 8. Or, for example, an application that cannot run V=R, but must not be swapped out because of real-time considerations, will need to be identified to the system as nonswappable. Entries for these programs are created in the program properties table (PPT).

### PGMNAME(name)

PGMNAME(name) identifies by name the program, specified in the PGM parameter on the EXEC statement for a job or step, that requires special attributes. It must consist of an alphabetic or national (#, @, or \$) character followed by 0 to 7 alphanumeric or national characters. PGMNAME(name) is required on the PPT statement. A program that is specified in the PPT will obtain special attributes only if all of the following are true:

- The program is fetched from an authorized library or from the link pack area (pageable, modified, fixed, or dynamic LPA).
- All STEPLIB data sets are authorized if a STEPLIB DD (or concatenation) exist for the step.
- All JOBLIB data sets are authorized if a JOBLIB DD (or concatenation) exists for this job and no STEPLIB DD exists for this step.

Otherwise, problem program attributes are assigned. All programs that are described by PPT entries must come from an APF library or concatenation, or from the link pack area.

### Notes:

1. To override an IBM-supplied entry in the PPT, use the same program name as the IBM-supplied entry.
2. Although you cannot remove entries from the PPT, you can create the effect of removing an entry from the PPT by specifying the program name without special attributes.

For example, a JES2 installation might (for auditing purposes) want to “remove” the IATINTK entry from the PPT by including the following statement in the SCHEDxx member:

```
PPT PGMNAME(IATINTK)
```

This statement overrides the existing IATINTK entry in the PPT, and causes any APF-authorized program that is named IATINTK to run with the same attributes as a problem program.

3. If you specify more than one PPT statement with the same program name, the systems accept only the first occurrence of the name and issues error message IEF732I for all subsequent occurrences of that name.
4. When referring to a DD statement, the system does not honor requests for special properties as defined in the PPT.

**Default:** None.

### [CANCEL | NOCANCEL]

The program that is specified on PGMNAME can be canceled (CANCEL) or cannot be canceled (NOCANCEL).

**Default:** CANCEL

### [KEY(n)]

The program that is specified on PGMNAME is to have the protection key (n) assigned to it. The range of values for n is 0–15. A KEY value greater than 8 requires special consideration. Usually, keys greater than 8 are reserved for V=R programs, and the system assigns these keys dynamically. If the KEY field is specified for a V=R program, ensure that no other V=R program runs at the same time with the same key. A V=V program can run with a KEY value greater than 8 when V=R programs are running with channel program translation.

**Value range:** 0-15

**Default:** Key 8

**[SWAP | NOSWAP]**

The program that is specified on PGMNAME is swappable (SWAP) or non-swappable (NOSWAP).

**Default:** SWAP

**[PRIV | NOPRIV]**

The program that is specified on PGMNAME is privileged (PRIV), or not privileged (NOPRIV).

A task marked PRIV is put in the SYSSTC service class if it is not explicitly classified in the WLM classification rules.

**Default:** NOPRIV

**[DSI | NODSI | NODSI\_ALLOWBATCH]**

The program specified on PGMNAME requires data set integrity (DSI) or does not require data set integrity (NODSI or NODSI\_ALLOWBATCH). Data set integrity means that the job holds an ENQ for the data sets it allocates. The DSI/NODSI/NODSI\_ALLOWBATCH options apply to batch type allocations only, as opposed to dynamic allocations, because the Dynamic Allocation service uses its input parameters to determine whether to enqueue on data sets. JES2 is an exception in that it honors the PPT specification and uses DSI/NODSI for dynamic allocations of the JES2 PROCLIB data sets.

If DSI is specified, the system acquires an ENQ for all data sets requested by the program. The ENQ is exclusive or shared, depending on the disposition on the DD request.

If NODSI or NODSI\_ALLOWBATCH is specified, the system still issues an ENQ for all data sets requested by the program. However, the ENQ is released before the program is started. NODSI is only honored when the program is running as a started task. If NODSI is requested for a program that is not running as a started task, NODSI is not honored and message IEF188I is issued.

If NODSI\_ALLOWBATCH is specified, the system will honor the 'no data set integrity' attribute for programs that run as a started task as well as for programs that run as a batch job step. Note that requesting NODSI\_ALLOWBATCH for a program that runs as a batch job step will expose potential integrity issues.

Jobs for which NODSI is specified are not started if the job contains either a JOBLIB or STEPLIB, and both of the following conditions are true:

- The job cannot get the ENQ on the following types of data set names:
  - GDG absolute generation data set name (unless the absolute generation data set name is specified on the JCL).
  - Real data set name (when its corresponding alias data set name is specified on the DD statement in the JCL).
- The installation has specified WAITALLOC(NO) on the SDSN\_WAIT keyword in the ALLOCxx member of SYS1.PARMLIB, or has taken the default. For more information about the SDSN\_WAIT keyword, see [Chapter 4, “ALLOCxx \(allocation system defaults\),” on page 67](#).

**Notes:**

1. For NODSI or NODSI\_ALLOWBATCH, the job must be a one-step job. If the job is not a one-step job, NODSI or NODSI\_ALLOWBATCH are nullified and the system issues message IEF188I. All other properties remain in effect, in accordance with system standards.
2. NODSI and NODSI\_ALLOWBATCH are not honored for jobs that use unauthorized JOBLIBs or STEPLIBs. The system assumes DSI for these jobs.
3. DSI, NODSI, and NODSI\_ALLOWBATCH are mutually exclusive.

**Default:** DSI

**[PASS | NOPASS | NOPASS\_ALLOWBATCH]**

The program specified on PGMNAME can or cannot bypass security protection (password protection and RACF). PASS indicates that security protection is in effect; NOPASS or NOPASS\_ALLOWBATCH indicate that security protection is not required. PASS is the default.

NOPASS is only honored when the program is running as a started task. If NOPASS is requested for a program that is not running as a started task, NOPASS is not honored and message IEF188I is issued.

If NOPASS\_ALLOWBATCH is specified, the system will honor the 'bypass-security-protection' property for programs that run as a started task as well as for programs that run as a batch job step. Note that requesting NOPASS\_ALLOWBATCH for a program that runs as a batch job step will expose potential integrity issues.

Jobs that request the bypass-security-protection property that run in the appropriate environment, as described above, will receive the property. However, a protected data set cannot be deleted via JCL (that is, by coding a disposition of DELETE) without the password. This is because the bypass-security-protection property is turned off when the job enters deallocation processing.

The NOPASS or NOPASS\_ALLOWBATCH parameter options do not apply to the STEPLIB or JOBLIB DD from which the named program is to be fetched, and that the address space in which the program is executing must have the security access required to open the JOBLIB or STEPLIB dataset.

PASS, NOPASS, and NOPASS\_ALLOWBATCH are mutually exclusive.

**Default:** PASS

**[SYST | NOSYST]**

The program that is specified on PGMNAME is a system task and is not timed (SYST) or is not a system task and is to be timed (NOSYST). For SYST, the program must be a one-step job started by a START or MOUNT command. If these conditions are not met, SYST is nullified and the system issues message IEF188I. All other properties remain in effect.

If procedures are multi-step or if NOSYST is specified, TIME=1440 might be required to prevent timeout.

In goal mode, a task marked SYST is put in the SYSSTC service class unless it is explicitly classified in the WLM classification rules before any SPM rule entries.

**Default:** NOSYST

**[AFF(xxxx)]**

Deprecated. The system accepts and ignores this parameter.

**[SPREF]**

The program that is specified on PGMNAME must have all private area short-term fixed pages assigned to preferred (nonreconfigurable and non-V=R) storage frames.

**Default:** None.

**[LPREF]**

The program that is specified on PGMNAME must have all private area long-term fixed pages assigned to preferred (nonreconfigurable and non-V=R) storage frames.

**Default:** None.

**[NOPREF]**

The program that is specified on PGMNAME does not need to have all private area short-term fixed pages assigned to preferred storage frames. That is, the program's short-term fixes are in fact short-term fixes and can be allowed in reconfigurable storage.

**Default:** None.

**Notes on using SPREF, LPREF, and NOPREF:**

1. LPREF is meaningless for programs that issue SYSEVENT TRANSWAP to become nonswappable.
2. Use of SPREF, LPREF, and NOPREF forces the program's private area fixed pages and LSQA pages into preferred storage frames, thus ensuring that they will not prevent taking storage offline.
3. Use SPREF, LPREF, or NOPREF for programs whose fixed pages could prevent the successful execution of a VARY STOR,OFFLINE command (or could fragment the V=R area) if they were assigned frames in reconfigurable or V=R storage.
4. SPREF and LPREF are significant for swappable programs (SWAP) that have a special requirement for preferred frames.
5. SPREF and LPREF are intended for use with authorized swappable programs that issue SYSEVENT DONTSWAP to become nonswappable for short periods (rather than using NOSWAP).
6. SPREF and LPREF should be specified when the preferred storage requirements for a nonswappable program are unknown. This ensures that all fix requests and LSQA requests will get preferred storage.
7. NOPREF is significant only for users of the SYSEVENT TRANSWAP. This includes V=R job steps, nonswappable programs, applications using the BTAM OPEN function, and any applications using a system function that issues SYSEVENT TRANSWAP.
8. For an application program that issues SYSEVENT DONTSWAP, or issues SYSEVENT REQSWAP followed by a SYSEVENT DONTSWAP, do one of the following:
  - List the program in the PPT and specify SPREF and LPREF.  
This allows the program to be attached as swappable, but all LSQA and private area fixed pages are assigned preferred frames during the entire job step.
  - Remove SYSEVENTs REQSWAP and DONTSWAP from the program. List the program in the PPT as nonswappable (NOSWAP) and do not specify NOPREF.  
This allows the program to be attached as nonswappable, and all LSQA and private area fixed pages will be assigned preferred frames during the entire job step.
9. An I/O device requiring operator intervention can interfere with taking storage offline by fixing pages in reconfigurable storage. For example, a printer requiring action to be taken, or a tape unit with a mount pending. Until the required action is completed, the storage that is associated with the I/O operation cannot be taken offline. This problem cannot be bypassed by using SPREF, LPREF, or NOPREF.

#### **[HONORIEFUSIREGION | NOHONORIEFUSIREGION]**

When HONORIEFUSIREGION is specified, region and MEMLIMIT settings that are specified through, or otherwise affected by the IEFUSI exit take effect.

When NOHONORIEFUSIREGION is specified, region and MEMLIMIT values specified through, or otherwise affected by the IEFUSI exit are ignored. In other words, when NOHONORIEFUSIREGION is specified for a program, MEMLIMIT values or limits cannot be altered through the IEFUSI exit. This PPT attribute is used to bypass IEFUSI region controls for specific programs that require a larger than normal region in order to successfully execute.

For more information about controlling region size and region limits using the IEFUSI exit, see *z/OS MVS Initialization and Tuning Guide*.

**Default:** HONORIEFUSIREGION

#### **[CRITICALPAGING | NOCRITICALPAGING]**

The program that is specified on PGMNAME owns storage that is critical or is not critical for HyperSwap operation. CRITICALPAGING indicates that the storage associated with the program specified on PGMNAME is critical for HyperSwap operation. Therefore, storage management should never page out this storage if possible. NOCRITICALPAGING (the default) indicates that the storage associated with the program specified on PGMNAME is not critical for HyperSwap operation and can be paged out at any time.

**Notes:**

1. IBM-supplied PPT entries that are marked CRITICALPAGING cannot be overridden.
2. Use this parameter in conjunction with the CRITICALPAGING switch to increase the likelihood of a successful HyperSwap operation. (See the FUNCTIONS statement of COUPLExx.)

**Default:** NOCRITICALPAGING

## Program properties table (PPT)

Table 58 on page 720 shows the values for the program properties supplied by IBM. (The column headings are defined in Table 59 on page 723.) The program name listed in the table is the PGM parameter value on the EXEC statement in a cataloged procedure in the SYS1.PROCLIB system library. The *membername* specified in the START operator command is the name of the SYS1.PROCLIB member. See *Starting a system task from a console in z/OS MVS System Commands* for more information.

| Table 58. IBM-supplied program properties table (PPT) values |   |    |    |    |    |    |    |     |    |    |    |    |    |    |    |
|--|---|----|----|----|----|----|----|-----|----|----|----|----|----|----|----|
| Program name   | Program description                     | NC | NS | PR | ST | ND | BP | Key | 2P | 1P | NP | NH | CP | DA | PA |
| AHLGTF   | GTF                                     | x  | x  |    | x  |    |    | 0   |    |    | x  |    |    |    |    |
| ANFFIEP  | IP PrintWay                             |    | x  |    | x  | x  |    | 1   |    |    |    |    |    |    |    |
| APSHPOSE   | PSF AFP Download Plus                   |    | x  |    | x  | x  |    | 1   |    |    | x  |    |    |    |    |
| APSKAFPD   | PSF Download                            |    | x  |    | x  | x  |    | 1   |    |    | x  |    |    |    |    |
| APSPPIEP   | PSF                                     |    | x  |    | x  | x  |    | 1   |    |    | x  |    |    |    |    |
| ASBSCHIN   | APPC/MVS Scheduler address space (ASCH) |    | x  |    | x  |    |    | 1   | x  | x  |    |    |    |    |    |
| ASBSCHWL   | APPC/MVS Message Log Writer             |    |    | x  |    |    |    | 1   |    |    |    |    |    |    |    |
| ATBINITM   | APPC/MVS address space                  |    | x  |    | x  |    |    | 1   | x  | x  |    |    |    |    |    |
| ATBSDFMU   | APPC/MVS SDFM Utility                   |    |    | x  |    |    |    | 1   |    |    |    |    |    |    |    |
| AVFMNBLD   | AVM                                     | x  | x  |    | x  |    |    | 3   |    |    | x  |    |    |    |    |
| AXRINIT  | System REXX                             | x  |    | x  |    |    |    | 8   |    |    |    |    |    |    |    |
| AXRRXTSS   | System REXX                             |    |    | x  |    |    |    | 8   |    |    |    |    |    |    |    |
| BHII1TPC   | Basic HyperSwap BHIHSRV address space   | x  |    | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| BNJLINTX   | NetView Start Up without SVC76          |    | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| BPEINI00   | IMS base primitive environment          |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| BPXBATA2   | WebSphere Application Server            |    |    | x  |    |    |    | 2   |    |    |    |    |    |    |    |
| BPXINIT  | z/OS UNIX                               | x  | x  |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| BPXPINPR   | z/OS UNIX                               | x  |    |    | x  |    |    | 8   | x  | x  |    |    |    |    |    |
| BPXVCLNY   | z/OS UNIX                               |    | x  | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| CBRIIAS  | OTIS                                    |    |    |    | x  |    |    | 5   |    |    |    |    |    |    |    |
| CBROAM   | OAM                                     |    | x  |    | x  |    |    | 5   |    |    |    |    |    |    |    |
| CBRWOLA  | OAM REST                                |    | x  |    | x  |    |    | 8   |    |    |    |    |    |    |    |

| Table 58. IBM-supplied program properties table (PPT) values (continued) |   |    |    |    |    |    |    |     |    |    |    |    |    |    |    |
|--|---|----|----|----|----|----|----|-----|----|----|----|----|----|----|----|
| Program name   | Program description                     | NC | NS | PR | ST | ND | BP | Key | 2P | 1P | NP | NH | CP | DA | PA |
| CNLSSDT  | MVS Message Service (MMS)               |    | x  |    | x  |    |    | 0   | x  | x  |    |    |    |    |    |
| COFMINIT   | VLF                                     |    | x  |    | x  | x  | x  | 0   |    |    |    |    |    |    |    |
| COFMISDO   | DLF                                     | x  | x  |    | x  | x  | x  | 0   |    |    |    |    |    |    |    |
| CQSINIT0   | IMS CQS                                 |    | x  |    | x  |    |    | 7   |    |    | x  |    |    |    |    |
| CSFINIT  | ICSF Initialization                     | x  | x  | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| CSQYASCP   | WebSphere IBM MQ                        |    |    |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| CSVLLCRE   | LLA                                     |    | x  |    | x  |    | x  | 0   |    |    |    |    |    |    |    |
| CSVVFCRE   | Virtual Fetch                           |    | x  |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| DFHSIP   | CICS driver                             |    | x  |    |    |    |    | 8   |    |    | x  |    |    |    |    |
| DFSMVRC0   | IMS Control Program                     |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| DFSYSVIO   | IMS OTMA callable service               |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| DSIMNT   | NetView for z/OS Start Up without SVC76 |    | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| DSNUTILB   | Db2 Batch                               |    |    |    |    |    |    | 7   |    |    |    |    |    |    |    |
| DSNYASCP   | Db2                                     |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| DUIFT000   | NetView GMFHS program                   |    | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| DWW1SJST   | CICSVR                                  | x  | x  | x  | x  |    |    | 5   |    |    |    |    |    |    |    |
| DXRRLM00   | IMS Manager                             |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| EKGTC000   | NetView RODM program                    | x  | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| EPWINIT  | FFST                                    | x  | x  |    |    | x  | x  | 0   |    |    | x  |    |    |    |    |
| ERBMFMFC   | RMF                                     |    | x  |    | x  | x  |    | 8   |    |    |    |    |    |    |    |
| ERB3GMFC   | RMF                                     |    | x  |    | x  | x  |    | 8   |    |    |    |    |    |    |    |
| EZAPPA00   | NPF                                     |    | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| EZAPPFS  | NPF                                     |    | x  |    |    |    |    | 1   |    |    |    |    |    |    |    |
| EZBADNR  | Automated Domain Name Registration      |    | x  | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| EZBLBADV   | Load Balancing Advisor                  |    | x  | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| EZBLBAGE   | Load Balancing Agent                    |    | x  | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| EZBREINI   | Communications Server - Resolver        | x  | x  | x  | x  |    |    | 6   |    |    |    |    |    |    |    |
| EZBTCPIP   | TCP/IP address space                    | x  | x  | x  | x  |    |    | 6   | x  | x  |    |    |    |    |    |
| EZBTNINI   | TN3270 Telnet procedure                 | x  | x  | x  | x  |    |    | 6   |    |    |    |    |    |    |    |
| FPGINIT  | Hardware accelerator manager            | x  | x  |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| FRDRVS00   | IMS ORS                                 |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| GDEICASB   | DFP/DFM                                 |    | x  |    | x  |    |    | 5   |    |    | x  |    |    |    |    |
| GDEISASB   | DFP/DFM                                 |    |    |    | x  |    |    | 5   |    |    | x  |    |    |    |    |
| GDEISBOT   | DFP/DFM                                 |    | x  |    | x  |    |    | 5   |    |    | x  |    |    |    |    |

Table 58. IBM-supplied program properties table (PPT) values (continued)

| Program name | Program description   | NC | NS | PR | ST | ND | BP | Key | 2P | 1P | NP | NH | CP | DA | PA |
|--------------|---|----|----|----|----|----|----|-----|----|----|----|----|----|----|----|
| GEOXCFST     | GDPS Address  |    | x  | x  | x  |    |    | 8   |    |    |    |    | x  |    |    |
| GLZBAIN      | zCX   | x  | x  |    |    |    |    | 0   |    |    |    |    |    |    |    |
| GTZINIT      | GTZ initialization  |    |    | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| HASJES20     | JES2  | x  | x  |    | x  | x  |    | 1   |    |    |    | x  |    |    |    |
| HHLGTF       | GTF   | x  | x  |    | x  |    |    | 0   |    |    | x  |    |    |    |    |
| HSAPINIT     | System Automation Manager                                     |    | x  | x  |    |    |    | 8   |    |    |    |    |    |    |    |
| HSFSRV00     | SDSF Data   |    | x  |    |    |    |    | 4   |    |    |    |    |    |    |    |
| HWIAMIN1     | Base control program internal interface (BCPii) address space |    | x  |    | x  |    |    | 4   |    |    |    |    |    |    |    |
| HWIAMIN2     | Base control program internal interface (BCPii) address space |    | x  |    | x  |    |    | 4   | x  | x  |    |    | x  |    |    |
| HZRINIT      | Runtime Diagnostics initialization                            |    | x  | x  | x  |    |    | 8   |    |    |    |    |    |    |    |
| IASXWR00     | External Writer   | x  |    |    | x  |    |    | 1   |    |    |    |    |    |    |    |
| IATCNDTK     | JES3  | x  | x  | x  | x  |    |    | 1   |    |    |    |    |    |    |    |
| IATINTK      | JES3  | x  | x  |    | x  | x  |    | 1   |    |    |    | x  |    |    |    |
| IATINTKF     | JES3 FSS  |    | x  |    | x  | x  |    | 1   |    |    |    |    |    |    |    |
| IATINXM      | JES3 Auxiliary address space                                  | x  | x  | x  | x  |    |    | 1   | x  | x  |    |    |    |    |    |
| IAZNJTCP     | JES - IAZ   |    |    | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| IDAVSJST     | SMSVSAM address space   | x  | x  | x  | x  |    |    | 5   |    |    |    |    |    |    |    |
| IEAVTDSV     | Dumping Services  |    |    | x  | x  |    | x  | 0   | x  | x  |    |    |    |    |    |
| IEDQTCAM     | TCAM (see <a href="#">Note</a> )                              |    | x  |    |    |    |    | 6   |    |    | x  |    |    |    |    |
| IEEMB860     | Master  | x  | x  |    | x  | x  | x  | 0   |    |    |    |    |    |    |    |
| IEEVMNT2     | Mount Command   | x  |    |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| IEFIIC       | Initiator   | x  |    | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| IFASMF       | SMF   | x  | x  | x  | x  | x  |    | 0   |    |    |    |    |    |    |    |
| IFDOLT       | OLTEP   |    |    |    |    |    |    | 8   | x  | x  |    |    |    |    |    |
| IGDSSI01     | SMS   | x  | x  |    | x  |    | x  | 5   |    |    |    |    |    |    |    |
| IGG0CLX0     | CAS   | x  | x  | x  | x  | x  |    | 0   | x  |    |    |    |    |    |    |
| IHLGTF       | GTF   | x  | x  |    | x  |    |    | 0   |    |    | x  |    |    |    |    |
| IHVOINI      | Automation I/O Operations                                     |    | x  |    |    |    |    | 8   |    |    |    |    |    |    |    |
| IKTCAS00     | TCAS  | x  |    | x  | x  |    |    | 6   |    |    |    |    |    |    |    |
| IOSHMCTL     | Basic HyperSwap management address space                      |    | x  | x  | x  |    |    | 0   |    |    |    |    | x  |    |    |
| IOSHSAPI     | Basic HyperSwap API services address space                    |    | x  | x  | x  |    |    | 0   |    |    |    |    | x  |    |    |
| IOSVROUT     | IOS   | x  | x  |    | x  |    | x  | 0   |    |    |    | x  |    |    |    |



| Table 58. IBM-supplied program properties table (PPT) values (continued) |                                   |    |    |    |    |    |    |     |    |    |    |    |    |    |    |
|--|-----------------------------------|----|----|----|----|----|----|-----|----|----|----|----|----|----|----|
| Program name   | Program description               | NC | NS | PR | ST | ND | BP | Key | 2P | 1P | NP | NH | CP | DA | PA |
| IQCINI0\$  | IMS queue control program         |    | x  |    | x  |    |    | 7   |    |    |    |    |    |    |    |
| IQPINIT  | PCIE services                     | x  | x  |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| IRRSSM00   | RACF                              | x  | x  | x  | x  |    |    | 2   |    |    |    |    |    |    |    |
| ISFHCTL  | SDSF                              |    | x  |    |    |    |    | 4   |    |    |    |    |    |    |    |
| ISTINM01   | VTAM                              | x  | x  |    | x  |    | x  | 6   |    |    | x  |    |    |    |    |
| ITTTTCWR   | CTRACE Writer address space       | x  | x  | x  | x  |    | x  | 0   | x  | x  |    |    |    |    |    |
| IWMINJST   | WLM                               | x  | x  |    | x  |    |    | 0   | x  | x  |    |    |    |    |    |
| IXCINJST   | XCF                               | x  | x  |    | x  |    |    | 0   | x  | x  |    |    | x  |    |    |
| IXGBLF00   | System Logger address space       |    | x  |    | x  |    |    | 0   |    |    |    |    |    |    |    |
| IXGBLF01   | System Logger address space       | x  | x  |    | x  |    |    | 0   |    | x  |    | x  |    |    |    |
| IXZIX00  | JES Common Coupling address space | x  | x  | x  | x  |    |    | 1   |    |    |    |    |    |    |    |
| MVPTNF   | TNF address space                 | x  | x  | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| MVPXVMCF   | VMCF address space                | x  | x  | x  | x  |    |    | 0   |    |    |    |    |    |    |    |
| OMPROUTE   | z/OS Communications Server        |    | x  | x  |    |    |    | 8   |    |    |    |    |    |    |    |
| SNALINK  | SNALINK address space             |    | x  |    | x  |    |    | 6   |    |    |    |    |    |    |    |

**Note:** Although telecommunications access method (TCAM) was withdrawn from service in 2002, IEDQTCAM remains in the PPT table for compatibility.

Table 59 on page 723 defines the column headings used in Table 58 on page 720.

| Table 59. Explanation of column headings in the PPT table |                                 |                     |
|---|---------------------------------|---------------------|
| Synonym   | Meaning                         | SCHEDxx keyword     |
| NC  | Non-cancelable                  | NOCANCEL            |
| NS  | Non-swappable                   | NOSWAP              |
| PR  | Privileged                      | PRIV                |
| ST  | System task                     | SYST                |
| ND  | No data set integrity           | NODSI               |
| BP  | Bypass password protection      | NOPASS              |
| Key   | PSW key for this program        | KEY(x)              |
| 2P  | Second level preferred storage  | SPREF               |
| 1P  | First level preferred storage   | LPREF               |
| NP  | No preferred storage            | NOPREF              |
| NH  | No honor IEFUSI region settings | NOHONORIEFUSIREGION |
| CP  | Critical paging                 | CRITICALPAGING      |
| DA  | Allow batch to receive NODSI    | NODSI_ALLOWBATCH    |
| PA  | Allow batch to receive NOPASS   | NOPASS_ALLOWBATCH   |



## Chapter 83. SMFLIMxx (specifying region and memlimit values)

Use the SMFLIMxx parmlib member to specify values that are similar to several of the output fields in the IEFUSI SMF exit. These values can override the REGION of a job step, set the MEMLIMIT for a job step or cause space to be reserved in high private subpools in the private area.

The SMFLIM specification becomes active when the SMF address space is initialized, regardless of whether SMF records are being collected and recorded.

SMFLIMxx consists of a set of REGION statements. Each REGION statement has one or more filter keywords and corresponding memory attributes to be set.

**Note:** For more information about region size, see [Limiting user region size](#) in *z/OS MVS Initialization and Tuning Guide*.

### Parameter in IEASYSxx (or supplied by the operator)

```
SMFLIM= {aa
        {(aa,bb... )}}
```

### Syntax rules for SMFLIMxx

The SMFLIMxx member consists of an ordered set of statements. Each statement consists of the required REGION keyword followed by a set of filters and a set of attributes to be applied. The statements are ordered; subsequent statements with matching filters that appear later in the parmlib member or in a subsequent parmlib member will override the values of statements that previously appeared. The result is a compendium of the IEFUSI exit results and the results of the various ordered SMFLIMxx statements that matched this job step program.

The filters are matched to existing specifics of the job step and the attributes alter the execution environment (for example, memory available) of the job step, when applied. Unless otherwise specified, each filter (for example, JOBNAME) can specify up to eight filter values. Those filter values can include wildcard characters \* and ?. The \* character is defined to match 0 or more characters, while the ? character matches exactly one character.

**Note:** A statement without any filters but only attributes will cause a match to any subsequent statement with filters. The attributes will be overridden.

Comments may appear in columns 1-71 and must begin with /\* and end with \*/.

The SYSNAME filter suppresses the REGION rule from being built into the in-storage copy. As such, it will not appear in DISPLAY SMFLIM output. LIMIT rules that do not match due to the SYSNAME filter are counted as statements for the statement number that appears in DISPLAY SMFLIM output and in the IEF043I message that might appear in the job log of a given job.

### Syntax format of SMFLIMxx

```
REGION {filters} {attributes}
```

The filter keywords are as follows:

```

JOBACCT(aaaa,[bbb,ccc,])
JOBCLASS(aaaa,[bbb,ccc,])
JOBNAME(aaaa,[bbb,ccc,])
PGMNAME(aaaa,[bbb,ccc,])
STEPACCT(aaaa,[bbb,ccc,])
STEPNAME(aaaa,[bbb,ccc,])
SUBSYS(aaaa,[bbb,ccc,])
SYSNAME(aaaa,[bbb,ccc,])
USER(aaaa,[bbb,ccc,])
SAFCHK(aaaa)

REQREGION({aaaaaK[,bbbbbbK]})
           {aaaaaM[,bbbbbbM] }
           {aaaaaG[,bbbbbbG] }

REQMEMLIMIT({NOLIMIT[,NOLIMIT] }[, {ANY|SMFDFLT|JCL|REGION}])
           {aaaaaM[,bbbbbbM] }
           {aaaaaG[,bbbbbbG] }
           {aaaaaT[,bbbbbbT] }
           {aaaaaP[,bbbbbbP] }

```

The attributes are as follows:

```

REGIONABOVE({NOLIMIT},{OVERRIDEIEFUSI})
            {nnnnnG }
            {nnnnnM }
            {nnnnnK }

REGIONBELOW({NOLIMIT},{OVERRIDEIEFUSI})
            {nnnnnM }
            {nnnnnK }

REGIONLIMITABOVE({NOLIMIT}[,RELATIVE])
                {nnnnnG }
                {nnnnnM }
                {nnnnnK }

REGIONLIMITBELOW({NOLIMIT}[,RELATIVE])
                {nnnnnM }
                {nnnnnK }

SYSRESVABOVE({nnnnnG})
            {nnnnnM }
            {nnnnnK }

SYSRESVBELOW({nnnnnM})
            {nnnnnK }

MEMLIMIT({NOLIMIT})
        {nnnnnM }
        {nnnnnG }
        {nnnnnT }
        {nnnnnP }
        {SMFDFLT}

CONTINUEMATCHING({YES|NO})

EXECUTE({YES|CANCEL|CANCELFROMIEFUSI|NOCHANGE})

DSLIMITNUM(nn)

DSLIMITSIZE({nnnnnG})
            {nnnnnM }
            {nnnnnT }

JOBMSG({ISSUE|SUPPRESS})

MAXSHARE(nn)

DEDICATEDMEMORY(aaaaa{G|T|P}[,bbbbbb{G|T|P}])

```

## IBM-supplied default for SMFLIMxx

There is no default member. You might want to create an empty member to deactivate SMFLIM processing during testing.

## Statements and parameters for SMFLIMxx

The SMFLIMxx parmlib member consists of a set of REGION statements. Each REGION statement has one or more filter keywords and corresponding attributes. Unless otherwise specified, each filter can specify up to eight filter values. Those filter values can include wildcard characters \* and ?. The \* character is defined to match 0 or more characters, while the ? character matches exactly one character.

REGION {filters} {attributes}

### {filters}

#### **JOBCLASS(aaaa,{bbb,ccc,})**

Specifies 1 to 8 job classes. Each job class can contain 1 to 8 characters.

#### **JOBNAME(aaaa,{bbb,ccc,})**

Specifies 1 to 8 job names. Each job name can contain 1 to 8 characters.

#### **PGMNAME(aaaa,{bbb,ccc,})**

Specifies 1 to 8 program names. Each program name can contain 1 to 8 characters. You can specify \*.DD to match a program that is referenced by a DD statement, which is specified in JCL using the PGM=\*.stepname.ddname or PGM=\*.stepname.procstepname.ddname syntax.

#### **STEPNAME(aaaa,{bbb,ccc,})**

Specifies 1 to 8 step names. Each step name can contain 1 to 8 characters.

#### **SUBSYS(aaaa,{bbb,ccc,})**

Specifies 1 to 8 subsystem IDs. Each subsystem ID can contain 1 to 4 characters.

Valid subsystem IDs are JES2, JES3, STC, ASCH, and TSO. Other valid subsystems include IBM-supplied (such as OMVS), vendor-supplied, and user-defined subsystems.

**Additional considerations for UNIX applications:** When you are running UNIX applications, remember that fork and spawn are issued to create new address spaces. The default processing on fork and spawn is for the UNIX kernel to propagate the region size from the parent to the child. Because the region size in the parent process has already passed through IEFUSI and SMFLIMxx rule processing and has an approved region size, IBM recommends that you add the SUBSYS keyword for the specific subsystem that you want to cover, and not include OMVS.

At the time that step initiation is using the SMFLIMxx data to influence the step's region and MEMLIMIT, the kernel has not yet propagated the parent's region size to the child, so there is nothing to work with. If SMFLIMxx rule processing modifies the region size of the child process, the kernel accepts that region size and does not propagate the region size from parent to child. Forking might fail if the region size is insufficient in the child to capture the parent's storage.

#### **SYSNAME(aaaa,{bbb,ccc,})**

Specifies 1 to 8 system names. Each system name can contain 1 to 8 characters.

#### **USER(aaaa,{bbb,ccc,})**

Specifies 1 to 8 usernames. Each username can contain 1 to 8 characters.

#### **JOBACCT(aaaa,{bbb,ccc,})**

Specifies 1 to 8 job account strings. Each job account string can be 1 to 142 characters. Special characters can be used; for a complete list, see the character sets section of [z/OS MVS JCL Reference](#).

Several wildcard characters are available.

**\***

Matches 0 or more characters.

**?**

Matches exactly one character.

**%**

Automatically matches all fields after which it occurs. For example, a job with JOB(NEWYORK,EFK) could match a rule that includes JOBACCT((NEWYORK,%)).

A single accounting string corresponds to the first accounting field for the job. For example, to specify multiple accounting fields to match a job that includes JOB (IBM,POK), include a second level of parentheses.

- Quoted strings can wrap lines, but must go to column 71 and start again at column 1. Blanks that are specified within the quotation marks are included as data.
- Nonquoted strings cannot wrap lines. The line can break at a comma or other delimiter such as a parenthesis and continue on the next line. For example:

```
JOBACCT((ABC,
        DEF))
```

### **STEPACCT(*aaaa*,{*bbb*,*ccc*},)**

Specifies 1 to 8 step account strings. Each step account string can be 1 to 142 characters. Special characters can be used; for a complete list, see the character sets section of [z/OS MVS JCL Reference](#).

Several wildcard characters are available.

**\***

Matches 0 or more characters.

**?**

Matches exactly one character.

**%**

Automatically matches all fields after which it occurs. For example, a rule with STEPACCT=(NEWYORK,%) might match a job step that includes EXEC ...,ACCT=(NEWYORK,EFK).

A single accounting string corresponds to the first accounting field for the job step. To specify multiple accounting fields, (for example, to match a job step that includes ACCT= (IBM,POK), for example, two accounting fields, include a second level of parentheses.

- Quoted strings can wrap lines, but must go to column 71 and start again at column 1. Blanks that are specified within the quotation marks are included as data.
- Nonquoted strings cannot wrap lines. The line can break at a comma or other delimiter such as a parenthesis and continue on the next line. For example:

```
STEPACCT((ABC,
        DEF))
```

### **SAFHECK(*aaaa*)**

Specifies an installation-defined SAF resource name in the FACILITY class. If the user associated with the job or job step does not have access to this resource, the rule is not applied. If the user has READ or higher access, the rule is applied if the other filters for this rule also match.

#### **Restriction:**

- Only 1 resource can be named (All other filter keywords support up to 8 values).
- Wildcards are not supported.

### **REQREGION({*nnnnnnM*|*nnnnnnG*|*nnnnnnK*},{*nnnnnnM*|*nnnnnnG*|*nnnnnnK*})**

Specifies a value or a range of values. If the REGION size that is specified in the JCL or the default value that is used from the job class is equal to the specified value, or equal to or between the specified values if two values are specified, the rule is applied if the other filters for this rule also match.

#### ***nnnnnnG***

Specifies the value in gigabytes.

#### ***nnnnnnM***

Specifies the value in megabytes.

#### ***nnnnnnK***

Specifies the value in kilobytes.

**Restriction:** Wildcards are not supported.

Values of OG, OM, and OK are treated as they are treated in JCL, meaning that the job step has requested all of the available storage.

**REQMEMLIMIT**(**{NOLIMIT|nnnnnP|nnnnnT|nnnnnG|nnnnnM}**[,**{NOLIMIT|nnnnnP|nnnnnT|nnnnnG|nnnnnM}**][,**{ANY|SMFDFLT|JCL|REGION}**])

Specifies a value or a range of values. If the MEMLIMIT size that is specified in the JCL or the default value that is used from the SMFPRMxx parmlib member is equal to the specified value, or equal to or between the specified values if two values are specified, the rule is applied if the other filters for this rule also match. If specified, an optional source parameter, ANY, SMFDFLT, JCL, or REGION, can limit when the filter should match.

**NOLIMIT**

There is no limit on the use of virtual storage above 2 gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnT**

Specifies the value in terabytes.

**nnnnnP**

Specifies the value in petabytes.

**ANY**

The filter matches regardless of the MEMLIMIT source if the requested MEMLIMIT is within the specified range. ANY is the default value when the source is not specified.

**SMFDFLT**

The filter matches only if the requested MEMLIMIT is within the specified range and the source is from the MEMLIMIT default in the SMFPRMxx parmlib member.

**JCL**

The filter matches only if the requested MEMLIMIT is within the specified range and the source is the JCL MEMLIMIT keyword.

**REGION**

The filter matches only if the requested MEMLIMIT is within the specified range and the MEMLIMIT is set implicitly by REGION=0M in the JCL.

**Restriction:** Wildcards are not supported.

The corresponding attributes can be set for a job step that matches the preceding filters.

**{attributes}**

**EXECUTE**(**{YES|CANCEL|CANCELFROMIEFUSI|NOCHANGE}**)

**YES**

The job step is executed. This can be used to override a previous SMFLIM rule that indicated to cancel the job step.

**CANCEL**

The job step is canceled, unless overridden by a later matching rule that contains EXECUTE(YES) or EXECUTE(CANCELFROMIEFUSI).

**CANCELFROMIEFUSI**

The job step is canceled if the IEFUSI exit sets the cancel return code (4).

**NOCHANGE**

Preserves any previous setting. NOCHANGE is the default when the EXECUTE keyword is not coded in a given rule. Barring any matching rule that changes the EXECUTE setting, the default action is to let the job step be executed, so EXECUTE(NOCHANGE) means that the job step is executed.

**MEMLIMIT({NOLIMIT|nnnnnM|nnnnnG|nnnnnT|nnnnnP|SMFDFLT})**

Overrides the memlimit that was coded in a job's JCL, or the default MEMLIMIT that was coded in the SMFPRMxx parmlib member. MEMLIMIT is the limit on the use of virtual storage above 2 gigabytes for a single address space.

**NOLIMIT**

There is no limit on the use of virtual storage above 2 gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnT**

Specifies the value in terabytes.

**nnnnnP**

Specifies the value in petabytes.

**SMFDFLT**

Use the default value specified in the SMFPRMxx parmlib member.

For a complete description of MEMLIMIT and the ways to define it, see [z/OS MVS Programming: Extended Addressability Guide](#).

**REGIONLIMITABOVE({NOLIMIT|nnnnnK|nnnnnM|nnnnnG},{RELATIVE})**

This attribute sets the limit to the total above-the-line primary storage allocated to a job by any combination of requests for additional storage using the GETMAIN or STORAGE macros. This corresponds to the IEFUSI parameter word 5, sub-word 5. This value can range from 1K to 2047M or 2G.

**NOLIMIT**

There is no limit on the use of virtual storage above 16 megabytes.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnK**

Specifies the value in kilobytes.

**RELATIVE**

This optional parameter indicates that REGIONLIMITABOVE is to be set to the specified value plus the above-the-line region size. When RELATIVE is not specified, REGIONLIMITABOVE is set to the specified value. If a relative value would result in a value that is greater than the maximum region limit, the region limit is set to the maximum.

**Notes:**

1. The REGIONLIMITABOVE setting may be ignored for some system address spaces.
2. A region limit that is lower than the region size causes the region size to be lowered to match the region limit.

**REGIONLIMITBELOW({NOLIMIT|nnnnnK|nnnnnM},{RELATIVE})**

This attribute sets the limit to the total below-the-line primary storage allocated to a job by any combination of requests for additional storage using the GETMAIN or STORAGE macros. This corresponds to the IEFUSI parameter word 5, sub-word 3. This value can range from 1K to 1638K or 16M.

**NOLIMIT**

There is no limit on the use of virtual storage below 16 megabytes.

**nnnnnM**

Specifies the value in megabytes.



**nnnnnK**

Specifies the value in kilobytes.

**RELATIVE**

This optional parameter indicates that REGIONLIMITBELOW is to be set to the specified value plus the below-the-line region size. When RELATIVE is not specified, REGIONLIMITBELOW is set to the specified value. If a relative value would result in a value that is greater than the maximum region limit, the region limit is set to the maximum.

**Notes:**

1. The REGIONLIMITBELOW setting may be ignored for some system address spaces.
2. A region limit that is lower than the region size causes the region size to be lowered to match the region limit.

**CONTINUEMATCHING({YES|NO})**

Determines whether the matching job step is to continue processing subsequent rules.

**YES**

The rules continue are to continue processing as normal and any subsequent rules that have filters match will apply their attributes to the current job step. YES is the default value if the CONTINUEMATCHING attribute is not specified.

**NO**

Subsequent rule processing is to be skipped for this matching job step.

**SYSRESVABOVE({nnnnnK|nnnnnM|nnnnnG})**

Specifies the minimum size of storage that is reserved for high private subpools in extended private storage above the 16 MB line. This value can range from 1K to 2047M or 2G. If an IEFUSI exit sets a smaller limit on the job step's storage, the system reserved area is larger than the minimum that is specified in the rule.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnK**

Specifies the value in kilobytes.

**Note:** The SYSRESVABOVE setting might be ignored for some system address spaces.

**SYSRESVBELOW({nnnnnK|nnnnnM})**

Specifies the minimum size of storage that is reserved for high private subpools in nonextended private storage below the 16 MB line. This value can range from 1 K to 16384K or 16M. If an IEFUSI exit sets a smaller limit on the job step's storage, the system reserved area is larger than the minimum that is specified in the rule.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnK**

Specifies the value in kilobytes.

**Note:** The SYSRESVBELOW setting may be ignored for some system address spaces.

**REGIONABOVE({NOLIMIT|nnnnnK|nnnnnM|nnnnnG},OVERRIDEIEFUSI)**

Overrides the extended region specification (set with the REGION or REGIONX keywords) that was coded in a job's JCL, or the default that was coded in the job class. This value can range from 1K to 2047M or 2G. The value can also be set to NOLIMIT, which specifies that the region size for this job step is not to be limited. The SYSRESVABOVE value ensures that storage is reserved in high private subpools of extended storage for use by authorized programs.

**NOLIMIT**

There is no limit on the use of virtual storage above 16 megabytes.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnK**

Specifies the value in kilobytes.

**VERRIDEIEFUSI**

Enforces the matching job to use this REGIONABOVE value instead of the one specified in the corresponding IEFUSI exit parameter Word 5, Subword 5 (Region limit above 16 megabytes). The default behavior, if this is not specified, is to honor the IEFUSI specified value over the SMFLIMxx value unless a SYSRESVABOVE value is also specified on the SMFLIMxx rule. OVERRIDEIEFUSI does not override IEFUSI Word 5, Subword 1 bit 4 (IEFUSI ignores SMFLIMxx parameters).

**Note:** The REGIONABOVE setting may be ignored for some system address spaces.

**REGIONBELOW({NOLIMIT|nnnnnK|nnnnnM},OVERRIDEIEFUSI)**

Overrides the nonextended region specification (set with the REGION or REGIONX keywords) that was coded in a job's JCL, or the default that was coded in the job class. This value can range from 1K to 16384K or 16M. The value can also be set to NOLIMIT, which specifies that the region size for this job step is not to be limited. The SYSRESVBELOW value ensures that storage is reserved in high private subpools of non-extended storage for use by authorized programs.

**NOLIMIT**

There is no limit on the use of virtual storage below 16 megabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnK**

Specifies the value in kilobytes.

**VERRIDEIEFUSI**

Enforces the matching job to use this REGIONBELOW value instead of the one specified in a corresponding IEFUSI exit parameter Word 5, Subword 3 (Region limit below 16 megabytes). The default behavior, if this is not specified, is to honor the IEFUSI specified value over the SMFLIMxx value unless a SYSRESVBELOW value is also specified on the SMFLIMxx rule. OVERRIDEIEFUSI does not override IEFUSI Word 5, Subword 1 bit 4 (IEFUSI ignores SMFLIMxx parameters).

When a matching rule that includes REGIONBELOW or REGIONABOVE is processed, the job step's REGION request is modified to be an internal representation of REGIONX. For example, if a rule with REGIONABOVE(NOLIMIT) and REGIONBELOW(NOLIMIT), the job step behaves as if REGIONX=(0M,0M) were coded, effectively having access to all extended and nonextended private storage, except for the storage reserved for use in high private subpools set by IEFUSI or the SYSRESVxxxxx keywords that were previously described.

**Note:** The REGIONBELOW setting may be ignored for some system address spaces.

**DSLIMITNUM(nn)**

Overrides the maximum number of user-key data spaces and hiperspaces for this address space. This corresponds to IEFUSI parameter Word 7, subword 3 output field. The IBM-supplied default is 4096. The maximum number that can be specified is 4,294,967,295 ( $2^{32} - 1$ ).

**DSLIMITSIZE({nnnnnM|nnnnnG|nnnnnT})**

Overrides the maximum combined size of all user-key data spaces and hiperspaces for this address space. The maximum value is ( $2^{24} - 1$ ), which is 16,777,215 megabytes, or approximately 16 terabytes minus 1 kilobyte.

**nnnnnG**

Specifies the value in gigabytes.

**nnnnnM**

Specifies the value in megabytes.

**nnnnnT**

Specifies the value in terabytes.

**JOBMSG(ISSUE|SUPPRESS)**

Specifies whether the IEF043I and IEF044I messages appear in the job log. This message describes the attributes that are applied by SMFLIM statements.

**ISSUE**

Indicates that IEF043I and IEF044I are to appear in the job log.

**SUPPRESS**

Indicates that IEF043I and IEF044I should not appear in the job log.

**Note:** If SMFLIM processing determines that the job should be canceled, IEF043I and IEF044I appear in the job log.

**MAXSHARE(32|nn)**

Specifies the maximum of source and target shared pages that can be used at one time by problem state callers using the IARV SERV SHARE services. This corresponds to IEFUSI parameter word 7, subword 4 output field. The maximum value for source and target shared pages is 2147483647.

**Note:** If you change the rule, be sure to balance this with other uses of real memory. The number of 4K frames to track real memory equals:

$$(number\ of\ shared\ pages + number\ of\ shared\ views + 252) \div 127$$

Ignore any remainder.

**DEDICATEDMEMORY(aaaaa{G|T|P}|,bbbb{G|T|P})**

Specifies a target value of *bbbb* to assign and a minimum value of *aaaaa* to assign if the target is unavailable. Both *aaaaa* and *bbbb* must be multiples of 2 when the units are in gigabytes (G). A maximum of 16384P can be specified. If the minimum cannot be satisfied then the job will be canceled. If the system is initializing dedicated memory while the job step is initializing, the system will attempt to satisfy as much of the request as possible. Once dedicated memory has completed initialization, the system will reprocess the job step, assigning at least the minimum and up to the target value. The job step can determine whether memory is initializing by interrogating RCEREALFRAMESINITIALIZED or can wait for memory initialization to complete by invoking IAXVWAIT.



## Chapter 84. SMFPRMxx (system management facilities (SMF) parameters)

The SMFPRMxx member allows you to control how system management facilities (SMF) works at your installation. You can use SMFPRMxx parameters to accomplish the following tasks:

- Identify the system on which SMF is active.
- Specify global values for interval recording and synchronization that SMF, RMF, and other requesters can use to schedule the execution of their interval functions.
- Specify the data sets or log streams to be used for SMF recording.
- Allow compression of SMF data before recording to log streams.
- Specify the system identifier to be used in all SMF records.
- Select the SMF record types and subtypes SMF is to generate.
- Allow the operator to change the SMF parameters that are established at IPL.
- Specify the job wait time limit.
- Specify whether SMF is to invoke installation-supplied SMF exit routines.
- Specify whether the SMF dump program is to attempt to recover from abends.
- Specify the system response when SMF has used all of the buffered storage in its address space and is recording on data sets.
- Specify the system response when the last SMF data set is filled and no other data sets are available for use.
- Specify the amount of real time that SMF allows data to remain in an SMF buffer before it is written to a recording data set or a log stream.
- Specify the installation default MEMLIMIT.
- Specify whether only registration data and not usage data is to be recorded when using the IFAUSAGE macro.
- Specify valid user exists for the IFASMFDL and IFASMFDL programs.
- Specify whether to suppress empty execute channel program (EXCP) using the EMPTYEXCPSEC parameter.
- Specify whether SMF record flood support is active and the filter for the SMF record flood.
- Specify whether SMF is to generate digital signatures for records recorded to log streams.
- Specify whether SMF is to record records to in-memory resources for real-time analysis.
- Specify whether SMF is to record high-frequency throughput statistics.
- Specify whether to enable IBM z/OS Workload Interaction Correlator.

**Note:** If you specify that SMF is to record on data sets, the SMF data sets must be cataloged on DASD. If there are no data sets for SMF to use, SMF buffers data until you specify a data set for SMF to use. If SMF runs out of buffers, there might be a loss of data.

You can specify SMF parameters in several ways:

- Before the first IPL of a newly generated system by creating an SMFPRMxx parmlib member.
- At each initialization of SMF by entering the parameters at the console.
- During SMF execution, by using the SET SMF command to specify a different SMFPRMxx parmlib member or by using the SETSMF command to replace one or more previously defined SMF parameters.

See *z/OS MVS System Commands* for more information about the commands that are used with SMF. For information about setting up and using SMF, see *z/OS MVS System Management Facilities (SMF)*.

## Using the SET command for SMFPRMxx

---

The SET operator command can be used to modify the SMF recording options dynamically by specifying which SMFPRMxx parmlib member is to be used. Also, if SMF terminates, the SET SMF command can be used to restart SMF.

Using the SET command, the installation can replace all the existing SMF options. For example, an installation can activate SMF recording after an IPL in which NOACTIVE is specified by using the SET command and choosing the parmlib member that contains the ACTIVE option. The SET command, however, cannot change the SID parameter.

For each IPL, a maximum of eight subsystems can be defined to SMF (through the SUBSYS parameter). This is a combined total of those specified at IPL and subsequent SET commands. If the maximum is reached, no new subsystems may be added. Those subsystems previously specified can be given different options.

## Using the SETSMF command for SMFPRMxx

---

In contrast to the SET SMF command, which allows an installation to specify a different SMFPRMxx parmlib member or to restart SMF, the SETSMF operator command allows an installation to:

- Add a SUBPARM parameter value to those SMFPRMxx parameter values already set for this IPL.
- Replace SMFPRMxx parameter values (except ACTIVE, PROMPT, SID, and EXIT) with new ones for this IPL.

If the SMFPRMxx parameter values set for this IPL include NOPROMPT, the operator cannot use the SETSMF command.

## Parameter in IEASYSxx (or supplied by the operator)

---

### SMF=xx

The two alphanumeric characters, represented by xx, are appended to SMFPRM to identify the SMFPRMxx member of parmlib. If the parameter is not specified either in IEASYSxx or by the operator, the system uses parmlib member SMFPRM00. If the parmlib does not contain an SMFPRM00 member, the system uses the defaults provided by SMF.

## Support for system symbols

---

You can specify system symbols in SMFPRMxx. In addition, you can specify the &SID symbol when naming SMF data sets (on the DSNAME parameter).

For information about how to use system symbols in shared parmlib members that require unique values, see Chapter 2, “Sharing parmlib definitions,” on page 31. For specific information about using symbols to name SMF data sets, see the description of the DSNAME and SID parameters in the description of this parmlib member.

## Syntax rules for SMFPRMxx

---

The following rules apply to the creation of SMFPRMxx:

- Use columns 1 through 72; however, avoid using column 72 when system symbols are coded on the same line.
- Avoid embedded blanks.
- Comments can appear in columns 1-71 and must begin with /\* and end with \*/.
- Enter each parameter in the format: *keyword(value)*
- Indicate continuation by placing a comma after the last entry on a record, followed by a blank before column 72.

- Limit SMFPRMxx to no more than 897 lines. If you exceed this limit, the system ignores the values specified in SMFPRMxx and uses default values instead. In addition, the system issues an informational message to the operator, indicating that SMFPRMxx is too large and that default values are to be used instead.

For a filter to have both MSG and DROP processing, the DROP filter will not be processed until the MSG filter has already been hit.

The following statements show an example of how to specify the syntax:

```
SID(3090), ACTIVE,
DSNAME(SYS1.MANA, SYS1.MANB, SYS1.MANC),
JWT(0030), SYS(TYPE(00:120), NOEXITS,
INTERVAL(004000), DETAIL)
```

In this next example, IFASMF.STREAM1 will use a maximum of 256M of buffer space and IFASMF.STREAM2 will use up to 1024M.

```
DSPSIZMAX(1024M)
LSNAME(IFASMF.STREAM1, TYPE(30, 89), DSPSIZMAX(256M))
LSNAME(IFASMF.STREAM1, TYPE(127:255))
```

## Syntax format of SMFPRMxx

INTVAL (*mm*)

SYNCVAL (*mm*)

ACTIVE | NOACTIVE

RECORDING (DATASET | LOGSTREAM)

```
DEFAULTLSNAME(logstreamname
[ , NOBUFFS (HALT | MSG) ]
[ , BUFUSEWARN (nn) ]
[ , DSPSIZMAX (nnnnM | nG) ]
[ , NOCOMPRESS | COMPRESS [ (PERMFIX (nnnnM)) ] ]
[ , NORECSIGN | RECSIGN (HASH (SHA1 | SHA256 | SHA384 | SHA512) ,
SIGNATURE (RSA | ECDSA) ,
TOKENNAME (tokenname)) ]
[ , NOARECSIGN | ARECSIGN (HASH (SHA512) ,
SIGNATURE (LI2) ,
TOKENNAME (tokenname)) ] )
```

```
LSNAME(log streamname, TYPE { (aa, bb) | (aa, bb:zz) | (aa, bb:zz, ...) }
[ , NOBUFFS (HALT | MSG) ]
[ , BUFUSEWARN (nn) ]
[ , DSPSIZMAX (nnnnM | nG) ]
[ , NOCOMPRESS | COMPRESS [ (PERMFIX (nnnnM)) ] ]
[ , NORECSIGN | RECSIGN (HASH (SHA1 | SHA256 | SHA384 | SHA512) ,
SIGNATURE (RSA | ECDSA) ,
TOKENNAME (tokenname)) ]
[ , NOARECSIGN | ARECSIGN (HASH (SHA512) ,
SIGNATURE (LI2) ,
TOKENNAME (tokenname)) ] )
```

```
INMEM(rname, RESSIZMAX({nnnnM | nG}), {TYPE({aa, bb | aa, bb:zz | aa, bb:zz, ...}) |
NOTYPE({aa, bb | aa, bb:zz | aa, bb:zz, ...}) }
```

DSNAME(*dataset*)

LISTDSN | NOLISTDSN

```
SID { (xxxx) }
{ (xxxx, SYSNAME(sysname)) }
{ (xxxx, ser#[ser#...]) }
{ (xxxx, COMBIN(ser#[ser#...])) } }
```

REC (PERM | ALL)

```

NORECSIGN | RECSIGN(HASH(SHA1|SHA256|SHA384|SHA512),
                    SIGNATURE(RSA|ECDSA),
                    TOKENNAME(tokenname))
NOARECSIGN | ARECSIGN(HASH(SHA512),
                      SIGNATURE(LI2),
                      TOKENNAME(tokenname))

```

```

MAXDORM(mmss) | NOMAXDORM

```

```

MEMLIMIT({NOLIMIT})
         {nnnnnM }
         {nnnnnG }
         {nnnnnT }
         {nnnnnP }

```

```

EMPTYEXCPSEC(NOSUPPRESS|SUPPRESS)

```

```

HFTSINTVL(ss) | NOHFTSINTVL

```

```

WIC | NOWIC

```

```

STATUS([hhmmss] ) | NOSTATUS
       [SMF[,SYNC|NOSYNC]]

```

```

JWT(hhmm)
SWT(hhmm)
TWT(hhmm)

```

```

DDCONS(YES|NO)

```

```

PROMPT(ALL,IPLR,LIST) | NOPROMPT

```

```

AUTHSETSMF | NOAUTHSETSMF

```

```

SYS([TYPE
    [,INTERVAL]
    [,EXITS
    [,DETAIL

```

```

    TYPE ({aa,bb(cc) })
    NOTYPE {aa,bb:zz }
           {aa,dd(cc:yy),...}
           {aa,bb(cc,...) }

```

```

    NOINTERVAL | INTERVAL({hhmmss })
                   {SMF[,SYNC|NOSYNC]}

```

```

    EXITS(exit-name,exit-name,...) | NOEXITS

```

```

    NODETAIL | DETAIL

```

```

SUBPARM(name(parameter))

```

```

SUBSYS(name,[TYPE
            [,INTERVAL]
            [,EXITS
            [,DETAIL

```

```

DUMPABND(RETRY|NORETRY)

```

```

NOBUFFS(MSG|HALT)

```

```

LASTDS(MSG|HALT)

```

```

MULCFUNC | NOMULCFUNC

```

```

BUFSIZMAX(nnnnM|1G)

```

```

BUFUSEWARN(nn)

```

```

SMFDLEXIT({USER1(exit-name[,exit-name,...]) | NOUSER1},
          {USER2(IRRADU00[,exit-name,...]) | NOUSER2},
          {USER3(IRRADU86[,exit-name,...]) | NOUSER3},
          {USER4(exit-name[,exit-name,...]) | NOUSER4},
          {USER5(exit-name[,exit-name,...]) | NOUSER5} )

```

```

SMFDPEXIT({USER1(exit-name[,exit-name,...]) | NOUSER1},
          {USER2(IRRADU00[,exit-name,...]) | NOUSER2},
          {USER3(IRRADU86[,exit-name,...]) | NOUSER3},
          {USER4(exit-name[,exit-name,...]) | NOUSER4},

```



```
{USER5(exit-name[,exit-name,...]) | NOUSER5} )
```

```
FLOOD(ON|OFF)
FLOODPOL(TYPE({aa,bb          },
               {aa,bb:zz      },
               {aa,bb:zz,...}
               RECTHRESH(xxxx),
               INTVLTIME(xxxx),
               MAXHIGHINTS(xxxx),
               ENDINTVL(xxxx),
               ACTION(MSG|DROP)
               )
MAXEVENTINTRECS(nn)
DSPSIZMAX(nnnnM|nG))
PERMFIx(nnnnM)
SMF30COUNT | NOSMF30COUNT
```

## IBM-supplied default for SMFPRMxx

None.

## IBM-supplied sample for SMFPRMxx

IBM provides sample member, SMFPRM0L, in SYS1.SAMPLIB. You can copy and modify this member according to your system requirements. You can place alternate values, plus additional values, in one or more alternate SMFPRMxx members.

## Statements and parameters for SMFPRMxx

### ACTIVE | NOACTIVE

Specifies whether SMF recording is to be active.

**Default:** ACTIVE

### AUTHSETSMF | NOAUTHSETSMF

This parameter specifies whether changes are authorized to be made to the SMF parameter options using the SETSMF command. When AUTHSETSMF is specified, the SETSMF command is authorized, regardless of the specification of PROMPT or NOPROMPT. When NOAUTHSETSMF is specified, the SETSMF command is not authorized, regardless of the specification of PROMPT or NOPROMPT.

**Default:** None. When not specified, by default, SETSMF is not authorized if the PROMPT(IPLR) or NOPROMPT parameter options are specified.

### BUFSIZMAX(*nnnnM*)

#### (1G)

Specifies the maximum amount of storage that SMF can allocate for SMF record data buffering purposes. This parameter applies only when recording to SMF data sets. It does not apply when recording to SMF log streams.

BUFSIZMAX values areas are defined with *nnnnM* for megabytes or 1 G for one gigabyte. For example, to request 1 gigabyte, specify BUFSIZMAX(1G) or BUFSIZMAX(1024M). To request 128 megabytes, specify BUFSIZMAX(128M).

The BUFSIZMAX value can be specified during an IPL in parmlib member SMFPRMxx and the value can be set higher or lower using the T SMF or SETSMF command.

The D SMF,O command displays the current BUFSIZMAX value.

**Value range:** 128 M–1024 M, or 1 G (128 megabytes to 1024 megabytes, or 1 gigabyte)

**Default:** 0128 M (128 megabytes)

**BUFUSEWARN(nn)**

Specifies the overall buffer warning level percentage (*nn*) when SMF starts to issue a warning message depending on the recording environment. For data set recording environments, the following occurs:

- SMF maintains a single buffer area for all data recording.
- The parameter option value specifies the overall buffer warning level percentage when SMF starts to issue warning message IEE986E. When the amount of in-use buffer percentage falls below the BUFUSEWARN value minus 5 (the default is 20%), message IEE986E is deleted. When SMF is using this percentage of buffer space, message IEE986E is issued. As each additional or incremental SMF buffer (8M) is used to buffer SMF record data, SMF issues an updated instance of message IEE986E that indicates the new buffer storage percentage in use. As in-use SMF buffers are no longer needed, the buffers are removed from the in-use chain. After eligible buffers are removed, an updated instance of message IEE986E is issued that indicates the changed (reduced) buffer storage percentage in-use. When the overall SMF buffer in-use percentage drops to 5 percent below the BUFUSEWARN value, SMF performs a delete-operator-message (DOM) for message IEE986E.

For log stream recording environments, the following occurs:

- A separate buffer area is maintained for each SMF log stream. The option value that is specified for this parameter applies to all SMF log streams unless it is also specified as a subparameter on the LSNNAME or DEFAULTLSNAME SMFPRMxx parameter options. BUFUSEWARN options that are specified on LSNNAME or DEFAULTLSNAME override the global specification of this BUFUSEWARN option for that log stream.
- The parameter option value specifies the overall buffer warning level percentage when SMF starts to issue warning message IFA785E. When the amount of in-use buffer percentage falls below the BUFUSEWARN value minus 5 (the default is 20%), message IFA785E is deleted. When SMF is using this percentage of buffer space, message IFA785E is issued. As each additional or incremental SMF buffer (8M) is used to buffer SMF record data, SMF issues an updated instance of message IFA785E that indicates the new buffer storage percentage in use. As in-use SMF buffers are no longer needed, the buffers are removed from the in-use chain. After eligible buffers are removed, an updated instance of message IFA785E is issued that indicates the changed (reduced) buffer storage percentage in-use. When the overall SMF buffer in-use percentage drops to 5 percent below the BUFUSEWARN value, SMF performs a delete-operator-message (DOM) for message IFA785E.
- SMF preallocates and maintains storage in the buffer for initial use and for internal control information. This is included in the in-use accounting of the buffer for BUFUSEWARN processing.
- SMF maintains the current and high water mark values of the percentage of the buffer that is in-use. The values are reported in SMF23LCP and SMF23LHP, respectively.

The BUFUSEWARN value can be specified during an IPL in parmlib member SMFPRMxx, and you can set the value higher or lower using the T SMF or SETSMF commands. The D SMF,O command displays the current BUFUSEWARN value.

**Value range:** 10–90 (10% to 90%)

**Default:** 25 % (25% of BUFSIZMAX value)

**Example:**

```
NOBUFFS(MSG)
BUFUSEWARN(25)
DEFAULTLSNAME(ifasmf.default)
LSNAME(ifasmf.important,NOBUFFS(HALT),BUFUSEWARN(30))
```

In this example, the default for all log streams is NOBUFFS(MSG) and BUFUSEWARN(25). Because the DEFAULTLSNAME did not override these defaults, they are applied to the IFASMF.DEFAULT log stream buffer. The IFASMF.IMPORTANT log stream did override these values, and therefore NOBUFFS(HALT) and BUFUSEWARN(30) are applied. In data set recording mode, the global values still apply.

**DEFAULTLSNAME**

This optional parameter specifies the default log stream name to use when writing SMF records to a log stream, except for record types that are specified on LSNNAME or INMEM parameters. When you

specify DEFAULTLSNAME (and do not override it with the LSNAME or INMEM parameter), records are queued and written to the specified default log stream name.

**Example:** Assume that the SMFPRMxx parmlib member contains the following statements:

```
DEFAULTLSNAME (IFASMF.DEFAULT)
LSNAME (IFASMF.PERF, TYPE (30,89))
RECORDING (LOGSTREAM)
```

Record types 30 and 89 go to the IFASMF.PERF log stream, while all other record types go to the default IFASMF.DEFAULT log stream.

#### Notes:

1. You can only specify DEFAULTLSNAME once in the SMFPRMxx member. If you specify DEFAULTLSNAME more than once, the system issues error message IFA701I and rejects the duplicate default log stream name.
2. If you do not specify a DEFAULTLSNAME in SMFPRMxx and the SYS and SUBSYS parameters specify record types (on the TYPE and NOTYPE subparameters) that are not defined on the LSNAME parameters, the system issues error message IFA702I and rejects the log stream-related parameters in the parmlib member.

The syntax for the DEFAULTLSNAME parameter is:

```
DEFAULTLSNAME (logstreamname
[ , NOBUFFS (HALT | MSG) ]
[ , BUFUSEWARN (nn) ]
[ , DSPSIZMAX (nnnnM | nG) ]
[ , NOCOMPRESS | COMPRESS [ (PERMFIX (nnnnM) ) ] ]
[ , NORECSIGN | RECSIGN (HASH (SHA1 | SHA256 | SHA384 | SHA512) ,
SIGNATURE (RSA | ECDSA) ,
TOKENNAME (tokenname) ) ]
[ , NOARECSIGN | ARECSIGN (HASH (SHA512) ,
SIGNATURE (LI2) ,
TOKENNAME (tokenname) ) ] )
```

The default behavior for each DEFAULTLSNAME subparameter is described in [Table 60 on page 741](#).

| Table 60. Default values for the DEFAULTLSNAME subparameters in SET SMF and SETSMF processing |   |
|---|---|
| Processing  | Default values  |
| SET SMF   | Each DEFAULTLSNAME subparameter description describes the default value.  |
| SETSMF  | DEFAULTLSNAME subparameters receive the previously specified value of the subparameter, if any. In order to receive the SET SMF default value for a DEFAULTLSNAME subparameter value that was previously specified in the SMFPRMxx member or in a SETSMF LSNAME command, that default value must have been explicitly coded on the SETSMF LSNAME command. |

When the following subparameters are not specified and the log stream is already connected, SMF does not use the default values or change the subparameters. SMF continues to use previous SET or SETSMF values. However, if the log stream is disconnected and then reconnected, and if the subparameters are not specified on the last SET or SETSMF command affecting the log stream, SMF uses the default values.

You can specify the following subparameters for DEFAULTLSNAME:

#### **logstreamname**

The name of the log stream. Follow the log stream naming guidelines that are specified for the LSNAME parameter.

#### **BUFUSEWARN(nn)**

BUFUSEWARN specifies the overall buffer warning level percentage (nn) when SMF starts to issue warning message IFA785E for the log stream specified on this DEFAULTLSNAME parameter. This option can also be specified as a global option setting that applies to all log streams defined by the LSNAME and DEFAULTLSNAME keywords. This option overrides the globally specified BUFUSEWARN option for the log stream specified on this DEFAULTLSNAME parameter only. For

a detailed description of this parameter, see the parameter option description for the global specification of BUFUSEWARN.

**Default:** The option that is specified on the global BUFUSEWARN parameter. Also, see [Table 60 on page 741](#), which lists the default values for the DEFAULTLSNAME subparameters in both SET SMF and SETSMF processing.

#### **NOCOMPRESS | COMPRESS[(PERMFX(nnnnM))]**

COMPRESS is an optional parameter. When specified with an zEDC Express feature available, SMF compresses SMF records before writing to the log stream. This option allows for greater throughput of SMF records.

If an zEDC Express feature fails or none are available for use, message IFA730E is issued and SMF continues writing non-compressed records to the log stream.

To restart a failed zEDC session, issue either of the following commands:

- SETSMF RECORDING=LOGSTREAM
- SET SMF=xx where xx is the SMFPRMxx member that specifies LSNAME with the COMPRESS option.

To turn off an zEDC session once it has successfully started:

- Specify NOCOMPRESS either as a global setting or on the LSNAME, as appropriate. Note that once COMPRESS is activated for a log stream, the default of NOCOMPRESS is not instated in the absence of the COMPRESS parameter.
- Issue SET SMF=xx or SETSMF to activate the changed setting.

Once SMF can successfully write compressed data, SMF issues message IFA731I.

**Default:** (If an zEDC session has not started) NOCOMPRESS (Also see [Table 60 on page 741](#), which lists the default values for the DEFAULTLSNAME subparameters in both SET SMF and SETSMF processing.)

#### **PERMFX(nnnnM)**

PERMFX is an optional parameter when COMPRESS is specified. PERMFX specifies the default amount of storage that SMF can keep permanently fixed for purposes of communicating with the zEDC Express feature. Storage that is used by the zEDC Express feature must be page fixed; however, fixed pages are a constrained resource. Increasing this number can improve performance of SMF, but decreases the fixed storage available to the other applications. Decreasing this number can increase the fixed storage available to other applications, but might degrade SMF performance. PERMFX can range from a minimum of 1M to a maximum of 2 GB. Due to processing needs, even if this value is NOPERMFX, SMF can use up to 2 MB of fixed storage for zEDC usage.

**Default:** If specified, this value overrides the global PERMFX value. Also, see [Table 60 on page 741](#), which lists the default values for the DEFAULTLSNAME subparameters in both SET SMF and SETSMF processing.

#### **DSPSIZMAX(nnnnM|nG)**

The DSPSIZMAX subparameter specifies the amount of storage this log stream is to use for buffers.

**Default:** 2G. Also, see [Table 60 on page 741](#).

#### **NOBUFFS(HALT|MSG)**

NOBUFFS specifies the system action when the log stream specified on this DEFAULTLSNAME parameter buffer area is full. This option can also be specified as a global option setting. This option overrides the globally specified NOBUFFS option for the log stream that is specified on this DEFAULTLSNAME parameter only. See the parameter option description for the global specification of NOBUFFS for a detailed description of this parameter.

**Default:** The option that is specified on the global NOBUFFS parameter. Also, see [Table 60 on page 741](#), which lists the default values for the DEFAULTLSNAME subparameters in both SET SMF and SETSMF processing.

**NORECSIGN | RECSIGN(HASH(SHA1|SHA256|SHA384|SHA512), SIGNATURE(RSA|ECDSA),TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded for the log stream specified by this DEFAULTLSNAME parameter. If NORECSIGN is specified, SMF will not sign records for this log stream. If RECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keywords must also be specified. The log stream must also have been defined with a MAXBUFSIZE of 65532. This specification overrides any global RECSIGN specification.

**Default:** None

**HASH(SHA1|SHA256|SHA384|SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. Valid values are SHA1, SHA256, SHA384, and SHA512.

**Default:** None

**SIGNATURE(RSA|ECDSA)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF command is issued to rectify the discrepancy. The valid values are RSA and ECDSA.

**Default:** None

**TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length and must be a valid token. See [z/OS Cryptographic Services System SSL Programming](#) for more information. If the token name and signature are not compatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see [Signing and validating SMF records in z/OS MVS System Management Facilities \(SMF\)](#).

**NOARECSIGN | ARECSIGN(HASH(SHA512), SIGNATURE(LI2),TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded for the log stream using an alternate signature method specified by this DEFAULTLSNAME parameter. If NOARECSIGN is specified, SMF will not sign records using an alternate signature for this log stream. If ARECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keywords must also be specified. This specification overrides any global ARECSIGN specification.

When using an alternate signature method, a primary signature method is also required. The primary signature method can be specified using the global RECSIGN specification or a RECSIGN specification on the DEFAULTLSNAME parameter.

**Default:** None

**HASH(SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. The only valid value is SHA512.

**Default:** None

**SIGNATURE(LI2)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records using an alternate signature until a SET SMF or SETSMF command is issued to rectify the discrepancy. The only valid value is LI2 (Dilithium). Cryptographic Support for z/OS V2R2 - V2R4 (HCR77D1) and IBM z15<sup>®</sup> are required for Dilithium signature support.

**Default:** None

### **TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length and must be a valid token. SMF only supports the use of Dilithium (6,5) Round 2, Dilithium(6,5) Round 3, Dilithium(8,7) Round 2, or Dilithium(8,7) Round 3 keys. See *z/OS Cryptographic Services System SSL Programming* for more information. If the token name and signature are not compatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see *Signing and validating SMF records in z/OS MVS System Management Facilities (SMF)*.

### **DDCONS(YES|NO)**

Specifies whether duplicate EXCP entries for type 30 SMF records are to be consolidated. When DDCONS(YES) is specified, SMF merges the EXCP count for these duplicate entries into one entry if the following information is the same:

- DDNAME
- Device class
- Unit type
- Channel address
- Unit address

Long-running jobs might take a long time to end in this case, because of the building of the SMF type 30 records for a long-running job.

DDCONS(NO) requests that this consolidation function be bypassed, which results in a reduction in the amount of processing required to build the records, and thus a reduction in the amount of time that is required to complete the job.

**Default:** YES

### **DSNAME(dataset)**

Specifies a list of data sets to be used for SMF data set recording. If DSNAME is specified with RECORDING(LOGSTREAM), the data sets specified is opened and prepared for use, so that they will be ready for immediate use if a SETSMF RECORDING(DATASET) is entered.

The maximum length of the data set name is 44 characters, and must follow standard MVS data set naming conventions.

You can use system symbols and the &SID symbol in SMF data set names. The resolved substitution text for the &SID system symbol is the system identifier that is specified on the SID parameter in SMFPRMxx. &SID can be used only to name resources in SMFPRMxx; you cannot specify &SID in other parmlib members.

Table 61 on page 744 shows examples of data set names that use the &SYSNAME system symbol and the &SID symbol. The table shows the substitution texts for &SYSNAME and &SID, the data set names that specify the symbols, and the resolved texts for the data set names.

| Table 61. Examples of data set names that use system symbols |          |                          |                        |
|--|----------|--------------------------|------------------------|
| Substitution text  |          | Data set name            | Resolved data set name |
| &SID   | &SYSNAME |                          |                        |
| WRR1   | —        | SYS1.&SID;DATA           | SYS1.WRR1DATA          |
| WRR1   | —        | SYS1.SID&SID;.DATA       | SYS1.SIDWRR1.DATA      |
| WRR1   | SP52     | SYS1.&SYSNAME;&SID;.DATA | SYS1.SP52WRR1.DATA     |
| —  | SP52     | SYS1.&SYSNAME            | SYS1.SP52              |

**Default:** The defaults are as follows:

- When RECORDING(DATASET) is specified, the default is SYS1.MANX and SYS1.MANY.
- When RECORDING(LOGSTREAM) is specified, no default.

**Note:** The SID parameter can be modified before initialization completes, if the PROMPT(LIST) or PROMPT(ALL) parameter in SMFPRMxx is specified. If the value of SID changes, any data set names that specify the &SID symbol will also change (because the value on the SID parameter is also the substitution text for the &SID symbol).

### **DSPSIEMAX(nnnnM|nG)**

Specifies the maximum amount of storage that a log stream data space will consume. This parameter applies to any log streams specified with the LSNAME or DEFAULTLSNAME keyword that does not have this keyword specified as a subparameter.

This is the global specification of the DSPSIEMAX value, and its value takes effect for log streams where DSPSIEMAX was not specified.

**Value range:** 128M - 2048M, or 1G - 2G (128 megabytes to 2048 megabytes, or 1 gigabyte to 2 gigabytes)

**Default:** 2G

### **DUMPABND(RETRY|NORETRY)**

Specifies whether the SMF dump program attempts to recover in the event an abend occurs.

#### **RETRY**

Specifies that the SMF dump program attempts to recover from abends and continue processing.

#### **NORETRY**

Specifies that the SMF dump program terminates when an abend occurs.

**Note:** The IFASMFDP and IFASMFDP dump programs will override this parameter and the ABEND dump program parameter if the input data set is to be dumped and cleared, or if the log stream is to be archived or deleted, and an ABEND occurs *after* the input data set has been cleared or the log stream has been deleted. For this case, the SMF dump program will attempt to recover from the ABEND to prevent the output data set from being deleted and SMF data from being lost, when the SMF dump program abnormally ends. For more information about the SMF dump program, see [z/OS MVS System Management Facilities \(SMF\)](#).

**Default:** RETRY

### **EMPTYEXCPSEC(NOSUPPRESS|SUPPRESS)**

Specifies whether to suppress empty execute channel program (EXCP) entries in the SMF type 30 record. IBM recommends that the SUPPRESS option is specified.

#### **NOSUPPRESS**

Specifies that the system generates an empty SMF type 30 record EXCP section for each SMS candidate volume in the storage group that is not allocated to the DD statement. By default, empty EXCP sections are also generated for non-dataset allocations like DD DUMMY or spool file allocations.

#### **SUPPRESS**

specifies that the system suppresses the creation of empty EXCP sections for non-allocated candidate volumes in the SMS storage group. With this option, empty EXCP sections that are generated for non-dataset allocations like DD DUMMY or spool file allocations are also suppressed.

**Default:** NOSUPPRESS

### **FLOOD(ON|OFF)**

Specifies whether SMF record flood support is active.

For a description of SMF flood policies, see the topic on [FLOOD and FLOODPOL — Specifying SMF record flood options in z/OS MVS System Management Facilities \(SMF\)](#).

**Default:** OFF



**FLOODPOL(ffff)**

Specifies a flood policy filter (ffff). The FLOOD SMFPRMxx option must be set to ON for this option to become activated. Each option must be present in the filter (ffff).

**ACTION(MSG|DROP)**

Specifies the action to be taken when a flood state is entered.

**DROP**

Issue message IFA782A at the start of the flood state and also begin dropping records. Any attempts to write a record through the SMFEWTFM or SMFWTFM macro results in a return code 52. At the end of the flood state, message IFA783I is issued that indicates the number of records that have been dropped.

For more information about SMFEWTFM and SMFWTFM, see [SMFEWTFM - Writing SMF records](#) and [SMFWTFM — Writing SMF records in z/OS MVS System Management Facilities \(SMF\)](#).

**MSG**

Issue warning message IFA780A at the start of the flood state. Message IFA781I is issued when the flooding has stopped.

**Default:** None

**ENDINTVL(ssss)**

Specifies the amount of time, in tenths of a second, that must elapse before SMF determines that a flood has ended. Once a flood state has begun, if less than the RECTHRESH records are generated in at least ENDINTVL amount of time, the flood will end. SMF only checks for ending a flood as records are generated, as opposed to checking at the specified ENDINTVL amount of time.

**Value range:** 1-9999

**Default:** None

**INTVLTIME(ssss)**

Specifies a flood interval time value, which is given in tenths of seconds. A flood rate is defined by the RECTHRESH number of records that are generated within INTVLTIME time. Flood policies are decided first on how many records are generated and then on how long it takes to generate them, rather than being based only on an interval basis.

**Value range:** 1-9999

**Default:** None

**MAXHIGHINTS(yyyy)**

Specifies the number of intervals, defined by INTVLTIME, that must occur at or above the flood rate before action is taken. When the THRESHRECS number of records are generated within the INTVLTIME time period (interval) for the MAXHIGHINTS consecutive number of intervals, SMF enters into a flood state for the designated record type.

**Value range:** 1-9999

**Default:** None

**RECTHRESH(yyyy)**

Specifies the number of records in an interval for this filter.

**Value range:** 1-9999

**Default:** None

**TYPE{(aa,bb)|(aa,bb:zz)|(aa,bb:zz,...)}**

Specifies the records for this filter.

**Value range:** 0-2047 (SMF record types).

**Default:** None

Consider the following example SMFPRMxx parmlib option settings:



**FLOOD(ON)**

```

FLOODPOL(TYPE(4,5),RECTHRESH(1000),INTVLTIME(50),MAXHIGHINTS(15),ENDINTVL(120),ACTION(MSG))
FLOODPOL(TYPE(102),RECTHRESH(5000),INTVLTIME(10),MAXHIGHINTS(15),ENDINTVL(100),ACTION(MSG))
FLOODPOL(TYPE(102),RECTHRESH(5000),INTVLTIME(10),MAXHIGHINTS(15),ENDINTVL(50),ACTION(DROP))

```

In this example, two filters are set up. The first filter sets up a monitor for both record types 4 and 5. This filter detects when 1000 records are generated within 5 seconds and, if records continue to be generated at this rate for more than 15 consecutive 5-second intervals, message IFA780A is issued. The flood state ends, for each record type, when fewer than 1000 records are generated in at least 12 seconds. Message IFA781I is issued when the flood state ends.

The second filter for record type 102 is a two-part filter. The first part that issues the warning message, IFA780A, is triggered when 5000 records are generated in less than 1 second, and records continue to be generated at that rate for more than 15 consecutive 1-second intervals. The flood state ends when fewer than 5000 records are generated in at least 10 seconds. Message IFA781I is issued when the flood ends. If the flood state persists, the DROP filter becomes active so that if 5000 type-102 records are generated within 1 second over more than 15 consecutive 1-second intervals, message IFA782A is issued and records are dropped. Records stop being dropped once fewer than 5000 type 102 records are generated in at least 5 seconds. Message IFA783I is issued when the flood state for dropping records ends.

**HFTSINTVL(ss) | NOHFTSINTVL**

When the NOWIC parameter is specified or allowed to default, the HFTSINTVL parameter specifies the time interval, in seconds, for writing SMF type 98 records, which record high-frequency throughput statistics (HFTS).

The supported values are 5, 10, 15, 20, 30, and 60 seconds. For instance, HFTSINTVL(20) indicates that SMF type 98 records are to be written every 20 seconds, starting at the top of the minute and each 20-second multiple that follows.. IBM recommends setting HFTSINTVL(5) to write SMF type 98 records every 5 seconds, starting at the top of the minute and each 5-second multiple that follows.

When you specify any HFTSINTVL value, SMF type 98 records are collected every 5 seconds starting at the top of the minute and each 5-second multiple for one minute at 0, 15, 30, and 45 minutes past each hour. For all other minutes during each hour, SMF type 98 records are written at the interval specified by the HFTSINTVL parameter.

The NOHFTSINTVL parameter disables the HFTS interval and prevents the collection of SMF type 98 records. This is the default value.

SMF collects type 98 records only when both the HFTSINTVL parameter and the TYPE(98) parameter are specified. Specifying NOHFTSINTVL along with TYPE(98) allows you to disable the collection of type 98 records without changing the TYPE setting.

When the WIC parameter is specified, the HFTSINTVL value is ignored.

**Default:** NOHFTSINTVL

**Values:** 5, 10, 15, 20, 30, or 60 seconds

**WIC | NOWIC**

When you specify the WIC parameter, the IBM z/OS Workload Interaction Correlator (WIC) feature is enabled on the system. z/OS components, middleware, and applications can use the IFAWIC service to register for instrumentation, request an instrumentation buffer for the job, and provide an exit routine.

The exit routine will be called to summarize instrumentation data and produce SMF type 98 records for subtype 2 or greater. This exit will be called every 5 seconds, starting at the top of the minute and each 5-second multiple that follows, when the following conditions are true:

- The WorkloadIntCorr feature is enabled in the product enablement policy (IFAPRDxx).
- SETSMF or SMFPRMxx has specified WIC.
- SMF is collecting type 98 subtype 2 or greater records.

SMF type 98 subtype 1 (supervisor) records are not generated through IBM z/OS Workload Interaction Correlator and will be generated when the following conditions are true:

- SETSMF or SMFPRMxx has specified WIC or HFTSINTVL(5) or greater.
- SMF is collecting type 98 subtype 1 records.

When you specify the WIC parameter, the HFTSINTVL parameter is ignored, and SMF type 98 subtype 1 records are generated every 5 seconds.

When you specify the NOWIC parameter, IBM z/OS Workload Interaction Correlator (WIC) is disabled on the system. The IFAWIC REQUEST=REGISTER service will fail for applications that call it. IFAWIC exploiters that are already registered for instrumentation will no longer have their exit routines called. When NOWIC is specified, HFTSINTVL is honored.

**Default:** NOWIC

## INMEM

Defines an in-memory resource to record SMF records in memory for real-time processing.

**Note:** The system supports a maximum of 32 in-memory resources at any time.

The syntax for the INMEM parameter is:

```
INMEM(rname, RESSIZMAX({nnnnM|nG}), {TYPE({aa,bb|aa,bb:zz|aa,bb:zz,...}) |
NOTYPE({aa,bb|aa,bb:zz|aa,bb:zz,...}) }
```

You must specify the following subparameters for INMEM:

### *rname*

Name of the in-memory resource. The resource name must begin with IFASMF . and can be up to 26 characters long. The resource name must be unique across resource names on other INMEM statements and log stream names on LSNAME statements.

You must also define a SAF resource in the FACILITY class to protect the in-memory resource. The SAF resource profile name must start with the IFA . high-level qualifier, followed by the same name that you specify for *rname*.

For more information, see [z/OS MVS System Management Facilities \(SMF\)](#).

**Default:** None.

### RESSIZMAX({*nnnnM*|*nG*})

Specifies the size of the buffer available for this in-memory resource, in megabytes or gigabytes.

The in-memory resource acts as a wrap-around buffer. When the buffer is full, older records are discarded as newer records are written. When planning the RESSIZMAX value, select a value that can be accommodated by the system's real and auxiliary storage, assuming that the entire amount will be used at all times.

**Default:** 2 GB

**Value range:** 128 MB - 2 GB

### TYPE({*aa*,*bb*|*aa*,*bb*:*zz*|*aa*,*bb*:*zz*,...})

### NOTYPE({*aa*,*bb*|*aa*,*bb*:*zz*|*aa*,*bb*:*zz*,...})

TYPE specifies the SMF record types that are to be recorded to this in-memory resource. The *aa*, *bb*, and *zz* values are the decimal notations for each SMF record type. You cannot specify subtypes on the TYPE subparameter for INMEM. A colon (:) indicates a range of SMF record types (*bb* through *zz*) to be recorded.

NOTYPE specifies that SMF is to collect all SMF record types *except* those specified. The *aa*, *bb*, and *zz* values are the decimal notations for each SMF record type. You cannot specify subtypes on the NOTYPE subparameter for INMEM. A colon indicates the range of SMF record types (*bb* through *zz*) that are not to be recorded.

The record types to be recorded to an in-memory resource do not also have to be recorded to a log stream.

**Note:** Record types that you specify on an **INMEM** parameter are not written to the default log stream, if any, defined by the **DEFAULTLSNAME** parameter. If you want certain record types to be written to both an in-memory resource and a log stream, specify those record types on both an **INMEM** parameter and an **LSNAME** parameter.

**Note:** An active connection prevents the SET SMF=xx command from changing the in-memory resource definition, such as changes to the **TYPE** or **RESSIZMAX** parameters.

**Default:** None.

**Value range:** 0 - 2047 (SMF record types)

### INTVAL(*mm*)

Specifies the length of time (in minutes) from the end of an SMF global recording interval to the end of the next interval. For example, if you specify INTVAL(15), the SMF global recording interval ends every 15 minutes. INTVAL is a global interval value that other requesters, such as RMF, can use to schedule interval functions to execute in conjunction with the SMF interval function.

Choose a two-digit global interval value, *mm*, that divides evenly into 60 (01, 02, 03, 04, 05, 06, 10, 12, 15, 20, 30, and 60). Otherwise, the system can synchronize only the first interval.

**Value range:** 01-60

**Default:** 30

**Note:** Only SMF records are controlled by the INTVAL and SYNCVAL parameters. The INTVAL and SYNCVAL parameters can influence other record types, such as when activated by the RMF Monitor I SYNC(SMF) option to write record types 70 through 79.

### LISTDSN | NOLISTDSN

Specifies whether the system is to generate SMF data set status messages to the operator at IPL or SET SMF time. This parameter applies to SMF data set recording only; it does not apply to SMF log stream recording. The messages contain the following information for each data set used for SMF recording:

- Data set name
- Data set status
  - Active
  - Alternative
  - Close pending
  - Error
  - Dump required
- Data set size (in number of VSAM control-interval-sized blocks)
- Percentage full

**Default:** LISTDSN

### LSNAME

LSNAME allows you to specify a log stream in which you want to record particular SMF record types specified on the TYPE subparameter.

If you specify the same record type on two or more different LSNAME parameters, the system writes the record to all specified log streams. For example, you might have an SMFPRMxx parmlib member with the following contents:

```
DEFAULTLSNAME (IFASMF.DEFAULT)
LSNAME (IFASMF.PERF,TYPE(30,89))
LSNAME (IFASMF.JOB,TYPE(30))
RECORDING(log stream)
```

This allows you to collect job-related SMF data in the JOB log stream, and performance-related SMF data in the PERF log stream. Record type 30 fits into both categories, so you can specify that it is written to both log streams. Note that this arrangement can result in duplicate records being recorded.

The syntax for the LSNAME parameter is:

```
LSNAME(log streamname,TYPE{(aa,bb)|(aa,bb:zz)|(aa,bb:zz,...)}
[,NOBUFFS(HALT|MSG)]
[,BUFUSEWARN(nn)]
[,DSPSIZMAX(nnnnM|nG)]
[,NOCOMPRESS|COMPRESS[(PERMFIX(nnnnM))]]
[,NORECSIGN|RECSIGN(HASH(SHA1|SHA256|SHA384|SHA512),
SIGNATURE(RSA|ECDSA),
TOKENNAME(tokenname)))]
[,NOARECSIGN|ARECSIGN(HASH(SHA512),
SIGNATURE(LI2),
TOKENNAME(tokenname)))])
```

The default behavior for each LSNAME subparameter is described in [Table 62 on page 750](#).

| Table 62. Default values for the LSNAME subparameters in SET SMF and SETSMF processing |   |
|--|---|
| Processing   | Default values  |
| SET SMF  | Each LSNAME subparameter description describes the default value.   |
| SETSMF   | LSNAME subparameters receive the previously specified value of the subparameter, if any. In order to receive the SET SMF default value for an LSNAME subparameter value that was previously specified in the SMFPRMxx member or in a SETSMF LSNAME command, that default value must be explicitly coded on the SETSMF LSNAME command. |

When the following subparameters are not specified and the log stream is already connected, SMF does not use the default values or make changes to the subparameters. SMF continues to use previous SET or SETSMF values. However, if the log stream is disconnected and then reconnected, and if the subparameters are not specified on the last SET or SETSMF against the log stream, SMF uses the default values.

You can specify the following subparameters for LSNAME:

#### **log streamname**

The name of the log stream. The log stream name must be composed as follows:

- The first seven characters must be: IFASMF.
- It must have a minimum of 8 characters.
- It must have a maximum of 26 characters.
- It must conform to other log stream naming conventions as documented in [IXGINVNT – Managing the LOGR inventory couple data set in z/OS MVS Programming: Assembler Services Reference IAR-XCT](#).
- It must be unique across log stream names on other LSNAME statements and in-memory resource names on INMEM statements.

You can use system symbols and the &SID symbol in SMF log stream names. The resolved substitution text for the &SID system symbol is the system identifier that is specified on the SID parameter in SMFPRMxx. &SID can only be used to name resources in SMFPRMxx; you cannot specify &SID in other parmlib members.

[Table 63 on page 750](#) shows examples of log stream names that use the &SYSNAME system symbol and the &SID symbol. The table shows the substitution texts for &SYSNAME and &SID, the data set names that specify the symbols, and the resolved texts for the log stream names.

| Table 63. Examples of log stream names that use system symbols |          |                        |                          |
|--|----------|------------------------|--------------------------|
| Substitution text  |          | Log stream name        | Resolved log stream name |
| &SID   | &SYSNAME |                        |                          |
| WRR1   | -        | IFASMF.SYS1.&SID..DATA | IFASMF.SYS1.WRR1DATA     |

Table 63. Examples of log stream names that use system symbols (continued)

| Substitution text |          | Log stream name                 | Resolved log stream name  |
|-------------------|----------|---------------------------------|---------------------------|
| &SID              | &SYSNAME |                                 |                           |
| WRR1              | -        | IFASMF.SYS1.SID&SID..DATA       | IFASMF.SYS1.SIDWRR1.DATA  |
| WRR1              | SP52     | IFASMF.SYS1.&SYSNAME;&SID..DATA | IFASMF.SYS1.SP52WRR1.DATA |
| -                 | SP52     | IFASMF.SYS1.&SYSNAME            | IFASMF.SYS1.SP52          |

If you specify an incorrect log stream name, the system issues message IFA700I.

### BUFUSEWARN(nn)

BUFUSEWARN specifies the overall buffer warning level percentage (*nn*) when SMF starts to issue warning message IFA785E for the log stream that is specified on this LSNAME parameter. This option can also be specified as a global option setting that applies to all log streams defined by the LSNAME and DEFAULTLSNAME keywords. This option overrides the globally specified BUFUSEWARN option for the log stream that is specified on this LSNAME parameter only. For a detailed description of this parameter, see the parameter option description for the global specification of BUFUSEWARN.

**Default:** The option that is specified on the global BUFUSEWARN parameter. Also, see Table 62 on page 750, which lists the default values for the LSNAME subparameters in both SET SMF and SETSMF processing.

### NOCOMPRESS | COMPRESS[(PERMFX(nnnnM))]

COMPRESS is an optional parameter. When specified with an zEDC Express feature available, SMF compresses SMF records before writing to the log stream.

**Default:** (If an zEDC session has not started) NOCOMPRESS (Also see Table 62 on page 750, which lists the default values for the LSNAME subparameters in both SET SMF and SETSMF processing.)

If all zEDC Express features fail or none are available for use, message IFA730I is issued and SMF continues writing non-compressed records to the log stream.

To restart a failed zEDC session, issue a SETSMF RECORDING=log stream to retry compression or alter other SMF parameters using the SET or the SETSMF command. Message IFA731I is issued when compression is successfully enabled.

To turn off an zEDC session once it has successfully started:

- Specify NOCOMPRESS either as a global setting or on the LSNAME, as appropriate. Note that once COMPRESS is activated for a log stream, the default of NOCOMPRESS is not instated in the absence of the COMPRESS parameter.
- Issue SET SMF=xx or SETSMF to activate the changed setting.

Once SMF can successfully write compressed data, SMF will issue message IFA731I.

### PERMFX(nnnnM)

PERMFX is an optional parameter when COMPRESS is specified. PERMFX specifies the default amount of storage that SMF can keep permanently fixed for purposes of communicating with the zEDC Express feature. Storage that is used by the zEDC Express feature has to be page fixed; however, fixed pages are a constrained resource. Increasing this number can improve performance of SMF, but decreases the fixed storage available to the other applications. Decreasing this number can increase the fixed storage available to other applications, but might degrade SMF performance. PERMFX can range from a minimum of 1M to a maximum of 2 GB. Due to processing needs, even if this value is NOPERMFX, SMF can use up to 2 MB of fixed storage for zEDC usage.

If specified, this value overrides the global PERMFX value.

### NOBUFFS(HALT|MSG)

NOBUFFS specifies the system action when the log stream specified on this LSNAME parameter buffer area is full. This option can also be specified as a global option setting. This option overrides

the globally specified NOBUFFS option for the log stream that is specified on this LSNAME parameter only. For a detailed description of this parameter, see the parameter option description for the global specification of NOBUFFS.

**Default:** The option that is specified on the global NOBUFFS parameter. Also, see [Table 62 on page 750](#), which lists the default values for the LSNAME subparameters in both SET SMF and SETSMF processing.

#### **TYPE{(aa,bb)|(aa,bb:zz)|(aa,bb:zz,...)}**

TYPE specifies the SMF record types that SMF is to collect to the specified log stream on the LSNAME parameter. aa, bb, and zz are the decimal notations for each SMF record type. You cannot specify subtypes on the TYPE subparameter for LSNAME. A colon indicates the range of SMF record types (bb through zz) to be recorded.

#### **Note:**

- A specified value of 126 is ignored by the system.
- The specified TYPE or NOTYPE parameter values must resolve to at least one non 126 type value.
- TYPE or NOTYPE parameter options that are specified after the first TYPE or NOTYPE are ignored.

**Default:** None.

#### **Value range:**

0-2047 (SMF record types)

#### **Value range:**

When any globally specified record types are rendered without an LSNAME home, the configuration is rejected with message IFA702I stating that no log streams were specified for record type *nnn nnn*. When all record types have a home, but LSNAME was specified without the TYPE parameter, the LSNAME parameter is accept but ignored. No record types are written to an LSNAME without the TYPE parameter.

#### **NORECSIGN | RECSIGN(HASH(SHA1|SHA256|SHA384|SHA512), SIGNATURE(RSA|ECDSA), TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded for the log stream specified by this LSNAME parameter. If NORECSIGN is specified, SMF will not sign records for this log stream. If RECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keyword must also be specified. The log stream must also have been defined with a MAXBUFSIZE of 65532. This specification overrides any global RECSIGN specification.

**Default:** None

#### **HASH(SHA1|SHA256|SHA384|SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. Valid values are SHA1, SHA256, SHA384, SHA512.

**Default:** None

#### **SIGNATURE(RSA|ECDSA)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF command is issued to rectify the discrepancy. The valid values are RSA and ECDSA.

**Default:** None

#### **TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length, and must be a valid token. See [z/OS Cryptographic Services System SSL Programming](#) for more information. If the token name and

signature are incompatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see [Signing and validating SMF records in z/OS MVS System Management Facilities \(SMF\)](#).

#### **NOARECSIGN | ARECSIGN(HASH(SHA512), SIGNATURE(LI2),TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded for the log stream using an alternate signature specified by this LSNAME parameter. If NOARECSIGN is specified, SMF will not sign records using an alternate signature for this log stream. If ARECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keywords must also be specified. This specification overrides any global ARECSIGN specification.

When using an alternate signature method, a primary signature method is also required. The primary signature method can be specified using the global RECSIGN specification or a RECSIGN specification on the DEFAULTLSNAME parameter.

**Default:** None

#### **HASH(SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. The only valid value is SHA512.

**Default:** None

#### **SIGNATURE(LI2)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF command is issued to rectify the discrepancy. The only valid value is LI2 (Dilithium). Cryptographic Support for z/OS V2R2 - V2R4 (HCR77D1) and IBM z15™ are required for Dilithium signature support.

**Default:** None

#### **TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length, and must be a valid token. SMF only supports the use of Dilithium (6,5) Round 2, Dilithium(6,5) Round 3, Dilithium(8,7) Round 2, or Dilithium(8,7) Round 3 keys. See [z/OS Cryptographic Services System SSL Programming](#) for more information. If the token name and signature are not compatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see [Signing and validating SMF records in z/OS MVS System Management Facilities \(SMF\)](#).

#### **MAXDORM(mmss) | NOMAXDORM**

This parameter applies to SMF data set recording and SMF log stream recording; it does not apply to in-memory resources used for SMF real-time processing.

MAXDORM specifies the amount of real time that SMF allows data to remain in an SMF buffer before it is written to a recording data set or a log stream, where *mm* is real time in minutes and *ss* is seconds. NOMAXDORM specifies that the data remains in the buffer until the buffer is full. The size of the non-full buffer written out when the MAXDORM reached is one control interval (CI).

**Value range:** 0001-5959

**Default:** MAXDORM (3000). This default indicates 30 minutes.

#### **MAXEVENTINTRECS(nn)**

This option is used to indicate the maximum number of event driven SMF type 30 and type 89 interval records that are allowed during a regular interval cycle. Extra SMF Type 30 and Type 89 interval records can be generated when a processor capacity change occurs. The additional interval records

are generated such that when a processor changes capacity, the current interval is expired and a new, event driven interval begins. The event-driven interval expires at the regularly scheduled end of the current interval, or when the processor changes capacity again, whichever occurs first. This serves to capture data for the interval records relevant to the current processor capacity.

The system detects a change in processor speed when an ENF 41 is signaled, along with a change in processor capacity data.

#### **nn**

Specifies the maximum number of these additional event driven interval records that are allowed during a single interval. When the number of processor capacity changes during a single interval exceeds the value that is specified by *nn*, no additional type 30 or 89 event driven interval records are generated for the interval, and data for the following, regularly scheduled interval is relevant to the most recent processor capacity change.

The default value of zero for this option results in only regularly scheduled interval records to be generated for each interval. A value greater than zero allows up to that many extra sets of type 30 and 89 records to be collected within one interval as the processor capacity is changed. If precise capacity measurements are needed for billing, the value of *nn* should match the number of processor capacity changes expected in a single interval.

**Value range:** 0-60

**Default:** 0

#### **MEMLIMIT(NOLIMIT|nnnnnM|nnnnnG|nnnnnT|nnnnnP)**

Specifies the default memlimit that will be used by jobs that do not establish a MEMLIMIT in their JCL. See *z/OS MVS JCL Reference*. MEMLIMIT is the limit on the use of virtual storage above 2 gigabytes for a single address space. NOLIMIT means that there is no limit on the use of virtual storage above 2 gigabytes.

MEMLIMIT values are defined with *nnnnnM* for megabytes, *nnnnnG* for gigabytes, *nnnnnT* for terabytes, or *nnnnnP* for petabytes. For example, to request 1275 gigabytes, specify MEMLIMIT(1275G), or to request 15 petabytes, specify MEMLIMIT(15P). The DISPLAY SMF,O command displays the current MEMLIMIT.

If MEMLIMIT is not specified in SMFPRMxx, the default value for this system default is 2G.

**Default:** 2G

For a complete description of MEMLIMIT, and the ways to define it, see *z/OS MVS Programming: Extended Addressability Guide*.

#### **NOBUFFS(MSG|HALT)**

- For data set recording environments, specifies the system action when the SMF address space has run out of buffer space.

##### **MSG**

Specifies that the system is to issue a message and continue processing; SMF data is lost until buffer storage is again available.

##### **HALT**

Specifies that the system is to enter a restartable wait state. HALT means that no SMF data is lost.

**Default:** MSG

- For log stream recording environments, specifies the system action when any one of the defined SMF log stream buffer areas run out of space. A separate buffer area is maintained for each SMF log stream and the option that is specified for this parameter applies to all log streams defined for SMF data collection. The specified option can be overridden for a particular log stream buffer if NOBUFFS is also specified as a subparameter on the LSNAME or DEFAULTLSNAME SMFPRMxx parameter options.



**MSG**

Specifies that the system is to issue message IFA786W and continue processing. Note that when the log stream buffer is full, data that is designated to be written to that log stream only will be lost until the log stream buffer storage becomes available.

**HALT**

Specifies that the system is to enter a restartable wait state when the log stream buffer is full. Specifying HALT prevents data loss when the log stream buffer is full.

**Default:** MSG

**PERMFIX(nnnnM)**

PERMFIX is an optional parameter when COMPRESS is specified. PERMFIX specifies the default amount of storage that SMF can keep permanently fixed for purposes of communicating with the zEDC Express feature. Storage used by the zEDC Express feature has to be page fixed; however, fixed pages are a constrained resource. Increasing this number can improve performance of SMF, but decreases the fixed storage available to the other applications. Decreasing this number can increase the fixed storage available to other applications, but might degrade SMF performance. PERMFIX can range from a minimum of 1 M to a maximum of 2 GB. Due to processing needs, even if this value is NOPERMFIX, SMF might use up to 2 MB of fixed storage for zEDC usage per log stream with a COMPRESS specification.

This is the global PERMFIX option and can be overridden by the PERMFIX subparameter of the LSNAM or DEFAULTLSNAME parameters.

**Default:** NOPERMFIX

**PROMPT(option) | NOPROMPT**

Specifies whether the selected SMF parameters are to be displayed on the system console at IPL time. The system can prompt the operator to supply a reason for the IPL or to modify the parmlib parameters. The *option* values are as follows:

**IPLR**

The operator is to supply a reason for the IPL.

**LIST**

The operator is prompted for possible modifications to the SMF parameters.

**ALL**

The operator is prompted for the IPL reason and can modify the SMF parameters.

NOPROMPT specifies that the parameters are not listed and the operator is not prompted unless there is a syntax error in the parmlib member.

**Note:** SMF parameter options cannot be changed using the SETSMF command when the PROMPT(IPLR) or NOPROMPT parameter options are specified. To authorize SETSMF regardless of the PROMPT or NOPROMPT parameter options, specify the AUTHSETSMF parameter.

**Default:** PROMPT (ALL)

**REC(PERM|ALL)**

Specifies whether information for type 17 SMF records (scratch data set status) is to be collected for temporary data sets. PERM specifies that type 17 SMF records are to be written only for non-temporary data sets. ALL specifies that type 17 SMF records are to be written for both temporary and non-temporary data sets.

**Note:** A temporary data set has a system-generated data set name either from DSN= &&datasetname or from the absence of any data set name. These system generated names are in the form SYSydd.Thhmmss....

**Default:** REC(PERM)

**RECORDING(DATASET|log stream)**

Specifies whether you want to write SMF records to MANx data sets or log streams. You can specify both SMF data sets and log streams in one SMFPRMxx member and then set either

RECORDING(DATASET) or RECORDING(LOGSTREAM) on the SETSMF command to switch between data set and log stream recording.

**Default:** RECORDING(DATASET)

**NORECSIGN | RECSIGN(HASH(SHA1|SHA256|SHA384|SHA512), SIGNATURE(RSA|ECDSA), TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded. This parameter applies to any log streams specified with the LSNAME or DEFAULTLSNAME parameters that do not have this keyword specified as a subparameter. If NORECSIGN is specified, SMF will not sign records. If RECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keyword must also be specified. The log streams must also have been defined with a MAXBUFSIZE of 65532. This is the global specification of the RECSIGN parameter, and its value takes effect for log streams where RECSIGN was not specified.

**Default:** None

**HASH(SHA1|SHA256|SHA384|SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. Valid values are SHA1, SHA256, SHA384, and SHA512.

**Default:** None

**SIGNATURE(RSA|ECDSA)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF command is issued to rectify the discrepancy. The valid values are RSA and ECDSA.

**Default:** None

**TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length and must be a valid token. See [z/OS Cryptographic Services System SSL Programming](#) for more information. If the token name and signature are not compatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see [Signing and validating SMF records in z/OS MVS System Management Facilities \(SMF\)](#).

**NOARECSIGN | ARECSIGN(HASH(SHA512), SIGNATURE(LI2),TOKENNAME(tokenname))**

Specifies whether SMF is to digitally sign the records that are being recorded using an alternate signature method. This parameter applies to any log streams specified with the LSNAME or DEFAULTLSNAME parameters that do not have this keyword specified as a subparameter. If NOARECSIGN is specified, SMF will not sign records using an alternate signature method. If ARECSIGN is specified, the HASH, TOKENNAME, and SIGNATURE keywords must also be specified. This is the global specification of the ARECSIGN parameter, and its value takes effect for log streams where ARECSIGN was not specified.

When the global ARECSIGN parameter is specified, the global RECSIGN parameter must also be specified.

**Default:** None

**HASH(SHA512)**

The HASH keyword specifies the hash-technique that ICSF will use to calculate the hash value for the digital signature. The only valid value is SHA512.

**Default:** None

**SIGNATURE(LI2)**

The SIGNATURE keyword specifies the signature type to be used in conjunction with the key specified above. If the signature type and token name are incompatible, IFA740E is issued and SMF will not sign records using an alternate signature until a SET SMF or SETSMF command is issued to rectify the discrepancy. The only valid value is LI2 (Dilithium). Cryptographic Support for z/OS V2R2 - V2R4 (HCR77D1) and IBM z15™ are required for Dilithium signature support.

**Default:** None

**TOKENNAME(tokenname)**

The TOKENNAME keyword specifies the token name to be used with the specified hashing technique. It must be 32 characters in length and must be a valid token. SMF only supports the use of Dilithium (6,5) Round 2, Dilithium(6,5) Round 3, Dilithium(8,7) Round 2, or Dilithium(8,7) Round 3 keys. See *z/OS Cryptographic Services System SSL Programming* for more information. If the token name and signature are not compatible, IFA740E is issued and SMF will not sign records until a SET SMF or SETSMF are issued to rectify the issue.

**Default:** None

For more information, see *Signing and validating SMF records in z/OS MVS System Management Facilities (SMF)*.

**SID { (xxxx) | (xxxx,SYSNAME(sysname)) | (xxxx,ser#[,ser#...]) | (xxxx,COMBIN(ser#[,ser#...])) }**

Specifies the system identifier that is used in all SMF records. It is also the substitution text for the &SID symbol (also known as the SID value). You can specify the &SID symbol only on the DSNNAME, LSNAME, and DEFAULTLSNAME parameters in this parmlib member. Do not specify &SID in other system definitions.

You can specify the SID value directly, or you can have the system select from several SID values, using the processor serial numbers or the SYSNAME value.

For example, suppose SMFPRMxx specifies:

```
SID(AAAA,012303)
SID(BBBB,012304)
```

When running on processor 012303, the system selects an SID value of AAAA. When running on processor 012304, the system selects an SID value of BBBB.

Suppose SMFPRMxx specifies:

```
SID(AAAA,SYSNAME(PRODSYS))
SID(BBBB,SYSNAME(TESTSYS))
```

When you IPL the system, the following is specified in IEASYSxx or IEASYMxx:

```
SYSNAME(TESTSYS)
```

In this case, the system selects BBBB as the SID value, because the name TESTSYS matches the name that is specified in IEASYSxx or IEASYMxx.

When defining the system identifier, you can use:

- System symbols and substrings of system symbols (the resolved substitution texts for the system symbols must contain 1–4 characters).

The system substitutes text for system symbols before it validates the syntax of the SID parameter. If errors occur in system symbol notation, the system prompts the operator to respecify the SID parameter. See [“What are system symbols?” on page 31](#) for information about the syntax of system symbols.

- The system name that is specified in IEASYSxx or IEASYMxx.
- Processor serial numbers that are used at IPL.
- Combinations of processor serial numbers that are used at IPL.

The preferred way to define the system identifier is to assign the identifier to a system symbol.

The formats for the SID are as follows:

**(xxxx)**

Specifies a 1–4 character string that the system is to use as the system identifier. The string may consist of numeric (0–9), alphabetic (A–Z), and national (# @ \$) characters, and periods (.).

**(xxxx,SYSNAME(sysname))**

Selects the specified system identifier when *sysname* matches the system name that is specified at IPL. See [“Step 3. Determine where to specify the system name” on page 41](#) for more information.

**(xxxx,ser#[,ser#...])**

Selects the system identifier by the processor identifier. The serial numbers must match exactly with the ID for the processors that are currently initialized. A serial number is six digits. If the system is running on a processor that supports more than 15 LPARs (for example, a z990 processor), the serial number format is *ppnnnn*, where *pp* is the LPAR identifier and *nnnn* is the CPU serial number. On a system that is running on a pre-z990 processor, or a processor that does not support more than 15 LPARs, the serial number format is *lpnnnn*, where *l* is the logical CPU address, *p* is the LPAR identifier, and *nnnn* is the CPU serial number.

**(xxxx,COMBIN(ser#[,ser#...]))**

Selects the system identifier by the processor identifier. If the set of currently initialized processors matches any possible combination of serial numbers that are specified in COMBIN, *xxxx* is used as the system identifier. A serial number is six digits. If the system is running on a processor that supports more than 15 LPARs (for example, a z990 processor), the serial number format is *ppnnnn*, where *pp* is the LPAR identifier and *nnnn* is the CPU serial number. On a system that is running on a pre-z990 processor, or a processor does not support more than 15 LPARs, the serial number format is *lpnnnn*, where *l* is the logical CPU address, *p* is the LPAR identifier, and *nnnn* is the CPU serial number.

Examples of syntax are as follows:

```
SID(SYSA)
SID(SYSB,006204,106204)
SID(SYSC,SYSNAME(SYS0001))
SID(&SYSNAME(1:4))
SID(SYSE,COMBIN(006204,106204,206204))
```

As the default, if the SID parameter is not specified, and no other SID specification is available, the system uses the four-digit processor model number.

It is possible for more than one SID specification to apply to one system. For example, if a SMFPRMxx member includes two SID specifications, SID(AAAA) and SID(BBBB,SYSNAME(SYSBBBB)) and the system is IPLed with a system name of SYSBBBB, both SID specifications apply. In this case, the precedence rules that are listed in [Table 64 on page 758](#) apply.

| Table 64. SID parameter syntax priority list |   |          |
|--|---|----------|
| Syntax                                       | Meaning   | Priority |
| SID(xxxx,ser#[,ser#...])                     | If the serial number <i>ser#</i> matches, the SID is <i>xxxx</i> .      | 1        |
| SID(xxxx,SYSNAME(sysname))                   | If the system name ( <i>sysname</i> ) matches, the SID is <i>xxxx</i> . | 1        |
| SID(xxxx,COMBIN(ser#[,ser#...]))             | If any of the listed serial numbers match, the SID is <i>xxxx</i> .     | 1        |
| SID(xxxx)                                    | The SID is <i>xxxx</i> .  | 2        |
| {Default}                                    | SID=four-digit processor model number.                                  | 3        |

The lower the number, the higher the priority. For syntax with similar priority numbers, the first occurrence in the SMFPRMxx parmlib member of a matching SID specification becomes the system identifier.

**Note:** These precedence rules do not apply if the SID parameter is modified using the PROMPT(LIST) or PROMPT(ALL) option. If the SID parameter is modified by using the PROMPT option, the SID value

changes if the modified SID specification applies, regardless of whether the previous SID syntax had a higher priority than the modified SID syntax.

Assumption: IPL the system as a multiprocessor (006204,106204) with SYSNAME=SYSSYSD.

|   |                   |                                       |
|---|-------------------|---------------------------------------|
| If SMFPRMAA specified at IPL<br>contains:<br>SID(SYSA)                                  | SID value<br>SYSA | Option Display (D SMF,0)<br>SID(SYSA) |
| If SMFPRMBB specified at IPL<br>contains:<br>SID(SYSB,006204,106204)                    | SYSB              | SID(SYSB,006204,106204)               |
| If SMFPRMCC specified at IPL<br>contains:<br>SID(SYSC,SYSNAME(SYSSYSD))                 | SYSC              | SID(SYSC,SYSNAME(SYSSYSD))            |
| If SMFPRMDD specified at IPL<br>contains:<br>SID(&SYSNAME(4:4))                         | SYSD              | SID(SYSD)                             |
| If SMFPRMEE specified at IPL<br>contains:<br>SID(SYSE,COMBIN(006204,<br>106204,206204)) | SYSE              | SID(SYSE,006204,106204)               |

**SMFDLEXIT**(**{USER1(exit-name[,exit-name,...]) | NOUSER1},**  
**{USER2(IRRADU00[,exit-name,...]) | NOUSER2},**  
**{USER3(IRRADU86[,exit name,...]) | NOUSER3},**  
**{USER4(exit-name[,exit name,...]) | NOUSER4},**  
**{USER5(exit-name[,exit name,...]) | NOUSER5}**)  
**SMFDPEXIT**(**{USER1(exit-name[,exit name,...]) | NOUSER1},**  
**{USER2(IRRADU00[,exit-name,...]) | NOUSER2},**  
**{USER3(IRRADU86[,exit-name,...]) | NOUSER3},**  
**{USER4(exit-name[,exit-name,...]) | NOUSER4},**  
**{USER5(exit-name[,exit-name,...]) | NOUSER5}**)

Specifies whether you want to specify valid exits for either the IFASMF DL program (through the SMFDLEXIT keyword) or the IFASMF DP program (through the SMFDPEXIT keyword). You can use the USER1, USER2, USER3, USER4, or USER5 parameters on either keyword to specify the exits. If a valid exit point does not exist, use the NOUSER1, NOUSER2, NOUSER3, NOUSER4, or NOUSER5 parameters. The NOUSERx parameters are optional for those exit points that do not have default exit names defined. For USER1, USER2, USER3, USER4, or USER5, you can specify any combination of valid exit names for both SMFDLEXIT or SMFDPEXIT.

For more information about the exits and their usage, see [Specifying parameters for the SMF log stream dump program](#) and [Specifying parameters for the SMF data set dump program in z/OS MVS System Management Facilities \(SMF\)](#).

#### Defaults:

- SMFDLEXIT(USER2(IRRADU00),USER3(IRRADU86))
- SMFDPEXIT(USER2(IRRADU00),USER3(IRRADU86))

#### **SMF30COUNT | NOSMF30COUNT**

Specifies whether the SMF30CDS section should be produced in any SMF Type 30 records. The SMF30CDS section contains data that is derived from the z/Architecture CPU Counter Facility. To receive non-zero data in the section, the Hardware Instrumentation Services (HIS) component must be active and collecting the basic counter set. For more information, see [Starting, configuring, and stopping hardware event collection in z/OS MVS System Commands](#).

SMF type 30 instruction counts may include instructions from z/OS events that are not attributable to the job. The instruction counts from these z/OS events can significantly impact the SMF type 30 instruction counts.

**Default:** NOSMF30COUNT

**STATUS(option) | NOSTATUS**

Specifies the time interval between creations of the type 23 SMF record (SMF status).

**Default:** STATUS

The *option* values are as follows:

**hhmmss**

Specifies the length of the time interval in *hhmmss* format, where *hh* is the hours, *mm* is the minutes, and *ss* is the seconds.

**Value range:** 000001-240000

**Default:** (010000), which indicates a one-hour interval.

**SMF[,SYNC|NOSYNC]**

Specifies that SMF is to use the global interval value (specified with the INTVAL parameter) as the time interval. Specify SYNC or NOSYNC to indicate whether SMF should synchronize the creation of type 23 records with the hour (using the global synchronization value that is specified with the SYNCVAL parameter).

**Default:** NOSYNC

**LASTDS(MSG|HALT)**

For SMF data set recording, specifies the system action when the last available SMF data set is filled and there are no more available for SMF use.

This parameter applies to SMF data set recording only; it does not apply to SMF log stream recording. If you are using SMF log stream recording, LASTDS(HALT) is ignored. When you specify data sets in SMFPRMxx, SMF issues messages that pertain to LASTDS(MSG) depending on the status of the data sets during SMF initialization.

**MSG**

Specifies that the system is to issue a message and continue processing; SMF data is buffered until an SMF data set is available. If SMF runs out of buffers, there might be a loss of data.

**HALT**

Specifies that the system is to enter a restartable wait state.

**Default:** MSG

**MULCFUNC | NOMULCFUNC**

Specifies whether users of the IFAUSAGE service that registered specifying SCOPE=FUNCTION must use IFAUSAGE with the REQUEST=FUNCTIONxxx parameters.

MULCFUNC indicates that users of the IFAUSAGE service that registered specifying SCOPE=FUNCTION must use IFAUSAGE with the REQUEST=FUNCTIONxxx parameters. SMF is to set the CVTMULFN indicator OFF.

NOMULCFUNC indicates that users of the IFAUSAGE service that registered specifying SCOPE=FUNCTION do not need to use IFAUSAGE with the REQUEST=FUNCTIONxxx parameters. SMF is to set the CVTMULFN indicator ON. Any measured usage program using SCOPE=FUNCTION, such as DB2, can record only its registration data only and omit recording the usage data.

**Default:** MULCFUNC

**SUBSYS(name,options)**

Specifies the SMF recording options and exits for particular subsystems.

**name**

Represents the one to four character name of a subsystem. The first character must be alphabetic or national (#, @, or \$), and the remaining characters can be either alphanumeric or national characters.

**options**

Represents the valid options for SUBSYS. The options are as follows:

**TYPE**

SMF record types and subtypes to be collected.

**Note:**

- A specified value of 126 is ignored by the system.
- The specified TYPE or NOTYPE parameter values must resolve to at least one non 126 type value.
- TYPE or NOTYPE parameter options that are specified after the first TYPE or NOTYPE are ignored.

**INTERVAL**

Time intervals between recording

**EXITS**

Exits that are to receive control at various points in SMF processing

**DETAIL**

The level of SMF data collection for TSO users and started tasks

The following information describes the *options* in greater detail.

**TYPE{aa,bb(cc) } NOTYPE ({aa,bb:zz }) {aa,dd(cc:yy),...} {aa,bb(cc,...)}**

TYPE specifies the SMF record types and subtypes that SMF is to collect. aa, bb, dd, and zz are the decimal notations for each SMF record type. cc and yy are the decimal notations for the SMF record subtypes. A colon indicates the range of SMF record types (bb through zz) to be recorded or the range of subtypes (cc through yy for SMF record type dd) to be recorded. You can select SMF record subtypes on all SMF record types, as well as on user records.

NOTYPE specifies that SMF is to collect all SMF record types and subtypes except those specified. aa, bb, and zz are the decimal notations for each SMF record type. cc and yy are the decimal notations for each subtype. A colon indicates the range of SMF record types (bb through zz) or the range of subtypes (cc through yy for SMF record dd) that are not to be recorded.

**Value range:**

- 0-2047 for SMF record types
- 0-32767 for subtypes - subtype selection applies only to SMF data set recording.

**Default:** TYPE (0:255)

**Subtype:** When not specified, all subtypes are assumed to be collected for the specified type.

**NOINTERVAL | INTERVAL(option)**

NOINTERVAL specifies that no interval recording takes place. INTERVAL requests interval recording and specifies the length of the recording interval. At the end of each interval, SMF generates a type 30 record. For TSO/E users, SMF can also generate a type 32 record.

Interval recording allows the user to preserve accounting data for long-running jobs or TSO/E sessions. Because SMF records accounting data for each job or task each time the interval expires, the data is not completely lost if there is a system failure.

**Default:** NOINTERVAL

The *option* values are as follows:

***hhmmss***

Specifies the length of the time interval in *hhmmss* format, where *hh* is the hours, *mm* is the minutes, and *ss* is the seconds.

**Value range:** 000001-240000

**Default:** Not applicable

**SMF[,SYNC|NOSYNC]**

Specifies that SMF is to use the global interval value (specified with the INTVAL keyword) as the time interval. Specify SYNC or NOSYNC to indicate whether SMF is to synchronize the

creation of type 30 and 32 records with the hour (based on the global synchronization value specified with the SYNCVAL keyword).

**Default:** NOSYNC

### **EXITS(exitname,exitname,...) | NOEXITS**

EXITS specifies which SMF exits are to be invoked. If an exit is not specified, it is not invoked. If this parameter is not specified, SMF behaves as if this parameter is specified with all 14 exits listed here and all SMF system exits are invoked.

NOEXITS specifies that SMF exits are not invoked.

You can specify exits on the SYS and SUBSYS statements of SMFPRMxx. Your choice of SYS or SUBSYS depends on the scope of work you want to influence (system-wide or subsystem-wide), as follows:

- On the SYS parameter, specify the exits that are to affect work throughout the system, regardless of the subsystem that processes the work.
- On the SUBSYS parameter, specify the exits that are to affect work that is processed by a particular SMF-defined subsystem (JES2, JES3, STC, ASCH, or TSO) and no other subsystem-specific exit points are to be taken.

The SUBSYS specification overrides the SYS specification. Use SUBSYS to make exceptions to your SYS specification for particular subsystems.

Some SMF exits are not called for particular subsystems. [Table 66 on page 766](#) shows which exits can be called for subsystems that are specified on the SUBSYS statement.

*Table 65. Which SMF exits are called for this subsystem?*

| Exit point | SUBSYS value     |      |     |                  |     |
|------------|------------------|------|-----|------------------|-----|
|            | JES2             | JES3 | STC | ASCH             | TSO |
| IEFACTRT   | Yes              | Yes  | Yes | Yes              | Yes |
| IEFUAV     | No               | No   | No  | Yes              | No  |
| IEFUJI     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFUJP     | Yes <sup>2</sup> | No   | Yes | No               | No  |
| IEFUJV     | Yes              | Yes  | Yes | Yes <sup>1</sup> | Yes |
| IEFUSI     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFUSO     | Yes <sup>2</sup> | No   | Yes | No               | No  |
| IEFUTL     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFU29     | No               | No   | Yes | No               | No  |
| IEFU29L    | No               | No   | No  | No               | No  |
| IEFU83     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFU84     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFU85     | Yes              | Yes  | Yes | Yes              | Yes |
| IEFU86     | Yes              | Yes  | Yes | Yes              | Yes |

#### **Footnotes:**

1. IBM suggests that you use IEFUAV instead of IEFUJV to validate accounting information for APPC/MVS transaction programs. For more information, see [z/OS MVS Installation Exits](#).
2. The installation can cause this exit to be bypassed on a job class basis, through the JOBCLASS(v) initialization statement. For more information about the JOBCLASS(v) statement, see [z/OS JES2 Initialization and Tuning Reference](#).

For more information, refer to [“Specifying SMF exits to the dynamic exits facility” on page 767](#).



**NODETAIL | DETAIL**

Specifies the level of SMF data collection for TSO and STC; specifying DETAIL or NODETAIL has no effect on any other types of work.

For TSO, when DETAIL is specified, type 32 SMF records contain the total count of each TSO/E command used, CPU time under TCBs and SRBs, and the total number of TGETs, TPUTs, EXCPs, and transactions. When NODETAIL is specified for TSO, type 32 SMF records contain only the total count of each TSO/E command used.

NODETAIL is enforced for the master address space.

For STC, specifying DETAIL has no effect. Specifying NODETAIL has an effect only if INTERVAL is also specified. Specify NODETAIL and INTERVAL to exclude the EXCP sections from SMF type 30 subtype 4 and subtype 5 records collected for started tasks. Otherwise, the EXCP sections for SMF type 30 subtype 4 and subtype 5 records are included. For long running tasks, excluding EXCP sections from SMF type 30 subtype 4 and subtype 5 records can greatly reduce:

- The amount of storage that is required to hold SMF records in memory.
- The amount of DASD space that is required to write the records out to data sets.
- The amount of CPU used at step end and job end.

**Default:** NODETAIL

These options are the same as those you can specify for the SYS parameter. When you specify SUBSYS, any option you omit from the SUBSYS parameter defaults to the value specified for that option on the SYS parameter. If you omit SUBSYS, SMF uses the values for all of the options on the corresponding SYS parameter. For the EXIT option, if you omit SUBSYS an exit point name is created for any exit that is specified on the SYS parameter.

Data can be recorded for up to eight subsystems in any IPL, including those specified at IPL and through subsequent SET commands. When the limit is reached, no additional subsystems can be added. The SMF-defined subsystems are JES2, JES3, STC, ASCH, and TSO. Other valid subsystems include IBM-supplied (such as OMVS), vendor-supplied, and user-defined subsystems. The system assigns work to these subsystems as follows:

- Batch jobs are assigned to the job entry subsystem (JES2 or JES3) that submitted the work to the system.
- Work started from the operator console is assigned to the STC subsystem.
- APPC/MVS transaction programs initiated by the IBM-supplied APPC/MVS transaction scheduler are assigned to the ASCH subsystem.
- Logged-on TSO/E users are assigned to the TSO subsystem.

**Default:** See the description of SYS (options).

**JWT(hhmm)**

Specifies the maximum amount of time that a job or TSO/E user address space is allowed to wait continuously, where *hh* is the amount of real time in hours and *mm* is in minutes. Continuous wait time is defined as time spent waiting while the application program is in control. For example, the time required to recall a data set from HSM migration levels 1 or 2, or the time required to mount a tape is counted towards the job's continuous wait time if the allocation of the data set is dynamic (that is, issued while the program was running), while the time required for those activities will not be counted towards the job's continuous wait time if the allocation is static (that is, for a DD statement).

**Note:** When specified, the SWT and TWT values will override the JWT value for started tasks and TSO/E address spaces, respectively.

If the specified time limit expires, the system passes control to the SMF time limit exit, IEFUTL (if active). IEFUTL either extends the wait time or allows the system to end the job or TSO/E user address space abnormally.

**Notes:**

- If TIME=1440 is coded on the JOB or EXEC JCL statement, or if it is defaulted by the JES class attribute of TIME=1440, IEFUTL is not invoked for that job.
- IEAVRTIO checks the JWT (job wait time) status every 90 seconds. A delay in the action taken might occur during this interval.

**Value range:** 0001-2400

**Default:** JWT (0010), which indicates 10 minutes.

### SWT(*hhmm*)

Specifies the maximum amount of time that a started task address space is allowed to wait continuously, where *hh* is the amount of real time in hours and *mm* is in minutes. When SWT is specified, its time value overrides the time value that is specified or defaulted to by the JWT parameter, for started tasks only. Continuous wait time is defined as time spent waiting while the application program is in control. For example, the time required to recall a data set from HSM migration levels 1 or 2, or the time required to mount a tape is counted towards the job's continuous wait time if the allocation of the data set is dynamic (that is, issued while the program was running), while the time required for those activities will not be counted towards the job's continuous wait time if the allocation is static (that is, for a DD statement).

If the specified time limit expires, the system passes control to the SMF time limit exit, IEFUTL (if active). IEFUTL either extends the wait time or allows the system to end started task address space abnormally.

#### Notes:

- If TIME=1440 is coded on the JOB or EXEC JCL statement, or if it is defaulted by the JES class attribute of TIME=1440, IEFUTL is not invoked for that job.
- IEAVRTIO checks the SWT (STC wait time) status every 90 seconds. A delay in the action taken might occur during this interval.

**Value range:** 0001-2400

**Default:** When SWT is not specified, the value that is specified for JWT is used for determining when to time out started task address spaces.

### TWT(*hhmm*)

Specifies the maximum amount of time that a TSO/E user address space is allowed to wait continuously, where *hh* is the amount of real time in hours and *mm* is in minutes. When TWT is specified, its time value overrides the time value that is specified or defaulted to by the JWT parameter, for TSO/E user address spaces only. Continuous wait time is defined as time spent waiting while the application program is in control. For example, the time required to recall a data set from HSM migration levels 1 or 2, or the time required to mount a tape is counted towards the job's continuous wait time if the allocation of the data set is dynamic (that is, issued while the program was running), while the time required for those activities will not be counted towards the job's continuous wait time if the allocation is static (that is, for a DD statement).

If the specified time limit expires, the system passes control to the SMF time limit exit, IEFUTL (if active). IEFUTL either extends the wait time or allows the system to end the TSO/E user address space abnormally.

#### Notes:

- If TIME=1440 is coded on the JOB or EXEC JCL statement, or if it is defaulted by the JES class attribute of TIME=1440, IEFUTL is not invoked for that job.
- IEAVRTIO checks the TWT (TSO wait time) status every 90 seconds. A delay in the action taken might occur during this interval.

**Value range:** 0001-2400

**Default:** When TWT is not specified, the value for JWT is used for determining when to time out TSO/E user address spaces.

**SYNCVAL(mm)**

Specifies the two-digit global synchronization value (in minutes) for the SMF global recording interval, synchronizing the recording interval with the end of the hour on the TOD clock. For example, if you specify SYNCVAL(15), the global recording interval is synchronized to 15 minutes past the hour. If you also specify INTVAL(30), SMF global recording intervals end at 15 minutes and 45 minutes past the hour.

When you specify the SYNCVAL parameter for interval synchronization, specify the global interval value with the INTVAL parameter (unless you accept the default for INTVAL).

**Value range:** 00-59

**Default:** 00

**Note:** Only SMF records can be controlled by the INTVAL and SYNCVAL parameters. The INTVAL and SYNCVAL parameters can influence other record types, such as when activated by the RMF Monitor I SYNC(SMF) option to write record types 70 through 79.

**SYS(options)**

Specifies the SMF recording options and exits for the entire system. The *options* are as follows; if the same *option* is specified more than once, the system uses the first valid operator reply.

**TYPE**

SMF record types and subtypes to be collected.

**Note:**

- A specified value of 126 is ignored by the system.
- The specified TYPE or NOTYPE parameter values must resolve to at least one non 126 type value.
- TYPE or NOTYPE parameter options that are specified after the first TYPE or NOTYPE are ignored.

**INTERVAL**

Time intervals between recording.

**EXITS**

Exits that are to receive control at various points in SMF processing.

**DETAIL**

The level of SMF data collection for TSO users and started tasks.

The following information describes the *options* in greater detail.

**TYPE{aa,bb(cc) } NOTYPE ({aa,bb:zz }) {aa,dd(cc:yy),...} {aa,bb(cc,...)}**

TYPE specifies the SMF record types and subtypes that SMF is to collect. aa, bb, dd, and zz are the decimal notations for each SMF record type. cc and yy are the decimal notations for the SMF record subtypes. A colon indicates the range of SMF record types (bb through zz) to be recorded or the range of subtypes (cc through yy for SMF record type dd) to be recorded. You can select SMF record subtypes on all SMF record types, as well as on user records.

NOTYPE specifies that SMF is to collect all SMF record types and subtypes except those specified. aa, bb, and zz are the decimal notations for each SMF record type. cc and yy are the decimal notations for each subtype. A colon indicates the range of SMF record types (bb through zz) or the range of subtypes (cc through yy for SMF record dd) that are not to be recorded.

**Value range:**

- 0-2047 for SMF record types.
- 0-32767 for subtypes - subtype selection applies only to SMF data set recording.

**Default:** TYPE (0:255)

**Subtype:** When not specified, all subtypes are assumed to be collected for the specified type.

**NOINTERVAL | INTERVAL(option)**

NOINTERVAL specifies that no interval recording takes place. INTERVAL requests interval recording and specifies the length of the recording interval. At the end of each interval, SMF generates a type 30 record. For TSO/E users, SMF can also generate a type 32 record.

Interval recording allows the user to preserve accounting data for long-running jobs or TSO/E sessions. Because SMF records accounting data for each job or task each time the interval expires, the data is not completely lost if there is a system failure.

**Default:** NOINTERVAL

The *option* values are as follows:

**hhmmss**

Specifies the length of the time interval in *hhmmss* format, where *hh* is the hours, *mm* is the minutes, and *ss* is the seconds.

**Value range:** 000001-240000

**Default:** Not applicable

**SMF[,SYNC|NOSYNC]**

Specifies that SMF is to use the global interval value (specified with the INTVAL keyword) as the time interval. Specify SYNC or NOSYNC to indicate whether SMF is to synchronize the creation of type 30 and 32 records with the hour (based on the global synchronization value specified with the SYNCVAL keyword).

**Default:** NOSYNC

**EXITS(exitname,exitname,...) | NOEXITS**

EXITS specifies which SMF exits are to be invoked. If an exit is not specified, it is not invoked. If this parameter is not specified, SMF behaves as if this parameter is specified with all 14 exits listed here and all SMF system exits are invoked.

NOEXITS specifies that SMF exits are not invoked.

You can specify exits on the SYS and SUBSYS statements of SMFPRMxx. Your choice of SYS or SUBSYS depends on the scope of work you want to influence (system-wide or subsystem-wide), as follows:

- On the SYS parameter, specify the exits that are to affect work throughout the system, regardless of the subsystem that processes the work.
- On the SUBSYS parameter, specify the exits that are to affect work that is processed by a particular SMF-defined subsystem (JES2, JES3, STC, ASCH, or TSO) and no other subsystem-specific exit points are to be taken.

The SUBSYS specification overrides the SYS specification. Use SUBSYS to make exceptions to your SYS specification for particular subsystems.

Some SMF exits are not called for particular subsystems. [Table 66 on page 766](#) shows which exits can be called for subsystems that are specified on the SUBSYS statement.

| Table 66. Which SMF exits are called for this subsystem? |                  |      |     |                  |     |
|--|------------------|------|-----|------------------|-----|
| Exit point   | SUBSYS value     |      |     |                  |     |
|  | JES2             | JES3 | STC | ASCH             | TSO |
| IEFACTRT   | Yes              | Yes  | Yes | Yes              | Yes |
| IEFUAV   | No               | No   | No  | Yes              | No  |
| IEFUJI   | Yes              | Yes  | Yes | Yes              | Yes |
| IEFUJP   | Yes <sup>2</sup> | No   | Yes | No               | No  |
| IEFUJV   | Yes              | Yes  | Yes | Yes <sup>1</sup> | Yes |
| IEFUSI   | Yes              | Yes  | Yes | Yes              | Yes |

Table 66. Which SMF exits are called for this subsystem? (continued)

| Exit point | SUBSYS value     |      |     |      |     |
|------------|------------------|------|-----|------|-----|
|            | JES2             | JES3 | STC | ASCH | TSO |
| IEFUSO     | Yes <sup>2</sup> | No   | Yes | No   | No  |
| IEFUTL     | Yes              | Yes  | Yes | Yes  | Yes |
| IEFU29     | No               | No   | Yes | No   | No  |
| IEFU29L    | No               | No   | No  | No   | No  |
| IEFU83     | Yes              | Yes  | Yes | Yes  | Yes |
| IEFU84     | Yes              | Yes  | Yes | Yes  | Yes |
| IEFU85     | Yes              | Yes  | Yes | Yes  | Yes |
| IEFU86     | Yes              | Yes  | Yes | Yes  | Yes |

**Footnotes:**

1. IBM suggests that you use IEFUAV instead of IEFUJV to validate accounting information for APPC/MVS transaction programs. For more information, see [z/OS MVS Installation Exits](#).
2. The installation can cause this exit to be bypassed on a job class basis, through the JOBCLASS(v) initialization statement. For more information about the JOBCLASS(v) statement, see [z/OS JES2 Initialization and Tuning Reference](#).

For more information, refer to “[Specifying SMF exits to the dynamic exits facility](#)” on page 767.

#### **NODETAIL | DETAIL**

Specifies the level of SMF data collection for TSO and STC; specifying DETAIL or NODETAIL has no effect on any other types of work.

For TSO, when DETAIL is specified, type 32 SMF records contain the total count of each TSO/E command used, CPU time under TCBs and SRBs, and the total number of TGETs, TPUTs, EXCPs, and transactions. When NODETAIL is specified for TSO, type 32 SMF records contain only the total count of each TSO/E command used.

NODETAIL is enforced for the master address space.

For STC, specifying DETAIL has no effect. Specifying NODETAIL has an effect only if INTERVAL is also specified. Specify NODETAIL and INTERVAL to exclude the EXCP sections from SMF type 30 subtype 4 and subtype 5 records collected for started tasks. Otherwise, the EXCP sections for SMF type 30 subtype 4 and subtype 5 records are included. For long running tasks, excluding EXCP sections from SMF type 30 subtype 4 and subtype 5 records can greatly reduce:

- The amount of storage that is required to hold SMF records in memory.
- The amount of DASD space that is required to write the records out to data sets.
- The amount of CPU used at step end and job end.

**Default:** NODETAIL

### **Specifying SMF exits to the dynamic exits facility**

IBM has defined the SMF exits to the dynamic exit facility. Through the PROGxx parmlib member, you can associate multiple exit routines with SMF exits, at IPL or while the system is running.

To define SMF exits to the dynamic exits facility, you must specify the exits in both PROGxx and SMFPRMxx. The system does not call SMF exits that are defined to PROGxx only. (If you do not plan to take advantage of the dynamic exits facility, you need only define SMF exits in SMFPRMxx).

As the default, all exits are invoked.

With the PROGxx parmlib member, you can specify installation exits and control their use. Through PROGxx, you can associate multiple exit routines with exits, at IPL or while the system is running. IBM

suggests that you use PROGxx in addition to SMFPRMxx to specify exits, whether or not you want to take advantage of these functions.

SMF exits should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when defining SMF exits in PROGxx, as the system will not be able to load these exits when restarting SMF.

The following example shows how you can specify SMF exits in a PROGxx parmlib member. If you specify the following in SMFPRMxx,

```
SYS(...EXITS(IEFU83,IEFU84,IEFUJI)...)  
SUBSYS(STC,...EXITS(IEFU83,IEFU85)...)  
SUBSYS(TSO,...)  
SUBSYS(JES3,...EXITS(IEFUJI)...)
```

You would add the following to get the equivalent processing in PROGxx:

```
EXIT ADD EXITNAME(SYS.IEFU83) MODNAME(IEFU83)  
EXIT ADD EXITNAME(SYS.IEFU84) MODNAME(IEFU84)  
EXIT ADD EXITNAME(SYS.IEFUJI) MODNAME(IEFUJI)  
EXIT ADD EXITNAME(SYSSTC.IEFU83) MODNAME(IEFU83)  
EXIT ADD EXITNAME(SYSSTC.IEFU85) MODNAME(IEFU85)  
EXIT ADD EXITNAME(SYSJES3.IEFUJI) MODNAME(IEFUJI)
```

- Because the TSO SUBSYS statement did not specify the EXITS parameter, all of the exits that are defined within the SYS statement are eligible to be called for the TSO subsystem.
- Because IEFU83 was defined in both the SYS statement and the STC SUBSYS statement, it needs to be specified on matching EXIT ADD statements for SYS and SYSSTC.
- Because IEFUJI was defined in both the SYS statement and the JES3 SUBSYS statement, it needs to be specified on matching EXIT ADD statements for SYS and SYSJES3.

When you associate new exit routines with SMF exits through PROGxx or the SETPROG command, you must use the following naming conventions:

- For exits listed on the EXITS keyword of the SYS statement in SMFPRMxx, each exit has the name SYS.yyyy (where yyyy is one of the exits listed).
- For exits listed on the EXITS keyword of the SUBSYS statement of SMFPRMxx, each exit has the name SYSxxxx.yyyy (xxxx is the name of the subsystem and yyyy is one of the exits listed).
- Where a SYS statement is coded that does not contain an EXITS keyword, each exit has the name SYS.yyyy (yyyy is one of the exits listed). The list of exits are all SMF system exits.
- Where a SUBSYS statement is coded that does not contain an EXITS keyword, each exit has the name SYSxxxx.yyyy (xxxx is the name of the subsystem and yyyy is one of the exits listed). The list of exits are propagated from the EXITS keyword in the SYS statement. If the EXITS keyword is not coded in the SYS statement as well, the list of exits are all SMF system exits.

For information about using PROGxx to control the use of exits and exit routines, see [Chapter 81, “PROGxx \(authorized program list, exits, LNKST sets and LPA\),”](#) on page 685.

## Using SMFPRMxx parameters

See [Using SMFPRMxx parameters in z/OS MVS System Management Facilities \(SMF\)](#).

## Chapter 85. TSOKEY00 (TSO/VTAM time sharing parameters)

TSOKEY00 contains TSO/VTAM time sharing parameters. Starting TSO/VTAM time sharing activates the terminal control address space (TCAS). The function of TCAS is to accept TSO/VTAM logon requests and to create an address space for each TSO/E user. TCAS builds a TCAS table (TCAST) and inserts the parameter values into it. The VTAM terminal I/O coordinator (VTIOC), which is the interface between TSO/E and VTAM, uses these values to control the time sharing buffers, the maximum number of users, and other operational variables.

TSOKEY00 or an alternate member name may be specified by using the MEMBER operand or the keyword operand (overriding keyword MBR) of the operator START command, or by coding it into the PARMLIB DD statement of the cataloged procedure evoked by the START command. If a member name is not specified but a parmlib name is specified (on the PARMLIB DD statement), the system defaults to TSOKEY00. If neither a member name nor a parmlib name is specified, default values in the TCAS program are used.

If, during TCAS initialization, an I/O error occurs after some of the values have been read from parmlib, the default values in the TCAS program supply the remaining parameter values for the TCAS table.

If the specified value for a parameter does not fall within the value range, the default value is used.

### Parameter in IEASYSxx (or supplied by the operator)

None

### Syntax rules for TSOKEY00

The following rules apply to the creation of the TSO/VTAM time sharing parmlib member:

- For each record, columns 1 through 71 are valid for data. Columns 72 through 80 are ignored.
- Data may be continued from one record to another by ending a record with a comma and blank in contiguous data columns, then inserting data in any column of the data area on the next record.
- A parameter must be complete in a record. It may not cross record boundaries. It may not be repeated.
- A comma must separate adjacent keywords.
- Invalid or misspelled parameters are ignored. Default values are substituted, and are listed on the device specified by the PRINTOUT DD statement of the procedure used to start TSO/VTAM time sharing, or on the device specified by the device name operand of the operator START command.

### IBM-supplied default for TSOKEY00

The default values are internal constants in the TCAS program.

```
USERMAX=40, RECONLIM=3, BUFRSIZE=132, HIBFREXT=48000,
LOBFREXT=24000, CHNLEN=4, SCRFSIZE=480, ENGTRANS=BASE,
ACBPW=password, (optional - no default)
MODE=NOBREAK, MODESW=NO,
RCFBDUMP=xyxyz, (optional - no default)
CONFTEXT=YES,
GNAME=gentso, (optional - no default)
BASENAME=TSO,, CODEPAGE=NO
```

**Note:** All parameters in the TSOKEY00 parmlib member must precede any comments; otherwise, the parameters will be ignored. For example:

```

USERMAX=100,
RECONLIM=3,
BUFRSIZE=132,
HIBFREXT=6600,
LOBFREXT=3300,
CHNLEN=4,
SCRSIZE=1920
ENGTRANS=BASE
/* CHANGE LOG
/*
/* DATE      WHO      WHAT
/* 12/04/09 MMB      INCREASED USERMAX FROM 70 TO 100
/* 11/02/09 MMB      INCREASED USERMAX FROM 50 TO 70
/* 09/26/11 KIB      ADD ENGTRANS VALUE
/*

```

## Statements and parameters for TSOKEY00

The TSO/VTAM time sharing parameters are as follows:

### ACBPW

Specifies the optional password that is associated with all TSO/VTAM ACBs. If a password is specified on the PRTCT parameter of VTAM's APPL definition statement, ACBPW must be specified.

To prevent unauthorized disclosure of the ACB password when the CBPW keyword is specified, take the following steps:

- Place the TSOKEY00 member in a password protected data set that is compatible with SYS1.PARMLIB (for example SYS1.VTAMLST).
- Modify the parmlib DD statement in the TSO/VTAM start procedure to refer to the password protected data set, as show in the following example:

```
//PARMLIB DD DSN=SYS1.VTAMLST(&MBR),DISP=SHR,FREE=CLOSE
```

**Value range:** Any 1 - 8 EBCDIC character.

**Default:** None.

### BASENAME

Specifies a 1 - 4 character prefix to be used for the ACBNAME operand in the VTAM application program major node. As an example, if you specify BASENAME=tttt, you would use the names tttt0001, tttt0002, tttt0003, and so forth. See the [z/OS Communications Server: SNA Network Implementation Guide](#) for an example of how to use BASENAME.

**Value range:** Any 1 - 4 EBCDIC characters, following the VTAM naming requirement that is specified in the [z/OS Communications Server: SNA Resource Definition Reference](#).

**Default:** TSO

### BUFRSIZE

Specifies the size in bytes of a VTIOC buffer. Input and output data smaller than the BUFRSIZE value uses cells equal to the BUFRSIZE value. Input and output data larger than the BUFRSIZE value is assigned to dynamically allocated buffers (allocated by the GETMAIN macro) equal to the data size.

**Value range:** 4 - 3016

**Default:** 132

### CHNLEN

Specifies for output the number of request units (RUs) in each RU chain for IBM 3767 and IBM 3770 terminals. This value determines the maximum size of a chain and, therefore, the maximum amount of data that can be sent to the terminal in one chain (CHNLEN x 256=data transmitted). This value also determines the maximum amount of data that is purged when the CANCEL key is pressed to stop printing of outbound (host-to-terminal) data.



The CHNLEN value is associated with the values specified on the PACING operand of the LU macro during network control program definition, and on the VPACING operand of the LU or PU macro during VTAM definition. Use the CHNLEN default value (4) if the PACING and VPACING default values are used. Otherwise, calculate CHNLEN by using the formula  $(2pn-2pm)+(2vn-2vm)$ , where  $pn$  and  $pm$  are the PACING  $n$  and  $m$  values, and  $vn$  and  $vm$  are the VPACING  $n$  and  $m$  values. If more than one network control program is used with TSO/VTAM time sharing, the smallest value that is found when calculating the CHNLEN value should be used. Otherwise, the network control program could enter slowdown mode.

**Value range:** 1 - 10

**Default:** 4

### CODEPAGE (YES | NO)

Specifies to obtain the code page (CGCSGID) information for a TSO session from the terminal or the emulator. YES indicates that TSO/VTAM queries the terminal or the emulator to obtain the code page information.

**Default:** NO

### CONFTEXT (YES | NO)

Specifies whether the buffer output is to be confidential. YES indicates that the buffer output is to be confidential and, as such, not traceable; the data in the VTAM buffers is overwritten with zeros immediately after it is sent to the terminal.

**Default:** YES

### ENGTRANS

Specifies the type of English language translation that is to be performed when the TPUT EDIT macro is used to write to terminals that support the coded graphic set global identifier (CGCSGID) X'02B90025'. (For details about TPUT, see [z/OS TSO/E Programming Services](#).) You can specify one of the following values:

#### BASE

Base English translation.

#### EXTENDED

Extended English translation, as described in *3174 Character Set Reference*, GA27-3831.

#### NONE

Translation is not performed.

**Value range:** BASE, EXTENDED, or NONE

**Default:** BASE

### GNAME

Specifies a generic name by which one or more TSO/VTAM systems in a sysplex can be referenced. A generic name can also be specified on the START command to activate TSO/VTAM. If a generic name is not specified in TSOKEY00, or on the START command, then no generic name is used. If a generic name is used, TSO/VTAM registers its generic name by issuing the SETLOGON GNAMEADD macro instruction.

For example, three TSO/VTAM systems in a sysplex could have network names of TSO1, TSO2, and TSO3 respectively, and each defined with GNAME=TSOGR. A TSO user could logon to the name "TSOGR" and be transparently assigned to any one of the 3 TSO systems as determined by load balancing.

**Value range:** Any 1 - 8 EBCDIC characters that must be unique from any real resource name in the network, and cannot be TSO.

**Default:** None.

**HIBFREXT**

Specifies the maximum amount (in bytes) of virtual storage that can be dynamically allocated for output data. When this value is reached, no more output requests are honored until LOBFREXT is reached. (Input requests are rejected only when no virtual storage is available in the address space.)

**Value range:** The maximum size TPUT used at the installation-maximum amount of available virtual storage. Minimum value of 48000 is forced to minimize the output wait due to an out of storage condition. For details about TPUT, see [z/OS TSO/E Programming Services](#).

**Default:** 48000

**LOBFREXT**

Specifies the minimum number of virtual storage bytes that can be dynamically allocated for output data. When this value is reached, tasks that are suspended for lack of output buffers are marked as dispatchable.

**Value range:** 0 - (HIBFREXT-1)

**Default:** 24000

**MODE (BREAK | NOBREAK)**

Specifies how 3276 and 3278 terminals are to be supported for TSO/VTAM. BREAK indicates that the terminal keyboard is unlocked whenever possible and does not necessarily correspond to the issuance of a TGET. NOBREAK indicates that the terminal keyboard is locked except when a TGET is issued. The BREAKIN option of TPUT applies only when BREAK is specified.

**Default:** NOBREAK

**MODESW (YES | NO)**

Specifies whether the TERMINAL command or the STBREAK macro can be used to change the mode of operation that is specified with the MODE parameter.

**Default:** NO

**RCFBDUMP**

Specifies the values of the return code (xx) and the feedback field (yy) for a RPL-type request. When an abnormal termination occurs that produces a return code and a feedback value that matches those specified in RCFBDUMP, a dump is taken to the extent specified in z. The specification z=0, specifies that only the local address space is to be dumped; z=1 specifies a full storage dump. The RCFBDUMP parameter can be used to request dumps for I/O errors from which TSO/VTAM can recover.

For the value range, see return code and feedback values in [z/OS Communications Server: SNA Programming](#).

**Default:** None.

**RECONLIM**

Specifies the time limit in minutes within which a user can reconnect after the line is disconnected. That is, the amount of time an address space remains active in the event of terminal disconnection. A setting of RECONLIM=0 means that there is a zero wait for reconnection, which means that a reconnect is not possible.

**Value range:** 0 - 32767

**Default:** 3

**SCRSIZE**

Specifies the default screen size of IBM 3270 systems network architecture (SNA) terminals. The valid values for this parameter are as follows:

| Screen size | Value |
|-------------|-------|
| 12 x 40     | 480   |
| 24 x 80     | 1920  |
| 32 x 80     | 2560  |

| Screen size | Value |
|-------------|-------|
| 43 x 80     | 3440  |
| 27 x 132    | 3564  |
| 62 x 160    | 9920  |

(Use the FEATUR2 operand of the LOCAL or TERMINAL macros to specify non-SNA IBM 3270 screen sizes.) This value affects only those terminals whose sizes were not specified by using the PSERVIC parameter of the MODEENT macro during VTAM definition.

If an installation has IBM 3270 SNA terminals of only one screen size, SCRSIZE should specify that size. If the installation has IBM 3270 SNA terminals of both screen sizes, SCRSIZE can be used to define the more common size, and the PSERVIC parameter can be used to define the less common size.

**Value range:** 480-9920

**Default:** 480

### USERMAX

Specifies the maximum number of users that can be logged on to the TSO/VTAM time sharing system at one time. Because VTAM considers each user to be an application program, and because there must be an APPL definition statement that defines each application program to VTAM during VTAM network definition. This value cannot exceed the number of APPL definition statements.

**Value range:** 0 - maximum number of address spaces in the system.

**Default:** 40



## Chapter 86. VATLSTxx (volume attribute list)

VATLSTxx contains one or more volume attribute lists that predefine the mount and use attributes of direct access volumes. The *mount* attribute determines the conditions under which a volume can be demounted. The *use* attribute controls the type of requests for which a volume can be allocated.

The system programmer can predefine volume “mount” attributes as permanently resident or reserved, and can predefine volume “use” attributes as storage, public, or private. Therefore, critical direct access volumes can be controlled because the “mount” and “use” attributes determine the type of data sets that can be placed on a volume. During allocation, data sets on volumes marked permanently resident or reserved are selected first because they require no serialization, thus minimizing processing time.

You can ensure a faster initialization by specifying the volume attribute list(s) efficiently. Do not, for example, specify a list at a given IPL that contains entries for volumes that will not be mounted. Un-mounted volumes require operator intervention with resultant delay.

There are two ways to define the use and mount attributes for DASD volumes. You can define them in individual entries in the VATLSTxx member, one volume to each entry, or you can use one entry to define a group of volumes. In this second way, you specify generic volume serial numbers and device types for groups of volumes.

Specifying generic values makes it easier for you to maintain your VATLSTxx members. Give one generic name to a group of volumes mounted on devices that have the same device type and the same mount and use attributes. Specify an asterisk (“\*”) for the device type when groups of volumes have the same volume serial numbers, mount attributes, and use attributes, regardless of the devices the volumes are mounted on. See [“Specifying a generic volume serial number” on page 780](#) and [“Specifying a generic device type” on page 781](#) for more information.

For JES3, DEVICE and SETRES initialization statements, rather than the VATLST, can be used to specify permanently-resident volumes. In a JES3 complex, you must assign the same mount attribute to a volume mounted on every system in the complex. For example, if you use the mount attribute of “permanently resident” for the system residence volume on one system, you must use the same use attribute on all the other systems.

If VATLST members are used for volumes resident on devices that are shared among multiple systems, the mount attributes for a specific volume must be the same on all systems.

### Definitions of the mount and use attributes

There are three mount attributes: permanently resident, reserved, and removable. The permanently resident or reserved attributes may be specified in a volume attribute list. The removable attribute automatically applies to any volume that VATLSTxx does not designate or default as permanently resident or reserved.

A *permanently resident* volume is either one that cannot be physically demounted (that is, a drum, 3344, or 3350) or one that cannot be demounted until its device is varied offline. Only direct access volumes can be made permanently resident.

The following volumes are *always* marked permanently resident by NIP. You should therefore specify only the use attribute of these volumes in a volume attribute list:

- Volumes that cannot be physically demounted (such as a 3350 volume).
- The system residence volume This volume includes the SYS1.SVCLIB and SYS1.NUCLEUS data sets.
- Volumes that contain these system data sets: SYS1.LINKLIB and data sets concatenated to it, SYS1.DUMPnn, VIO journaling data set, page data sets, and swap data sets.

A *reserved* volume remains mounted until the operator issues an UNLOAD or a VARY OFFLINE command. A volume is marked reserved when it is so designated in a volume attribute list, or when the operator issues a MOUNT command for the volume.

A *removable* volume can be demounted after its last use in a job, or when the device on which it is mounted is needed for another volume. Any volume not designated as either permanently resident or reserved is considered removable. The operator can change a removable volume to a reserved volume by issuing the MOUNT command for the volume.

The *use* attribute controls the type of request for which a volume can be assigned:

- a specific volume request.
- a temporary, non-private non-specific volume request.
- a non-temporary, non-private, non-specific volume request.

Three *use* attributes are used for allocating these types of volume requests, as follows:

- A *private* volume is allocated only to a specific volume request. For more information about this attribute, see [z/OS MVS JCL Reference](#).
- A *public* volume is allocated to a temporary, non-specific volume request (or possibly to a specific volume request). Thus, a scratch data set would be placed on a public volume.
- A *storage* volume is allocated primarily to a non-temporary, non-specific volume request. (A storage volume can also be allocated to a specific volume request or a temporary non-specific volume request.)

**Note:** A storage volume is required by the SAVE subcommand of EDIT for a newly created data set. If a *storage* volume is not available, the SAVE subcommand cannot save the data set.

## Processing the VATLSTxx members

---

The system reads the VATLSTxx members that were specified in the VAL parameter in IEASYSxx. If the system detects an incorrect VATLSTxx entry, the system issues informational message IEA855I, and continues processing the remaining entries.

If an I/O error occurs during the reading, the operator can choose to display informational message IEA850I, which lists the volumes, device types, and attributes that will be processed. A second message (IEA853A) allows the operator to choose one of the following recovery options:

- Continue processing any remaining lists.
- Stop the processing of remaining lists.
- Specify a new VATLSTxx member by replying r 0,xx, where xx is the two-character identifier for VATLSTxx.
- If necessary, reIPL the system.

If an I/O error does not occur during the reading, the system lists the IPL and SYSTEM use attributes in message IEA168I.

Volume attribute processing compiles a list of all VATLSTxx entries. If a particular volume serial number appears on more than one entry, the system uses the volume attributes specified in the last entry for that volume serial.

Mount messages can be issued for unmounted volumes, up to the maximum number of processed entries. The system can process up to 64000 unique VATLSTxx entries at IPL.

The operator can respond to the mount messages by replying with the device number of the requested device type (that is, 3330-1). If the operator chooses not to mount a volume, the operator replies 'U' or ENTER.

If the operator enters an incorrect device number, or a path to a device is not available, the operator can reenter new device numbers.

To indicate that no more volumes will be mounted, enter 'U' or ENTER.

When message IEA860A lists the devices that need volumes, the operator should mount the required volumes on the replied devices. When all devices have become ready (green lights on), the operator replies 'U' or ENTER to message IEA860A. Volume attribute processing then scans for mounted volumes.

If a volume that did not appear in the mount message is mounted on a unit specified by the operator, it is unloaded. The volume is also unloaded if the operator mounts the requested volume on a device type other than the one specified in the volume attribute list, or on an un-requested unit.

If all the required devices do not become ready, volume attribute processing issues message IEA893A, which lists the devices that are not ready. If the operator intends to ready these devices, the operator may do so before replying 'U' or ENTER to the message. If a volume cannot be mounted on a device for some reason (such as a hardware problem), the operator should reply NO to the message, after all other required devices have been processed. This response indicates to volume attribute processing that no more volumes will be mounted.

If the system does not find a volume that matches a generic volume serial number entry, it issues message IEA166I.

## Parameter in IEASYSxx (or supplied by the operator)

```
VAL={aa      }
-----
      {(aa,bb,...)}
```

Two alphanumeric characters (such as, A1 or 30) are appended to VATLST to specify the VATLSTxx member(s) of parmlib. If the parameter is not specified either in IEASYSxx or by the operator, the default member VATLST00 is used, if it exists. If the VAL parameter specifies multiple members, the members are processed in the order specified. If a particular volume serial number appears on more than one entry, the volume attributes specified in the last entry for that volume serial will be accepted. If the VAL parameter has an invalid format, or if it specifies a member that does not exist in parmlib, the operator is prompted to respecify the member or to reply 'U' to cause the member to be ignored.

## Support for system symbols

You can specify system symbols in VATLSTxx. However, be aware that the fields in VATLSTxx are column-dependent (except for the VATDEF statement). The resolved substitution texts for the system symbols must conform to the rules described in [“Statements and parameters for VATLSTxx” on page 781](#).

The following rules apply when you use system symbols in VATLSTxx:

- If a system symbol is used anywhere in the volume serial number, there must be a blank after the entire volume serial number. This blank delimits the end of the volume serial number, not the end of the system symbol, and does not become part of the volume serial number when resolved.
- A period at the end of the system symbol delimits the end of that symbol. The period is optional for the following cases:
  - between 2 system symbols. In this case, the & that begins the second system symbol acts as a delimiter.
  - before the blank delimiter at the end of the entire volume serial number.
  - before a generic character, such as % or \*.
- The volume serial number field in the VATLSTxx entry must be exactly 6 characters long. If a combination of system symbols resolves to less than 6 characters, you must add blanks to pad the volume serial number.

Let us assume we have an IEASYMxx member with the following definitions:

- SYMDEF(&SYMB1.='PA')
- SYMDEF(&SYMB2.='GE')
- SYMDEF(&SYMB3.='%%')

With these assumptions, each of the examples that follow will resolve to a volume serial number of PAGE% %:

- This example leaves out periods before &.

```
&SYMB1.&SYMB2.&SYMB3. ,0,0,3390...
&SYMB1&SYMB2&SYMB3. ,0,0,3390...
```

- This example leaves out periods before %.

```
&SYMB1&SYMB2.%% ,0,0,3390...
&SYMB1&SYMB2%% ,0,0,3390...
```

- In this example, the blank that delimits the end of the volume serial number also delimits the end of the system symbol.

```
PAGE&SYMB3. ,0,0,3390...
PAGE&SYMB3 ,0,0,3390...
```

Using the same assumptions for the IEASYMxx member, the following VATLSTxx entry would be invalid:

```
&SYMB1GE%% ,0,0,3390...
```

Instead of appending "GE%%" to the end of &SYMB1, the system would look for a system variable &SYMB1GE, which does not exist in our example.

For information about how to use system symbols in shared parmlib members that require unique values, see [Chapter 2, "Sharing parmlib definitions,"](#) on page 31.

## Creating a VATLSTxx member

The VATLSTxx member contains an optional VATDEF statement followed by entries that define the mount and use attributes of DASD volumes.

Use the VATDEF statement in VATLSTxx to specify a default use attribute. If you do not specify VATDEF, the system assigns a default of PUBLIC to those volumes that are not specifically assigned a use attribute in the VATLSTxx member or in a MOUNT command.

If specified, the VATDEF statement must be the first non-comment line in VATLSTxx. Any VATDEF statement after the first line is treated as a DASD volume entry.

In the first VATLSTxx member that is specified in the VAL= operand, all of the VATDEF keywords are processed. In subsequent VATLSTxx members, only the STARCOMMENT keyword value is accepted and used. The IPLUSE and SYSUSE keywords are ignored.

The following is the syntax for the VATDEF statement. Unlike DASD volume entries in VATLSTxx members, the VATDEF statement is not column-dependent but it also cannot be continued on another line.

```
VATDEF
      IPLUSE( {PUBLIC }
              {PRIVATE} )
              {STORAGE}

      SYSUSE( {PUBLIC }
              {PRIVATE} )
              {STORAGE}

      STARCOMMENT( {YES} )
                  {NO }
```

### VATDEF

The default for use attributes for DASD volumes and comment processing in VATLSTxx. If you specify VATDEF without any operands, the system uses the operands IPLUSE(PUBLIC), SYSUSE(PUBLIC), and STARCOMMENT(YES).



**IPLUSE**

The use attribute default that the system applies to permanently resident volumes that are brought online during IPL (that is, have no VATLST entry, or whose use attribute is not specified correctly in VATLSTxx).

**SYSUSE**

The use attribute default that the system applies to volumes that are varied online after IPL and have no entry in a VATLSTxx member.

**PRIVATE**

Sets the default use attribute to PRIVATE.

**PUBLIC**

Sets the default use attribute to PUBLIC. This operand is the default for VATDEF IPLUSE and VATDEF SYSUSE.

**STORAGE**

Sets the default use attribute to STORAGE.

**STARCOMMENT**

Indicates whether an asterisk in column 1 will be processed as a comment for subsequent lines in the current VATLSTxx member. This value only applies to the current VATLSTxx member.

**YES**

A line with an asterisk in column 1 will be treated as a comment. This is the default when the STARCOMMENT keyword is not specified.

**NO**

A line with an asterisk in column 1 will be treated as a DASD volume entry.

## Example of default use attributes

At an installation where the VATLSTxx members are defined as VAL=(00,05), member VATLST00 contains the following entries:

```
VATDEF SYSUSE(PRIVATE)
30565A,0,2,3330      ,      TSO
```

The system ignores any VATDEF entry in VATLST05. It uses PRIVATE as the default use attribute for any volume varied online after IPL and PUBLIC for any volume brought online during IPL. The optional information TSO appears in installation printouts, but is ignored by VATLST processing.

## Syntax rules for VATLSTxx

The following rules apply to the entire VATLSTxx member:

- Each record is 80 characters long. The system ignores columns 72 through 80.
- Prior to the VATDEF statement (if provided) or the first DASD volume entry (if no VATDEF statement is provided), lines with an asterisk in column 1 will be treated as comments. This is not affected by the VATDEF STARCOMMENT keyword value.
- If the VATDEF statement was provided with STARCOMMENT(NO), lines after the VATDEF statement that begin with an asterisk in column 1 are treated as DASD volume entries. Otherwise, by default all lines with an asterisk in column 1 are treated as comments.
- The VATDEF STARCOMMENT keyword value applies only to the current VATLSTxx member. Each VATLSTxx member will be processed according to the STARCOMMENT keyword value specified in that member, or if no STARCOMMENT keyword value is provided, according to the defaults described in this list.

The following rules apply to the creation of a DASD volume entry in the VATLSTxx member:

- Each record consists of 80 columns, although columns 22 through 80 are ignored.
- The fields are column-dependent, as shown in [“Statements and parameters for VATLSTxx” on page 781](#).

- There are only two required fields: the volume serial number and the device types. All other fields have defaults.
- Use a comma to separate adjacent fields, except before the optional information field.
- Specify all characters in EBCDIC.

“Statements and parameters for VATLSTxx” on page 781 includes a graphic description of all fields in the record and their lengths.

The following sections describe how to specify DASD volume entries.

## Specifying a generic volume serial number

Generic volume serial numbers allow you to reduce the number of entries in the VATLSTxx members. The valid generic characters are % and \*; you can use any combination of these characters in an entry. If a volume serial number does not contain any generic characters, it defines only the volume with the specified volume serial number. Rules for generic volume serial numbers follow, with examples of the generic numbers and the possible matching numbers. These examples are provided to illustrate how generic volume serial matches are processed, and in some cases it may be necessary to specify VATDEF STARCOMMENT(NO) for these to be treated as DASD volume entries.

The character \* in the generic volume serial number indicates that any character in that position and all subsequent characters are a match.

| Generic volume serial number | Matching volume serial numbers |
|------------------------------|--------------------------------|
| <b>TSO*</b>                  | TSO01, TSO, and TSO123         |
| <b>*TSO*</b>                 | XABTSO, ABTSO1, and TSO01      |
| <b>P*5</b>                   | PROD05 and P5                  |
| <b>*PROD</b>                 | 12PROD and PROD                |

The character % in the generic volume serial number indicates that any single character within the volume serial number is a match to that character position.

| Generic volume serial number | Matching volume serial numbers |
|------------------------------|--------------------------------|
| <b>TSO%</b>                  | TSO1                           |
| <b>%TSO%</b>                 | ATSO1                          |
| <b>P%%5</b>                  | P125                           |
| <b>%PROD</b>                 | 1PROD                          |

Both symbols can appear in the same number.

You can enter the generic volume serial numbers in any order. However, if more than one generic specification can be applied to a particular volume serial, the system finds the attributes that are specified in the last entry with such a generic specification.

For example, an installation has the volume serial numbers WK982A and WK9BBB, and the VATLSTxx has the following entries.

```
WK982%,1,0,3350      ,N  STORAGE VOLUME
WK9%%%,1,1,3350      ,N  PUBLIC  VOLUME
```

The system finds the second entry. WK9%%% matches both volume serial number WK982A and WK9BBB.

| Generic volume serial number | Matching volume serial numbers |
|------------------------------|--------------------------------|
| <b>*TSO%</b>                 | TSO1 and XXTSO2                |

| Generic volume serial number | Matching volume serial numbers |
|------------------------------|--------------------------------|
| P%5*                         | P05PRO                         |

## Specifying a generic device type

The character "\*" identifies a generic device type, based on which DASD are defined at your installation. Use the generic device type when you have the same use attribute and the same mount attributes regardless of the device you want the volumes mounted on.

If you specify a generic volume serial number, you can specify a generic device type. For example, if you specify the generic volume serial as TSO\*, the matching volume serial numbers for this are TSO01, TSO, and TSO123, as above. TSO01 is on a 3350, TSO is on a 3380, and TSO123 is on a 3390. If you want to specify the same mount and use attributes for these volumes, regardless of the device types, you can specify a generic device type and then the mount and use attributes.

## Example of setting the generic device type

The following VATLSTxx entry:

```
TSO*   ,0,2,*
```

Is equivalent to the following three entries:

```
TSO01  ,0,2,3350
TSO     ,0,2,3380
TSO123 ,0,2,3390
```

These examples assume that only 3350, 3380, and 3390 DASD are defined.

### Note:

1. Generic device types do not support specifications such as 33%% or 33\*
2. A VATLSTxx statement with a specific volume cannot have a generic device type.

## Statements and parameters for VATLSTxx

Figure 32 on page 781 shows the entries in VATLSTxx members that define the mount and use attributes of direct access volumes. The fields are column-dependent.




Figure 32. Entries in VATLSTxx members that define attributes of DASD

## Examples of VATLSTxx entries

Figure 33 on page 782 shows the entries in VATLSTxx that define the mount and use attributes. Table 67 on page 782 describes the fields in more detail.

Columns:      1            8 10 12            21 23

                 ↓            ↓ ↓ ↓            ↓            ↓

                 30565A,0,2,3330            ,            PAGING VOLUME

                 \*TSO\* ,1,1,\*            ,            TSO

                 305%\* S0,2,3380

                 30565BS0,2,3380

Figure 33. Entries in VATLSTxx members that define mount and use attributes of DASD

In the first entry in Figure 33 on page 782, a volume whose serial number is 30565A is to be mounted on a 3330 and marked permanently resident. The volume's use attribute is to be private. A mount message is to be issued if the volume is unmounted. The optional information, PAGING VOLUME, appears in installation printouts but does not affect VATLST processing.

In the second entry in the example, volumes with serial numbers that include the character string "TSO" are to be mounted on any DASD and reserved. The volumes' use attribute is to be public. Because you specified a generic volume serial number, the system does not issue a mount message for un-mounted volumes. This entry would require that a VATDEF statement with STARCOMMENT(NO) be provided, otherwise it would be treated as a comment instead of a DASD volume entry. The optional information, TSO, appears in installation printouts but does not affect VATLST processing.

In the third entry, volumes with serial numbers included in the 305%\* specification, are to be mounted on a 3380 and marked permanently resident. The use attribute is to be private.

In the fourth entry, a specific volser name, 30565B, contains an S in column 7, indicating that the volser is specific. However, error message IEA855I is issued because the volser does not contain either of the special characters, % or \*. The S should only be coded for specific volsers containing special characters.

| Table 67. Explanation of VATLSTxx entries |        |   |   |               |
|---|--------|---|---|---------------|
| Parameter                                 | Column | Meaning and use   | Value range   | Default value |
| volume serial                             | 1-6    | Specifies either the direct access volume with <i>mount</i> and <i>use</i> attributes to be set, or a generic volume serial number. The volume serial number must begin at the first character position in the record.  | 1 - 6 alphanumeric characters plus special characters % and *, left-aligned in the field and padded with blanks at right to occupy six columns. | None          |
| specific vol. ser. identifier             | 7      | S specifies that the entry is a specific volume serial number, not a generic one. Code the S only when your volume serial number has an asterisk or percent sign in it and you do not want the system to process it as a generic entry. Code a comma when the volser is a specific volser without the special characters or the volser is a generic volser. | S or ,  | None          |
| mount attribute                           | 8      | Specifies whether the volume is to be permanently resident or reserved. Default is assigned if any character other than 1 is specified.<br><br><b>0</b><br>Specifies permanently resident.<br><br><b>1</b><br>Specifies reserved.   | 0 or 1  | 0             |

| Table 67. Explanation of VATLSTxx entries (continued) |        |  |   |   |
|---|--------|--|---|---|
| Parameter   | Column | Meaning and use  | Value range   | Default value   |
| use attribute   | 10     | Specifies whether the volume is to be defined as storage, public, or private. The default is assigned if any character other than 0, 1, or 2 is specified.<br><br><b>0</b><br>Specifies storage.<br><b>1</b><br>Specifies public.<br><b>2</b><br>Specifies private.  | 0-2   | 1, unless the VATDEF operand specifies a different default. |
| Device type   | 12-19  | Specifies the device type, such as 3380. Up to eight characters may be specified, but the first character must start at column 12. Only supported device types that were defined through HCD are acceptable. This parameter indicates the basic device but does not denote special features, such as track overflow. An asterisk (*) in column 12 indicates a generic device type. | Up to 8 characters, left-aligned within the field, and padded with blanks at the right to occupy eight columns. | None  |
| mount message suppression                             | 21     | Specifies whether mount messages should be issued for the volume if it is not already mounted. This parameter is ignored for volumes that are defined with generic VATLST entries.<br><br><b>N</b><br>specifies that mount messages should be suppressed.<br><br><b>x</b><br>where x, which is a blank or any character except N, specifies that mount messages should be issued.  | N, blank, or any character.   | Blank, indicating that mount messages should be issued.     |
| optional information                                  | 23-80  | Contains optional, installation-defined information (for example, an eye-catcher or brief comment) to be included in installation printouts. The system does not use this information.   | Not applicable.   | None  |

## IBM-supplied default for VATLSTxx

No default member is supplied by IBM. The installation can, however, create its own default member, named VATLST00.



---

## Chapter 87. XCFPOLxx (XCF PR/SM policy)

In a multisystem sysplex on PR/SM, the XCF PR/SM policy provides a way for the installation to obtain high availability for multisystem applications on the MVS systems in the sysplex. You specify the XCF PR/SM policy in a parmlib member. IBM suggests naming this member XCFPOLxx, where xx is a unique 2-character identifier. You activate (or deactivate) the policy with the SETXCF PRSMPOLICY command, and display the name of the active policy with the DISPLAY XCF,PRSMPOLICY command.

The XCF PR/SM policy allows you to specify the actions that XCF on a system in the sysplex on PR/SM is to take when a “status update missing” or “system gone” occurs on another system in the sysplex.

Some reasons a status update missing condition might occur are:

- The system has failed and entered a non-restartable wait state.
- The system is in a disabled spin loop.
- The operator stopped or reset the system.
- The system has failed and cannot dispatch normal work.
- The system entered a restartable wait state but the operator has not restarted the system.

A system gone condition occurs after a system reset is confirmed.

The XCF PR/SM policy reduces the need for operator intervention because XCF on a remaining system in the sysplex on PR/SM can automatically reset the failing system, deactivate the LPAR, and reconfigure processor storage for use by the remaining system.

**Note:** The XCF PR/SM policy in an XCFPOLxx parmlib member will not work unless the installation enables the system to do a reset of an MVS system on an LPAR and deactivate the LPAR on the PR/SM processor. See the *PR/SM Planning Guide* for information about the assignment of LPARs and processor storage.

For more information about using XCF, see [z/OS MVS Setting Up a Sysplex](#).

---

### Parameter in IEASYSxx (or supplied by the operator)

None.

---

### Syntax rules for XCFPOLxx

The following syntax rules apply to XCFPOLxx:

- Use columns 1 through 71. Do not use columns 72 - 80 for data; these columns are ignored.
- At least one delimiter (space or comma) is required between a statement and keyword. Delimiters are not required between keywords.
- Use at least one delimiter to separate multiple keyword values within parentheses.
- Comments may appear in columns 1-71 and must begin with "/\*" and end with "\*/".

## Syntax format of XCFPOLxx

```

NOSTATUS(failsys)
    { RESETTIME(nnnnn) }
    { DEACTTIME(nnnnn) }

SYSGONE(failsys)
    SYSTEM(sysname)
    DEACTIVATE(othersys|ALL)
    [ STORE(YES|NO) ]
    [ ESTORE(YES|NO) ]

```

## IBM-supplied default for XCFPOLxx

None.

## Statements and parameters for XCFPOLxx

### **NOSTATUS(*failsys*)**

The NOSTATUS statement specifies an action to take when the specified system appears to have failed (status update missing). You can choose to either reset or deactivate the failed system. The current system and the failing system must be running in LPAR mode on the same processor. If the processor is physically partitioned, then both LPARs must be on the same side.

#### **DEACTTIME(*nnnnn*)**

Specifies that the logical partition (LPAR) where the failing system resides is to be deactivated after the specified number of seconds have elapsed. If you specify DEACTTIME(15), this system will deactivate the LPAR of the failing system 15 seconds after the status update missing condition is detected for the failing system. Specifying DEACTTIME(*nnnnn*) also causes the system to be reset.

If the failing system becomes active before the specified time interval elapses, the LPAR is not deactivated.

**Tip:** Specify a time interval of less than 60 seconds because longer intervals might cause SETXCF PRSMPOLICY commands to be delayed.

**Value range:** 0 - 86400 seconds

#### **RESETTIME(*nnnnn*)**

Specifies that the failing system is to be reset after the specified number of seconds have elapsed. If you specify RESETTIME(10), this system will perform a system reset of the failing system 10 seconds after the status update missing condition is detected for the failing system.

If the failing system becomes active before the specified time interval elapses, the system reset is not performed.

**Tip:** Specify a time interval of less than 60 seconds, because longer intervals might cause SETXCF PRSMPOLICY commands to be delayed.

**Value range:** 0 - 86400 seconds

### **SYSGONE(*failsys*)**

Specifies an action to take when the specified system was reset by the operator or by the policy that is specified by the NOSTATUS parameter.

#### **DEACTIVATE(*othersys*|ALL)**

Specifies either that the logical partition (LPAR) where the specified system (*othersys*) resides is to be deactivated or all LPARs within the current system's addressing range are to be deactivated. The specified system (*othersys*) must be in the same sysplex as the current system and on the same processor as the system specified with the SYSTEM(sysname) keyword.



Specifying DEACTIVATE(*othersys*) where *othersys* is the same system that is specified in the NOSTATUS statement with the RESETTIME keyword has no effect. Instead, use the DEACTTIME keyword. The following example is a correct use of the policy.

```
NOSTATUS(SYS1) DEACTTIME(25)
SYSGONE(SYS1) SYSTEM(SYS2) DEACTIVATE(SYS1)
```

**Default:** None. This parameter is required.

### **ESTORE(YES|NO)**

Specifies whether the specified system (SYSTEM(sysname)) is to acquire the expanded storage that is freed up by the deactivated LPARs.

**Restriction:** ESTOR is not supported in the z/Architecture environment.

**Default:** NO

### **STORE(YES|NO)**

Specifies whether the specified system (SYSTEM(sysname)) is to acquire the storage that is freed up by the deactivated LPARs.

**Default:** NO

### **SYSTEM(sysname)**

Identifies the system in the sysplex that is to take the following actions when the specified system (*failsys* on the SYSGONE statement) failed. The system indicated by *sysname* is not necessarily the current system. Instead, it is the system that you are designating to perform the deactivation of the LPAR. This allows a single XCFPOLxx parmlib member to be used on all systems in the sysplex.



## Appendix A. IEFSSNxx (subsystem definitions) - positional parameter form

**Note:** This appendix describes the IEFSSNxx parmlib member in the positional parameter form. IBM suggests that you use the IEFSSNxx parmlib member in the keyword parameter form instead, which allows subsystems defined in the member to use the dynamic SSI services.

IEFSSNxx is a parmlib member that contains parameters defining the primary subsystem and the various secondary subsystems that are to be initialized during system initialization. IEFSSNxx allows you to name the subsystem initialization routine to be given control during master scheduler initialization. IEFSSNxx also allows you to specify the input parameter to be passed to the subsystem initialization routine. Using the PRIMARY keyword, you can specify a primary subsystem name. The NOSTART keyword used with the PRIMARY keyword indicates that the system is not to issue an automatic start for the primary subsystem.

For information about writing subsystems, see *z/OS MVS Using the Subsystem Interface*.

The order in which the subsystems are initialized depends on the order in which they are defined in the IEFSSNxx parmlib member on the SSN parameter. Unless you are starting the Storage Management Subsystem (SMS), start the primary subsystem (JES) first. Some subsystems require the services of the primary subsystem in their initialization routines. Problems will occur if subsystems that use the subsystem affinity service in their initialization routines are initialized before the primary subsystem. If you are starting SMS, specify its record before you specify the primary subsystem record.

The format of the IEFSSNxx record for SMS is described in [“Defining SMS through the IEFSSNxx member” on page 531](#).

### Parameter in IEASYSxx (or supplied by the operator)

The SSN parameter in IEASYSxx identifies the IEFSSNxx member that the system is to use to initialize the subsystems, as follows:

```
SSN  {aa      }
      {(aa,bb,...)}
```

The two-character identifier, represented by aa (or bb, and so forth) is appended to IEFSSN to identify IEFSSNxx members of parmlib. If the SSN parameter is not specified, the system will use the IEFSSN00 parmlib member.

The order in which the subsystems are defined on the SSN parameter is the order in which they are initialized. For example, a specification of SSN=(13,Z5) would cause those subsystems defined in the IEFSSN13 parmlib member to be initialized first, followed by those subsystems defined in the IEFSSNZ5 parmlib member. you specify duplicate subsystem names in IEFSSNxx parmlib member, the system issues message IEE730. For more information, see the topic on handling errors in defining your subsystem in *z/OS MVS Using the Subsystem Interface*.

### Syntax rules for IEFSSNxx

The following rules apply to the creation of IEFSSNxx:

- Each record in IEFSSNxx defines one and only one subsystem that is to be initialized.
- Parameters begin with the comma following the *init-routine* and end with the first blank or comma.
- Each record in IEFSSNxx is 80 bytes long and has the following format:

```
ssname[,init-routine[,parm]][,PRIMARY[,NOSTART]]  comments
```

**ssname**

The subsystem name. The name can be up to 4 characters long; it must begin with an uppercase alphabetic or national character (#, @, or \$), and the remaining characters (if any) can be alphanumeric or national. The name begins with the first non-blank character in the record and continues to the first comma or blank. When a blank follows the name, the system assumes that no initialization routine exists and that only comments (if any) follow.

In general, the subsystem name should be the same as the started procedure name. Some products (such as IMS and CICS), however, require the subsystem name to be different from the started procedure name. For more information, refer to the topic on coding initialization routines for subsystem in *z/OS MVS Using the Subsystem Interface* and the documentation for the particular product.

**init-routine**

The name of the subsystem initialization routine. This name can be 1-8 characters long, and the characters can be alphanumeric or national (#, @, or \$). The name begins with the first character following the first comma after “ssname” and continues to the next comma or blank. When a blank follows the name, the system assumes that no initialization routine input parameters are supplied and that only comments (if any) follow.

For information about writing subsystem initialization routines, see *z/OS MVS Using the Subsystem Interface*.

**parm**

Input parameters to be passed to the subsystem initialization routine. The input parameters are variable in length for the remainder of the 80-byte record (for a maximum of 60 characters); they begin after the comma that ended the “init-routine” name and end with the first blank. If blanks, commas, or single quotation marks are included in the input parameters, then the entire parm field must be enclosed in single quotation marks. If the parm field is enclosed in single quotation marks, a single quotation mark within the field must be specified as a double quotation mark.

**PRIMARY**

Parameter indicating the primary subsystem name. The primary subsystem is typically a job entry subsystem (either JES2 or JES3). This keyword indicates that the subsystem name (ssname) will be the primary subsystem name. Initialize the primary subsystem before any secondary subsystem(s). If you specify PRIMARY more than once, the system will issue a message.

**NOSTART**

Parameter indicating that an automatic start is not to be issued. NOSTART indicates that an automatic start of the primary subsystem is not to be issued. NOSTART cannot be used without the PRIMARY parameter.

**comments**

Comments can be specified after the first blank in the record following the input parameters, or PRIMARY and NOSTART, for as many characters as remain in the 80-byte record.

You can include any number of records in the IEFSSNxx parmlib member.

## IBM-supplied default for IEFSSNxx

If you do not specify the SSN system parameter, the system will use the IEFSSN00 parmlib member. IEFSSN00 specifies JES2 as the primary subsystem.

If you specify a set of IEFSSNxx members that do not identify a primary subsystem, the system will issue a message that prompts the operator to specify the primary subsystem.

## Statements and parameters for IEFSSNxx

---

None.



# Appendix B. Symbolic Parmlib Parser

The Symbolic Parmlib Parser allows you to verify symbolic substitutions without doing an IPL. The Parser is in SYS1.SAMPLIB and is activated as follows:

## Activation

Enter the following commands to install the Parser for the first time:

```
EX 'SYS1.SAMPLIB(SPPINST)' '''SYS1.SAMPLIB(SPPPACk)'''
```

Enter the following commands to install a new version of the Parser. The / R option indicates to replace the previous instance.

```
EX 'SYS1.SAMPLIB(SPPINST)' '''SYS1.SAMPLIB(SPPPACk)''' / R'
```

**Note:** See SYS1.SAMPLIB(SPPINST) for more details about the (/ R) replace option.

Enter the following command to activate the Parser, where *myid* equals your user ID.

```
TSO ex 'myid.PARMLIB.EXEC(SYSPARM)'
```

**Note:** Browse SYS1.SAMPLIB(SPPINST) for more details about installation and activation syntax.

Once activated, you see a panel similar to that shown in [Figure 34 on page 793](#).

COMMAND ==>

```
Member Name      ==> IEAYSYSTT (Enter '?' for supported member list)
Browse, Edit or View ==> V      (Optional. Default is VIEW for symbol
                                substitution, and EDIT otherwise.)
Dsn ==>PARMLIB      Dflt: 'SYS1.PARMLIB'
Volume of above Dsn ==>      (Optional)
SYS1.NUCLEUS Volume ==>      (If different from one catalogued)
FMID              ==>      (Optional. Enter '?' for list)

Do Symbol Substitution ==> Y      (Y or N)
Symbol Substitution Values:
LOADxx Member    ==> LOADTT (Use '*' for Current val
Hardware Name     ==>      Default LOAD00. LOADF1      <===Current
LPAR Name        ==>      (Optional) PR9672A          <===Current
VM Userid        ==>      (Optional) AQFT             <===Current
SYSRES Volume    ==>      (Optional) PRIPK5           <===Current
Master Cat Volume ==>      (Optional - Substituted for *MCAT* )
```

Figure 34. Symbolic parmlib parser panel

Help is available on all panels by pressing PF1 or typing help on the command line.

## Capabilities

The myid.PARMLIB.NOTES file, member WORKFLOWS, gives an overview of the tool's capabilities. The following is an enhanced version of that file.

The Parmlib Processing tool provides several functions.

The tool can be used as a LOADxx processor by specifying:

- Member Name = desired LOADxx value
- Do Symbol Substitution = N
- LOADxx Member = blank

This brings up the LOADxx processing panel, which allows the following types of data validation:

- Syntax Checking

Syntax checking examines the LOADxx parmlib member, looking for data specification errors such as missing commas and illegal keywords. Syntax checking is performed when an existing supported LOADxx parmlib member is selected for EDIT or BROWSE mode. Any errors detected are listed before the EDIT or BROWSE panel is initialized or displayed. Only data that is valid and recognized by the tool is displayed on the EDIT or BROWSE panel.

- Range and Type Checking

Range and Type checking examines the data that is extracted from the LOADxx parmlib member, looking for value and type specification errors such as alphabetic characters being used when numerical data is required and numerical data that is not within a required range. The ISPF Panel and associated REXX program perform range and type checking. No range or type checking is done during syntax checking.

- Data Verification

Data verification is performed by typing VERIFY on the command line of the BROWSE or EDIT panels. Data verification takes the valid data from syntax, range and type checking and examines what they mean in the current system environment. For example, one of the fields in a LOADxx parmlib member may contain a pointer to another parmlib member. Data verification checks to see if that member exists in the specified parmlib.

GRSRNLXX PROCESSING: The tool can be used as a GRSRNLxx syntax checker by specifying:

- Member Name = desired GRSRNLxx value
- Do Symbol Substitution = Y - substitution must be specified in order to have syntax checking performed
- LOADxx Member = blank
- Syntax Checking

Syntax checking examines the GRSRNLxx parmlib member, looking for data specification errors such as missing commas and illegal keywords, invalid QNAMEs, and duplication of entries. Syntax checking is performed when an existing GRSRNLxx parmlib member is selected for EDIT or BROWSE mode and symbol substitution is specified. Any errors detected are noted in ISPF EDIT or BROWSE messages that state the type of error and the record number containing the error.

**Note:** GRSCNFxx parmlib member syntax checking is not supported by the tool.

The tool can be used as a parmlib symbolic preprocessor by specifying:

- Member Name = the name of a parmlib member containing symbolics to be processed
- Do Symbol Substitution = Y
- LOADxx Member = Desired LOADxx member. LOADxx is where a Symbol set is specified via the IEASYM statement.

The tool performs the following steps as a Parmlib Preprocessor:

1. Verifies that the LOADxx member exists where it is supposed to.
2. Reads the LOADxx member and examines its statements.
3. Reads the IEASYMxx members and thoroughly processes each one using the same code that is used at IPL time. Any errors are noted with the same messages used during IPL. If no IEASYMxx members can be found, a message will be issued.
4. Reads the IEASYSxx members and thoroughly processes each one. Any errors are noted with appropriate error messages. If no IEASYMxx members can be found, a message will be issued.
5. Searches for the input member and opens it if found.
6. Processes the input member through the symbol table built from reading the IEASYMxx members and the panel input fields. Any symbols that cannot be substituted are highlighted.
7. If DOALL is invoked, each line of the IEASYSxx member will be read to see if other parmlib members are implied. If these members are not found, an error message will be issued. If these members are found, they will be processed as described in Step “6” on page 794. Any apparent processing problems for IEASYSxx are also noted.



The tool can be used to obtain a parmlib member selection list by specifying:

- Member Name = blank
- Do Symbol Substitution = Y
- LOADxx Member = blank

This places you in a panel displaying the different types of available parmlib members. When you select a parmlib member type the tool shows you a list of all members of that type in your parmlib data set, as specified on the main panel.

The tool can be used to obtain a parmlib member selection list from a concatenation of parmlibs by specifying:

- Member Name = blank
- Do Symbol Substitution = Y
- LOADxx Member= LOADxx (where that LOADxx member has defined a concatenated parmlib via the PARMLIB keyword)

The parmlib processor places you in a panel displaying the different types of available parmlib members. When you select a parmlib member type the tool shows you a list of all members of that type in your data set concatenation, as determined by the LOADxx member specified on the main panel.

## Limitations

---

1. The tool does not support editing of SYSn.IPLPARM data sets. You can use the tool to generate the member in SYS1.PARMLIB or high\_level\_qualifier.PARMLIB and then you can copy the member into the appropriate SYSn.IPLPARM data set.
2. The tool assumes that any SYSn.IPLPARM data set is on the same volume as the specified parmlib data set. It does not support the concept of a separate IODF and SYSRES volume, nor does it use Master Catalog to locate a SYSn.IPLPARM data set.
3. If the tool is running on a partial ship release or a point release, in the Parmlib Processor Member Selection Panel under the FMID field, use the LATEST keyword or a full ship release FMID to select the parser release used to process or verify the SYS1.PARMLIB member that you selected.
4. Although the code can detect the presence of a VSAM data set, it does not have the ability to read one. Therefore, the IODF data set is only checked for existence. Its contents are not verified.
5. The Master Catalog information is not verified.
6. When in EDIT mode, the data in a member is not altered until it is saved. If you are running in split screen mode, you will not see the effects of the changes until the EDIT mode changes are saved.
7. Syntax checking is not done generally for the parmlib members that the tool lists as supported.
8. When processing an IEASYMxx parmlib member, the tool manipulates the data into an internal format. If that internal format exceeds 320080 bytes, the tool will terminate, with a message indicating that the IEASYMxx member is too large. It takes an IEASYMxx member on the order of 10000 lines long to reach this limit. If the limit is exceeded, the tool user will have to specify a different IEASYMxx member, possibly created from the original member but with data for non-applicable systems removed.



---

## Appendix C. Accessibility

Accessible publications for this product are offered through [IBM Documentation for z/OS \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS documentation see [How to Send Feedback to IBM](#) to leave documentation feedback.



## Notices

---

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
United States of America*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Corporation  
Site Counsel  
2455 South Road*

Poughkeepsie, NY 12601-5400  
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## Terms and conditions for product documentation

---

Permissions for the use of these publications are granted subject to the following terms and conditions.

### **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

### **Personal use**

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

### **Commercial use**

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

## **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

## **IBM Online Privacy Statement**

---

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at [ibm.com/privacy](http://ibm.com/privacy) and IBM's Online Privacy Statement at [ibm.com/privacy/details](http://ibm.com/privacy/details) in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at [ibm.com/software/info/product-privacy](http://ibm.com/software/info/product-privacy).

## **Policy for unsupported hardware**

---

Various z/OS elements, such as DFSMSdfp, JES2, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

## **Minimum supported hardware**

---

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: [IBM Lifecycle Support for z/OS \(www.ibm.com/software/support/systemsz/lifecycle\)](http://www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

## Programming Interface information

---

This book is intended to help the customer initialize and tune the MVS element of z/OS. This book documents information that is NOT intended to be used as Programming Interfaces of z/OS.

## Trademarks

---

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at [Copyright and Trademark information \(www.ibm.com/legal/copytrade.shtml\)](http://www.ibm.com/legal/copytrade.shtml).

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

The registered trademark Linux® is used pursuant to a sublicense from the Linux Foundation, the exclusive licensee of Linus Torvalds, owner of the mark on a worldwide basis.

UNIX is a registered trademark of The Open Group in the United States and other countries.



# Index

## Special Characters

- `_CEE_RUNOPTS` variable
  - when specifying `RUNOPTS` [148](#)
- `.DEFAULT` statement in `MPFLSTxx`
  - defaults [648](#)
  - purpose [648](#)
- `.FORNSSI` statement in `MPFLSTxx`
  - syntax for [650](#)
- `.MSGCOLR` statement in `MPFLSTxx` [644](#), [645](#)
- (`IEATDUMP`) transaction dump
  - `ADYSETxx` parmlib member [61](#)

## A

- abend code
  - adding [713](#)
  - deleting [713](#)
  - eligible for automatic restart [713](#)
- ABEND dump parameter
  - for a `SYSABEND` data set [357](#)
  - for a `SYSMDUMP` data set [377](#)
  - for a `SYSUDUMP` data set [373](#)
- ABEND operand
  - `DUMPCAPTURETIME` parameter
    - `CEAPRMxx` parmlib member [160](#), [161](#)
- ABEND parameter in `EXSPATxx` [314](#)
- ABNORMALTERM parameter in `IEAOPTxx` [388](#)
- ABSMSUCAPPING parameter in `IEAOPTxx` [388](#)
- ACBPW parameter in `TSOKEY00` [770](#)
- accessibility
  - contact IBM [797](#)
- ACCURACY parameter in `CLOCKxx` [172](#)
- ACDS parameter in `IGDSMSxx` [535](#)
- ACOUPLE parameter in `COUPLExx` [230](#)
- ACR (alternate CPU recovery)
  - specified in `EXSPATxx` member
    - example [315](#)
- ACR parameter in `EXSPATxx` [314](#)
- ACSDEFAULTS parameter in `IGDSMSxx` [535](#)
- action message retention facility [643](#)
- ACTIVE|NOACTIVE parameter
  - in `SMFPRMxx` parmlib member [739](#)
- ADD parameter
  - in `PROGxx` parmlib member [696](#), [703](#)
- address space
  - region size [135](#)
  - specifying maximum number of concurrent [453](#)
- address space quiesce
  - recovery for excessive spinning [313](#)
- ADYSETxx parmlib member
  - description [61](#)
  - IBM-supplied defaults [62](#)
  - overview [14](#)
  - statements and parameters [62](#)
  - syntax rules [61](#)
- AFF parameter in `SCHEDxx` [718](#)
- AFTER parameter
  - in `PROGxx` parmlib member [707](#)
- AKP parameter in `IGDSMSxx` [536](#)
- ALERTAGE parameter in `COFVLFxx` [189](#)
- ALLOC parameter in `IEASYSxx` [427](#)
- ALLOCATE parameter in `IKJTSOxx` [573](#)
- ALLOCxx parmlib member
  - description [67](#)
  - IBM-supplied default [70](#)
  - overview [14](#)
  - statements and parameters [70](#)
  - syntax format [68](#)
  - syntax rules [67](#)
- ALLOWCMD parameter in `CONSOLxx` [208](#)
- alternate CPU recovery [315](#)
- alternate nucleus ID [613](#)
- alternate nucleus substitution [8](#), [613](#)
- AMRF (action message retention facility)
  - description [643](#)
  - selectively retaining action messages [643](#)
- AMRF parameter in `CONSOLxx` [223](#)
- ANTMIN00 parmlib member
  - description [87](#)
  - overview [14](#)
- ANTXIN00 parmlib member
  - description [89](#)
  - overview [14](#)
- APF (authorized program facility)
  - authorization
    - for program libraries [361](#)
    - required for programs in the PPT [716](#)
  - parmlib member [361](#)
  - `PROGxx` parmlib member [685](#)
- APF list
  - defining aliases [686](#)
- APF parameter in `IEASVCxx` [410](#)
- APF parameter in `IEASYSxx` [428](#)
- APF parameter in `PROGxx` [695](#)
- APF statement in `PROGxx` [685](#)
- APF-authorized library list
  - choosing a dynamic or static format [26](#)
  - description [26](#)
  - specifying the contents [27](#)
- APPCPMxx parmlib member
  - description [91](#)
  - overview [14](#)
  - statements and parameters [92](#)
- AREA parameter in `CONSOLxx`
  - maximum and default specification [227](#), [228](#)
- ARM [325](#)
- ASCHPMxx parmlib member
  - description [97](#)
  - overview [15](#)
  - statements and parameters [98](#)
- ASID parameter in `CTnccccxx` [252](#)
- ASID parameter in `IGDSMSxx` [536](#)
- assistive technologies [797](#)

- ATBOTTOM parameter
  - in PROGxx parmlib member [706](#)
- ATTOP parameter
  - in PROGxx parmlib member [706](#)
- AUTH parameter in CONSOLxx [208](#)
- AUTHCMD parameter in IKJTSOxx [574](#)
- authority level
  - for consoles [202](#)
- authorized program facility [379](#)
- AUTHPGM parameter in IKJTSOxx [574](#)
- AUTHSETSMF parameter in SMFPRMxx [739](#)
- AUTHTSF parameter in IKJTSOxx [574](#)
- AUTOACT parameter in CONSOLxx [209](#)
- AUTOMNT file system type
  - customizing in FILESYSTYPE [132](#)
- AUTOR parameter in IEASYSxx [428](#)
- AUTORxx parmlib member
  - description [103](#)
  - overview [15](#)
  - statements and parameters [104](#)
  - syntax format [103](#)
- AXR parameter in IEASYSxx [428](#)
- AXR00 parmlib member
  - overview [15](#)
- AXRxx parmlib member
  - description [107](#)
  - statements and parameters [107](#)
  - syntax format [107](#)

## B

- BASENAME parameter in TSOKEY00 [770](#)
- BIND BREAK completion
  - recovery for excessive spinning [313](#)
- BLOCKTOKENSIZE parameter in IGDSMSxx [538](#)
- BLSCECT parmlib member
  - description [109](#)
  - overview [15](#)
  - statements and parameters [109](#), [113](#)
  - syntax rules [109](#)
- BLSCUSER parmlib member
  - description [111](#)
  - overview [15](#)
  - statements and parameters [113](#)
  - syntax format [112](#)
  - syntax rules [111](#)
- BLWLINTHD parameter in IEAOPTxx [389](#)
- BLWLTRPCT parameter in IEAOPTxx [389](#)
- BMFTIME parameter in IGDSMSxx [547](#)
- BOOST parameter of IEASYSxx [429](#)
- BOX\_LP parameter in IECIOSxx [493](#)
- BPXPRMxx parmlib member
  - description [123](#)
  - example [126](#)
  - overview [15](#)
  - statements and parameters [128](#)
  - syntax [125](#), [126](#)
  - syntax rules [123](#)
- BPXTAMD module name
  - customizing in FILESYSTYPE [132](#)
- BPXTCINT module name
  - customizing in FILESYSTYPE [132](#)
- BPXTFS module name
  - customizing in FILESYSTYPE [132](#)

- BPXTUINT module name
  - customizing in FILESYSTYPE [132](#)
- BPXUNINT module name
  - customizing in FILESYSTYPE [132](#)
- BRANCH parameter
  - CEAPRMxx parmlib member [160](#)
- BREAKPOINTVALUE parameter in IGDSMSxx [538](#)
- BROADCAST operand of SEND parameter [580](#)
- BUFFER parameter in IGDSMSxx [547](#), [550](#)
- BUFRSIZE parameter in TSOKEY00 [770](#)
- BUFSIZE parameter in CTnccccxx [252](#)
- BYPASS\_CLUSTER\_PREFERENCING parameter in IGDSMSxx [538](#)

## C

- CA\_RECLAIM parameter in IGDSMSxx [539](#)
- CACHETIME parameter in IGDSMSxx [539](#)
- CANCEL parameter in SCHEDxx [716](#)
- CAPTUCB parameter in IECIOSxx [496](#)
- CATALOG parameter in IEASYSxx [430](#)
- cataloging [56](#)
- CCCAWMT parameter in IEAOPTxx [389](#)
- CCCSIGUR parameter in IEAOPTxx [390](#)
- CCImp parameter in IEAOPTxx [390](#)
- CCImpBoost parameter in IEAOPTxx [390](#)
- CEA parameter in IEASYSxx [430](#)
- CEAPRMxx parmlib member
  - BRANCH parameter [160](#)
  - COUNTRYCODE parameter [160](#)
  - DUMPCAPTURETIME parameter
    - ABEND operand [160](#), [161](#)
    - DUMP operand [160](#), [161](#)
    - SLIP operand [160](#), [161](#)
  - HLQ(CEA) parameter [161](#)
  - HLQLONG(CEA) parameter [161](#)
  - IBM-supplied defaults [160](#)
  - overview [15](#)
  - SNAPSHOT parameter [162](#)
  - statements and parameters [160](#)
  - STORAGE parameter [162](#)
  - syntax format [159](#)
  - TSOASMGR parameter
    - MAXSESSIONS operand [162](#)
    - MAXSESSPERUSER operand [163](#)
    - RECONSESSIONS operand [163](#)
    - RECONTIME operand [163](#)
- CEE parameter in IEASYSxx [430](#)
- CEEAPRMxx parmlib member
  - syntax rules [159](#)
- CEEPRMxx parmlib member
  - description [165](#)
  - example of [167](#)
  - overview [15](#)
  - statements and parameters [166](#)
  - syntax format [166](#)
- CF\_TIME parameter in IGDSMSxx [539](#)
- CFRMOWNEDCFPROMPT parameter in COUPLExx [231](#)
- CFRMPOL parameter in COUPLExx [232](#)
- CFRMTAKEOVERCF parameter in COUPLExx [232](#)
- changing system symbols [52](#)
- CHAR parameter in IECIOSxx [487](#)
- CHNLEN parameter in TSOKEY00 [770](#)
- CHP statement in CONFIGxx [195](#)

- CICSVR\_BACKOUT\_CONTROL parameter in IGDSMSxx [539](#)
- CICSVR\_DSNAME\_PREFIX parameter in IGDSMSxx [540](#)
- CICSVR\_GENERAL\_CONTROL parameter in IGDSMSxx [540](#)
- CICSVR\_GRPNAME\_SUFFIX parameter in IGDSMSxx [540](#)
- CICSVR\_INIT parameter in IGDSMSxx [539](#)
- CICSVR\_RCDS\_PREFIX parameter in IGDSMSxx [540](#)
- CICSVR\_UNDOLOG\_CONTROL parameter in IGDSMSxx [540](#)
- CICSVR\_UNDOLOG\_PREFIX parameter in IGDSMSxx [540](#)
- CICSVR\_ZZVALUE\_PARM parameter in IGDSMSxx [540](#)
- CINET file system type
  - customizing in FILESYSTYPE [132](#)
- CIPHER parameter in IKJTSOxx [577](#)
- CLASS parameter in COUPLExx [237](#)
- CLASS statement in COFDLFxx [186](#)
- CLASS statement in COFVLFxx [189](#)
- CLASSDEF statement in COUPLExx [237](#)
- CLASSLEN parameter in COUPLExx [232](#), [237](#)
- CLASSNAME parameter in ASCHPMxx [100](#)
- CLEANUP parameter in COUPLExx [233](#)
- CLOCK parameter in IEASYSxx [430](#)
- CLOCKxx parmlib member
  - description [171](#)
  - IBM-supplied default [172](#)
  - overview [15](#)
  - statements and parameters [172](#)
  - syntax format [172](#)
- CLPA parameter of IEASYSxx [431](#)
- CMB parameter of IEASYSxx [431](#)
- CMD parameter in IEASYSxx [432](#)
- CMD parameter in PFKTABxx [682](#)
- CMDDELIM keyword [224](#)
- CMDDELIM parameter in CONSOLxx [224](#)
- CMDLEVEL parameter in CONSOLxx [220](#)
- CMDSYS parameter in CONSOLxx [209](#)
- CMMNDxx parmlib member
  - syntax rules [192](#)
- CNGRP parameter in CONSOLxx [224](#)
- CNGRPxx parmlib member
  - description [177](#)
  - overview [15](#)
- CNLcccxx parmlib member
  - description [179](#)
  - effects of the SET MMS command [179](#)
  - overview [16](#)
  - selection [179](#)
  - statements and parameters [181](#)
- CNTCLIST parameter in IEAOPTxx [391](#)
- CODEPAGE parameter in TSOKEY00 [771](#)
- COFDLFxx
  - statements and parameters [186](#)
- COFDLFxx parmlib member
  - description [185](#)
  - overview [16](#)
- COFVLFxx parmlib member
  - description [187](#)
  - overview [16](#)
  - statements and parameters [189](#)
  - syntax rules [188](#)
- cold start IPL
  - after a system installation [4](#)
  - definition [4](#)
  - reloading the PLPA [4](#)
- COM parameter in COMMNDxx [192](#)
- COMM parameter in IECIOSxx [487](#)
- command delimiter
  - defining [224](#)
- command exit
  - deactivating [658](#)
- COMMDS parameter in IGDSMSxx [535](#)
- comments parameter in IEFSSNxx [790](#)
- COMMNDxx parmlib member
  - description [191](#)
  - overview [16](#)
  - statements and parameters [192](#)
- common area data space
  - specifying maximum number [453](#)
- component trace parmlib member [249](#)
- COMPRESS parameter in IGDSMSxx [540](#)
- CON parameter in CONSOLxx [209](#)
- CON parameter of IEASYSxx [433](#)
- CONEXIT parameter in COFDLFxx [186](#)
- CONFIGxx parmlib member
  - description [193](#)
  - overview [16](#)
  - statements and parameters [195](#)
- CONFTXT parameter in TSOKEY00 [771](#)
- CONparameter in CONSOLxx [209](#)
- CONSNAM(consnam) parameter in IEFSSNxx [518](#)
- console
  - characteristics, defining
    - default routing codes [204](#)
    - IEAVMXIT exit routine [203](#)
    - in MMSLSTxx member [202](#)
    - in MPFLSTxx member [202](#)
    - in PFKTABxx member [202](#)
    - message routing [203](#)
    - using the MONITOR command [203](#)
    - WTO/WTOR buffer limit [203](#)
  - message display
    - defaults [644](#)
  - message display :
    - .MSGCOLR, defaults for [644](#)
- console group parmlib member [177](#)
- console initialization
  - JES3 [222](#)
  - MCS console [222](#)
  - MVS [222](#)
- console message display
  - using the SET command [645](#)
- console name
  - for the system console [214](#)
- CONSOLE statement in CONSOLxx [210](#)
- CONSOLE statement in IKJTSOxx [574](#)
- CONSOLxx parmlib member
  - CONSOLE syntax and parameters [206](#)
  - DEFAULT syntax and parameters [218](#)
  - description [201](#)
  - HARDCOPY syntax and parameters [220](#)
  - overview [16](#)
  - statements and parameters [206](#)
  - syntax rules [205](#)
- contact
  - z/OS [797](#)
- control [644](#)
- converting IEAAPFxx to PROGxx [57](#)
- COPYFROM parameter
  - in PROGxx parmlib member [705](#)
- CORE statement in CONFIGxx [195](#)

- COUNTRYCODE parameter
  - CEAPRMxx parmlib member [160](#)
- COUPLE parameter of IEASYSxx [433](#)
- COUPLExx parmlib member
  - description [229](#)
  - overview [16](#)
  - statements and parameters [230](#)
  - syntax format [230](#)
- CPENABLE parameter in IEAOPTxx [391](#)
- CPU (central processing unit)
  - spin loop condition
    - recovery [313](#)
  - stopped state
    - recovery [313](#)
- CPU statement in CONFIGxx [196](#)
- CPUAD statement in CONFIGxx [196](#)
- CREATE\_POOL macro [593](#)
- CRITICALPAGING/NOCRITICALPAGING parameter in SCHEDxx [719](#)
- cross-system coupling facility [229](#)
- CRYPCTRS parameter in IEASYSxx [434](#)
- CSA (common service area)
  - tracking function
    - DIAGxx parmlib member [295](#)
    - IGGCATxx parmlib member [565](#)
- CSA parameter in IEASYSxx [434](#)
- CSCBLOC parameter of IEASYSxx [435](#)
- CSM (Communication Storage Manager) [593](#)
- CSSLIB parameter
  - in PROGxx parmlib member [701](#)
- CSVLLAxx parmlib member
  - description [243](#)
  - overview [16](#)
  - statements and parameters [244](#)
  - syntax format [244](#)
- CSVLNKPR [57](#)
- CSVLNKPR exec
  - converting LNKLTxx to PROGxx [689](#)
- CTC parameter in IECIOSxx [487](#)
- CTnccccxx parmlib member
  - description [249](#)
  - overview [17](#)
  - statements and parameters [251](#)
  - syntax format [251](#)
- CTRACE macro
  - HEADOPTS parameter [251](#)
  - with the DEFINE parameter [249](#)
- CTRACE parameter in CONSOLxx [225](#)
- CTRACE parameter in COUPLExx [233](#)
- CTRACE parameter in IECIOSxx [495](#)
- CUNUNIXx
  - sample of parmlib member activating a new conversion environment [266](#)
  - sample of parmlib member deleting an inactive conversion environment [266](#)
- CUNUNIXx parmlib member
  - description [255](#)
  - overview [17](#)
  - statements and parameters [256](#)
  - syntax format [256](#)
  - syntax rules [255](#)
- CVIO parameter in IEASYSxx [436](#)

## D

- DAE (dump analysis elimination)
  - ADYSETxx parmlib member [61](#)
- DAPREFIX parameter in IKJTSOxx [577](#)
- DASD parameter in IECIOSxx [487](#)
- data lookaside facility [185](#)
- data set optimization configuration (IEFOPZxx) [507](#), [508](#), [514](#)
- DATA statement in COUPLExx [240](#)
- data verification [794](#)
- DATE statement in CNLccccxx [181](#)
- DAY statement in CNLccccxx [181](#)
- DCCF usage [500](#)
- DCCF=MESSAGE [500](#)
- DCCF=WAIT\_STATE [500](#)
- DDCONS parameter in SMFPRMxx [744](#)
- DEACTIVATE parameter in XCFPOLxx [786](#)
- DEACTTIME parameter in XCFPOLxx [786](#)
- DEFAULT operand in MPFLSTxx [645](#)
- DEFAULT statement in CONSOLxx [218](#)
- defaults
  - DEVSUPxx [270](#)
- DEFAULTS statement in CNLccccxx [182](#)
- DEFINE parameter
  - in PROGxx parmlib member [703](#)
- DEL parameter in CONSOLxx [210](#)
- DELETE parameter
  - in PROGxx parmlib member [696](#), [703](#)
- DELETE parameter in CUNUNIXx [260](#)
- delimiter [224](#)
- DESELECT parameter in IGDSMSxx [542](#)
- DEV parameter in IECIOSxx [487](#)
- DEV statement in CONFIGxx [196](#)
- DEVICE parameter in COUPLExx [238](#), [239](#)
- DEVICE statement in CONFIGxx [196](#)
- device type
  - specifying in VATLSTxx [783](#)
- DEVNUM parameter in CONSOLxx [220](#)
- DEVSUP parameter of IEASYSxx [436](#)
- DEVSUPxx parmlib member
  - description [267](#)
  - IBM-supplied defaults [270](#)
  - overview [17](#)
  - statements and parameters [271](#)
  - syntax format [269](#)
- DEVSUPxx parmlib membersyntax rules [269](#)
- DFHSSIxx parmlib member
  - description [293](#)
  - overview [17](#)
- DFLT110 parameter in IECIOSxx [493](#)
- DFLT111 parameter in IECIOSxx [493](#)
- DFLT112 parameter in IECIOSxx [493](#)
- DFSMSTvs parmlib member
  - parameters, specifying [563](#)
- DIAG parameter in IEASYSxx [436](#)
- DIAGxx parmlib member
  - description [295](#)
  - IBM-supplied default [297](#)
  - overview [17](#)
  - specifying members [295](#)
  - statements and parameters [298](#)
- DIALOG statement
  - in IPCS parmlib members [115](#)

- DINTERVAL parameter in IGDSMSxx [543](#)
- DIRECTORY parameter in IGDSMSxx [547](#), [550](#)
- DLF (data lookaside facility)
  - parmlib member [185](#)
  - setting system defaults [185](#)
- DRMODE parameter [436](#)
- DRMODE parameter in IEASYSxx [436](#)
- DSI parameter in SCHEDxx [717](#)
- DSN keyword in IFGPSEDI [530](#)
- DSNAME parameter
  - in PROGxx parmlib member [696](#), [706](#), [707](#)
  - in SMFPRMxx parmlib member [744](#), [745](#)
- DSNAME parameter in IGDSMSxx [543](#)
- DSNTYPE parameter in IGDSMSxx [543](#)
- DSP parameter in GTFPARM [337](#)
- DSSTIMEOUT parameter in IGDSMSxx [543](#)
- dump analysis elimination [61](#)
- DUMP operand
  - DUMPCAPTURETIME parameter
    - CEAPRMxx parmlib member [160](#), [161](#)
- DUMP parameter in IEASYSxx [437](#)
- DUMPABND parameter
  - in SMFPRMxx [745](#)
- DUMPCAPTURETIME parameter
  - CEAPRMxx parmlib member [160](#)
- DVIO parameter in IEAOPTxx [391](#)
- DVTHRSH parameter in IECIOSxx [493](#)
- dynamic system symbols [34](#)

## F

- ECSA MAX parameter in IVTPRM00 [593](#)
- EDSN parameter in COFVLfxx [189](#)
- EDT (eligible device table)
  - removed in MVS/SP 5.1
  - [713](#)
- EMAJ parameter in COFVLfxx [190](#)
- EMPTYEXCPSEC parameter in SMFPRMxx [745](#)
- END parameter in GTFPARM [337](#)
- END statement
  - in IPCS parmlib members [116](#)
- ENGTRANS parameter in TSOKEY00 [771](#)
- enhanced data integrity parmlib member [529](#)
- EPNAME parameter in IEASVCxx [411](#)
- ERV parameter in IEAOPTxx [391](#)
- ESTOR statement in CONFIGxx [197](#)
- ESTORE parameter in XCFPOLxx [787](#)
- ETR (external time reference) [171](#)
- ETRDELTA parameter in CLOCKxx [173](#)
- ETRMODE parameter in CLOCKxx [173](#)
- ETRZONE parameter in CLOCKxx [173](#)
- example [193](#)
- excessive spin loop [313](#)
- EXCLUDE statement in NUCLSTxx [679](#)
- EXEPRMxx parmlib member
  - overview [17](#)
- EXIT parameter in IEASYSxx [438](#)
- EXIT statement
  - in IPCS parmlib members [116](#)
- EXIT statement in PROGxx [686](#)
- EXITNAME parameter in EXITxx [312](#)
- EXITxx parmlib member
  - description [311](#)
  - overview [17](#)

- EXITxx parmlib member (*continued*)
  - statements and parameters [312](#)
- EXSPATxx parmlib member
  - current statements and parameters [314](#)
  - description [313](#)
  - IBM-supplied default [314](#)
  - overview [17](#)
- external time reference [171](#)
- EZBPFINI load module
  - in BPXPRMxx [152](#)
- EZBPFINI module name
  - customizing in FILESYSTYPE [132](#)

## F

- FEATURENAME parameter in IFAPRDxx [524](#)
- FICON parameter [495](#)
- FICON parameter in IECIOSxx [495](#)
- FIX parameter in IEASYSxx [438](#)
- fixed link pack area [379](#)
- fixed LPA [379](#)
- FIXED MAX parameter in IVTPRM00 [593](#)
- fixed page
  - assigned in the PPT [718](#)
- FLOOD
  - SMFPRMxx parameter [745](#)
- FLPA (fixed link pack area)
  - parmlib member [379](#)
- FORMAT parameter in CNLcccxx [181](#)
- FORMAT parameter in PROGxx [695](#)
- FULLPRESYSTEM parameter in IEAOPTxx [392](#)
- FUNCTIONS statement in COUPLExx [236](#)
- FXE parameter of IEASYSxx [439](#)
- FXEPRMxx
  - syntax [317](#)
- FXEPRMxx parmlib member
  - description [317](#)
  - statements and parameters [317](#)

## G

- GDEICASB program [723](#)
- GDEISASB program [723](#)
- GDEISBOT program [723](#)
- generic entry for volume
  - in VATLSTxx [775](#)
- generic volume serial number
  - specifying [780](#)
- GET\_LIB\_ENQ keyword in CSVLLAxx [246](#)
- GFSCINIT module name
  - customizing in FILESYSTYPE [132](#)
- GNAME parameter in TSOKEY00 [771](#)
- GRAF parameter in IECIOSxx [488](#)
- GREATER\_253 parameter in DEVSUPxx [278](#)
- GROUP parameter in COUPLExx [238](#)
- GROUP statement in CNGRPxx [178](#)
- GRS parameter in IEASYSxx [439](#)
- GRSCNF statement of IEASYSxx [440](#)
- GRSCNFxx parmlib member
  - description [319](#)
  - overview [17](#)
  - statements and parameters [321](#)
- GRSMONxx parmlib member



GRSMONxx parmlib member (*continued*)

- defaults [327](#)
- description [325](#)
- overview [17](#)
- parameters [325](#)
- statements [327](#)
- syntax format [327](#)
- syntax rules [325](#)

GRSRNL parameter in IEASYSxx [440](#)

GRSRNLxx parmlib member

- description [331](#)
- overview [17](#)
- statements and parameters [333](#)
- syntax rules [331](#)

GRSRNLXX PROCESSING [794](#)

GTFPARM parmlib member

- description [335](#)
- overview [18](#)
- statements and parameters [337](#)
- syntax rules [335](#)

GTZ parameter in IEASYSxx [441](#)

GTZPRM parmlib member

- overview [18](#)

GTZPRMxx parmlib member

- description [339](#)
- parameters [339](#)
- statements [340](#)
- syntax format [340](#)
- syntax rules [339](#)

## H

HALT parameter in IECIOSxx [488](#)

hard-copy message log

- flagging messages [648](#)
- JES3 messages [648](#)

HARDCOPY statement in CONSOLxx [220](#)

hardware configuration definition [3](#)

HCD (hardware configuration definition)

- I/O configuration [3](#)

HCFORMAT parameter in CONSOLxx [221](#)

HELP parameter in IKJTSOxx [575](#)

HIBFREXT parameter in TSOKEY00 [772](#)

HIDT (hot I/O definition table). [483](#)

HLQ(CEA) parameter

- CEAPRMxx parmlib member [161](#)

HLQLONG(CEA) parameter

- CEAPRMxx parmlib member [161](#)

HOLDMODE parameter in CONSOLxx [219](#)

HONOR\_DSNTYPE\_PDSE (YES|NO) parameter in IGDSMSxx [544](#)

HONORIEFUSIREGION/NOHONORIEFUSIREGION  
parameter in SCHEDxx [719](#)

HOT I/O (HOTIO) [492](#)

HOTIO recovery

- options for [494](#)

HPAV statement in CONFIGxx [200](#)

HSP\_SIZE parameter in IGDSMSxx [547](#)

HVCOMMON parameter in IEASYSxx [441](#)

HVSHARE parameter in IEASYSxx [442](#)

HWNAME of IEASYMxx parmlib member [414](#)

HWNAME parameter in IFAPRDxx [526](#)

HWNAME, segmenting LOADxx statements [615](#)

HYPERPAV parameter in IECIOSxx [496](#)

HYPERWRITE parameter in IECIOSxx [497](#)

HZS parameter in IEASYSxx [442](#)

HZSPRMxx parmlib member

- description [351](#)
- overview [18](#)

HZSPROC parameter in IEASYSxx [442](#)

## I

I/O timing [485](#)

IAFAPRDxx parmlib member

- examples [527](#)

IARPRMxx parmlib member

- example of [354](#)

- overview [18](#)

- Real Storage Manager controls [353](#)

- specifying members [353](#)

- statements and parameters [353](#)

- syntax rules [353](#)

IBM zHyperWrite data replication [497](#)

IBM-supplied default [128](#)

ICSF parameter in IEASYSxx [443](#)

ICSFPROC parameter in IEASYSxx [443](#)

ID parameter in IFAPRDxx [524](#)

IDAVDTx

- DSNAME parameter [355](#)

IDAVDTx parmlib member

- overview [18](#)
- statements and parameters [355](#)
- VSAM dynamic trace parameters [355](#)

IDAVSJST program [723](#)

IEAABD00 parmlib member

- description [357](#)
- IBM-supplied default [358](#)
- overview [18](#)
- PDATA parameter [358](#)
- syntax rules [357](#)

IEAAPFxx parmlib member

- description [361](#)
- IBM-supplied default [363](#)
- overview [18](#)
- statements and parameters [363](#)

IEAAPP00 parmlib member

- description [365](#)
- overview [19](#)
- statements and parameters [365](#)

IEACMD00 parmlib member

- description [367](#)
- IBM-supplied default [368](#)
- overview [19](#)
- statements and parameters [368](#)
- syntax rules [368](#)

IEADMCxx parmlib member

- description [369](#)
- overview [19](#)
- statements and parameters [369](#)
- syntax rules [369](#)

IEADMP00

- syntax rules [373](#)

IEADMP00 parmlib member

- description [373](#)
- IBM-supplied default [374](#)
- overview [19](#)
- statements and parameters [374](#)

- IEADMR00
  - statements and parameters [378](#)
- IEADMR00 parmlib member
  - description [377](#)
  - IBM-supplied default [378](#)
  - overview [19](#)
  - syntax rules [377](#)
- IEAFIXxx
  - statements and parameters [381](#)
- IEAFIXxx parmlib member
  - description [379](#)
  - overview [19](#)
- IEALPaxx parmlib member
  - description [383](#)
  - overview [19](#)
  - statements and parameters [385](#)
  - syntax example [384](#)
  - syntax format [384](#)
  - syntax rules [384](#)
- IEANUC0x member
  - substituting an alternate [8](#)
- IEAOPTxx
  - FULLPRESYSTEM parameter [392](#)
- IEAOPTxx parmlib member
  - description [387](#)
  - IBM-supplied default [388](#)
  - overview [20](#)
  - statements and parameters [388](#)
- IEAPAKxx parmlib member
  - description [403](#)
  - IBM-supplied default [404](#)
  - overview [20](#)
  - syntax and parameters [404](#)
  - syntax rules [403](#)
- IEASLPxx parmlib member
  - description [405](#)
  - IBM-supplied default [406](#)
  - overview [20](#)
  - syntax arules [405](#)
- IEASVCxx parmlib member
  - description [409](#)
  - overview [20](#)
  - statements and parameters [410](#)
- IEASYMxx parmlib member
  - coding [43](#), [44](#)
  - contents of [42](#)
  - description [413](#)
  - HWNAME parameter [414](#)
  - LPARNAME parameter [414](#)
  - overview [20](#)
  - statements and parameters [414](#)
  - SYMDEF parameter [415](#)
  - SYSCLONE parameter [417](#)
  - SYSNAME parameter [418](#)
  - SYSARM parameter [417](#)
  - VMUSERID parameter [418](#)
- IEASYSxx
  - BOOST parameter [429](#)
  - CSCBLOC parameter [435](#)
  - MAXCAD parameter [453](#)
  - UNI parameter [478](#)
- IEASYSxx parmlib member
  - CMB parameter [431](#)
  - description [421](#)
- IEASYSxx parmlib member (*continued*)
  - FXE parameter [439](#)
  - GRSCNF statement [440](#)
  - HVSHARE parameter [442](#)
  - IQP parameter [444](#)
  - LICENSE parameter [449](#)
  - MAXUSER parameter [453](#)
  - overview [21](#)
  - PAGESCM parameter [462](#)
  - parameter supplied by operator [405](#)
  - parameters, overview [421](#)
  - specifying members [353](#)
  - statements and parameters [427](#)
  - syntax rules [426](#)
- IEASYSxx parmlib memberEKM parameter in IEASYSxx
  - EKM parameter [497](#)
- IECIOSxx
  - CAPTUCB [496](#)
- IECIOSxx parmlib member
  - description [483](#)
  - HYPERPAV [496](#)
  - HYPERWRITE parameter [497](#)
  - MIDAW parameter [496](#)
  - overview [21](#)
  - RECOVERY parameter [503](#)
  - syntax examples [506](#)
  - syntax rules [484](#)
- IECIOSxx parmlib statement
  - SPOF [504](#)
  - ZHL [505](#)
  - ZHPF [504](#)
  - ZHPFOPTS [505](#)
  - ZHYPERLINK [505](#)
- IEFOPZ parameter in IEASYSxx [443](#)
- IEFOPZxx parmlib member
  - description [507](#)
  - IBM-supplied default [508](#)
  - overview [21](#)
  - statements and parameters [508](#)
  - syntax format [507](#)
  - syntax rules [507](#)
  - usage notes [514](#)
- IEFSSNxx parmlib member
  - defining SMS [531](#)
  - description [515](#), [789](#)
  - overview [21](#)
  - restrictions [515](#)
  - statements and parameters [517](#), [791](#)
  - syntax rules [517](#)
- IEFUSI user exit [135](#)
- IFAPRDxx parmlib member
  - description [521](#)
  - overview [21](#)
  - PRODUCT statement [523](#)
  - syntax format [523](#)
  - WHEN statement [523](#)
- IFGPSEDI parmlib member
  - description [529](#)
  - overview [21](#)
  - statements and parameters [530](#)
- IGDSMSxx parmlib member
  - description [531](#)
  - optional keywords [535](#)
  - overview [22](#)

IGDMSxx parmlib member (*continued*)  
 syntax format [533](#)  
 syntax rules [533](#)

IGGCATxx  
 syntax rules for [565](#)

IGGCATxx parmlib member  
 description [565](#)  
 overview [22](#)  
 parameters for [567](#)  
 statements for [567](#)  
 syntax format [566](#)  
 syntax rules [565](#)

IIPHONORPRIORITY parameter in IEAOPTxx [392](#), [401](#)

IKJTSO parameter in IEASYSxx [444](#)

IKJTSOxx member  
 selecting [571](#)

IKJTSOxx parmlib member  
 description [571](#)  
 overview [22](#)  
 parameters for [573](#)  
 syntax format of [573](#)

IMBED statement  
 in IPCS parmlib members [118](#)

Improved Data Recording Capability feature  
 setting defaults [267](#)

INCLUDE statement in NUCLSTxx [679](#)

indirect reference [55](#)

indirect volume serial support [55](#), [56](#)

INET file system type  
 customizing in FILESYSTYPE [132](#)

InfoWindow display device  
 specified in CONSOLxx member [217](#)

INIT statement in CONSOLxx [222](#)

init-routine parameter in IEFSSNxx [790](#)

initial program load [4](#)

INITIMP parameter in IEAOPTxx [393](#)

INITPARM(initparm) parameter in IEFSSNxx [518](#)

INITRTN(initrtn) parameter in IEFSSNxx [518](#)

installation exit  
 defining  
   in EXITxx parmlib member [311](#)  
   in PROGxx parmlib member [685](#)  
 specifying [29](#)

interactive problem control system [109](#), [111](#)

INTERVAL parameter in COUPLExx [233](#)

INTERVAL parameter in IGDMSxx [544](#)

INTSECT release  
 recovery for excessive spinning [313](#)

IOEFSCM module name  
 customizing in FILESYSTYPE [132](#)

IOEPRMxx parmlib member  
 description [585](#)  
 overview [22](#)

IOS parameter in IEASYSxx [444](#)

IOSVROUT program [723](#)

IOTDASD parameter in IECIOSxx [488](#)

IOTHSWAP parameter in IECIOSxx [488](#)

IOTTAPE parameter in IECIOSxx [488](#)

IOTTERM parameter in IECIOSxx [488](#)

IPCS (interactive problem control system)  
 exit routines  
   specified in BLSCECT member [109](#)  
   specified in BLSCUSER member [111](#)

IPCSPARM data set [109](#)

IPCSPRnn parmlib member  
 description [587](#)  
 IBM-supplied default [587](#)  
 session parameters [587](#)  
 syntax rules [587](#)

IPCSPRxx parmlib member  
 overview [22](#)

IPCSRPRnn parmlib member  
 statements and parameters [587](#)

IPL (initial program load)  
 type of IPL [4](#)

IPXLOADX member of SYS1.SAMPLIB [618](#)

IQP parameter in IEASYSxx [444](#)

IQPPRMxx parmlib member  
 description [589](#)  
 overview [22](#)  
 session parameters [589](#)

IRA405I parameter in IEAOPTxx [393](#)

IRRPRMxx parmlib member  
 description [591](#)  
 overview [22](#)

IVTPRM00 parmlib member  
 description [593](#)  
 IBM-supplied defaults [593](#)  
 overview [22](#)  
 statements and parameters [594](#)  
 syntax format [593](#)

IXCINJST program [723](#)

IXGCNF parameter in IEASYSxx [444](#)

IXGCNFxx parmlib member  
 description [597](#)  
 overview [23](#)  
 specifying [597](#)  
 statements and parameters [599](#)  
 syntax format [599](#)  
 syntax rules [598](#)

IZU parameter in IEASYSxx [445](#)

IZUPRMxx parmlib member  
 description [609](#)  
 overview [23](#)

## J

JCL (job control language)  
 master JCL [9](#)

JES (job entry subsystem)  
 master JCL  
   defining [9](#)  
   IEFSSNxx parmlib member [9](#)  
   START command [9](#)

JES messages  
 suppressible  
   aggressive list [661](#)  
   conservative list [661](#)

job control language [9](#)

job entry subsystem [9](#)

JOB statement  
 syntax and parameters [670](#)

JOBNAME parameter in CTncccx [252](#)

JOBNAME parameter in IGDMSxx [544](#)

JWT parameter in SMFPRMxx [763](#)



## K

KEY parameter in PFKTABxx [682](#)

KEY parameter in SCHEDxx [716](#)

keyboard

navigation [797](#)

PF keys [797](#)

shortcut keys [797](#)

## L

L (list option)

specified in IEASYSxx [427](#)

LFAREA

request handling for insufficiently contiguous online real storage [449](#)

request handling for the LFAREA system limit [448](#)

LFAREA parameter in IEASYSxx [445](#)

LIBRARIES statement in CSVLLAxx [246](#)

library lookaside [367](#)

LICENSE parameter in IEASYSxx [449](#)

LIKEHEAD parameter in CTncccx [253](#)

LINELENGTH parameter in IPCSPRnn [587](#)

LINKLIB parameter

in PROGxx parmlib member [701](#)

LINKLIBE parameter

in PROGxx parmlib member [701](#)

list option (L)

specified in IEASYSxx [427](#)

LISTDSN parameter in SMFPRMxx [749](#)

LLA (library lookaside)

creating the LNKLST concatenation [690](#)

IEACMD00 member [367](#)

LLA REFRESH command [691](#)

START command [367](#)

SYS1.PROCLIB library [367](#)

LLA REFRESH command [691](#)

LNK parameter in IEASYSxx [423](#), [450](#)

LNKAUTH parameter in IEASYSxx [450](#)

LNKAUTH system parameter

effect [691](#)

LNKLST concatenation

APF authorization [691](#)

APF parameter in IEASYSxx [428](#)

cataloging data sets [691](#)

concatenation [690](#)

creation [690](#)

description [690](#)

IEAFIXxx [379](#)

IEALPAxx member [383](#)

LNKAUTH system parameter [363](#)

specified in IEASYSxx member [363](#)

specifying [611](#)

SYS1.LINKLIB [690](#)

using PDSE data sets [691](#)

LNKLST set

activating [704](#)

definition [688](#)

locating a routine [704](#)

relationship to LNKLST concatenation [688](#)

LNKLST statement

examples [707](#)

LNKLST statement in PROGxx [688](#)

LNKLST statement in PROGxx parmlib member [702](#), [703](#)

LNKLSTxx parmlib member

description [611](#)

overview [23](#)

syntax example [612](#)

syntax rules [611](#)

using PROGxx instead of [611](#)

LNKMEMBERS statement in CSVLLAxx [246](#)

LOAD system parameter

operator entry [5](#)

LOADxx parmlib member

coding [46](#)

description [613](#)

filtering [614](#)

overview [23](#)

placing [613](#)

statements and parameters [618](#)

syntax format [617](#)

LOBFREXT parameter in TSOKEY00 [772](#)

LOCALMSG statement in COUPLExx [239](#)

LOCKS parameter in IEASVCxx [411](#)

LOG\_OF\_LOGS parameter in IGDSMSxx [545](#)

LOGCLS parameter in IEASYSxx [450](#)

logical extensions [55](#)

logical unit [91](#)

LOGLIM parameter in CONSOLxx [223](#)

LOGLMT parameter in IEASYSxx [451](#)

LOGNAME parameter in IKJTSOxx [577](#)

LOGON parameter in CONSOLxx [218](#)

LOGON parameter in IKJTSOxx [575](#)

LOGREC parameter in IEASYSxx [451](#)

LOGSEL parameter in IKJTSOxx [578](#)

LPA

PROGxx parmlib member [685](#)

LPA parameter in IEASYSxx [452](#)

LPA statement in PROGxx [693](#)

LPA statements

syntax format [708](#)

LPALIB parameter

in PROGxx parmlib member [701](#)

LPALST concatenation [635](#)

LPALST parmlib member

statements and parameters [637](#)

LPALSTxx parmlib member

description [635](#)

overview [23](#)

LPARNAME of IEASYMxx parmlib member [414](#)

LPARNAME parameter in IFAPRDxx [526](#)

LPARNAME, segmenting LOADxx statements [615](#)

LPREF parameter in SCHEDxx [718](#)

LRUCYCLES parameter in IGDSMSxx [548](#)

LRUTIME parameter in IGDSMSxx [549](#)

LSNAME

in SMFPRMxx parmlib member [749](#)

LU (logical unit)

definition in parmlib [91](#)

## M

MANAGENONENCLAVEWORK parameter in IEAOPTxx [394](#)

master catalog

specifying an alternate [8](#)

master JCL

alternate versions [9](#)

changing [9](#)

- master JCL (*continued*)
  - defining the job entry subsystem [9](#)
  - MSTJCL00 load module [9](#)
  - MSTJCLxx parmlib member [675](#)
  - START command [9](#)
  - updating
    - example [9](#)
- master scheduler JCL data set
  - adding MSTJCLxx statements [12](#)
  - defining the job entry subsystem [10](#)
  - IBM-supplied sample
    - IEESMJCL member [10](#)
    - SYS1.SAMPLIB [10](#)
  - IEFSSNxx member
    - deleting the JES START command [10](#)
  - modifying [12](#)
  - MSTRJCL parameter in IEASYSxx [10](#)
- master trace table
  - setting size [713](#), [715](#)
- MAXCAD parameter of IEASYSxx [453](#)
- MAXCONN parameter in IECIOSxx [499](#)
- MAXDORM parameter in SMFPRMxx [753](#)
- MAXEVENTINTRECS
  - SMFPRMxx parameter [753](#)
- MAXEXPB parameter in COFDLFxx [186](#)
- MAXGENS\_LIMIT parameter in IGDSMSxx [545](#)
- MAXLOCKS parameter in IGDSMSxx [545](#)
- MAXMSG parameter in COUPLExx [234](#), [237](#), [238](#)
- MAXPCONN parameter in IECIOSxx [499](#)
- MAXPROMOTETIME parameter in IEAOPTxx [395](#)
- MAXSESSIONS operand
  - TSOASMGR parameter
    - CEAPRMxx parmlib member [162](#)
- MAXSESSPERUSER operand
  - TSOASMGR parameter
    - CEAPRMxx parmlib member [163](#)
- MAXUIDS parameter in BPXPRMxx [139](#)
- MAXUSER parameter in IEASYSxx [453](#)
- MAXUSERMOUNTSYS parameter in BPXPRMxx [139](#)
- MAXUSERMOUNTUSER parameter in BPXPRMxx [139](#)
- MAXVIRT parameter in COVFLFxx [190](#)
- MCCFXEPR parameter in IEAOPTxx [395](#)
- MCCFXTPR parameter in IEAOPTxx [395](#)
- MCS (multiple console support)
  - device used as MCS console [226](#)
- member selection list [795](#)
- MEMBERS keyword in CNGRPxx [178](#)
- MEMLIMIT parameter in SMFPRMxx [754](#)
- message
  - at the operator's console [643](#)
  - control [643](#)
  - display [643](#)
  - management [643](#)
  - presentation [643](#)
- message area
  - .MSGCOLR statement [645](#)
  - color attribute [645](#)
  - default values for display [645](#)
  - highlighting attribute
    - intensity attribute [645](#)
- message automation
  - NetView subsystem [647](#)
- message management
  - automation [643](#)
- message management (*continued*)
  - controllingsyntax for [649](#)
  - exit routine [643](#)
  - flagging JES3 messages [648](#)
  - retention [643](#)
  - suppression [643](#)
- message managements
  - IBM defaults for [649](#)
- message presentation
  - control
    - .MSGCOLR statement [644](#)
    - MPFLSTxx parmlib member [644](#)
- message processing
  - .DEFAULT statement
    - options [653](#)
    - syntax [653](#)
  - controlling
    - defining color [648](#)
    - defining highlighting [648](#)
    - defining intensity [648](#)
  - examples in MPFLSTxx
    - automation processing [663](#)
    - overriding system defaults [663](#)
    - passing a token [663](#)
- message suppression
  - methods [659](#)
- MPFHCF statement
  - options [655](#)
  - syntax [655](#)
- MPFLSTxx parmlib member [647](#), [648](#)
- MSGID NOCHANGE statement [655](#)
- msgid parameter
  - options [648](#), [651](#)
  - syntax [648](#), [651](#)
- options [656](#)
- syntax [656](#)
- message processing facility list [643](#)
- message routing
  - for consoles [202](#)
- message table [648](#)
- message type [645](#)
- MFORM parameter in CONSOLxx [213](#)
- MIDAW parameter in IECIOSxx [496](#)
- MIGLIB parameter
  - in PROGxx parmlib member [701](#)
- MIGLIBE parameter
  - in PROGxx parmlib member [701](#)
- MIH (missing interrupt handler)
  - statements and parameters [487](#)
- missing interrupt handler [484](#)
- missing interrupt handler (MIH)
  - statements and parameters [487](#)
- MLIM parameter in CONSOLxx [222](#)
- MLPA (modified link pack area)
  - adding module
    - through the MLPA parameter [379](#)
- MLPA parameter in IEASYSxx [454](#)
- MMS parameter in CONSOLxx [223](#)
- MMSLSTxx
  - statements and parameters [640](#)
- MMSLSTxx parmlib member
  - description [639](#)
  - overview [23](#)
- MNTS parameter in IECIOSxx [489](#)

- MOD parameter in IFAPRDxx [524](#)
- MODE parameter in TSOKEY00 [772](#)
- MODE statement in IFGPSEDI [530](#)
- MODESW parameter in TSOKEY00 [772](#)
- modified link pack area [379](#)
- MODIFY CSM command [593](#)
- MODNAME parameter in EXITxx [312](#)
- MONITOR parameter on CONSOLE statement [213](#)
- MONITOR parameter on INIT statement [224](#)
- MONTH statement in CNLcccxx [182](#)
- mount attribute
  - specifying in VATLSTxx [782](#)
- mount message suppression
  - specifying in VATLSTxx [783](#)
- MOUNTMSG parameter in IECIOSxx [489](#)
- MPF parameter in CONSOLxx [223](#)
- MPFHCF parameter in MPFLSTxx [655](#)
- MPFHCF statement in MPFLSTxx
  - defaults [648](#)
  - purpose [648](#)
- MPFLSTxx
  - statements and parameters [651](#)
- MPFLSTxx parmlib member
  - .FORNSSI statement
    - syntax rules for [650](#)
  - command processing [643](#)
  - controlling message presentation
    - .MSGCOLR statement [644](#)
  - controlling message processing
    - syntax [648](#)
  - controlling verbose message production [650](#)
  - description [643](#)
  - examples [662](#)
  - IBM defaults for message management [649](#)
  - message display
    - defaults [644](#)
  - message management
    - syntax [649](#)
  - message processing [647](#)
  - message suppression [649](#)
  - message table [648](#)
  - overview [24](#)
- MPFLSTxx parmlib members
  - parameters for managing verbose message production [651](#)
  - verbose message production
    - controlling [651](#)
- MSCOPE parameter in CONSOLxx [214](#)
- msgarea parameter in MPFLSTxx [645](#)
- MSGFLD parameter in CONSOLxx [226](#)
- MSGFLDxx
  - syntax rules [665](#)
- MSGFLDxx parmlib member
  - description [665](#)
  - IBM-supplied default [666](#)
  - statements and parameters [667](#)
- msgid parameter in MPFLSTxx
  - defaults [648](#)
  - purpose [648](#)
- MSGIDS statement in MPFLSTxx
  - defaults [648](#)
  - purpose [648](#)
- MSGONLY parameter in IECIOSxx [489](#)
- MSGPROTECT operand of SEND parameter [582](#)

- MSTJCL00 load module
  - changing [9](#)
- MSTJCLxx load module in SYS1.LINKLIB
  - changing [9](#)
- MSTJCLxx parmlib member
  - changing [9](#)
  - description [675](#)
  - overview [24](#)
  - statements and parameters [676](#)
- MSTRJCL parameter in IEASYSxx [10](#), [455](#)
- MSTRJCL system parameter [9](#)
- MT statement in SCHEDxx [715](#)
- MT\_CP\_MODE parameter in IEAOPTxx [396](#)
- MT\_ZIIP\_MODE parameter in IEAOPTxx [396](#)
- multiple console support [226](#)
- MVS message service list [639](#)

## N

- NAME keyword in CNGRPxx [178](#)
- NAME parameter
  - in PROGxx parmlib member [705](#)
- NAME parameter in COFVLFxx [190](#)
- NAME parameter in CONSOLxx [214](#)
- NAME parameter of IFAPRDxx [525](#)
- navigation
  - keyboard [797](#)
- NetView subsystem [647](#)
- Network File System (NFS)
  - customizing in FILESTYPE [132](#)
- NETWORK statement in BPXPRMxx [144](#)
- NOAUTHSETSMF parameter in SMFPRMxx [739](#)
- NOCHANGE option on the .MSGCOLR statement [645](#)
- NOCHANGE parameter in MPFLSTxx [655](#)
- NOCHECK parameter
  - in PROGxx parmlib member [706](#)
- NODESMF parameter in IKJTSOxx [577](#)
- NOLISTDSN parameter in SMFPRMxx [749](#)
- NOMAXDORM parameter in SMFPRMxx [753](#)
- non-JES messages
  - suppressible
    - aggressive list [660](#)
    - conservative list [659](#)
- NONVIO parameter in IEASYSxx [455](#)
- NOPREF parameter in SCHEDxx [718](#)
- NOPROMPT parameter in SMFPRMxx [755](#)
- NOREFRPROT [694](#)
- NOREFRPROT statement in PROGxx [694](#)
- NORESTART statement in SCHEDxx [715](#)
- NOSTART parameter in IEFSSNxx [790](#)
- NOSTATUS parameter in SMFPRMxx [760](#)
- NOSTATUS statement in XCFPOLxx [786](#)
- NOTBKGND parameter in IKJTSOxx [576](#)
- NOTE statement
  - in IPCS parmlib members [119](#)
- NOTRACKDIRLOAD statement in PROGxx [694](#)
- NOWRAP parameter in CTncccxx [254](#)
- NPRMPT parameter in IEASVCxx [411](#)
- NSYSLX parameter of IEASYSxx [456](#)
- nucleus
  - substituting an alternate [8](#), [613](#)
- nucleus region
  - load module
    - adding [677](#)

nucleus region (*continued*)

load module (*continued*)

excluding [677](#)

replacing [677](#)

NUCLSTxx parmlib member

description [677](#)

in the SYSn.IPLPARM data set [678](#)

nucleus region

adding load modules [677](#)

replacing load modules [677](#)

overview [24](#)

statements and parameters [679](#)

## O

OAMTASK parameter in IGDSMSxx [546](#)

OFF parameter in CTnccccxx [253](#)

OMVS parameter in IEASYSxx [457](#)

ON parameter in CTnccccxx [251](#)

OPER parameter in EXSPATxx [314](#)

operator command

and system tailoring [3](#)

operator console

display [644](#)

OPERATOR parameter in CLOCKxx [174](#)

OPI parameter in IEASYSxx [457](#)

OPNOTIFY parameter in COUPLExx [234](#)

OPT parameter of IEASYSxx [458](#)

OPTIONS parameter in CTnccccxx [252](#)

OSPROTECT parameter in IEASYSxx [459](#)

OUTLIM parameter in IKJTSOxx [578](#)

OUTWARN parameter in IKJTSOxx [579](#)

override expiration date

on SMS-managed DASD data set [539](#), [546](#)

OVRD\_EXPDT parameter in IGDSMSxx [546](#)

OWNER parameter in IFAPRDxx [524](#)

## P

page data set

specifying [460](#)

PAGE parameter in IEASYSxx [459](#)

pageable link pack area [379](#)

PAGESCM parameter in IEASYSxx [462](#)

PAGESIZE parameter in IPCSPRnn [587](#)

paging space

minimum amount required [461](#)

shortage [461](#)

PAGTOTL parameter in IEASYSxx [462](#)

PAK parameter in IEASYSxx [464](#)

PANDEF statement

in IPCS parmlib members [119](#)

Parallel Access Volumes (PAV) [199](#)

parm parameter in IEFSSNxx [790](#)

parmlib

controlling [6](#)

parmlib concatenation [613](#), [628](#)

Parmlib Concatenation

using [6](#)

parmlib member

ADYSETxx [61](#)

ALLOCxx [67](#)

ANTMIN00 [87](#)

parmlib member (*continued*)

ANTXIN00 [89](#)

APPCPMxx [91](#)

ASCHPMxx [97](#)

AUTORxx [103](#)

AXRxx [107](#)

BLSCCT 109

BLSCUSER [111](#)

BPXPRMxx [123](#)

CEEPRMxx [165](#)

CLOCKxx [171](#)

CNGRPxx [177](#)

CNLccccxx [179](#)

COFDLFxx [185](#)

COFVLFxx [187](#)

COMMNDxx [191](#)

CONFIGxx [193](#)

CONSOLxx [201](#)

COUPLExx [229](#)

CSVLLAxx [243](#)

CTnccccxx [249](#)

CUNUNIx

sample of parmlib member activating a new

conversion environment [266](#)

sample of parmlib member deleting an inactive

conversion environment [266](#)

DEVSUPxx [267](#)

DFHSSIxx [293](#)

DIAGxx [295](#)

EXITxx [311](#)

EXSPATxx [313](#)

FXEPRMxx [317](#)

GRSCNFxx [319](#)

GRSMONxx [325](#), [327](#)

GTFPARMxx [335](#)

GTZPRMxx [339](#), [340](#)

HZSPRMxx [351](#)

IEAABD00 [357](#)

IEAAPFxx [361](#)

IEAAP00 [365](#)

IEACMD00 [367](#)

IEADMCxx [369](#)

IEADMP00 [373](#)

IEADMR00 [377](#)

IEAFIXxx [379](#)

IEALPAxx [383](#)

IEAOPTxx [387](#)

IEAPAKxx [403](#)

IEASLPxx [405](#)

IEASVCxx [409](#)

IEASYMxx [413](#)

IEASYSxx [421](#)

IECIOSxx [483](#)

IEFOPZxx [507](#)

IEFSSNxx [515](#), [789](#)

IFAPRDxx [521](#)

IFGPSEDI [529](#)

IGDSMSxx [531](#)

IGGCATxx [565](#)

IKJTSOxx [571](#)

IOEPRMxx [585](#)

IPCSPRnn [587](#)

IQPPRMxx [589](#)

IRRPRMxx [591](#)

parmlib member (*continued*)

- IVTPRM00 [593](#)
- IXGCNFxx [597](#)
- IZUPRMxx [609](#)
- LNKLSTxx [611](#)
- LOADxx [613](#)
- LPALSTxx [635](#)
- MMSLSTxx [639](#)
- MPFLSTxx [643](#)
- MSGFLDxx [665](#)
- MSTJCLxx [675](#)
- NUCLSTxx [677](#)
- objectives for sharing [31](#)
- PFKTABxx [681](#)
- PROGxx [685](#)
- SCHEDxx [713](#)
- sharing [8](#)
- SMFLIMxx [725](#)
- SMFPRMxx [735](#)
- syntax rules [7](#)
- system symbols [31](#)
- TSOKEY00 [769](#)
- VATLSTxx [775](#)
- XCFPOLxx [785](#)
- parmlib member selection list [795](#)
- parmlib symbolic preprocessing [794](#)
- PASS parameter in SCHEDxx [718](#)
- path recovery [501](#)
- PATH\_SCOPE=CU [501](#)
- PATH\_SCOPE=DEVICE [502](#)
- PATHIN statement in COUPLExx [238](#)
- PATHOUT statement in COUPLExx [239](#)
- PAV statement in CONFIGxx [199](#)
- PCI parameter in GTFPARM [337](#)
- PCOUPLE parameter in COUPLExx [234](#)
- PCTRETB parameter in COFDLFxx [186](#)
- PDSE (partitioned data set extended)
  - sharing across systems in a sysplex [552](#)
  - starting or modifying the PDSE monitor [547](#)
- PDSE\_MONITOR parameter in IGDSMSxx [547](#), [549](#)
- PDSE\_PENDING\_DELETE\_INTERVAL parameter in IGDSMSxx [549](#)
- PDSE\_RESTARTABLE\_AS parameter in IGDSMSxx [549](#)
- PDSE\_SYSEVENT\_DONTSWAP parameter in IGDSMSxx [552](#)
- PDSE\_VERSION parameter in IGDSMSxx [550](#)
- PDSE!\_LRUTIME parameter in IGDSMSxx [552](#)
- PDSE1\_BMFTIME parameter in IGDSMSxx [550](#)
- PDSE1\_HSP\_SIZE parameter in IGDSMSxx [550](#)
- PDSE1\_LRUCYCLES parameter in IGDSMSxx [551](#)
- PDSE1\_MONITOR parameter in IGDSMSxx [552](#)
- PDSESHARING parameter in IGDSMSxx [552](#)
- PFID statement in CONFIGxx [198](#)
- PFK parameter in CONSOLxx [223](#)
- PFK parameter in PFKTABxx [682](#)
- PFK settings in CONSOLxx [201](#)
- PFKTAB parameter in CONSOLxx [214](#)
- PFKTABxx parmlib member
  - description [681](#)
  - overview [24](#)
  - statements and parameters [682](#)
  - syntax rules [681](#)
- PGNNAME parameter in SCHEDxx [716](#)
- planning
  - IEASYMxx parmlib member [41](#)

planning (*continued*)

- LOADxx parmlib member [46](#)
- values, specifying [31](#)
- PLATCMD statement in IKJTSOxx [576](#)
- PLATPGM parameter in IKJTSOxx [576](#)
- PLEXCFG parameter in IEASYSxx [464](#)
- PLPA (pageable link pack area)
  - adding module
    - through the INCLUDE parameter [381](#)
- POLICY parameter in ALLOCxx [77](#)
- POOL parameter in IVTPRM00 [593](#)
- PPT (program properties table)
  - APF-authorization [716](#)
  - default entries [713](#)
  - effects of the SET SCH command [714](#)
  - IBM-supplied PPT [714](#)
  - modifying [714](#)
  - preferred storage frame
    - assigning [718](#)
  - special properties
    - assigning [713](#)
  - V=R program [716](#)
  - V=V program [716](#)
  - values for [720](#)
  - with VARY STOR,OFFLINE [719](#)
- PPT statement in SCHEDxx [716](#)
- preferred storage frame
  - assigning [718](#)
- PRESCPU parameter in IEASYSxx [465](#)
- PRESET parameter in CTnccccxx [249](#), [253](#)
- PRIMARY parameter in IECIOSxx [498](#)
- PRIMARY parameter in IEFSSNxx [518](#), [790](#)
- PRIV parameter in SCHEDxx [717](#)
- PROC file system type
  - customizing in FILESYSTYPE [132](#)
- processor storage increment size [468](#)
- PROCVIEW [629](#)
- PROD parameter in IEASYSxx [465](#)
- PRODUCT parameter in IFAPRDxx [523](#)
- PRODUCT statement in IFAPRDxx member [523](#)
- PROG parameter in IEASYSxx [466](#)
- program function key
  - defining the PFK table [681](#)
  - setting [201](#), [681](#)
- program properties table [713](#)
- program properties table (PPT)
  - values for [720](#)
- PROGxx
  - converting LNKLSTxx to PROGxx [689](#)
- PROGxx parmlib member
  - APF statement [685](#)
  - description [685](#)
  - LNKLST [692](#)
  - LNKLST statement [688](#)
  - LPA statement [693](#)
  - overview [24](#)
  - REFRPROT statement [694](#)
  - syntax format of the SYSLIB statement [701](#)
  - SYSLIB statement [687](#), [692](#)
- PROMPT parameter in SMFPRMxx [755](#)

Q

- QTIMEOUT parameter in IGDSMSxx [553](#)



quick start IPL  
after a power-up [4](#)  
definition [4](#)

## R

RACF parameter in IEASYSxx [467](#)  
RBUF parameter in CONSOLxx [215](#)  
RCCFXET parameter in IEAOPTxx [397](#)  
RCCFXTT parameter in IEAOPTxx [397](#)  
RCFBDUMP parameter in TSOKEY00 [772](#)  
RDE parameter in IEASYSxx [467](#)  
REAL parameter in IEASYSxx [467](#)  
REALSTORAGE parameter in CUNUNIXx [262](#)  
REC parameter in SMFPRMxx [755](#)  
RECONNECTIONS operand  
TSOASMGR parameter  
CEAPRMxx parmlib member [163](#)  
RECONLIM parameter in TSOKEY00 [772](#)  
RECONTIME operand  
TSOASMGR parameter  
CEAPRMxx parmlib member [163](#)  
RECORDING parameter  
in SMFPRMxx parmlib member [756](#)  
RECOVERY parameter in IECIOSxx  
statements and parameters [503](#)  
REFRPROT statement in PROGxx [694](#)  
region size [135](#)  
RELEASE parameter in IFAPRDxx [525](#)  
REPLACE parameter in IEASVCxx [411](#)  
RER parameter in IEASYSxx [468](#)  
RESETTIME parameter in XCFPOLxx [786](#)  
RESTART resource  
recovery for excessive spinning [313](#)  
RESTART statement in SCHEDxx [715](#)  
RETAIN parameter in MPFLSTxx [652](#), [654](#), [657](#)  
RETRY parameter in COUPLExx [235](#), [238](#)  
REVERIFY parameter in IGDSMSxx [553](#)  
RISGNL response  
recovery for excessive spinning [313](#)  
RLIM parameter in CONSOLxx [223](#)  
RLS\_MAX\_POOL\_SIZE parameter in IGDSMSxx [553](#)  
RLS\_MaxCfFeatureLevel in IGDSMSxx [554](#)  
RLS\_RECOV\_LOGGING parameter in IGDSMSxx [554](#)  
RLSABOVETHEBARMAXPOOLSIZE parameter in IGDSMSxx [555](#)  
RLSFIXEDPOOLSIZE parameter in IGDSMSxx [555](#)  
RLSINIT parameter in IGDSMSxx [553](#)  
RLSTMOUT parameter in IGDSMSxx [554](#)  
RMAX parameter in CONSOLxx [219](#)  
RMPTTOM parameter in IEAOPTxx [397](#)  
RNUM parameter in CONSOLxx [215](#)  
ROUTCODE parameter in CONSOLxx [220](#)  
routing code  
for console message [201](#)  
for console message in CONSOLxx [201](#)  
RSM parameter in IEASYSxx [468](#)  
RSU parameter of IEASYSxx [468](#)  
RSVNONR parameter for IEASYSxx [470](#)  
RSVSTRT parameter of IEASYSxx [471](#)  
RTBELEADTIME parameter in IEAOPTxx [397](#)  
RTCAPLEADTIME parameter in IEAOPTxx [397](#)  
RTME parameter in CONSOLxx [215](#)  
RTPIFACTOR parameter in IEAOPTxx [398](#)

RUCSA parameter in IEASYSxx [471](#)

## S

SAM\_USE\_HPF parameter in IGDSMSxx [555](#)  
SCH parameter in IEASYSxx [472](#)  
SCHEDxx parmlib member  
abend code  
adding [713](#)  
deleting [713](#)  
description [713](#)  
example in SYS1.SAMPLIB [714](#)  
overview [24](#)  
statements and parameters [714](#)  
SCRSIZE parameter in TSOKEY00 [772](#)  
SDATA parameter in IEADMR00 [378](#)  
SDFT110 parameter in IECIOSxx [493](#)  
SDFT111 parameter in IECIOSxx [493](#)  
SDFT112 parameter in IECIOSxx [493](#)  
SECONDARY parameter in IECIOSxx [498](#)  
SEG parameter in CONSOLxx  
maximum and default specification [227](#), [228](#)  
SELECT parameter in IGDSMSxx [556](#)  
SEND command [571](#)  
SEND parameter  
BROADCAST operand [580](#)  
MSGPROTECT operand [582](#)  
SEND statement in IKJTSOxx [580](#)  
session parameter in IPCSPRnn  
member dataset [587](#)  
modifying [587](#)  
respecifying [587](#)  
SET command  
used to modify SMF processing [736](#)  
SET EXS command  
used to change EXSPATxx member [314](#)  
SET MMS command  
use [179](#)  
SETSMF command [736](#)  
sharing parmlib members [8](#)  
shortcut keys [797](#)  
SID parameter in SMFPRMxx [757](#)  
SIMETRID parameter in CLOCKxx [174](#)  
SIZE parameter in IGDSMSxx [556](#)  
SLIP operand  
DUMPCAPTURETIME parameter  
CEAPRMxx parmlib member [160](#), [161](#)  
SMF parameter in IEASYSxx [473](#)  
SMF record  
record type [42](#)  
synchronized with SMF interval [556](#)  
SMF\_TIME parameter in IGDSMSxx [556](#)  
SMFLIMxx parmlib member  
description [725](#)  
IBM-supplied default [726](#)  
overview [25](#)  
statements and parameters [727](#)  
syntax format [725](#)  
syntax rules [725](#)  
SMFPRMxx  
DUMPABND parameter [745](#)  
SMFPRMxx parameter  
FLOOD [745](#)  
MAXEVENTINTRECS [753](#)

- SMFPRMxx parmlib member
  - ACTIVE|NOACTIVE parameter [739](#)
  - description [735](#)
  - IBM-supplied default [739](#)
  - LSNAME [749](#)
  - overview [25](#)
  - RECORDING parameter [756](#)
  - SID parameter [757](#)
  - statements and parameters [739](#)
  - SYNCVAL parameter [765](#)
  - syntax format [737](#)
  - syntax rules [736](#)
  - system symbols [750](#)
- SMFTBUF parameter in IEASYSxx [473](#)
- SMS (Storage Management Subsystem)
  - changing options [533](#)
  - defined to MVS [531](#)
  - parmlib member [531](#)
  - starting SMS [533](#)
- SMS parameter in IEASYSxx
  - IEASYSxx parmlib member
    - SMS parameter [473](#)
- SMS parameter in IGDSMSxx [535](#)
- SMS parameter in PROGxx [696](#)
- SNAPSHOT parameter
  - CEAPRMxx parmlib member [162](#)
- SOLUT parameter in IEASYSxx [474](#)
- spin lock release
  - recovery for excessive spinning [313](#)
- spin loop
  - automatic recovery [313](#)
  - default recovery action [314](#)
  - recovery [313](#)
  - specifying system default [313](#)
  - specifying timeout interval [313](#)
- SPIN parameter in EXSPATxx [314](#)
- SPINRCVY statement in EXSPATxx [314](#)
- SPINTIME parameter in EXSPATxx [314](#)
- SPOF statement in IECIOSxx [504](#)
- SPOOLCL parameter in IKJTSOxx [579](#)
- SPPINST member of SYS1.SAMPLIB [618](#)
- SPREF parameter in SCHEDxx [718](#)
- SQA (system queue area)
  - SQA parameter in IEASYSxx [474](#)
  - tracking function
    - DIAGxx parmlib member [295](#)
    - IGGCATxx parmlib member [565](#)
- SRM parameter in GTFPARM [337](#)
- SSN parameter in IEASYSxx [476](#)
- ssname parameter in IEFSSNxx [790](#)
- START parameter in IEFSSNxx [518](#)
- STATE parameter in IFAPRDxx [525](#)
- statements and parameters [178](#), [589](#)
- static system symbols [33](#)
- STATUS parameter in SMFPRMxx [760](#)
- STEPLIBLIST parameter in BPXPRMxx [152](#)
- STEPNAME parameter in IGDSMSxx [556](#)
- STND parameter in IECIOSxx [489](#)
- stopped CPU (central processing unit)
  - recovery for excessive spinning [313](#)
- STOR statement in CONFIGxx [198](#)
- storage increment size [468](#)
- Storage Management Subsystem [531](#)
- Storage Management Subsystem (SMS)

- Storage Management Subsystem (SMS) (*continued*)
  - changing options [533](#)
- STORAGE parameter
  - CEAPRMxx parmlib member [162](#)
- STORAGE parameter in IECIOSxx [496](#)
- STORAGE statement in CONFIGxx [198](#)
- STORAGENSWDWP parameter in IEAOPTxx [398](#)
- STORAGENWTOR parameter in IEAOPTxx [399](#)
- STORAGESERVERMGT parameter in IEAOPTxx [398](#)
- STORE parameter in XCFPOLxx [787](#)
- STPMODE parameter in CLOCKxx [175](#)
- STPZONE parameter in CLOCKxx [175](#)
- STRNAME statement in COUPLExx [238](#), [239](#)
- SUB parameter in CTncccxx [254](#)
- SUBFILESYSTYPE parameter in BPXPRMxx [152](#)
- sublevel trace
  - specified in CTncccxx parmlib member [249](#)
  - specified in SUB parameter [254](#)
- SUBNAME(subname) parameter in IEFSSNxx [519](#)
- SUBSYS parameter in IEFSSNxx [518](#)
- SUBSYS parameter in SMFPRMxx [760](#)
- summary of changes xxxiii, xxxiv
- SUP parameter in MPFLSTxx [653](#), [655](#), [657](#)
- SUPPRESS\_DRMSGS (YES|NO) parameter in IGDSMSxx [556](#)
- SUPPRESS\_SMSMSG parameter in IGDSMSxx [556](#)
- suppressible JES messages
  - aggressive list [661](#)
  - conservative list [661](#)
- suppressible non-JES
  - messages
    - aggressive list [660](#)
    - conservative list [659](#)
- SUPPSAFINFOMSG parameter in IEAOPTxx [399](#)
- SUPSBY parameter on CONSOLE statement in CONSOLxx [216](#)
- SVC
  - user-defined [409](#)
- SVC parameter in IEA99sys [476](#)
- SVC table [409](#)
- SVC Parm statement in IEASVCxx [410](#)
- SWAP parameter in SCHEDxx [717](#)
- SWITCH statement in CONFIGxx [199](#)
- SWT parameter in SMFPRMxx [764](#)
- SYMBOL statement
  - in IPCS parmlib members [119](#)
- Symbolic Parmlib Parser [793](#)
- symbolic preprocessing [794](#)
- symbolic substitutions [793](#)
- symbols
  - reserved for system use [36](#)
- SYMDEF of IEASYMxx parmlib member [415](#)
- SYNCASYNC statement in COUPLExx [241](#)
- SYNCHDEST parameter in CONSOLxx [219](#)
- SYNCVAL parameter of SMFPRMxx parmlib member [765](#)
- syntax
  - FXEPRMxx [317](#)
  - rules for parmlib members [7](#)
- syntax checking [794](#)
- syntax format [297](#)
- syntax format of LPA statements [708](#)
- syntax format of statements [702](#)
- SYS parameter in SMFPRMxx [765](#)
- SYS1.DAE dataset
  - ADYSETxx parmlib member [61](#)

- SYS1.LINKLIB data set [611](#)
- SYS1.LPALIB
  - concatenation [635](#)
- SYS1.STGINDEX [479](#)
- SYSABEND data set
  - parmlib member [357](#)
- SYSCLONE of IEASYMxx parmlib member [417](#)
- SYSDDIR statement
  - in IPCS parmlib members [121](#)
- SYSDEF statement in IEASYMxx [416](#)
- SYSGONE statement in XCFPOLxx [786](#)
- SYSLIB statement
  - example [702](#)
- SYSLIB statement in PROGxx [687](#), [701](#)
- SYSM parameter in GTFPARM [337](#)
- SYSMDUMP data set
  - parmlib member [377](#)
- SYSn.IPLPARM data set
  - contains NUCLSTxx member [678](#)
  - on the IODF volume [678](#)
- SYSNAME of IEASYMxx parmlib member [418](#)
- SYSNAME parameter in IEASYSxx [476](#)
- SYSNAME parameter in IFAPRDxx [526](#)
- SYSNAME parameter in IGDSMSxx [557](#)
- SYSOUT parameter in IKJTSOxx [579](#)
- SYSP parameter
  - specified by operator [426](#)
- SYSP parameter in IEASYSxx [477](#)
- SYSPARM of IEASYMxx parmlib member [417](#)
- sysplex
  - console definition
    - defining the same console to different systems [203](#)
  - CONSOLxx parameters with sysplex scope [201](#)
  - serialization [171](#)
  - synchronization [171](#)
  - time stamp [171](#)
  - using system symbols in shared CONSOLxx members [201](#)
- SYSPLEX parameter in COUPLExx [235](#)
- SYSPLEX parameter in IFAPRDxx [526](#)
- Sysplex Timer [171](#)
- SYSPLEXSHR parameter in IKJTSOxx [583](#)
- SYSR1
  - defining substitution texts [32](#)
  - definition [33](#)
  - example [419](#)
- SYSRES [55](#)
- SYST parameter in SCHEDxx [718](#)
- system catalog
  - specifying an alternate [8](#)
- system console
  - naming [214](#)
  - naming restrictions [214](#)
- system initialization
  - overview [3](#)
  - system tailoring [3](#)
- system parameter
  - operator entry [5](#)
- SYSTEM parameter in XCFPOLxx [787](#)
- SYSTEM parameter on CONSOLE statement in CONSOLxx [216](#)
- system residence (sysres) volume
  - specifying volume serial number [361](#)
- system REXX options [107](#)

- system symbol
  - support for [617](#)
  - using in parmlib members [31](#)
- system symbol console name
  - specifying in CONSOLxx [203](#)
  - using [203](#)
- system symbols
  - changing [52](#)
  - in SMFPRMxx parmlib member [750](#)
- system tailoring
  - at initialization time [3](#)
  - implicit system parameters [25](#)
  - operator command [3](#)
  - security
    - APF-authorized library list [26](#)
- system trace
  - modifying [191](#)
- SYSTEMS parameter in IGDSMSxx [557](#)
- SYSUDUMP data set
  - parmlib member [373](#)

## T

- TABLE parameter in PFKTABxx [682](#)
- TAPE parameter in IECIOSxx [490](#)
- TERM parameter in EXSPATxx [314](#)
- TERMINAL parameter in IECIOSxx [494](#)
- TEST parameter
  - in PROGxx parmlib member [704](#)
- TEST parameter in IECIOSxx [490](#)
- TEST parameter in IKJTSOxx [577](#)
- TFS file system type
  - customizing in FILESYSTYPE [132](#)
- time
  - setting [171](#)
  - synchronizing [171](#)
- time of day (TOD) [171](#)
- TIME parameter in IECIOSxx [490](#)
- TIME statement in CNLccccx [182](#)
- TIMDELTA parameter in CLOCKxx [175](#)
- timeout interval
  - specifying default [313](#)
- TIMEOUT parameter in CONSOLxx [216](#)
- TIMESLICES parameter in IEAOPTxx [399](#)
- TIMEZONE parameter in CLOCKxx [176](#)
- TOD (time-of-day) clock
  - setting [171](#)
  - synchronizing with ETR [171](#)
- TRACE parameter on IGDSMSxx [558](#)
- TRACEEXIT parameter on IGDSMSxx [558](#)
- TRACEOPTS statement in CTnccccx [251](#)
- TRACKDIRLOAD statement in PROGxx [694](#)
- trademarks [802](#)
- transaction initiator class
  - definition in parmlib [97](#)
- TRANSREC statement in IKJTSOxx [577](#)
- TRC parameter in GTFPARM [337](#)
- TRUSTED attribute
  - assigning [28](#)
- TSO/E (time sharing option extensions)
  - APF-authorized program [571](#)
  - authorized commands table [571](#)
  - authorized program table [571](#)
  - defaults for the SEND command [571](#)



- TSOASMGR parameter
  - CEAPRMxx parmlib member [162](#)
- TSOKEY00 parmlib member
  - description [769](#)
  - IBM-supplied default [769](#)
  - overview [25](#)
  - statements and parameters [770](#)
- TVS\_START\_TYPE parameter in IGDSMSxx [559](#)
- TVSAMCOM parameter in IGDSMSxx [558](#)
- TVSNAME parameter in IGDSMSxx [558](#)
- TWT parameter in SMFPRMxx [764](#)
- TYPE parameter in IEASVCxx [411](#)
- TYPE parameter in IGDSMSxx [559](#)

## U

- UDS file system type
  - customizing in FILESYSTYPE [132](#)
- UEXIT parameter in CONSOLxx [223](#)
- UNDEFINE parameter
  - in PROGxx parmlib member [704–706](#)
- UNI parameter in IEASYSxx [478](#)
- Unicode Services environment [255](#)
- UNIT parameter in CONSOLxx [216](#)
- UPDATE parameter
  - in PROGxx parmlib member [704](#)
- UREC parameter in IECIOSxx [490](#)
- use attribute
  - specifying in VATLSTxx [783](#)
- USE parameter in CONSOLxx [217](#)
- USE\_MOST\_FREE\_SPACE parameter in IGDSMSxx [560](#)
- USEEAV parameter in IGDSMSxx [559](#)
- user interface
  - ISPF [797](#)
  - TSO/E [797](#)
- USEREXIT parameter in MPFLSTxx [653, 655](#)
- USERMAX parameter in TSOKEY00 [773](#)
- USR parameter in GTFPARM [338](#)
- USRCTL parameter in IKJTSOxx [579](#)

## V

- V=R area
  - and the PPT [719](#)
- VAL parameter in IEASYSxx [478](#)
- value range
  - explanation of [427](#)
- VARYCPU parameter in IEAOPTxx [399](#)
- VARYCPUMIN parameter in IEAOPTxx [400](#)
- VATDEF statement in VATLSTxx [775](#)
- VATLSTxx parmlib member
  - creating [778](#)
  - description [775](#)
  - examples of entries [781](#)
  - overview [25](#)
  - statements and parameters [781](#)
  - syntax rules [779](#)
- verbose message production
  - controlling [650](#)
- verbose messages
  - controlling [651](#)
- VERSION parameter in IFAPRDxx [525](#)
- VIO parameter in IKJTSOxx [579](#)

- VIODSN parameter in IEASYSxx [479](#)
- virtual lookaside facility [187](#)
- virtual lookaside facility (VLF)
  - starting [189](#)
- VLF (virtual lookaside facility)
  - parmlib member [187](#)
  - starting [189](#)
- VMCPUIDTOLERATION parameter in COUPLExx [236](#)
- VMUSERID of IEASYMxx parmlib member [418](#)
- VMUSERID parameter in IFAPRDxx [526](#)
- VMUSERID, segmenting LOADxx statements [615](#)
- VOL statement in CONFIGxx [199](#)
- VOLNSNS parameter in DEVSUPxx [289](#)
- VOLSELMSG parameter in IGDSMSxx [560](#)
- VOLUME parameter
  - in PROGxx parmlib member [706](#)
- VOLUME parameter in PROGxx [696](#)
- volume partitioning parameters [289](#)
- volume serial
  - specifying in VATLSTxx [782](#)
- VOLUME statement in CONFIGxx [199](#)
- VOLUME\_MNT statement in ALLOCxx [77](#)
- VOLUME|VOLSER|VOL parameter
  - in PROGxx parmlib member [702](#)
- VRREGN parameter in IEASYSxx [479](#)

## W

- warm start IPL
  - after a system crash [4](#)
  - definition [4](#)
- WARNUND parameter in IEASYSxx [480](#)
- WASROUTINGLEVEL parameter in IEAOPTxx [400](#)
- WHEN parameter in IFAPRDxx [525](#)
- WHEN statement in IFAPRDxx member [523](#)
- WLMIRDSTRUC parameter in IEAOPTxx [400](#)
- WORKINST parameter in IEASYSxx [480](#)
- WRAP parameter in CTnccccxx [254](#)
- WTR parameter in CTnccccxx [252](#)
- WTRSTART parameter in CTnccccxx [254](#)
- WTRSTOP parameter in CTnccccxx [254](#)

## X

- XCF (cross-system coupling facility)
  - setting system defaults [229](#)
  - specifying policy for PR/SM [785](#)
- XCFPOLxx parmlib member
  - description [785](#)
  - overview [25](#)
  - statements and parameters [786](#)
  - syntax format [786](#)
- XES (cross-system extended services)
  - setting system defaults [229](#)

## Z

- z/OS File System (zFS)
  - setting system defaults [585](#)
- ZAAPZIIP parameter in IEASYSxx [480](#)
- zEDC Express feature [589](#)
- ZEDC parameter in IQPPRMxx [589](#)
- zEnterprise Data Compression (zEDC) [589](#)

ZFS file system type  
    customizing in FILESYSTYPE [132](#)  
ZHL statement in IECIOSxx [505](#)  
ZHPF statement in IECIOSxx [504](#)  
ZHPFOPTS statement in IECIOSxx [505](#)  
ZHYPERLINK statement in IECIOSxx [505](#)  
zHyperWrite data replication, IBM [497](#)  
ZIIPAWMT parameter in IEAOPTxx [400](#), [401](#)





Product Number: 5655-ZOS

SA23-1380-70

