



# **Program Directory for IBM Infoprint XT for z/OS**

V03.03.00

Program Number 5655-O15

FMID H29Q330

for Use with  
z/OS

Document Date: April 2019

GI11-9495-03

**Note**

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 25.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

**Copyright International Business Machines Corporation 2003, 2019.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>1.0 Introduction</b>	1
1.1 Infoprint XT Description	1
1.2 Infoprint XT FMID	2
<b>2.0 Program Materials</b>	3
2.1 Basic Machine-Readable Material	3
2.2 Program Publications	3
2.2.1 Optional Program Publications	3
2.3 Program Source Materials	4
2.4 Publications Useful During Installation	4
<b>3.0 Program Support</b>	5
3.1 Program Services	5
3.2 Preventive Service Planning	5
3.3 Statement of Support Procedures	6
<b>4.0 Program and Service Level Information</b>	7
4.1 Program Level Information	7
4.2 Service Level Information	7
<b>5.0 Installation Requirements and Considerations</b>	9
5.1 Driving System Requirements	9
5.1.1 Machine Requirements	9
5.1.2 Programming Requirements	9
5.2 Target System Requirements	10
5.2.1 Machine Requirements	10
5.2.2 Programming Requirements	10
5.2.2.1 Installation Requisites	10
5.2.2.2 Operational Requisites	11
5.2.2.3 Toleration/Coexistence Requisites	11
5.2.2.4 Incompatibility (Negative) Requisites	12
5.2.3 DASD Storage Requirements	12
5.3 FMIDs Deleted	15
5.4 Special Considerations	15
5.4.1 Data Set and Path Names	15
5.4.2 SYS1.PARMLIB member IFAPRD00	15
<b>6.0 Installation Instructions</b>	17
6.1 Installing Infoprint XT	17
6.1.1 SMP/E Considerations for Installing Infoprint XT	17
6.1.2 SMP/E Options Subentry Values	17
6.1.3 Sample Jobs	17

6.1.4	Perform SMP/E RECEIVE	19
6.1.5	Allocate SMP/E Target and Distribution Libraries	19
6.1.6	Allocate File System Paths	19
6.1.7	Create DDDEF Entries	19
6.1.8	Perform SMP/E APPLY	20
6.1.9	Execute Installation Verification Procedures (IVPs)	21
6.1.10	Perform SMP/E ACCEPT	22
6.1.11	Run REPORT CROSSZONE	22
6.1.12	Cleaning Up Obsolete Data Sets, Paths, and DDDEFs	23
6.1.13	Dynamic Enablement - Update PARMLIB	24
6.2	Activating Infoprint XT	24
6.2.1	File System Execution	24
6.3	Product Customization	24
<b>7.0</b>	<b>Notices</b>	<b>25</b>
7.1	Trademarks	25
	<b>Reader's Comments</b>	<b>29</b>

---

## Figures

1.	Basic Material: Unlicensed Publications	3
2.	Publications Useful During Installation	4
3.	PSP Upgrade and Subset ID	5
4.	Component IDs	6
5.	Driving System Software Requirements	10
6.	Target System Mandatory Installation Requisites	10
7.	Target System Conditional Operational Requisites	11
8.	Total DASD Space Required by Infoprint XT	12
9.	Storage Requirements for Infoprint XT Target Libraries	14
10.	Infoprint XT File System Paths	14
11.	Storage Requirements for Infoprint XT Distribution Libraries	14
12.	Infoprint XT HFS Additional Paths	15
13.	SMP/E Options Subentry Values	17
14.	Sample Installation Jobs	18

---

## 1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Infoprint XT for z/OS. This publication refers to IBM Infoprint XT for z/OS as Infoprint XT.

The Program Directory contains the following sections:

2.0, "Program Materials" on page 3 identifies the basic program materials and documentation for Infoprint XT.

3.0, "Program Support" on page 5 describes the IBM support available for Infoprint XT.

4.0, "Program and Service Level Information" on page 7 lists the APARs (program level) and PTFs (service level) that have been incorporated into Infoprint XT.

5.0, "Installation Requirements and Considerations" on page 9 identifies the resources and considerations that are required for installing and using Infoprint XT.

6.0, "Installation Instructions" on page 17 provides detailed installation instructions for Infoprint XT. It also describes the procedures for activating the functions of Infoprint XT, or refers to appropriate publications.

Before installing Infoprint XT, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; after which, keep the documents for your reference. Section 3.2, "Preventive Service Planning" on page 5 tells you how to find any updates to the information and procedures in this program directory.

Infoprint XT is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for Infoprint XT are included on the CBPDO.

Do not use this program directory if you install Infoprint XT with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

---

## 1.1 Infoprint XT Description

IBM Infoprint XT for z/OS helps you migrate efficiently from your Xerox print environment to an Advanced Function Presentation (AFP) print environment, allowing you to standardize on a single output architecture. With Infoprint XT, you can easily transform established Xerox application data to AFP format for storing, retrieving, viewing, and printing without changing your existing applications. Using IBM Xerox transform (XT) technology, Xerox print resources, such as fonts, forms, images, and logos are converted into their AFP equivalents, and Line Conditioned Data Stream (LCDS), and Xerox Metacode data streams are converted into AFP Mixed Object Document Content Architecture (MO:DCA) data streams. Once

converted, you can print these resources and data streams on high-speed, reliable Intelligent Printer Data Stream (IPDS) devices or you can place them in the IBM Content Manager OnDemand archival and retrieval system. When stored in libraries identified to Print Services Facility (PSF), the AFP print resources are automatically accessed for printing on all of the printers that use such resources. You need not be concerned about coordinating the correct version of each resource on every printer. You can print to cut sheet devices to retain control over options, such as tray selection, or you can move Xerox applications to print on continuous form printers that usually offer a lower total cost of operation (TCO) than cut sheet devices. Infoprint XT for z/OS helps optimize the productivity of your output operations by automating much of the migration from Xerox resources and data streams to AFP and allowing you to standardize on a single output architecture.

Infoprint XT for z/OS, V3.3 provides the following new capabilities or enhanced functions:

- Add Infoprint XT product registration verification using z/OS Registration Services.
- Improve output information for jobs containing multiple duplicate inline graphic images.
- Improve job progress monitoring for large data stream conversions.
- Improve performance control for data stream conversions.
- Improve control of duplicate messages.
- Improve graphic image processing message.
- Enhance parameter matching information.
- Improve capture mechanism for diagnostic job information.
- Add trace functions for the InfoPrint XT Xerox FRMs converter.
- Batch JCL program changes
  - Add new parameter to pdxtpdl.
  - New pdxtversion and form sampling JCLs.

---

## 1.2 Infoprint XT FMID

Infoprint XT consists of the following FMID:

H29Q330

---

## 2.0 Program Materials

An IBM program is identified by a program number. The program number for Infoprint XT is 5655-O15.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by Infoprint XT. Ask your IBM representative for this information if you have not already received a copy.

---

### 2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 17 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for Infoprint XT in the *CBPDO Memo To Users Extension*.

---

### 2.2 Program Publications

The following sections identify the basic publications for Infoprint XT.

Figure 1 identifies the basic unlicensed publications for Infoprint XT. Those that are in softcopy format publications can be obtained from the IBM Publications Center website at <http://www.ibm.com/shop/publications/order/>.

<i>Figure 1. Basic Material: Unlicensed Publications</i>		
<b>Publication Title</b>	<b>Form Number</b>	<b>Media Format</b>
<i>IBM Infoprint XT for z/OS</i>	G111-9492	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>
<i>IBM Infoprint XT for z/OS: Licensed Program Specification</i>	G111-9493	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>

#### 2.2.1 Optional Program Publications

No optional publications are provided for Infoprint XT.

---

## 2.3 Program Source Materials

No program source materials or viewable program listings are provided for Infoprint XT.

---

## 2.4 Publications Useful During Installation

You might want to use the publications listed in Figure 2 during the installation of Infoprint XT.

<i>Figure 2. Publications Useful During Installation</i>		
<b>Publication Title</b>	<b>Form Number</b>	<b>Media Format</b>
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883	<a href="http://www.ibm.com/shop/publications/order/">http://www.ibm.com/shop/publications/order/</a>



---

## 3.0 Program Support

This section describes the IBM support available for Infoprint XT.

---

### 3.1 Program Services

Contact your IBM representative for specific information about available program services.

---

### 3.2 Preventive Service Planning

Before you install Infoprint XT, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.PRODUCTINSTALL-REQUIRESERVICE fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on the **APPLY CHECK** command. See 6.1.8, “Perform SMP/E APPLY” on page 20 for a sample APPLY command

If you obtained Infoprint XT as part of a CBPDO, HOLDDATA is included.

If the CBPDO for Infoprint XT is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<http://www14.software.ibm.com/webapp/set2/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <http://www.ibm.com/support/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Infoprint XT are included in Figure 3.

<i>Figure 3. PSP Upgrade and Subset ID</i>		
UPGRADE	SUBSET	Description
5655O15	H29Q330	IBM Infoprint XT

---

### 3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 4 on page 6 identifies the component IDs (COMPID) for Infoprint XT.

<i>Figure 4. Component IDs</i>			
<b>FMID</b>	<b>COMPID</b>	<b>Component Name</b>	<b>RETAIN Release</b>
H29Q330	5655O1500	IBM Infoprint XT	330

---

## 4.0 Program and Service Level Information

This section identifies the program and relevant service levels of Infoprint XT. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

---

### 4.1 Program Level Information

The following APAR fixes against previous releases of Infoprint XT have been incorporated into this release. They are listed by FMID.

FMID H29Q310

OA44471

---

### 4.2 Service Level Information

No PTFs against this release of Infoprint XT have been incorporated into the product package.

Frequently check the Infoprint XT PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your **APPLY CHECK** command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.



---

## 5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Infoprint XT. The following terminology is used:

*Driving system:* the system on which SMP/E is executed to install the program.

The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.

*Target system:* the system on which the program is configured and run.

The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.

When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

---

### 5.1 Driving System Requirements

This section describes the environment of the driving system required to install Infoprint XT.

#### 5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

#### 5.1.2 Programming Requirements

Figure 5. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	V02.02.00 or higher	N/A	No

**Note:** SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

**Note:** Installation might require migration to new z/OS releases to be service supported. See [https://www-01.ibm.com/software/support/lifecycle/index\\_z.html](https://www-01.ibm.com/software/support/lifecycle/index_z.html).

## 5.2 Target System Requirements

This section describes the environment of the target system required to install and use Infoprint XT.

Infoprint XT installs in the z/OS (Z038) SREL.

### 5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

### 5.2.2 Programming Requirements

#### 5.2.2.1 Installation Requisites

Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

Figure 6. Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	02.02.00 or higher	N/A	No

**Note:** Installation might require migration to new z/OS releases to be service supported. See [http://www-03.ibm.com/systems/z/os/zos/support/zos\\_eos\\_dates.html](http://www-03.ibm.com/systems/z/os/zos/support/zos_eos_dates.html).

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

Infoprint XT has no conditional installation requisites.

### 5.2.2.2 Operational Requisites

Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

Infoprint XT has no mandatory operational requisites.

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

Figure 7. Target System Conditional Operational Requisites		
Program Number	Product Name and Minimum VRM/Service Level	Function
5655-M32	PSF for z/OS Version V04.05.00 or higher	Print AFP documents on IPDS printers
5650-ZOS	Font Collection element of z/OS V02.02.00 or higher	IBM Fonts
5650-ZOS	Infoprint Server element of z/OS V02.02.00 or higher	Run Infoprint XT as a managed transform
5697-CMD	IBM Content Manager OnDemand for z/OS, V9.5 or higher	Archive and retrieve AFP documents.
5724-J33	IBM Content Manager OnDemand Multiplatforms, V9.5 or higher	Archive and retrieve AFP documents.

### 5.2.2.3 Toleration/Coexistence Requisites

Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

Infoprint XT has no toleration/coexistence requisites.

### 5.2.2.4 Incompatibility (Negative) Requisites

Negative requisites identify products that must *not* be installed on the same system as this product.

Infoprint XT has no negative requisites.

### 5.2.3 DASD Storage Requirements

Infoprint XT libraries can reside on all supported DASD types.

Figure 8 lists the total space that is required for each type of library.

<i>Figure 8. Total DASD Space Required by Infoprint XT</i>		
Library Type	Total Space Required in 3390 Trks	Description
Target	45 Tracks on 3390 DASD	
Distribution	750 Tracks on 3390 DASD	
File System	700 Tracks on 3390 DASD	/usr/lpp/pdxt/V3R3M0/

#### Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any



service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.5, "Allocate SMP/E Target and Distribution Libraries" on page 19.

3. Abbreviations used for the file system path type are as follows.

<b>N</b>	New path, created by this product.
<b>X</b>	Path created by this product, but might already exist from a previous release.
<b>P</b>	Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE, with some exceptions. If the value in the "ORG" column specifies "PDS", the data set must be a PDS. If the value in "DIR Blks" column specifies "N/A", the data set must be a PDSE.

5. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

6. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can not be in the LPA, with some exceptions. If the value in the "Member Type" column specifies "LPA", it is advised to place the data set in the LPA.
- These data sets can be in the LNKLIST.
- These data sets are not required to be APF-authorized, with some exceptions. If the value in the "Member Type" column specifies "APF", the data set must be APF-authorized.

The following figures describe the target and distribution libraries and file system paths required to install Infoprint XT. The storage requirements of Infoprint XT must be added to the storage required by other programs that have data in the same library or path.

**Note:** Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 9. Storage Requirements for Infoprint XT Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
LINKLIB	LMOD	TVOL1	E	PDS	U	0	30	2
SAIOSAMP	SAMP	TVOL2	U	PDS	FB	80	10	2
SAIOIVPD	DATA	TVOL2	U	PDS	FBA	70	3	1
SAIOXRES	DATA	TVOL2	U	PDS	FB	128	6	1

Figure 10. Infoprint XT File System Paths

DDNAME	T Y P E	Path Name
SAIO33BI	N	/usr/lpp/pdxt/V3R3M0/bin/IBM
SAIO33LI	N	/usr/lpp/pdxt/V3R3M0/lib/IBM
SAIO33N7	N	/usr/lpp/pdxt/V3R3M0/nls/man/en_US/cat7/IBM
SAIO33NL	N	/usr/lpp/pdxt/V3R3M0/nls/msg/en_US/IBM
SAIO33RE	N	/usr/lpp/pdxt/V3R3M0/resources/IBM
SAIO33SM	N	/usr/lpp/pdxt/V3R3M0/samples/IBM
SAIO33TS	N	/usr/lpp/pdxt/V3R3M0/testjob/IBM

Figure 11. Storage Requirements for Infoprint XT Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ALINKLIB	E	PDS	U	0	30	2
AAIOHFS	U	PDS	VB	255	700	5
AAIOIVPD	U	PDS	FBA	70	3	1
AAIOXRES	U	PDS	FB	128	6	1
AAIOSAMP	U	PDS	FB	80	10	2

The following figures list data sets that are not used by SMP/E, but are required for Infoprint XT to run.

Figure 12. Infoprint XT HFS Additional Paths

Path Name
/usr/lpp/pdxt/V3R3M0/local
/usr/lpp/pdxt/V3R3M0/localsrc
/usr/lpp/pdxt/V3R3M0/nls/doc

---

## 5.3 FMIDs Deleted

Installing Infoprint XT might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install Infoprint XT into separate SMP/E target and distribution zones.

**Note:** These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETFMID command. See the SMP/E Commands book for details.

---

## 5.4 Special Considerations

### 5.4.1 Data Set and Path Names

IBM recommends you do not change the data set and path names that are defined by the sample installation jobs. The execution of Infoprint XT will depend on these naming conventions.

### 5.4.2 SYS1.PARMLIB member IFAPRD00

The SYS1.PARMLIB member, IFAPRD00, may have been customized by IBM to enable the IBM products and optional integrated features specifically ordered by you.

Please verify that the SYS1.PARMLIB member IFAPRD00 contains the following information for Infoprint XT and add if necessary.

```
PRODUCT OWNER('IBM CORP')
  NAME('XT for z/OS')
  FEATURENAME('XT for z/OS')
  ID(5655-O15)
  VERSION(*) RELEASE(*) MOD(*)
  STATE(ENABLED)
```



---

## 6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Infoprint XT.

Please note the following points:

If you want to install Infoprint XT into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMP/CSI and the SMP/E control data sets.

You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.

You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

---

### 6.1 Installing Infoprint XT

#### 6.1.1 SMP/E Considerations for Installing Infoprint XT

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of Infoprint XT.

#### 6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 13. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

<i>Figure 13. SMP/E Options Subentry Values</i>		
Subentry	Value	Comment
DSSPACE	(500,50,6) TRK	Recommended value for Infoprint XT.
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

#### 6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Infoprint XT:

Figure 14. Sample Installation Jobs

Job Name	Job Type	Description	RELFILE
AIOALLOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.H29Q330.F1
AIOISMKD	MKDIR	Sample job to invoke the supplied AIOMKDIR EXEC to allocate file system paths	IBM.H29Q330.F1
AIODDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.H29Q330.F1

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.4, “Perform SMP/E RECEIVE” on page 19) then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 14 on page 17 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the product files by submitting the following job. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1      EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=
//IN          DD DSN=IBM.H29Q33 .F1,UNIT=SYSALLDA,DISP=SHR,
//            VOL=SER=filevol
//OUT         DD DSNAME=jcl-library-name,
//            DISP=(NEW,CATLG,DELETE),
//            VOL=SER=dasdvol,UNIT=SYSALLDA,
//            SPACE=(TRK,(5,5,2))
//SYSUT3      DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN       DD
              COPY INDD=IN,OUTDD=OUT
              SELECT MEMBER=AIOALLOC
              SELECT MEMBER=AIODDDEF
              SELECT MEMBER=AIOISMKD
              SELECT MEMBER=AIOMKDIR
/
```

See the following information to update the statements in the previous sample:

IN:

**filevol** is the volume serial of the DASD device where the downloaded files reside.

OUT:

**jcl-library-name** is the name of the output data set where the sample jobs are stored.

**dasdvol** is the volume serial of the DASD device where the output data set resides.

## 6.1.4 Perform SMP/E RECEIVE

If you have obtained Infoprint XT as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the Infoprint XT FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.5 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job AIOALLOC to allocate the SMP/E target and distribution libraries for Infoprint XT. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.6 Allocate File System Paths

The target system HFS or zFS data set must be mounted on the driving system when running the sample AIOISMKD job since the job will create paths in the HFS or zFS.

Before running the sample job to create the paths in the file system, you must ensure that OMVS is active on the driving system and that the target system's HFS or zFS file system is mounted to the driving system. zFS must be active on the driving system if you are installing Infoprint XT into a file system that is zFS.

If you plan to install Infoprint XT into a new HFS or zFS file system, you must create the mountpoint and mount the new file system to the driving system for Infoprint XT.

The recommended mountpoint is `/usr/lpp/pdxt/V3R3M0/`.

Edit and submit sample job AIOISMKD to allocate the HFS or zFS paths for Infoprint XT. Consult the instructions in the sample job for more information.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.7 Create DDDEF Entries

Edit and submit sample job AIODDDEF to create DDDEF entries for the SMP/E target and distribution libraries for Infoprint XT. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.8 Perform SMP/E APPLY

Perform an SMP/E APPLY CHECK for Infoprint XT.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holdata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

1. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU )
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

2. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.



```

APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU )
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
    ..any other parameters documented in the program directory

```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.PRODUCTINSTALL-REQUIREDSERVICE to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

**Note:** The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from APPLY CHECK:** You will receive a return code of 0 if this job runs correctly.

**Expected Return Codes and Messages from APPLY:** You will receive a return code of 0 if this job runs correctly.

## 6.1.9 Execute Installation Verification Procedures (IVPs)

### Perform IVPs

This step is optional but recommended.

Running IVP batch jobs AIOZIVP1, AIOZIVP2 and AIOZIVP3 will verify that the general installation of Infoprint XT was successful.

For more information about IVP procedures, see publication *IBM Infoprint XT for z/OS*, G111-9492. Chapter 2 - Configuring Infoprint XT - *Running the installation verification procedure*

## 6.1.10 Perform SMP/E ACCEPT

Perform an SMP/E ACCEPT CHECK for Infoprint XT.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

**Note:** The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from ACCEPT CHECK:** You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

**Expected Return Codes and Messages from ACCEPT:** You will receive a return code of 0 if this job runs correctly.

## 6.1.11 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command identifies requisites for products that are installed in separate zones. This command also creates APPLY and ACCEPT commands in the SMPPUNCH data set. You can use the APPLY and ACCEPT commands to install those cross-zone requisites that the SMP/E REPORT CROSSZONE command identifies.

After you install Infoprint XT, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on.

For more information about REPORT CROSSZONE, see the SMP/E manuals.

## 6.1.12 Cleaning Up Obsolete Data Sets, Paths, and DDDEFs

The following file system paths, which were created and used by previous releases of this product, are no longer used in this release. You can delete these obsolete file system paths after you delete the previous release from your system.

Migrating customers may want to keep their user information such as exits in /V3R1M0/local and /V3R1M0/localsrc.

```
/usr/lpp/pdxt/V3R1M0/bin
/usr/lpp/pdxt/V3R1M0/lib
/usr/lpp/pdxt/V3R1M0/local
/usr/lpp/pdxt/V3R1M0/localsrc
/usr/lpp/pdxt/V3R1M0/nls/doc
/usr/lpp/pdxt/V3R1M0/nls/man/en_US/cat7
/usr/lpp/pdxt/V3R1M0/nls/msg/en_US
/usr/lpp/pdxt/V3R1M0/resources
/usr/lpp/pdxt/V3R1M0/samples
/usr/lpp/pdxt/V3R1M0/testjob
```

**Note:** IBM Infoprint XT V3R3M0 for z/OS uses the same /var/pdxt system path that was used in the previous version. This system path contains original Xerox and converted AFP resources, reformatted Xerox resources, parameter maps, directives and other files that your Infoprint XT installation requires, DO NOT delete the /var/pdxt system path or any of its contents.

The following DDDEF entries, which were created and used by previous releases of this product, are no longer used in this release. You can delete these obsolete DDDEF entries after you delete the previous release from your system.

```
DDDEF (SAIO3BIN) PATH('/usr/lpp/pdxt/V3R1M0/bin/IBM/').
DDDEF (SAIO3LIB) PATH('/usr/lpp/pdxt/V3R1M0/lib/IBM/').
DDDEF (SAIO3NL7) PATH('/usr/lpp/pdxt/V3R1M0/nls/man/en_US/cat7/IBM/').
DDDEF (SAIO3NLM) PATH('/usr/lpp/pdxt/V3R1M0/nls/msg/en_US/IBM/').
DDDEF (SAIO3REC) PATH('/usr/lpp/pdxt/V3R1M0/resources/IBM/').
DDDEF (SAIO3SMP) PATH('/usr/lpp/pdxt/V3R1M0/samples/IBM/').
DDDEF (SAIO3TST) PATH('/usr/lpp/pdxt/V3R1M0/testjob/IBM/').
```

### 6.1.13 Dynamic Enablement - Update PARMLIB

To enable Infoprint XT, to run with z/OS, the following entries must be in the IFAPRDxx PARMLIB member:

```
PRODUCT OWNER('IBM CORP')
  NAME('XT for z/OS')
  FEATURENAME('XT for z/OS')
  ID(5655-O15)
  VERSION(*) RELEASE(*) MOD(*)
  STATE(ENABLED)
```

For more information on Dynamic Enablement, see publication *IBM Infoprint XT for z/OS*, GI11-9492.

---

## 6.2 Activating Infoprint XT

### 6.2.1 File System Execution

If you mount the file system in which you have installed Infoprint XT in read-only mode during execution, then refer to the publication *IBM Infoprint XT for z/OS*, to activate Infoprint XT.

For Infoprint XT, the recommended mountpoint is `usr/lpp/pdxt/V3R3M0/`

---

## 6.3 Product Customization

The publication *IBM Infoprint XT for z/OS* (GI11-9492) contains the necessary information to customize and use Infoprint XT.

---

## 7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, New York 10504-1785  
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan, Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan

---

## 7.1 Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).









---

## Reader's Comments

**Program Directory for IBM Infoprint XT for z/OS, April 2019** We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Send your comments by emailing us at [ibmkc@us.ibm.com](mailto:ibmkc@us.ibm.com), and include the following information:

Your name and address Your email address Your telephone or fax number The publication title and order number The topic and page number related to your comment The text of your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.



Printed in USA

GI11-9495- 3

