

z/OS
3.2

ISPF Reference Summary



Note

Before using this information and the product it supports, read the information in [“Notices” on page 281.](#)

This edition applies to IBM® z/OS® 3.2 (5655-ZOS) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2025-09-30

© **Copyright International Business Machines Corporation 1989, 2025.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures.....	xi
Tables.....	xiii
Preface.....	xv
Who should use this document.....	xv
How to read the syntax diagrams.....	xv
z/OS information.....	xix
How to provide feedback to IBM.....	xxi
Summary of changes.....	xxiii
Summary of changes for z/OS 3.2.....	xxiii
Summary of changes for z/OS 3.1.....	xxiii
What's in the library?.....	xxv
Chapter 1. ISPF general information.....	1
Invoking an ISPF application—the ISPSTART command.....	2
ISPF system information.....	2
Files used by ISPF.....	3
ISPF system commands.....	3
Command table actions.....	10
Dialog test commands.....	10
PDF Browse primary commands.....	11
PDF member list commands.....	12
PDF member generation list commands.....	14
PDF data set list commands.....	14
PDF Edit and View commands.....	16
Chapter 2. Dialog development information.....	29
Invoking the ISPF DTL conversion utility.....	29
Panel definition sections.....	30
Panel statements and built-in functions.....	34
Panel control variables.....	40
Message definitions.....	42
Skeleton control statements.....	42
Chapter 3. ISPF service syntax with return codes.....	45
The importance of parameter order, and using placeholders for optional parameters.....	45
Command format.....	46
ISPEXEC command invocation.....	46
ISPEXEC parameter conventions.....	46
The ISPLINK interface.....	46
CALL ISPLINK parameters.....	46
The ISPEXEC interface.....	47
CALL ISPEXEC parameters.....	47

ADDPop—start pop-up window mode.....	47
BRIF—Browse interface.....	48
BROWSE—Browse a data set.....	49
CONTROL—set processing modes.....	51
DIRLIST—directory list service.....	53
DISPLAY—display panels and messages.....	54
DSINFO—data set information dialog.....	55
EDIF—Edit interface.....	55
EDIREC—initialize edit recovery.....	57
EDIT—edit a data set.....	58
EDREC—specify edit recovery handling.....	61
FTCLOSE—end file tailoring.....	62
FTERASE—erase file tailoring output.....	63
FTINCL—include a skeleton.....	63
FTOPEN—begin file tailoring.....	64
GENLIST - list a member's generations.....	65
GETMSG—get a message.....	66
GRERROR—graphics error block service.....	67
GRINIT—graphics initialization.....	67
GRTERM—graphics termination service.....	68
LIBDEF—allocate application libraries.....	68
LIST—write lines to the list data set.....	69
LMCLOSE—close a data set.....	70
LMCOMP—compresses a partitioned data set.....	71
LMCOPY—copy members of a data set.....	71
LMDDISP—data set display service.....	73
LMDFREE—free a data set list.....	74
LMDINIT—initialize a data set list.....	75
LMDLIST—list a data set.....	76
LMERASE—erase a data set.....	77
LMFREE—free data set from its association with data ID.....	78
LMGET—read a logical record from a data set.....	79
LMINIT—generate a data ID for a data set.....	80
LMMADD—add a member to a data set.....	81
LMMDEL—delete members from a data set.....	82
LMMDISP—member list service: Display option.....	83
LMMDISP—member list service: GET option.....	84
LMMDISP—member list service: PUT option.....	85
LMMDISP—member list service: ADD option.....	86
LMMDISP—member list service: DELETE option.....	87
LMMDISP—member list service: FREE option.....	88
LMMFIND—find a library member.....	88
LMMLIST—list a library's members.....	90
LMMOVE—move members of a data set.....	91
LMMREN—rename a data set member.....	92
LMMREP—replace a member of a data set.....	93
LMMSTATS—set and store ISPF statistics.....	94
LMOPEN—open a data set.....	96
LMPRINT—print a partitioned or sequential data set.....	97
LMPUT—write a logical record to a data set.....	98
LMQUERY—give a dialog information about a data set.....	99
LMRENAME—rename an ISPF library.....	100
LOG—write a message to the log data set.....	101
MEMLIST—member list dialog.....	101
PQUERY—obtain panel information.....	102
QBASELIB—query base library information.....	103
QLIBDEF—query LIBDEF definition information.....	104
QTABOPEN—query open ISPF tables.....	104

QUERYENQ—query system ENQ data.....	105
REMPop—remove a pop-up window.....	106
SELECT—select a panel or function.....	107
SETMSG—set next message.....	108
TBADD—add a row to a table.....	109
TBBOTTOM—set the row pointer to bottom.....	109
TBCLOSE—close and save a table.....	110
TBCREATE—create a new table.....	111
TBDELETE—delete a row from a table.....	112
TBDISPL—display table information.....	112
TBEND—close a table without saving.....	114
TBERASE—erase a table.....	114
TBEXIST—determine whether a row exists in a table.....	115
TBGET—retrieve a row from a table.....	116
TBMOD—modify a row in a table.....	116
TBOPEN—open a table.....	117
TBPUT—update a row in a table.....	118
TBQUERY—obtain table information.....	119
TBSARG—define a search argument.....	120
TBSAVE—save a table.....	120
TBSCAN—search a table.....	121
TBSKIP—move the row pointer.....	122
TBSORT—sort a table.....	123
TBSTATS—retrieve table statistics.....	124
TBTOP—set the row pointer to the top.....	125
TBVCLEAR—clear table variables.....	126
TRANS—translate data from one Coded Character Set Identifier (CCSID) to another.....	126
VCOPY—create a copy of a variable.....	127
VDEFINE—define function variables.....	128
VDELETE—remove a definition of function variables.....	128
VERASE—remove variables from shared and/or profile pool.....	129
VGET—retrieve variables from a pool or profile or system symbol.....	129
VIEW—view a data set.....	130
VIIF—view interface.....	133
VMASK—associate an edit mask with a dialog variable.....	135
VPUT—update variables in the shared or profile pool.....	135
VREPLACE—replace a variable.....	136
VRESET—reset function variables.....	136
VSym service—resolve system symbols.....	137

Chapter 4. Edit macro commands..... 139

AUTOLIST - set or query Autolist mode.....	139
AUTONUM—set or query Autonum mode.....	139
AUTOSAVE—set or query Autosave mode.....	140
BLKSIZE—query the block size.....	140
BOUNDS—set or query the edit boundaries.....	141
BROWSE—browse from within an edit session.....	141
BUILTIN—process a built-in command.....	141
CANCEL—cancel edit changes.....	142
CAPS—set or query Caps mode.....	142
CHANGE—change a search string.....	143
CHANGE_COUNTS—query change counts.....	143
COMPARE—compare data set.....	144
COPY—copy data.....	144
CREATE—create a data set or data set member.....	145
CURSOR—set or query the cursor position.....	145
CUT—cut and save lines.....	146

DATA_CHANGED—query the data changed status.....	146
DATA_WIDTH—query data width.....	146
DATAID—query data ID.....	147
DATASET—query the current data set name.....	147
DEFINE—define a name.....	147
DELETE—delete lines.....	148
DISPLAY_COLS—query display columns.....	148
DISPLAY_LINES—query display lines.....	149
DOWN—scroll down.....	149
EDIT—edit from within an edit session.....	149
END—end the edit session.....	150
EXCLUDE—exclude lines from the panel.....	150
EXCLUDE_COUNTS—query exclude counts.....	151
FIND—find a search string.....	151
FIND_COUNTS—query find counts.....	152
FLIP—reverse excluded status of lines.....	152
FLOW_COUNTS—query flow counts.....	152
HEX—set or query Hexadecimal mode.....	153
HIDE—hide excluded lines message.....	153
HILITE—enhanced edit coloring.....	154
IMACRO—set or query an initial macro.....	155
INSERT—prepare display for data insertion.....	155
LABEL—set or query a line label.....	155
LEFT—scroll left.....	156
LEVEL—set or query the mod level number.....	156
LF—realign data on the ASCII linefeed character.....	157
LINE—set or query a line from the data set.....	157
LINE_AFTER—add a line to the current data set.....	157
LINE_BEFORE—add a line to the current data set.....	158
LINE_STATUS—query source and change information for a line in a data set.....	158
LINENUM—query the line number of a labeled line.....	158
LOCATE—locate a line.....	159
LRECL—query the logical record length.....	159
MACRO—identify an edit macro.....	160
MACRO_LEVEL—query the macro nesting level.....	160
MACRO_MSG—set or query the macro message switch.....	160
MASKLINE—set or query the mask line.....	161
MEMBER—query the current member name.....	161
MEND—end a macro in the batch environment.....	162
MODEL—copy a model into the current data set.....	162
MOVE—move a data set member.....	162
NONUMBER—turn off Number mode.....	163
NOTES—set or query Note mode.....	163
NULLS—set or query Nulls mode.....	164
NUMBER—set or query Number mode.....	164
PACK—set or query Pack mode.....	165
PASTE—move or copy lines from clipboard.....	165
PRESERVE—enable saving of trailing blanks.....	166
PROCESS—process the panel.....	166
PROFILE—set or query the current profile.....	167
RANGE_CMD—query a command that you entered.....	167
RCHANGE—repeat a change.....	168
RECFM—query the record format.....	168
RECOVERY—set or query Recovery mode.....	168
RENUM—renumber data set lines.....	169
REPLACE—replace a data set or data set member.....	169
RESET—reset the data display.....	170
RFIND—Repeat Find.....	170

RIGHT—scroll right.....	171
RMACRO—set or query the recovery macro.....	171
SAVE—save the current data.....	171
SAVE_LENGTH—set or query length for variable-length data.....	172
SCAN—set command scan mode.....	172
SEEK—seek a data string, positioning the cursor.....	173
SEEK_COUNTS—query seek counts.....	173
SESSION—identify type of session.....	173
SETUNDO—set UNDO mode.....	174
SHIFT (—shift columns left.....	174
SHIFT) —shift columns right.....	175
SHIFT <—shift data left.....	175
SHIFT > —shift data right.....	175
SORT—sort data.....	176
SOURCE—describe format of data.....	176
STATS—set or query Stats mode.....	176
SUBMIT—submit data for batch processing.....	177
TABS—set or query Tabs mode.....	177
TABSLINE—set or query tabs line.....	178
TENTER—set up panel for text entry.....	178
TFLOW—text flow a paragraph.....	179
TSPLIT—text split a line.....	179
UNNUMBER—remove sequence numbers.....	179
UP—scroll up.....	180
USER_STATE—save or restore user state.....	180
VERSION—set or query version number.....	180
VIEW—view from within an edit session.....	181
VOLUME—query volume information.....	181
XSTATUS—set or query exclude status of a line.....	181

Chapter 5. SCLM services and macros..... 183

SCLM services.....	183
ACCTINFO—retrieve accounting information.....	183
AUTHCODE—set or retrieve an AUTHCODE.....	184
BUILD—build a member.....	185
DBACCT—retrieve accounting records for a member.....	186
DBUTIL—generate a tailored data set and report.....	188
DELETE—delete database components.....	189
DELGROUP—delete database components from group.....	190
DSALLOC—allocate data sets for group/type.....	191
EDIT— edit a member of a controlled library.....	192
END—end an SCLM services session.....	193
ENDEC— encode and decode members.....	194
EXPORT—extract SCLM accounting information for a group.....	194
FREE—free database from its association with SCLM ID.....	195
GETBLDMP—retrieve build map information.....	196
GETXDEP—return cross-dependency information.....	197
IMPORT—import SCLM accounting information to current project.....	197
INIT—generate an SCLM ID for a database.....	198
LOCK—lock a member or assign an access key.....	199
MIGRATE—create accounting information for selected members.....	200
NEXTGRP—find the next group in a hierarchy.....	201
PARSE—parse a member for statistical and dependency information.....	201
PROMOTE—promote a member from one library to another.....	202
RPTARCH—generate an SCLM architecture report.....	203
SAVE—lock, parse, and store a member.....	204
SCLMINFO—return project information.....	205

START—generate an application ID for a service session.....	205
STORE—store member information in an accounting record.....	206
UNLOCK—unlock a member in a development library.....	207
VERDEL—delete version information.....	207
VERHIST—Retrieve Versioned Member Information.....	208
VERINFO—retrieve version information.....	209
VERRECOV—recover a version.....	210
XDEPUPDT—Update Cross-dependency Information.....	211
SCLM macros.....	211
FLMABEG—define the project name of the project definition.....	211
FLMAEND—last macro in the project definition.....	211
FLMAGRP—define a group of authorization codes.....	212
FLMALLOC—define each DDname in the DDname substitution list for a translator.....	213
FLMALTC—specify alternate control information.....	214
FLMATVER—enable the audit and version utility.....	214
FLMCNTRL—specify project-specific control options.....	215
FLMCPYLB—identify additional data sets to be concatenated to a DDname.....	220
FLMGROUP—define one group in the project definition.....	220
FLMINCLS—associate include-sets with types in the project hierarchy.....	221
FLMLANGL—define a language to SCLM.....	221
FLMLRBLD—rebuild members with a particular language after promotion.....	222
FLMPROJ—define a subproject to an SCLM project/alternate.....	222
FLMNPROM—specify which SCLM editable elements may or may not be marked as non- promotable.....	222
FLMSYSLB—define a set of data sets for a language containing project macros or included members.....	222
FLMTCOND—select build translators based on group and return codes.....	223
FLMTOPTS—select the options based on group.....	223
FLMTRNSL—define once for each translator to be invoked for a language.....	224
FLMTYPE—define one FLMTYPE in the project definition.....	225
Chapter 6. System variables.....	227
Configuration utility.....	227
Time and date.....	228
General.....	229
Terminal and function keys.....	233
Scrolling.....	235
PRINTG command.....	236
Table display service.....	236
LIST service.....	237
LOG and LIST data sets.....	237
Dialog error.....	237
Tutorial panels.....	238
Selection panels.....	238
DTL panels or panels containing a)PANEL section.....	238
Chapter 7. Dialog variables.....	239
PDF non-modifiable variables.....	247
Chapter 8. Dialog Tag Language (DTL) tags.....	249
Appendix A. Accessibility.....	279
Notices.....	281
Terms and conditions for product documentation.....	282
IBM Online Privacy Statement.....	283
Policy for unsupported hardware.....	283

Minimum supported hardware.....	283
Programming Interface Information.....	284
Trademarks.....	284
Index.....	285

Figures

1. Sample syntax diagram.....	xvi
-------------------------------	-----

Tables

1. Picture search strings - special characters for string-1.....	27
2. Picture search strings - additional characters.....	27
3. Picture search strings - special characters for string-2.....	27
4. Character search string format.....	28
5. Variables Returned in Each Row of the Table.....	105
6. System variables: Configuration utility.....	227
7. System variables: Time and date.....	228
8. General variables.....	229
9. System variables: Terminal and function keys.....	233
10. Scrolling variables.....	235
11. System variables: PRINTG command.....	236
12. System variables: Table display service.....	236
13. System variables: LIST service.....	237
14. System variables: LOG and LIST data sets.....	237
15. System variables: Dialog error.....	237
16. System variables: Tutorial panels.....	238
17. System variables: Selection panels.....	238
18. System variables: DTL panels or panels containing a)PANEL section.....	238
19. Dialog function pool variables.....	239
20. Read-only variables available to PDF component dialogs.....	247
21. Tag summary.....	249

Preface

This document is a quick reference for application developers and library administrators who use various components of the ISPF product.

Chapter 1, “ISPF general information,” on page 1 contains general information about ISPF.

Chapter 2, “Dialog development information,” on page 29 contains information relevant to dialog developers, including panel definition statements and built-in functions, message definitions, and file-tailoring skeleton statements.

Chapter 3, “ISPF service syntax with return codes,” on page 45 through Chapter 5, “SCLM services and macros,” on page 183 contain the syntax and return codes for the following items:

- ISPF services
- Edit macro commands
- SCLM services and macros

This document also contains tables of ISPF system variables (Chapter 6, “System variables,” on page 227) and dialog variables (Chapter 7, “Dialog variables,” on page 239) and a summary of the Dialog Tag Language (DTL) tags (Chapter 8, “Dialog Tag Language (DTL) tags,” on page 249).

Information in this document was extracted from the following prerequisite books:

- [*z/OS ISPF Dialog Developer's Guide and Reference*](#)
- [*z/OS ISPF User's Guide Vol I*](#)
- [*z/OS ISPF User's Guide Vol II*](#)
- [*z/OS ISPF Services Guide*](#)
- [*z/OS ISPF Edit and Edit Macros*](#)
- [*z/OS ISPF Software Configuration and Library Manager Guide and Reference*](#)
- [*z/OS ISPF Dialog Tag Language Guide and Reference*](#)

We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information. See [How to send feedback to IBM](#) for additional information.

Who should use this document

This document is for:

- Application programmers who write programs or command procedures that invoke ISPF services.
- Application programmers who use the ISPF editor and edit macros.
- Library administrators who use library management facilities.

How to read the syntax diagrams

The syntactical structure of commands described in this document is shown by means of syntax diagrams.

Figure 1 on page xvi shows a sample syntax diagram that includes the various notations used to indicate such things as whether:

- An item is a keyword or a variable.
- An item is required or optional.
- A choice is available.
- A default applies if you do not specify a value.

- You can repeat an item.




Figure 1. Sample syntax diagram

Here are some tips for reading and understanding syntax diagrams:

Order of reading

Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The ➤ symbol indicates the beginning of a statement.

The → symbol indicates that a statement is continued on the next line.

The ← symbol indicates that a statement is continued from the previous line.


The ⇨ symbol indicates the end of a statement.

Keywords

Keywords appear in uppercase letters.

➤ COMMAND_NAME ➤

Sometimes you only need to type the first few letters of a keyword, The required part of the keyword appears in uppercase letters.



In this example, you could type "KEY", "KEYW", "KEYWO", "KEYWOR" or "KEYWORD".

The abbreviated or whole keyword you enter must be spelled exactly as shown.

Variables

Variables appear in lowercase letters. They represent user-supplied names or values.

➤ *required_variable* ➤


Required items

Required items appear on the horizontal line (the main path).

➤ COMMAND_NAME — *required_variable* ➤

Optional items


Optional items appear below the main path.




Choice of items

If you can choose from two or more items, they appear vertically, in a stack.


If you *must* choose one of the items, one item of the stack appears on the main path.



If choosing one of the items is optional, the entire stack appears below the main path.




If a default value applies when you do not choose any of the items, the default value appears above the main path.




Repeatable items

An arrow returning to the left above the main line indicates an item that can be repeated.




If you need to specify a separator character (such as a comma) between repeatable items, the line with the arrow returning to the left shows the separator character you must specify.




Fragments

Where it makes the syntax diagram easier to read, a section or *fragment* of the syntax is sometimes shown separately.



⋮

fragment_name



z/OS information

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross-document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see *z/OS Information Roadmap*.

How to provide feedback to IBM

We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information. For more information, see [How to send feedback to IBM](#).

Summary of changes

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

Note: IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under [IBM z/OS Product Documentation Update Policy](http://www.ibm.com/docs/en/zos/latest?topic=zos-product-documentation-update-policy) (www.ibm.com/docs/en/zos/latest?topic=zos-product-documentation-update-policy).

Summary of changes for z/OS 3.2

The following content is new, changed, or no longer included in z/OS 3.2.

New

The following content is new.

September 2025 release

- [“GENLIST - list a member’s generations” on page 65](#) is a new ISPF service.

Changed

The following content is changed.

September 2025 release

- [Table 19 on page 239](#) is updated with new variables ZABSGEN and ZRELGEN, and GENLIST(W) is added to applicable variables.
- [“COMPARE—compare data set” on page 144](#) is updated with new parameter GEN.

Deleted

The following content is deleted.

September 2025 release

- None.

Summary of changes for z/OS 3.1

The following changes are made for z/OS 3.1.

The following content is new, changed, or no longer included in z/OS 3.1.

New

- PDSE v2 member generation enhancements, see the following topic:
 - [“PDF member generation list commands” on page 14](#)

Changed

- Externalize Edit HILITE settings to ISPF z variables, see the following topic:
 - [Chapter 7, “Dialog variables,” on page 239](#)
- PDSE v2 member generation enhancements, see the following topics:
 - [“PDF Browse primary commands” on page 11](#)

- [“PDF member list commands” on page 12](#)
- [“PDF Edit and View commands” on page 16](#)
- [“BROWSE—Browse a data set” on page 49](#)
- [“EDIT—edit a data set” on page 58](#)
- [“VIEW—view a data set” on page 130](#)
- [Chapter 7, “Dialog variables,” on page 239](#)

Deleted

- None.

What's in the library?

You can order the ISPF books using the numbers provided below.

Title

Order Number

z/OS ISPF Dialog Developer's Guide and Reference

SC19-3619-40

z/OS ISPF Dialog Tag Language Guide and Reference

SC19-3620-40

z/OS ISPF Edit and Edit Macros

SC19-3621-40

z/OS ISPF Messages and Codes

SC19-3622-40

z/OS ISPF Planning and Customizing

GC19-3623-40

z/OS ISPF Reference Summary

SC19-3624-40

z/OS ISPF Software Configuration and Library Manager Guide and Reference

SC19-3625-40

z/OS ISPF Services Guide

SC19-3626-40

z/OS ISPF User's Guide Vol I

SC19-3627-40


z/OS ISPF User's Guide Vol II

SC19-3628-40

Chapter 1. ISPF general information

Invoking an ISPF application—the ISPSTART command

➡ ISPSTART ➡



ISPF system information

Files used by ISPF

Note: Files used by a given invocation of ISPF must be allocated before ISPF is invoked.

DDNAME(lib-type)	Description
ISPFIL	File tailoring output
ISPILIB	Image library
ISPMLIB	Message
ISPPLIB	Panel
ISPPROF	User profile
ISPSLIB	Skeleton
ISPTABLE	Table output
ISPTLIB	Table input
SYSPROC	REXX/CLIST library
SYSEXEC	REXX library

Note:

The image library with the associated ddname ISPILIB is no longer used by ISPF.

ISPF system commands

ACTIONS

BACKWARD

BOTTOM

CANCEL

CMDE

COLOR


CRETRIEV

CUAATTR

CURSOR


DOWN


DDLIST

➤ DSLIST —  ➤


➤ DTEST — *parameter_number* ➤


END






ISPD TLC





ISPFWORK




ISPPREP

ISPVCALL

ISRRLIST


ISRROUTE





KEYS

KEYSHELP



LEFT





NOP

NRETRIEV



PRINT

PRINTG







PRINT-HI

PRINTL

PRINTLHI

PSCOLOR


RCHANGE



REFOPEND

REFOPENL



RESIZE
 RETF
 RETP
 RETRIEVE
 RETURN
 RFIND
 RIGHT
 SAREA




SETTINGS
 SHRPROF




SPLITV
 START



TOP
 TS0
 TSOCMD



UP



WINDOW

ZKEYS

Command table actions

ALIAS

When followed by the name of another command and optional parameters, allows specification of command aliases.

NOP

Causes the command to be functionless. System displays an "inactive command" message in this case.

PASSTHRU

Causes the command to be passed to the dialog, as though it had not been found in the table.

SELECT

When followed by selection keywords, causes the selected dialog command, program or selection panel to be given control immediately.

SETVERB

Causes the command to be passed to the dialog with the command verb stored separately from the parameters.

Blank (no action)

Causes the table entry to be ignored, and scanning to continue (to search for additional entries having the same verb).

Variable name

Begins with an ampersand. Its content may be one of the listed actions. Allows dynamic specification of a command action.

Dialog test commands


Primary commands

You can enter these commands on the Command line while using Dialog Test (option 7).


CANCEL

END

Syntax



QUAL




Line commands

These line commands have special meaning during testing operations:



Delete one or n lines starting with this line.







Insert one or n lines directly after this line, with underscores and quotes in the appropriate fields.





Repeat this line once or n times.


PDF Browse primary commands

You can enter these commands on the command line while using the Browse function.



OR:





You can use this format to enter label definitions on the command line:


.cccc
Defines a label (PDF component internal symbol), which is equated to the top line on the screen. Can be used with LOCATE to scroll directly to that line.


PDF member list commands

Primary commands

You can enter these commands on the command line on member list displays.

CONFIRM









MLC

MLS

REFRESH

RESET

RFIND



Line commands

On all member list displays except those for option 3.1 and 3.4, you can enter this 1-character command at the beginning of a line.

S

Selects the member.

On option 3.1 and 3.4 member list displays, you can enter these 1-character commands at the beginning of a line.

B

Browses the member.

C

Copies the member.

D

Deletes the member.

E

Edits the member.

G

Resets the member.

J

Submits the member.

M

Moves the member.

N

Displays the generation list for the member (if PDSE generation type).

P

Prints the member.

R

Renames the member. When using this command, you must also enter the new name to the right of the member name.

T

TSO command.

V

Views the member.

TSO commands, CLISTs, and REXX EXECs can be entered in member lists that have an expanded line command field. These are member lists displayed by using option M of the Data Set List utility. Here, any command other than B, D, E, P, R, or V is considered to be a TSO command, CLIST, or REXX exec.

PDF member generation list commands

The member generation list is accessible via the member list panel from options 3.1 and 3.4. You can enter these 1-character line commands.

B

Browses the generation.

D

Deletes the generation.

E

Edits the generation.

P

Prints the generation.

V

Views the generation.

I

Displays information about a generation.

/

Displays the Action for Generation panel.


Multiple line commands cannot be entered at one time. TSO commands are also not supported on member generation lists.

PDF data set list commands

Primary commands


You can enter these commands on the command line on option 3.4 data set list displays.

APPEND




DSLIS

EXCLUDE






LC



REFRESH

RESET

RFIND



VA

VS

VT

VW

Line commands

On option 3.4 data set list displays, you can enter the following 1-character commands at the beginning of a line. Any other command entered at the beginning of a line is considered to be a TSO command, CLIST, or REXX exec.

B

For a library or partitioned data set, displays a member list. You can then use the S command to select a member to browse. For a sequential data set, displays the data set in browse mode.

C

Catalogs the data set.

CO

Copies a data set.

D

Deletes an entire data set. Displays a Confirm Delete panel if you request confirmation.

E

For a library or partitioned data set, displays a member list. You can then use the S command to select a member to edit. For a sequential data set, displays the data set in edit mode.

F

Frees unused space in a data set.

I

Displays library or data set information.

M

For a library or partitioned data set, displays a member list.

MO

Moves a data set.

NX

Unexclude a line from display.

NXF

Unexclude the first of a set of excluded data sets.

NXL

Unexclude the last of a set of excluded data sets.

P

Prints the library or data set.

PX

Prints an index listing.

R

Displays a panel, on which you can rename the library or data set.

RA

Adds a data set to a reference list.

RS

Resets statistical data.

S

Displays library or data set information in short format.

U

Uncatalogs the data set.

V

For a library or partitioned data set, displays a member list. You can then use the S command to select a member to view. For a sequential data set, displays the data set in view mode.

X

Excludes a data set from the list.

Z

Compresses a library or data set.


=



Repeats the last line command entered.

PDF Edit and View commands

Primary commands

While you are using the PDF editor to edit or view data, these commands can be entered on the command line.






Notes:





¹ If you don't specify the group of lines using labels, you must specify the group by using C[®] or M line commands.

➔ CUT ➔









Notes:

¹ You can also specify the group of lines using C or M line commands.




➤➤ END ➤➤




➤➤ LEVEL — num ➤➤


➤➤ LF ➤➤



Notes:


¹ If you don't specify the position using a label, you must specify the position by using an A or B line command.






Notes:


¹ STD is the default for non-COBOL data set types. COBOL is the default for COBOL data set types.






Notes:

¹ STD is the default for non-COBOL data set types. COBOL is the default for COBOL data set types.





Notes:

¹ If you don't specify the group of lines using labels, you must specify the group by using C or M line commands.




➡ RFIND ➡










sort_field:




SOURCE — *character_encoding* →



UNDO →







Line commands

Under Edit or View, you can enter these line commands at the beginning of a line by typing over the line number. If you do not enter a value of *n*, the default is 1 except for:


- The shift commands, which default to 2 column positions
- The TE command, which defaults to the number of lines remaining on the screen
- The TF command, which defaults to the current right boundary.




Shifts columns left the specified number of positions



Shifts columns right the specified number of positions



Shifts data left the specified number of positions (default 2).




Shifts data right the specified number of positions (default 2).




Identifies the line after which copied, moved, or model lines are to be inserted.




Identifies the line before which copied, moved, or model lines are to be inserted.




Displays the column boundary definition line.



Copies one or more lines from one location to another.




Displays a position identification line.




Deletes one or more lines.



Redisplays one or more lines at the beginning of a block of excluded lines.




Displays characters in hexadecimal format.




Inserts a blank data entry line.



Redisplays one or more lines at the end of a block of excluded lines.




Converts all uppercase alphabetic characters in one or more lines to lowercase.




Moves one or more lines from one location to another.

➤ MASK ➤

Displays the contents of the mask when used with the I (insert), TE (text entry), and TS (text split) line commands.



Makes NOTE, MSG, INFO, and COLS lines into data lines.




Rearranges a single column list of items into multiple column, or tabular, format.




Repeats one or more lines.




Redisplays one or more lines with the leftmost indentation in a block of excluded lines.




Displays the tab definition line.




Inserts blank lines to allow power typing for text entry.




Restructures paragraphs following deletions, insertions, splitting, and so forth.



Divides a line so that data can be added.



Converts all lowercase alphabetic characters in one or more lines to uppercase.



Excludes one or more lines from a panel.

Picture search strings – special characters for string-1:

<i>Table 1. Picture search strings - special characters for string-1</i>	
String	Character
P '='	Any character
P '¬'	Any character that is not a blank
P '.'	Any character that cannot be displayed
P '#'	Any numeric character, 0-9
P '-'	Any nonnumeric character
P '@'	Any alphabetic character, uppercase or lowercase
P '<'	Any lowercase alphabetic character
P '>'	Any uppercase alphabetic character
P '\$'	Any special character, neither alphabetic nor numeric.

If you are using an APL or TEXT keyboard, you can use the following additional characters in a picture string:

<i>Table 2. Picture search strings - additional characters</i>	
String	Character
P '␣'	Any APL-specific or TEXT-specific character
P ' _ '	Any underscored nonblank character.

Picture search strings – special characters for string-2

<i>Table 3. Picture search strings - special characters for string-2</i>	
String	Character
P '='	Equal to the corresponding character in string-1
P '>'	Converts the corresponding character in string-1 to uppercase
P '<'	Converts corresponding character in string-1 to lowercase.

Character search string format

<i>Table 4. Character search string format</i>	
String	Character
Simple string:	cccccc (no embedded blanks or commas)
Delimited string:	' ccccc ' or " ccccc "
Hex string:	X ' hhhh ' or ' hhhh ' X
Text string:	T ' cccc ' or ' cccc ' T
Picture string:	P ' ssss ' or ' ssss ' P
Character string:	C ' cccc ' or ' cccc ' C
Previous string:	* (single asterisk)

Chapter 2. Dialog development information

This topic contains information relevant to dialog developers.

Invoking the ISPF DTL conversion utility


```
ISPD TLC      (for interactive interface)
```

OR

```
ISPD TLC ?    (for help information)
```

OR

```
(command syntax)
```



Panel definition sections

All parameters on header statements are optional. When preparing a panel header statement, use only one line.

Coded Character Set Identifier Section

►►)CCSID — NUMBER(*ccsid-number*) ◄◄

Panel Section

The diagram illustrates the syntax for various SQL aggregate functions. Each function is represented by a horizontal line with brackets indicating the positions of its arguments:

- FIELD**: `FIELD(field-name)`
- LEN**: `LEN(value)`
- IND**: `IND(value)`
- LIND**: `LIND(value)`
- RIND**: `RIND(value)`
- SIND**: `SIND(value)`
- LCOL**: `LCOL(field-name)`
- RCOL**: `RCOL(field-name)`
- SCALE**: `SCALE(field-name)`
- SCROLL**: `SCROLL(value)`


Attribute Section

```

)ATTR (
  DEFAULT (def1 def2 def3)
  FORMAT (EBCDIC DBCS MIX)
  OUTLINE (NONE L R O U BOX)
)

```

Action Bar Choice Section



Action Bar Choice Initialization Section

➤)ABCINIT ➤


Note: Only valid when the Action Bar Choice section is specified.

Action Bar Choice Processing Section

➤)ABCPROC ➤


Note: Only valid when the Action Bar Choice section is specified.

Body Section




Note: All keywords must be specified on the same panel line.

Model Section



Area Section



Initialization Section




Reinitialization Section




Processing Section



Field Section




Help Section



List Section

`)LIST list-name VAL(value) CHOICE(value)`

`)PNTS FIELD(field-name) VAR(variable) VALUE(value)`





`)END`


Panel statements and built-in functions

Attribute section


`attrchar`







Note: Common User Access (CUA) attribute TYPE values listed below are identified in the section that follows.



CUA attribute TYPE values

TYPE Value
Description

AB

Action Bar Unselected Choices

ABSL

Action Bar Separator Line

CEF

Choice Entry Field

CH

Column Heading

CHAR

Character attributes in a dynamic area

CT

Caution Text

DATAIN

Input (unprotected) field in a dynamic area

DATAOUT

Output (protected) field in a dynamic area

DT

Descriptive Text

EE

Error Emphasis

ET

Emphasized Text

FP

Field Prompt

GRPBOX

Group Box

INPUT

Input (unprotected) field

LEF

List Entry Field

LI

List Items

LID

List Item Description

NEF

Normal Entry Field

NT

Normal Text

OUTPUT

Output (protected) field

PIN®

Panel Instruction

PS

Point-and-Shoot

PT

Panel Title

RP

Reference Phrase

SAC

Select Available Choices

SC

Selected choice

SI

Scroll Information

SUC

Select Unavailable Choices

TEXT

Text (protected) field

VOI


Variable Output Information

WASL

Work Area Separator Line


WT

Warning Text

Initialization, Reinitialization, and Processing sections➤ *variable* — = ➔➤ **GOTO** — *label* ➤


➤ **IF** — (*variable* — *operator* — *value*) — **ELSE** — **EXIT** ➤

➤ **PANEXIT** — ((— *value*), ➔

➤ **)** ➤

➤ **REFRESH**(— *field*) ➤


Panel definition statements and functions



VER keywords

ALPHA	ALPHAB	BIT	DBCS	DSNAME	DSNAMEF
DSNAMEFM	DSNAMEPQ	DSNAMEQ	EBCDIC	ENUM	FILEID
HEX	IDATE	INCLUDE	ITIME	JDATE	JSTD
LEN	LIST	LISTV	LISTVX	LISTX	MIX
NAME	NAMEF	NUM	PICT	PICTCN	RANGE
STDDATE	STDTIME	VSYM			

Panel control variables



➤➤ .ATTR(*field*) — = — ' — keyword(*value*) — ' ➤➤

➤➤ .ATTRCHAR(*char*) — = — ' — keyword(*value*) — ' ➤➤

➤➤ . — { — AUTOSEL=YES) — } ➤➤

➤➤ . — { — AUTOSEL=NO) — } ➤➤

➤➤ .CSRPOS =*cursor-position* ➤➤

➤➤ .CSRROW =*table-row-number* ➤➤

➤➤ .CURSOR =*field-name* ➤➤

➤➤ .HELP =*panel-name* ➤➤

➤➤ .MSG =*message-id* ➤➤

➤➤ .NRET — = — { — ON — } ➤➤

➤➤ .NRET — = — { — OFF — } ➤➤

➤➤ .NRET — = — { — DSN — } ➤➤

➤➤ .NRET — = — { — LIB — } ➤➤

➤➤ .PFKEY = ¹ ➤➤

Notes:

¹ Contains function key pressed by user (PF01,PF02, ...,PF24).

➤➤ .RESP — = — { — ENTER — } ➤➤

➤➤ .RESP — = — { — END — } ➤➤


➤➤ .TRAIL = ¹ ➤➤

Notes:


¹ Contains remainder from TRUNC operation.



➤➤ .ZVARS = '*name-list*' ➤➤

Message definitions



Skeleton control statements






➤➤)SEL — *relational-expression* —)ENDSEL — ➤➤


➤➤)SET — *variable* — = — *expression* — ➤➤

➤➤)SETF — *variable* — = — *expression* — ➤➤




Notes:

¹ Maximum of 16 values.



Notes:

¹ Maximum of 16 values.



Notes:

¹ Maximum of 16 values.

Chapter 3. ISPF service syntax with return codes

Here are the ISPF services. The services are presented in alphabetical order. For each service, the command procedure format is shown, followed by the PL/I call formats. For more complete information, see the [z/OS ISPF Services Guide](#).

Each service description consists of this information:

Format

The syntax used to code the service, showing both command invocation and call invocation.

Return codes

A description of the codes returned by the service. For all services, a return code of 12 or higher implies a severe error. This error is usually a syntax error, but can be any severe error detected when using the services.

The importance of parameter order, and using placeholders for optional parameters

For several of the ISPF services, the syntax for call invocation (shown under "**Call invocation format**") includes a number of optional parameters. These optional parameters are *positional*; that is:

- Each optional parameter you choose to specify must be specified in the sequence shown in the syntax diagram.
- Where you specify a parameter without specifying one or more previous optional parameters, the absence of each previous optional parameter must be indicated by a placeholder in the form of a blank enclosed in single quotes followed by a comma.

For example, in the call invocation for the ADDPOP service shown here, the first and third optional parameters have been specified (field-name and column respectively), whilst the second optional parameter (in this case, row) has been omitted:

```
CALL ISPLINK ('ADDPOP ', field-name, ' ', column);
```

When you do not specify an optional parameter, the default value (if any) for that parameter applies.

It is only necessary to include placeholders for unspecified *intermediate* parameters. That is, once you have specified the last optional parameter you want, there is no need to specify placeholders for subsequent optional parameters (if any); if there are default values for any subsequent optional parameters, then they will apply.

Further examples:

All optional parameters specified:

```
CALL ISPLINK ('DISPLAY ', panel-name, message-id, cursor-field-name, cursor-position, stack-buffer-name, ret-buffer-name, ret-length-name, message-field-name);
```

First five optional parameters specified:

```
CALL ISPLINK ('DISPLAY ', panel-name, message-id, cursor-field-name, cursor-position, stack-buffer-name);
```

First, third, and fourth optional parameters specified:

```
CALL ISPLINK ('DISPLAY ', panel-name, ' ', cursor-field-name, cursor-position);
```

Third, fourth, and seventh optional parameters specified:


```
CALL ISPLINK ('DISPLAY ', ' ', ' ', cursor-field-name, cursor-position, ' ', ' ', ret-length-name);
```

Command format

This section describes the general format for ISPF services.

ISPEXEC command invocation

The general format for a command invocation is:



ISPEXEC parameter conventions

service-name

Alphabetic; up to 8 characters long.

parameter1

Positional parameter; required for some services.

parameter2 parameter3 ...


Keyword parameters. They can take either of two forms:

```

keyword
or
keyword(value)
  
```

The ISPLINK interface

For calls in PL/I or COBOL, the general call format for invoking ISPF services from functions by using ISPLINK is:



CALL ISPLINK parameters

These parameters are positional. They must appear in the order described for each service.

Parameters shown below the line are optional, but ISPF assumes default values for those parameters you do not choose.

If you want to omit a parameter, you must still account for it by inserting a blank enclosed in single quotes (' ') in its place. This is how you would omit **parm2** from this sample call:

```
CALL ISPLINK (service-name, parm1, ' ', parm3);
```

If you need only the first few of a list of parameters, you must omit all other parameters to the right of the last parameter you need. For example, if you are using a service that has five parameters, but you need to use only the first three, code it like this:

```
CALL ISPLINK (service-name, parm1, parm2, parm3);
```

You must show the last parameter in the calling sequence with a '1' as the high order bit in the last entry of the address list. PL/I, COBOL, Pascal, and FORTRAN call statements automatically generate this high-order bit. However, you must use the VL keyword in assembler call statements.

The ISPEXEC interface

You can use the command function form for service requests in a program function by using the call format of ISPEXEC. Excluding calls in FORTRAN, Pascal, and APL2®, the general call format for invoking ISPF services from program functions by using ISPEXEC is:

```
CALL ISPEXEC (buf-len, buffer);
```

CALL ISPEXEC parameters

buf-len

Specifies a fullword fixed binary integer containing the length of the buffer.

buffer


Specifies a buffer containing the name of the service and its parameters just as they would appear in an ISPEXEC invocation for a command invocation written in CLIST.

The maximum buffer size is 32767 bytes.

All services that are valid through ISPEXEC command invocation statements are valid through the CALL ISPEXEC interface.

ADDPOP—start pop-up window mode


Command invocation format



Call invocation format

```
➤ CALL — ISPEXEC — (buf-len, — buffer); ➤
```

OR



Return codes

0

Normal completion.

12

An ADDPOP service call was issued before a panel was displayed or another ADDPOP service call was issued before a panel was displayed for the previous ADDPOP call.

20

Severe error.

BRIF—Browse interface

Command invocation format

Command procedures cannot be used to invoke this service.

Call invocation format

```

➤ CALL — ISPLINK — ('BRIF_...' — , data-name , rec-format — , rec-len →

➤ , read-routine — , cmd-routine , dialog-data →

➤ , { 'ISRBROBA'
      panel-name
      ' ' } , format-name , { 'NO_'
      ' '
      'YES' } →

➤ , { 'EXTEND_'
      ' ' } ); ➤

```

Read routine return codes

- 0**
Normal completion.
- 4**
Temporary end of file.
- 8**
Record requested beyond end of data. The relative record number of the last data record and a pointer to the last data record are returned.
- 16**
Read error. Browse data obtained up to the read error is formatted and displayed with an indication that a read error was encountered.
- 20**
Severe error. (The BRIF service terminates immediately with a return code of 20.)

Command routine return codes

- 0**
Normal completion.
- 4**
ISPF should process the requested function.
- 12**
Command deferred; retain the command on the Command line. Browse data is redisplayed.
- 20**
Severe error. (The BRIF service terminates immediately with a return code of 20.)

BRIF service return codes

- 0**
Normal completion.

Call invocation format

```
CALL ISPLINK ('BROWSE_', dsname, serial, , pswd-value, panel-name, data-id, , member-name, format-name, {'NO_', 'YES'}, file-var, rec-len, generation);
```

OR

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

Return codes

O

Normal completion.

12

Zero-length data; empty sequential data set or z/OS UNIX file, or zero-length member of a partitioned data set.

13

The specified generation of the member was not found in the specified data sets.

14

Member not found.

15

A non-current generation was specified. None of the specified data sets are PDSE version 2 data sets that are configured for member generations.

16

Either:

- No members matched the specified pattern.
- No members in the partitioned data set.

18


A VSAM data set was specified but the ISPF Configuration Table does not allow VSAM processing.

20

Severe error; unable to continue.

CONTROL—set processing modes

Command invocation format



Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

- 0** Normal completion.
- 8** Split-screen mode and `term` remains enabled.
- 20** Severe error.



0

Normal completion.

8


Split-screen mode already in effect. Applies only to a SPLIT DISABLE request. Split-screen mode remains enabled.

20

Severe error.

DISPLAY—display panels and messages


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

OR



Return codes

0

Normal completion.

For the COMMAND option, the *ret-buffer-name* is set to blanks and the *ret-length-name* is set to zero. Passing an empty command chain buffer also results in a normal completion.

4

One or more commands in the stack could not be found in the active set of command tables.

8

User requested termination using the END or RETURN command. If CANCEL and EXIT are requested from a panel displayed using the DISPLAY service call and the panel was defined with the dialog tag language (DTL), the dialog manager returns the command in ZVERB and sets a return code of 8 from the display screen.

12

The specified panel, message, message location field, or cursor field could not be found.

16


Truncation or translation error in storing defined variables.

20

Severe error.

DSINFO—data set information dialog

Command invocation format

►► ISPEXEC — DSINFO — DATASET(*dsname*) —  VOLUME(*serial*) —►◄

Call invocation format

►► CALL — ISPEXEC — (*buf-len* , — *buffer*); ►◄

OR

►► CALL — ISPLINK — ('DSINFO_...' — , — *dsname* — , — *serial* —); ►◄

Return codes

0

Normal completion.

8

User requested information unavailable. Dialog error variables (ZERRLM, and so on) contain further information.

12

One of these:

- Internal Service Failure
- Error when using the OBTAIN macro to read the DSCB
- Error obtaining directory information

20

Severe error.

EDIF—Edit interface

Command invocation format

You cannot use command procedures to invoke this service.

Call invocation format

```

➤ CALL — ISPLINK — ('EDIF_<u>      </u>' — , <u>data-name</u> — , <u>profile-name</u> — , <u>rec-format</u> —
                                     <u>'<u>          </u>'</u>
                                     <u>          </u>

➤ , <u>rec-len</u> — , <u>read-routine</u> — , <u>write-routine</u> — , <u>cmd-routine</u> —
                                     <u>'<u>          </u>'</u>

➤ , <u>dialog-data</u> — , <u>edit-len</u> — , <u>panel-name</u> —
                                     <u>'<u>          </u>'</u>

➤ , <u>macro-name</u> — , <u>format-name</u> — , { <u>'NO_<u>      </u>'</u>
                                     <u>'<u>          </u>'</u>
                                     <u>'YES_<u>      </u>'</u> } —
                                     <u>          </u>

➤ , { <u>'NO_<u>      </u>'</u>
      <u>'<u>          </u>'</u>
      <u>'YES_<u>      </u>'</u> } — , <u>parm-var</u> — , <u>tabname</u> — ); ➤
                                     <u>'<u>          </u>'</u>
                                     <u>          </u>

```

OR

```

➤ CALL — ISPLINK — ('EDIF_<u>      </u>' — , <u>data-name</u> — , '<u>          </u>' — , <u>rec-format</u> —
                                     <u>'<u>          </u>'</u>
                                     <u>          </u>

➤ , <u>rec-len</u> — , <u>read-routine</u> — , <u>write-routine</u> — , <u>cmd-routine</u> — , ➤
                                     <u>'<u>          </u>'</u>
                                     <u>          </u>

➤ <u>dialog-data</u> — , '<u>          </u>' — , '<u>          </u>' — , '<u>          </u>' — , '<u>          </u>' — , ➤
      <u>'<u>          </u>'</u>
      <u>          </u>

➤ , '<u>YES_<u>      </u>'</u> — , '<u>          </u>' — , <u>tabname</u> — ); ➤
                                     <u>'<u>          </u>'</u>
                                     <u>          </u>

```

Read routine return codes

0

Normal completion.

8

End of data records (no data record returned).

16

Read error. If a read error is encountered when the system builds the initial edit display, the EDIF service terminates with a return code of 20. Otherwise, the edit data is redisplayed.

20

Severe error. (The EDIF service terminates immediately with a return code of 20.)

Write routine return codes

0

Normal completion.

- 16**
Output error, return to Edit mode.
- 20**
Severe error. (The EDIF service terminates immediately with a return code of 20.)

Command routine return codes

- 0**
Normal completion.
- 4**
ISPF should process the requested function.
- 12**
Command deferred; retain the command on the Command line. Edit data is redisplayed.
- 20**
Severe error. (The EDIF service terminates immediately with a return code of 20.)

EDIF return codes

- 0**
Normal completion, data saved.
- 4**
Normal completion, data not saved.
- 16**
Unexpected return code received from a dialog-supplied routine. When an unexpected return code is received, the EDIF service terminates immediately with a return code of 16.
- 20**
Severe error; unable to continue.

EDIREC—initialize edit recovery

Command invocation format

You cannot use command procedures to invoke this service.

Call invocation format

```
➤ CALL — ISPLINK — ('EDIREC_...' — , — 'INIT_...' — , — command-name — ); ➤
```

'INIT_...'	
'QUERY_...'	
'CANCEL_...'	
'DEFER_...'	

Return codes

- 0**
Normal completion.
- INIT - EDIF recovery table was successfully created.
 - QUERY - Recovery is not pending.
- 4**
Normal completion.
- INIT - EDIF recovery table already exists for current application.


- QUERY - Entry found in EDIF recovery table (recovery is pending).

20

Severe error; unable to continue.


EDIT—edit a data set

Command invocation format




OR

►► ISPEXEC — EDIT — DATAID(*data-id*) →




OR

►► ISPEXEC — EDIT — FILE(*file-var*) — PANEL(*panel-name*)



Call invocation format



OR

➤ CALL — ISPEXEC — (*buf-len* , — *buffer*); ➤

Return codes

0

Normal completion; data was saved.

4

Normal completion; data was *not* saved for one of these reasons.

- No data changes were made during the EDIT session.
- The CANCEL command was used to exit EDIT.
- Browse was substituted for EDIT because insufficient storage was available to read in the requested data.

9

The specified generation of the member was not found in the specified data sets.

10

Member not found.

11

A non-current generation was specified. None of the specified data sets are PDSE version 2 data sets that are configured for member generations.

12

YES was specified for the LOCK parameter or the ws-filename-buffer-name parameter was specified.

14

Member, sequential data set, or z/OS UNIX file in use.

16

Either:

- No members matched the specified pattern.
- No members in the partitioned data set.

18

A VSAM data set was specified but the ISPF Configuration Table does not allow VSAM processing.


20

Severe error; unable to continue.

EDREC—specify edit recovery handling


Command invocation format

►► ISPEXEC — EDREC →



Call invocation format

►► CALL — ISPLINK — ('EDREC_...' →



OR

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

Return codes

0

Normal return.

INIT

Edit recovery table was successfully created.

QUERY

Recovery is not pending.

PROCESS

Recovery was completed and the data was saved.

4

Normal return.

INIT

Edit recovery table already exists for current application.

QUERY

Entry found in edit recovery table; recovery is pending.

PROCESS


Recovery was completed, but user did not save data.

20

Severe error; unable to continue.

FTCLOSE—end file tailoring


Command invocation format

➤ ISPEXEC — FTCLOSE — 

Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

➤ CALL — ISPLINK — ('FTCLOSE_ ' — , 

Return codes


0

Normal completion.

- 4** Member already exists in the output library and NOREPL was specified. The original member is unchanged.
- 8** File not open. FTOPEN was not used before FTCLOSE.
- 12** Output file in use. ENQ failed.
- 16** Skeleton library or output file not allocated.
- 20** Severe error.

FTERASE—erase file tailoring output


Command invocation format

►► ISPEXEC — FTERASE — *member-name* —  LIBRARY(*library*)

Call invocation format

►► CALL — ISPEXEC — (*buf-len* , — *buffer*); ►◄

OR


►► CALL — ISPLINK — ('FTERASE_' — , — *member-name* — , —  library —); ►◄

Return codes

- 0** Normal completion.
- 8** File does not exist.
- 12** Output file in use; ENQ failed.
- 16** Alternate output library not allocated.
- 20** Severe error.

FTINCL—include a skeleton

Command invocation format

►► ISPEXEC — FTINCL — *skel-name* —  NOFT EXT

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

OR

**► CALL — ISPLINK — ('FTINCL_...' — , — *skel-name* — , — 'NOFT_...' —
 '_' —) ; ►**

Return codes

0	Normal completion.
8	Skeleton does not exist.
12	Skeleton in use; ENQ failed.
16	Data truncation occurred or skeleton library or output file not allocated.
20	Severe error.

FTOPEN—begin file tailoring

Command invocation format

►► ISPEXEC — FTOPEN —————►
 TEMP

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

OR

```
➤ CALL — ISPLINK — ('FTOPEN_<<' — , — 'TEMP_<<<<<<'); ➤
```

Return codes


- 0** Normal completion.
- 8** File tailoring already in progress.
- 16** Skeleton library or output file not allocated.
- 12** Output file in use; ENQ failed.

20


Severe error.

GENLIST - list a member's generations

Command invocation format



Call invocation format



OR

CALL — ISPEXEC — (buf-len , — buffer);

Return codes

0

One of the following options:

- LIST option - Normal completion. The member generation list is available.
- FREE option - Normal completion. The member generation list is freed successfully.
- SAVE option - Normal completion. The member generation list is successfully written to a data set.

4

Empty member generation list.

8

One of the following options:

- LIST option - End of member generation list.
- FREE option - Member generation list does not exist.
- SAVE option - For a data ID, the **GENLIST** service was started with the SAVE option after the LIST option, but before the FREE option.

10

No data set is associated with the specified data ID. That is, LMINIT was not completed.

12

One of the following options:

- The data set is not open or is not a PDSE v2 configured for member generations.
- A parameter value is invalid.

16


A truncation or conversion error occurred in accessing dialog variables.

20

Severe error; unable to continue.

GETMSG—get a message


Command invocation format



Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄

OR



Return codes

0

Normal completion.

12

The specified message could not be found.

20

Severe error.

GRERROR—graphics error block service

Command invocation format

```
ISPEXEC *This service does not apply to
        command or APL2 procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used
              with this interface*
```

►► CALL — ISPLINK — ('GRERROR_' — , — *error-record-pointer* , —►

 ► — *call-format-descriptor-module-pointer*); ►◄

Return codes

- 0 Normal completion
- 8 ISPF/GDDM interface is not established
- 20 Severe error.

GRINIT—graphics initialization

Command invocation format

```
ISPEXEC *This service does not apply to
        command or APL2 procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used
              with this interface*
```

OR

►► CALL — ISPLINK — ('GRINIT_' — , *application-anchor-block* — , — *panel-name* —); ►◄

└───┬───┘
 ' '

Return codes

- 0 Normal completion.
- 8 The specified panel does not contain a GRAPHIC area.
- 12 The specified panel could not be found.
- 20 Severe error.

GRTERM—graphics termination service

Command invocation format

```
ISPEXEC *This service does not apply to
        command or APL2 procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used
              with this interface*
```

OR

➤ CALL — ISPLINK — ('GRTERM_'); ➤


Return codes

- 0 Normal completion
- 20 Severe error.

LIBDEF—allocate application libraries

Command invocation format

Note: If none of the processing options COND, UNCOND, STACK, or STKADD is specified, the processing option is set using the value in the ISPF configuration table keyword DEFAULT_LIBDEF_PROCESSING_OPTION. If this keyword is not set in the ISPF configuration table, the processing option is set to the default value UNCOND. Always specify a processing option for the LIBDEF service to ensure that changes to the DEFAULT_LIBDEF_PROCESSING_OPTION value in the configuration table do not cause unexpected changes to your dialog processing.



Call invocation format

Note: If none of the processing options COND, UNCOND, STACK, or STKADD is specified, the processing option is set using the value in the ISPF configuration table keyword DEFAULT_LIBDEF_PROCESSING_OPTION. If this keyword is not set in the ISPF configuration table, the processing option is set to the default value UNCOND. Always specify a processing option for the LIBDEF

service to ensure that changes to the DEFAULT_LIBDEF_PROCESSING_OPTION value in the configuration table do not cause unexpected changes to your dialog processing.

►► CALL — ISPEXEC — (*buf-len* , — *buffer*); ►►

OR

►► CALL — ISPLINK — ('LIBDEF_...' — , — *lib-type* — , — '...' —
 'DATASET_'
 'EXCLDATA'
 'LIBRARY_'
 'EXCLLIBR'
 , — '...' — , — '...' —); ►►
 dataset-list
 libname
 'COND_...'
 'UNCOND_...'
 'STACK_...'
 'STKADD_...'

Return codes

- 0** Normal completion.
- 4** When removing the application library: Application library does not exist for this type.
When STKADD is specified: There is no existing stack.
- 8** When COND is used: Application library already exists for this type.
- 12** ISPPROF was specified as the lib-type; invalid lib-type specified with EXCLDATA or EXCLLIBR.
- 16** A libname was not allocated, or the dataset-list contains an invalid MVS dsname.
- 20** Severe error.

LIST—write lines to the list data set

Command invocation format


►► ISPEXEC — LIST — BUFNAME(*dialog-variable-name*) — LINELEN(*line-length*) —
 PAGE
 SINGLE
 DOUBLE
 TRIPLE
 OVERSTRK
 CC ►►

Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►

OR

► CALL — ISPLINK — ('LIST_____', — *dialog-variable-name*, — *line-length* →



Return codes

- 0** Normal completion.
- 8** Maximum line length or data set LRECL exceeded; data has been truncated.
- 12** Specified dialog variable not found.
- 20** Severe error.

LMCLOSE—close a data set

Command invocation format

► ISPEXEC — LMCLOSE — DATAID(*data-id*) ►

Call invocation format

► CALL — ISPLINK — ('LMCLOSE_', *data-id*); ►

OR

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►

Return codes

- 0** Normal completion.
- 8** Data set is not open.
- 10** No ISPF library or data set associated with the given data ID; that is, LMINIT has not been completed.
- 20** Severe error; unable to continue.

LMCOMP—compresses a partitioned data set

Command invocation format

► ISPEXEC — LMCOMP — DATAID(*data-id*) ►

Call invocation format

► CALL — ISPLINK — ('LMCOMP_', *data-id*); ►

OR


► CALL — ISPEXEC — (*buf-len*, *buffer*); ►

Return codes


- 0** Successful completion.
- 8** Library type is a PDSE and cannot be compressed
- 10** No data set associated with the given data ID.
- 12** One of these:
- Data set not partitioned
 - Data set specified not allocated
 - Data set is open
 - Data set is not movable
 - Data set must be allocated exclusively. Use ENQ(EXCLU) in LMINIT service.
 - Concatenated libraries are not allowed for LMCOMP.
- 20** Severe error; unable to continue.

LMCOPY—copy members of a data set

Command invocation format



Call invocation format



OR

CALL — ISPEXEC — (*buf-len*,*buffer*);

Return codes

0

Normal completion.

4

Member not available, which indicates one of these situations:

- The "from" data set is empty.
- No members matched the specified pattern in the "from" data set.

8

- The *from-member-name* was not found.
- The same name was specified for *to-member-name* and *from-member-name*.

10

No data set is associated with the given data ID.

12

One of these:

- A like-named member already exists in the "to" data set and the Replace option was not specified
- One or more members of the "to" data set are "in use", either by you or by another user, and could not be copied
- Invalid data set organization
- Data set attribute invalid for copying or copying packed data
- Open error
- LOCK parameter is specified

16


Truncation error.

20

Severe error; unable to continue.

LMDDISP—data set display service


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*,*buffer*); ►►

OR



Return codes

- 0** Normal completion.
- 8** Error building data set list. The error condition is described in the ISPF system dialog variables.
- 10** A data set list does not exist for the list-id specified via keyword LISTID.
- 12** A keyword value is incorrect.
- 20** A severe error occurred while processing the data set list.

LMDFREE—free a data set list

Command invocation format

ISPEXEC LMDFREE LISTID(*list-id*)

Call invocation format

CALL ISPLINK('LMDFREE_', *list-id*)

OR

CALL ISPEXEC(*buf-len*, *buffer*)

Return codes

- 0**
Normal completion.
- 8**
Free dslist ID failed. For more information about the error condition, see *System variables used to format error messages* in *ISPF Services Guide*.
- 10**
No data set level or volume is associated with given dslist ID. LMDINIT has not been completed.
- 20**
Severe error; unable to continue.

LMDINIT—initialize a data set list

Command invocation format

```
➤ ISPEXEC — LMDINIT — LISTID( dslist-id-var ) —————➤
                                     |
                                     | LEVEL( dsname-level )
                                     |
➤ —————➤
   |
   | VOLUME( volume-serial )
   |
➤ —————➤
```

Call invocation format

```
➤ CALL — ISPLINK — ('LMDINIT_' — , dslist-id-var — , —————➤
                                     |
                                     | dsname-level
                                     |
                                     | ' '
                                     |
➤ —————➤
   |
   | , ————— volume-serial ————— ) ; ➤
   |
   | ' '
   |
➤ —————➤
```

OR


```
➤ CALL — ISPEXEC — ( buf-len , — buffer ) ; ➤
```

Return codes


- 0**
Normal completion. LMDINIT returns a unique dslist ID in the variable specified in keyword LISTID.
- 8**
The dslist ID was not created; for more information about the error condition, see *System variables used to format error messages* in *ISPF Services Guide*.
- 12**
A keyword value is incorrect.
- 16**
A truncation or translation error occurred in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMDLIST—list a data set

Command invocation format



Call invocation format



OR

```
CALL — ISPEXEC — (buf-len , — buffer);
```

Return codes

0

One of these:

- LIST option - Normal completion. The name of next data set in the list is returned in the variable specified in keyword DATASET. Data set statistics are returned, if requested.

Call invocation format

```

➤ CALL — ISPLINK('LMERASE_', — , — project — , — group — , — type —
                                     ' ' ' ' ' '
                                     , — dataset — , — volume —
                                     ' ' ' '
                                     , — password — ); ➤
                                     ' '

```

OR

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

Return codes**0**

Normal completion.

8

One of these:

- Data set is not cataloged or other allocation failure.
- Data set delete failed.
- Data set name is an alias.
- Expiration date not expired and PURGE parameter omitted
- No data set specified as input
- PROJECT specified, but GROUP or TYPE not specified.

12

Expiration date not expired and PURGE(NO) specified.

20

Severe error; unable to continue.

LMFREE—free data set from its association with data ID

Command invocation format

```

➤ ISPEXEC — LMFREE — DATAID( data-id ) ➤

```

Call invocation format

```

➤ CALL — ISPLINK('LMFREE_', data-id); ➤

```

OR

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

Return codes

These return codes are possible:

- 0**
Normal completion.
- 8**
Free data ID failed; for more information about the error condition, see *System variables used to format error messages* in *ISPF Services Guide*.
- 10**
No ISPF library or data set is associated with the given data ID; that is, LMINIT has not been completed.
- 20**
Severe error; unable to continue.

LMGET—read a logical record from a data set

Command invocation format

```

➤ ISPEXEC — LMGET — DATAID( data-id ) — MODE(
    MOVE
    LOCATE
    INVAR
    MULTX
) →

➤ DATALOC( dataloc-var ) — DATALEN( datalen-var ) — MAXLEN( max-length ) →

```

Call invocation format

```

➤ CALL — ISPLINK — ('LMGET_...', data-id — , —
    'MOVE_...'
    'LOCATE_...'
    'INVAR_...'
    'MULTX_...'
) — ,dataloc-var →

➤ ,datalen-var — ,max-length — );

```

OR

```

➤ CALL — ISPEXEC — ( buf-len , — buffer );

```

Return codes

- 0**
Normal completion.
- 8**
End-of-data set condition; no message formatted.
- 10**
No ISPF library or data set associated with the given data ID; that is, LMINIT has not been completed.
- 12**
One of these:
- The data set is not open or is not open for input.
 - An LMMFIND was not done for a partitioned data set.
 - The parameter value is invalid.

16


A truncation or translation error occurred in accessing dialog variables.

20


Severe error; unable to continue.

LMINIT—generate a data ID for a data set


Command invocation format



PROJECT options



Call invocation format



OR

CALL — ISPEXEC — (buf-len,buffer); →

Return codes

These return codes are possible:

0

Normal completion.

8

Data ID not created; for more information about the error condition, see *System variables used to format error messages* in *ISPF Services Guide*.

12

The parameter value is invalid.

16

Truncation or translation error in accessing dialog variables.

20

Severe error; unable to continue.

For more information about dialog variables, see *System variables used to format error messages* in *ISPF Services Guide*.


Note: Data sets allocated with an XTIOIOT will return a "DDNAME Not Found" message and set RC=8 if XTIOIOT support is not fully enabled.

Note: Data sets allocated with an XTIOIOT will return a "DDNAME Not Found" message and set RC=8 if XTIOIOT support is not fully enabled.

LMMADD—add a member to a data set


Command invocation format

► ISPEXEC — LMMADD — DATAID(*data-id*) — MEMBER(*member-name*) —►



Call invocation format

► CALL — ISPLINK — ('LMMADD_<_>' — ,*data-id* — ,*member-name* — , { 'NO_<_>' 'YES_<_>' }) —►



OR

► CALL — ISPEXEC — (*buf-len* , — *buffer*); ◄

Return codes

0

Normal completion.

4

The directory already contains the specified name.

10

No ISPF library or MVS data set is associated with the given data ID; that is, LMINIT has not been completed.

12

One of these:

- The data set is not open or is not open for output.
- The parameter value is invalid.
- The data set organization is invalid.
- The values for some member statistics are invalid.

14

No record has been written for the member to be added.

16

A truncation or translation error occurred in accessing dialog variables.

20

Severe error; unable to continue.

LMMDEL—delete members from a data set

Command invocation format

```
➤ ISPEXEC — LMMDEL — DATAID( data-id ) — MEMBER( member-name ) — NOENQ ➤
```

Call invocation format

```
➤ CALL — ISPLINK('LMMDEL_...' — ,data-id — ,member-name — , 'NOENQ_...' ); ➤
```

OR

```
➤ CALL — ISPEXEC — ( buf-len , — buffer ); ➤
```

Return codes

0

Normal completion.

8

The member was not found.

10

No data set is associated with the given data ID; that is, LMINIT has not been completed.

12

One of these:


- The data set is not open or is not open for output.
- The parameter value is invalid.
- The data set organization is invalid.

20


Severe error; unable to continue.

LMMDISP—member list service: Display option


Command invocation format



Call invocation format



OR




Return codes


- 0**
One or more members were selected and/or a primary command not recognized by LMMDISP was entered.
- 4**
The requested data sets were empty, or no members matched the specified pattern.
- 8**
END or RETURN was entered.
- 10**
No data set is associated with the given data ID; LMINIT has not been completed.
- 12**
Indicates one of these conditions:
- Data set not open.
 - Data set not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
- 16**
A truncation or translation error occurred in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMMDISP—member list service: GET option

Command invocation format



Call invocation format

►► CALL — ISPLINK('LMMDISP_' — , — *data-id* — 'GET_————' — ',' — , —  — , —) ; ►►

OR

►► CALL — ISPEXEC — (*buf-len* , — *buffer*) ; ►►

Return codes

- 0**
Successful completion.
- 8**
No more selected members.
- 10**
No data set is associated with the given data ID; LMINIT has not been completed.
- 12**
Indicates one of these conditions:
- Data set not open.
 - Data set not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16**
A truncation or translation error occurred in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMMDISP—member list service: PUT option


Command invocation format

►► ISPEXEC — LMMDISP — DATAID(*data-id*) — OPTION(PUT) — MEMBER(*member-name*) — ►►



Call invocation format

►► CALL — ISPLINK('LMMDISP_' — , — *data-id* — 'PUT_————' — , *member-name* — ',' — ',' — ►►



OR

►► CALL — ISPEXEC — (*buf-len*,*buffer*); ►◄


Return codes

- 0**
Successful completion.
- 8**
A specified member does not exist in the member list.
- 10**
No data set is associated with the given data ID; LMINIT has not been completed.
- 12**
Indicates one of these conditions:
- Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16**
A truncation or translation error occurred in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMMDISP—member list service: ADD option


Command invocation format

►► ISPEXEC — LMMDISP — DATAID(*data-id*) — OPTION(ADD) — MEMBER(*member-name*) ►►



Call invocation format

►► CALL — ISPLINK('LMMDISP_' — , — *data-id* — , 'ADD_XXXX' — , *member-name* — , '_' — , '_' — ►►



OR

►► CALL — ISPEXEC — (*buf-len*,*buffer*); ►◄

Return codes

- 0**
Successful completion.
- 8**
The member already exists in the member list.

- 10**
No data set is associated with the given data ID; LMINIT has not been completed.
- 12**
Indicates one of these conditions:
- Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16**
A truncation or translation error occurred in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMMDISP—member list service: DELETE option

Command invocation format

►► ISPEXEC — LMMDISP — DATAID(*data-id*) — OPTION(DELETE) — MEMBER(*member-name*) ►◄

Call invocation format

►► CALL — ISPLINK('LMMDISP_' — , — *data-id* — , 'DELETE_' — , *member-name*); ►◄

OR

►► CALL — ISPEXEC — (*buf-len* , *buffer*); ►◄

Return codes

- 0**
Successful completion.
- 8**
A specified member does not exist in the member list.
- 10**
No data set is associated with the given data ID; LMINIT has not been completed.
- 12**
Indicates one of these conditions:
- Data sets not open.
 - Data sets not partitioned.
 - Invalid parameter value.
 - Invalid data set organization.
 - Invalid invocation syntax.
 - Member list has not been created.
- 16**
A truncation or translation error occurred in accessing dialog variables.

20

Severe error; unable to continue.

LMMDISP—member list service: FREE option

Command invocation format

➤ ISPEXEC — LMMDISP — DATAID(*data-id*) — OPTION(FREE) ➤

Call invocation format

➤ CALL — ISPLINK('LMMDISP_' — , — *data-id* — , 'FREE_____'); ➤

OR

➤ CALL — ISPEXEC — (*buf-len* , *buffer*); ➤

Return codes

0

Successful completion.

8

No member list is associated with the given data ID.

10

No data set is associated with the given data ID; LMINIT has not been completed.

12

Indicates one of these conditions:

- Data sets not open.
- Data sets not partitioned.
- Invalid parameter value.
- Invalid data set organization.
- Invalid invocation syntax.

16

A truncation or translation error occurred in accessing dialog variables.

20

Severe error; unable to continue.

LMMFIND—find a library member

Command invocation format

➤ ISPEXEC — LMMFIND — DATAID(*data-id*) — MEMBER(*member-name*) — LOCK ➤

➤ LRECL(*recl-var*) RECFM(*recfm-var*) GROUP(*group-var*) ➤

➤ STATS(NO) STATS(YES) NOLLA ➤

Call invocation format

```

▶ CALL — ISPLINK — ('LMMFIND_' — ,data-id — ,member-name — ,
└──────────────────┘ └──────────┘
'LOCK_...'
└───┘

, └─── lrecl-var ───┘ , └─── recfm-var ───┘ , └─── group-var ───┘
└───┘ └───┘ └───┘

, { 'NO_...'
└───┘
'YES_...' } , └─── 'NOLLA_...' ───┘ ); ▶
└───┘

```

OR


►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

Return codes


0	Normal completion.
8	Member not found.
10	No data set is associated with the given data ID; that is, LMINIT has not been completed.
12	One of these: <ul style="list-style-type: none">• Data set is not open or is not open for input.• A parameter value is invalid.• Data set is not partitioned.• LOCK parameter was specified.
16	A truncation or translation error occurred in accessing dialog variables.
20	Severe error; unable to continue.

LMMLIST—list a library's members

Command invocation format



Call invocation format



OR

```
➔ CALL — ISPEXEC — ( buf-len , — buffer ); ➔
```

Return codes

0

One of these:

- LIST option - Normal completion. The member list is available and the next member in the list is returned in the member-var parameter.
- FREE option - Normal completion. The member list is freed successfully.
- SAVE option - Normal completion. The member list is successfully written to a data set.

4

Empty member list.

8

One of these:

- LIST option - End of member list.
- FREE option - Member list does not exist.

- SAVE option - For a data ID, the LMMLIST service has been invoked with the SAVE option after being invoked with LIST option, but before being invoked with the FREE option.

10

No data set is associated with the given data ID; that is, LMINIT has not been completed.

12

One of these:

- The data set is not open or is not partitioned.
- A parameter value is invalid.
- Member list was created using LMMDISP.

16


A truncation or translation error occurred in accessing dialog variables.

20


Severe error; unable to continue.

LMMOVE—move members of a data set

Command invocation format



Call invocation format



OR

►► CALL — ISPEXEC — (*buf-len*,*buffer*); ►◄

Return codes

0

Successful completion.

4

Either:

- "From" data set is empty.
- No member matched the pattern in the "from" data set.

8

"From" member not found.

10

No data set is associated with given data ID.

12

One of these:

- A like-named member already exists in the "to" data set and the Replace option was not specified.
- One or more members of the 'TO' or 'FROM' data sets are "in use" by you or another user and could not be moved.
- Invalid data set organization.
- Data set attribute invalid for packed data.
- Open error.

16

A truncation error occurred.

20

Severe error; unable to continue.

LMMREN—rename a data set member

Command invocation format

►► ISPEXEC — LMMREN — DATAID(*data-id*) — MEMBER(*old-member-name*) —►

► NEWNAME(*new-member-name*) — NOENQ —►

Call invocation format

►► CALL — ISPLINK('LMMREN_...' — ,*data-id* — ,*old-member-name* — ,*new-member-name* —►

► , 'NOENQ_...'); ►◄

OR

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

Return codes

O

Normal completion.

4

Directory already contains the specified new name.

8

Member not found.

10

No data set is associated with the given data ID; that is, LMINIT has not been completed.

12

One of these:


- The data set is not open or is not open for output.
- The parameter value is invalid.
- The data set organization is invalid.

20

Severe error; unable to continue.

LMMREP—replace a member of a data set


Command invocation format



Call invocation format



OR



Return codes

0


Normal completion.

- 8** Member is added; it did not previously exist.
- 10** No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12** One of these:
- The data set is not open or is not open for output.
 - The parameter value is invalid.
 - The data set organization is invalid.
 - Some member statistics have invalid values.
- 14** No record has been written for the member to be replaced.
- 16** Truncation or translation error in accessing dialog variables.
- 20** Severe error; unable to continue.


LMMSTATS—set and store ISPF statistics

Command invocation format

►► ISPEXEC — LMMSTATS — DATAID(*data-id*) — MEMBER(*member-name*) —►



Call invocation format



OR

➤ CALL — ISPEXEC — (buf-len ,buffer); ➤

Return codes

- 0** Normal completion.
- 4** Either:
- Data set is empty.
 - No members matched the pattern.
- 8** Member not found.
- 10** No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12** One of these:
- Invalid parameter value.
 - Data set is not partitioned.
 - Data ID represents a concatenation of data sets.
 - Data set is opened for output.


- Data set name is an alias. And the NOALIAS parameter was specified.

20


Severe error; unable to continue.

LMOPEN—open a data set

Command invocation format



Call invocation format



OR

CALL **—** **ISPEXEC** **—** (*buf-len* , **—** *buffer*);

Return codes

0

Normal completion.

8

Data set could not be opened.

10

No data set is associated with the given data ID; that is, LMINIT has not been completed.

12

One of these:

- The parameter value is invalid.
- Data set is already open.
- Cannot open concatenated data sets for output.
- Cannot open a data set allocated SHR for output.

16


Truncation or translation error in accessing dialog variables.

20


Severe error; unable to continue.

LMPRINT—print a partitioned or sequential data set

Command invocation format



Call invocation format



OR

CALL — ISPEXEC — (buf-len ,buffer);

Return codes

- 0**
Normal completion.
- 4**
Either:
- Data set is empty or contains an empty member.
 - No members matched the pattern.
- 8**
Member not found.
- 10**
No data set associated with given data ID.
- 12**
Either:
- Invalid data set organization; must be partitioned or sequential.
 - Invalid parameter.
- 20**
Severe error; unable to continue.

LMPUT—write a logical record to a data set

Command invocation format

```

▶▶ ISPEXEC — LMPUT — DATAID( data-id ) — MODE(
    ┌ INVAR ────┐
    │ MOVE      │
    └ MULTX      ┘
) →

    ── DATALOC( dataloc-var ) — DATALEN( data-length ) —
    └───────────────────┐
    NOBSCAN              ┘
  
```

Call invocation format

```

▶▶ CALL — ISPLINK — ('LMPUT_...', data-id — ,
    ┌ 'INVAR_...' ────┐
    │ 'MOVE_...'      │
    └ 'MULTX_...'      ┘
, dataloc-var →

    ── , data-length — ';' — ,
    ┌ 'NOBSCAN' ────┐
    │                │
    └                ┘
); ▶▶

▶▶ CALL — ISPEXEC — ( buf-len , — buffer ); ▶▶
  
```


OR

Return codes


- 0**
Normal completion.
- 10**
No data set is associated with the given data ID; that is, LMINIT has not been completed.
- 12**
Either:
- The data set is not open or is not open for output.
 - The parameter value is invalid.
- 16**
Truncation or translation error in accessing dialog variables.
- 20**
Severe error; unable to continue.

LMQUERY—give a dialog information about a data set

Command invocation format



Call invocation format



OR

```
CALL — ISPEXEC — ( buf-len , — buffer );
```

Return codes

0

Normal completion.

4

No applicable information available for a specified keyword; blanks are returned.

10

No data set is associated with the given data ID; that is, LMINIT has not been completed.

16

Truncation or translation error in accessing dialog variables.


20

Severe error; unable to continue.

LMRENAME—rename an ISPF library


Command invocation format

► ISPEXEC — LMRENAME — PROJECT(*project*) — GROUP(*group*) — TYPE(*type*) —►



Call invocation format

```
➤ CALL — ISPLINK('LMRENAME' — ,project — ,group — ,type — , new-project — )
```



➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

Return codes

0

Normal completion.

4

New name already exists.

8

One of these:

- Specified data set does not exist.
- Rename or catalog failed.
- Data set name is an alias.

12

The parameter value is invalid.

20

Severe error; unable to continue.

LOG—write a message to the log data set

Command invocation format

►► ISPEXEC — LOG — MSG(*message-id*) ►◄

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

OR

►► CALL — ISPLINK — ('LOG_####', — *message-id*); ►◄

Return codes

0

Normal completion.

12

The message-id contains invalid syntax or was not found.

20

Severe error.

MEMLIST—member list dialog

Command invocation format

►► ISPEXEC — MEMLIST — DATAID(*data-id*) — MEMBER(*pattern*) — { CONFIRM(YES) / CONFIRM(NO) } —


— { FIELD(9) / FIELD(1) } — { DEFAULT(S) / DEFAULT(*action*) } ►◄

PANEL(*panel-name*)

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

OR




Return codes

- 0** Normal completion.
- 8** The requested data set was empty or no members matched the specified pattern.
- 10** No data set is associated with the given data ID. LMINIT has not been completed.
- 12** Indicates one of these:
- Data set not partitioned.
 - Parameter value not valid.
 - Invocation syntax not valid.
- 16** A truncation or translation error occurred in accessing dialog variables.
- 20** Severe error.

PQUERY—obtain panel information

Command invocation format



Call invocation format

CALL ISPEXEC (buf-len, buffer);

OR


```

➤➤ CALL — ISPLINK — ('PQUERY_...' — , — panel-name , — area-name →
      , — area-type-name — , — area-width-name →
      , — area-depth-name — , — row-number-name →
      , — column-number-name — ); ➤➤

```

Return codes

- 0** Normal completion
- 8** The panel does not contain the specified area.
- 12** The specified panel cannot be found.
- 16** Not all are values returned because insufficient space was provided.
- 20** Severe error.

QBASELIB—query base library information

Command invocation format

```

➤➤ ISPEXEC — QBASELIB — dd-name — ID(id-var) ➤➤

```

Call invocation format

```

➤➤ CALL — ISPEXEC — (buf-len , — buffer); ➤➤

```

OR

```

➤➤ CALL — ISPLINK — ('QBASELIB' — , dd-name , — id-var — ); ➤➤

```

Return codes


- 0** A DDNAME for the specified ddname exists and the requested information has been successfully returned.
- 4** The specified dd-name is not defined.
- 16** A dialog variable translation or truncation error has occurred.

20

A severe error has occurred.

QLIBDEF—query LIBDEF definition information



Command invocation format

➤ ISPEXEC — QLIBDEF — *lib-type* — 

Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

➤ CALL — ISPLINK — ('QLIBDEF_' — ,*lib-type*, , ); ➤

Return codes

0

A LIBDEF definition for the specified lib-type exists and the requested information, if any, has been successfully returned.

4

The specified lib-type does not have an active LIBDEF definition.

12

An invalid lib-type value of ISPPROF has been specified.

16

A dialog variable translation or truncation error has occurred.

20

A severe error has occurred.

QTABOPEN—query open ISPF tables

Command invocation format

➤ ISPEXEC — QTABOPEN — LIST(*list-var*) ➤

Call invocation format

➤ CALL — ISPLINK — ('QTABOPEN' — ,*list-var*); ➤

Return codes

These return codes are possible:

0

Normal completion.

4

List incomplete. There was insufficient space to construct a valid variable name.

Command invocation format

Call invocation format

OR

Variables returned in each row of the table

Name	Size	Description
ZENJOB	8	Job or address space name holding or requesting the ENQ
ZENQNAME	8	Qname portion of the ENQ
ZENRNAME	255	Rname portion of the ENQ
ZENDISP	5	SHARE or EXCLU
ZENHOLD	4	OWN or WAIT
ZENSCOPE	7	SYSTEM or SYSTEMS
ZENSTEP	7	STEP or blank
ZENGLOBL	6	GLOBAL or blank
ZENSYST	8	System name
ZENRESV	7	RESERVE or blank

Return codes

Chapter 3. ISPF service syntax with return codes **105**

- 4**
Table returned but truncated due to limit.
- 8**
No ENQs satisfy the request.
- 10**
No ENQs satisfy the request, but XSYS parameter was not specified and the system is running in STAR mode. The data returned may not reflect all ENQs on all systems.
- 12**
Table creation error, parameter or other termination error. See messages for more detail. This includes services not available due to configuration table restrictions.
- 14**
The SAVE data set is in use by another user.
- 20**
Severe error, including TBADD error or data set creation errors.

REMPPOP—remove a pop-up window


Command invocation format

►► ISPEXEC — REMPOP —  ALL ◀◀

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◀◀

OR

►► CALL — ISPLINK — ('REMPPOP_<<>' — , —  'ALL_<<>>' —); ◀◀


Return codes

- 0**
Normal completion.
- 16**
A pop-up window does not exist at this select level.
- 20**
Severe error.

SELECT—select a panel or function

Command invocation format

►► ISPEXEC — SELECT —►




Call invocation format

►► CALL — ISPEXEC — (buf-len, — buffer); ►◄

OR

►► CALL — ISPLINK — ('SELECT_...' — , — length, —►



Return codes

These return codes are possible if a panel is specified:

0

Normal completion. The END command was entered from the selected menu.

4

Normal completion. The RETURN command was entered or the EXIT option was specified from the selected menu or from some lower-level menu.

12

The specified panel could not be found.

16

Truncation error in storing the ZCMD or ZSEL variable.

20


Severe error.

Note:

1. A return code of 0 is returned when the SELECT service has been coded with no other parameters.
2. If a command or program is invoked by using SELECT, the return code from the command or program is passed to the function that invoked SELECT.

SETMSG—set next message


Command invocation format



Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄

OR



Return codes

0

Normal completion.

4

SETMSG with COND parameter issued and a SETMSG request was pending.

12

The specified message field name or message not be found.

20

Severe error.

TBADD—add a row to a table

Command invocation format

➡ ISPEXEC — TBADD — *table-name* —————
 └────────── SAVE(*name-list*) ─────────┘ └── ORDER ───┘
 ───────────┘
 └────────── MULT(*number-of-rows*) ─────────┘

Call invocation format

➡ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➡

OR

```

▶ CALL — ISPLINK — ('TBADD_<table-name>' — , — table-name — , — name-list —
                                ' , ' —
                                'ORDER_<table-name>' — , — number-of-rows —
                                ' , ' —
                                ); ▶

```

Return codes

0	Normal completion.
4	The number-of-rows parameter was specified but storage was obtained for only a single row.
8	A row with the same key already exists; CRP set to TOP (zero). Returned only for tables with keys.
12	Table is not open.
16	Numeric convert error; see numeric restrictions for TBSORT. Returned only for sorted tables.
20	Severe error.

TBBOTTOM—set the row pointer to bottom

Command invocation format

```

graph LR
    ISPEXEC --> TBBOTTOM
    TBBOTTOM --> table_name[table-name]
    table_name --> SAVENAME[SAVENAME(var-name)]
    SAVENAME --> ROWID[ROWID(rowid-name)]
    ROWID --> NOREAD[NOREAD]
    NOREAD --> POSITION[POSITION(crp-name)]
    POSITION --> End[ ]
  
```

ISPEXEC — TBBOTTOM — *table-name* — SAVENAME(*var-name*) — ROWID(*rowid-name*) — NOREAD — POSITION(*crp-name*)

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

OR

```

➤ CALL — ISPLINK — ('TBBOTTOM' — , — table-name — , — var-name — )
                                     └───┬───┘
                                     ' '
➤ , — rowid-name — , — 'NOREAD_ ' — , — crp-name — ); ➤
      └───┬───┘      └───┬───┘      └───┬───┘
      ' '              ' '              ' '

```

Return codes

0

Normal completion.

8

Table is empty; CRP set to TOP (zero).

12

Table is not open.

16

Variable value has been truncated or insufficient space provided to return all extension variable names.

20

Severe error.

TBCLOSE—close and save a table

Command invocation format

```

➤ ISPEXEC — TBCLOSE — table-name — { REPLCOPY
                                     { NEWCOPY
                                     NAME(alt-name)
➤ └───┬───┘
      PAD(percentage) └───┬───┘
                        LIBRARY(library)

```

Call invocation format

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

OR

```

➤ CALL — ISPLINK — ('TBCLOSE_ ' — , — table-name — , — { 'REPLCOPY'
                                                         { ' '
                                                         'NEWCOPY_ '
➤ , — alt-name — , — percentage — , — library — ); ➤
      └───┬───┘      └───┬───┘      └───┬───┘
      ' '              ' '              ' '

```

Return codes


0

Normal completion.

- 12** Table is not open.
- 16** Alternate table output library was not allocated.
- 20** Severe error.

TBCREATE—create a new table


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (buf-len, — buffer); ►◄

OR



Return codes

- 0** Normal completion.
- 4** Normal completion—a duplicate table exists but REPLACE was specified.
- 8** Either the table already exists and REPLACE was not specified, or REPLACE was specified and the table is in SHARE mode.
- 12** Table in use; ENQ failed.
- 16** WRITE mode specified and alternate table input library not allocated. TBCREATE checks the input library to determine if a duplicate table exists. See return code 8.

20

Severe error.

TBDELETE—delete a row from a table

Command invocation format

► ISPEXEC — TBDELETE — *table-name* ►

Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►

OR

► CALL — ISPLINK — ('TBDELETE' — , — *table-name*); ►

Return codes

0

Normal completion.

8

Keyed tables: The row specified by the value in key variables does not exist; CRP set to TOP (zero).
Non-keyed tables: CRP was at TOP (zero) and remains at TOP.

12

Table is not open.

20

Severe error.

TBDISPL—display table information

Command invocation format

► ISPEXEC — TBDISPL — *table-name* — *PANEL(panel-name)* — *MSG(message-id)* —

— *CURSOR(field-name)* — *CSRROW(table-row-number)* —

— *CSRPOS(cursor-position)* — *AUTOSEL(YES)* — *AUTOSEL(NO)* — *POSITION(crp-name)* —

— *ROWID(rowid-name)* — *MSGLOC(message-field-name)* ►

Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►

OR

```

➔ CALL — ISPLINK — ('TBDISPL_' — , — table-name — , — panel-name — ➔
                                     ' ' —
➔ , — message-id — , — field-name — , — table-row-number — ➔
      ' ' —           ' ' —           ' ' —
➔ , — cursor-position — , — 'YES' — , — crp-name — ➔
      ' ' —           ' ' — 'NO' —
                                     ' ' —
➔ , — rowid-name — , — message-field-name — ); ➔
      ' ' —           ' ' —

```

Return codes

0

If the panel definition contains neither a)REINIT nor a)PROC section, the Enter key was pressed, or a scroll command was entered. Any of these occurred:

- One row was selected in the scrollable part of the display. The CRP is set to point to that table row and the row is retrieved. The input fields from the selected model set on the display are then stored in the function pool.
- The user entered information into the fixed portion of the display.
- All of these:
 - A scroll return to function has been specified (ZTDRET defined to UP, DOWN, or VERTICAL).
 - More rows are needed to fill a scroll request.
 - No selected rows remain to be processed.

If the panel definition contains a)REINIT or)PROC section, there is the additional possibility that the user entered no information and just pressed the Enter key.

4

The Enter key was pressed or a scroll command was entered. The first or both of these occurred:

- Two or more rows in the scrollable part of the display were selected. The CRP is set to the first selected row and the row is retrieved. The input fields from the selected model set on the display are then stored in the function pool.
- The user entered information into the fixed portion of the display.
- If scroll return to function has been specified, and two or more rows are selected for processing, TBDISPL returns a return code 4 until all selected rows are processed. You process the request for more rows to be added to the table only after all selected rows have been processed; that is, only when ZTDSELS has a value of 0.

For subsequent TBDISPL requests with no panel name and no message-id, return code 4 is issued for each request until one selected row remains to be accessed. For this last row, a return code of zero is issued by TBDISPL, still specified with no panel name and no message-id. The variable ZTDSELS will have a value of one.

8

The END or RETURN command was entered. For panels created by the conversion utility, CANCEL and EXIT commands also give return code 8. If CANCEL and EXIT is requested from a panel displayed using TBDISPL service calls and the panel was defined with Dialog Tag Language (DTL), the dialog manager returns the command in ZVERB and sets a return code of 8 from the display screen. The CRP

is set to the first of any selected rows in the scrollable part of the display. The input fields from the selected model set on the display are then stored in the function pool.

If no rows were selected, the CRP is at the top (zero).

To process all selected rows when END or RETURN was entered, continue to issue TBDISPL requests with no panel name or message-id specified until ZTDSELS is one.

If you enter the END command on a table display panel, a subsequent redisplay will result in a return code of 8.

The user might have entered information into the fixed portion of the display.

12

The specified panel, message, cursor field, or message location field could not be found.

16

Truncation or translation error in storing defined variables.

20

Severe error.

TBEND—close a table without saving

Command invocation format

►► ISPEXEC — TBEND — *table-name* ►◄

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

OR

►► CALL — ISPLINK — ('TBEND_...' — , — *table-name*); ►◄

Return codes

0

Normal completion.

12


Table is not open.

20

Severe error.

TBERASE—erase a table

Command invocation format

►► ISPEXEC — TBERASE — *table-name* —  ►◄

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►◄

OR

```

➤ CALL — ISPLINK — ('TBERASE_' — , — table-name — , — library — ); ➤

```

Return codes

- 0**
Normal completion.
- 8**
Table does not exist in the output library.
- 12**
Table in use; ENQ failed.
- 16**
Table output library not allocated.
- 20**
Severe error.

TBEXIST—determine whether a row exists in a table

Command invocation format

```

➤ ISPEXEC — TBEXIST — table-name ➤

```

Call invocation format

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

OR

```

➤ CALL — ISPLINK — ('TBEXIST_' — , — table-name); ➤


```

Return codes

- 0**
Normal completion; the CRP is positioned to the specified row.
- 8**
Keyed tables: the specified row does not exist; the CRP is set to TOP (zero).
Non-keyed tables: service not possible; the CRP is set to TOP.
- 12**
Table is not open.
- 20**
Severe error.

TBGET—retrieve a row from a table

Command invocation format



Call invocation format

➤➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤➤

OR

► CALL — ISPLINK — ('TBGET_...' — , — *table-name* — , — *var-name* — ►
 , — *rowid-name* — , — 'NOREAD_...' — , — *crp-name* —); ►

Return codes

0

Normal completion.

8

Keyed tables: The row specified by the value in the key variables does not exist in any row after the current row pointer, the CRP is set to TOP (ZERO).

Non-keyed tables: the CRP was at TOP and remains at TOP.

12

Table is not open.

16


Variable value has been truncated, or insufficient space was provided to return all extension variable names.

20

Severe error.

TBMOD—modify a row in a table

Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

OR

0	Normal completion. Keyed tables: Existing row updated. Non-keyed tables: New row added to table.
8	Keys did not match; new row added to the table. Returned only for tables with keys.
12	Table is not open.
16	Numeric conversion error; see numeric restrictions for TBSORT. Returned only for sorted tables.
20	Severe error.

```

graph LR
    ISPEXEC --> TBOPEN
    TBOPEN --> table_name[table-name]
    table_name --> options_group
    subgraph options_group [ ]
        WRITE
        NOWRITE
    end
    options_group --> library_option[LIBRARY(library)]
    library_option --> end_arrow[ ]
    style end_arrow fill:none,stroke:none
  
```

ISPEXEC TBOPEN *table-name* [WRITE | NOWRITE] [LIBRARY(*library*)]

SHARE

```

▶ CALL ISPLINK ('TBOPEN_' , table-name , { 'WRITE_...'
                                             ' '
                                             'NOWRITE_' }
, library , 'SHARE_...' ); ▶

```

Chapter 3. ISPF service syntax with return codes **117**

12

ENQ failed; table was in use by another user or the current user.

16


Table input library was not allocated.

20

Severe error.

TBPUT—update a row in a table


Command invocation format


►► ISPEXEC — TBPUT — *table-name* —  ►►

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►►

OR

►► CALL — ISPLINK — ('TBPUT_...' — , — *table-name* — , — *name-list* —  ►►

►► , — 'ORDER_...' —); ►► 

Return codes

0

Normal completion.

8

Keyed tables: The key does not match that of the current row; CRP set to TOP (zero).

Non-keyed tables: CRP was at TOP and remains at TOP.

12

Table is not open.

16


For sorted tables: numeric conversion error; see numeric restrictions for TBSORT.

20

Severe error.

TBQUERY—obtain table information


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►

OR




Return codes

- 0** Normal completion.
- 12** Table is not open.
- 16** Not all keys or names were returned because insufficient space was provided.
- 20** Severe error.

TBSARG—define a search argument


Command invocation format



Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR



Return codes

0

Normal completion.

8

All column variables are null, and the name-list parameter was not specified; no argument is established.

12


Table is not open.

20

Severe error.

TBSAVE—save a table

Command invocation format



Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

```

➤ CALL — ISPLINK — ('TBSAVE_<u><u>' — , — table-name — , — { 'REPLCOPY'
                                                                ' '
                                                                'NEWCOPY_<u><u>' }
➤ , — { alt-name
        ' '
      } , — { percentage
              ' '
            } , — { library
                    ' '
                  } ); ➤

```

Return codes

- 0**
Normal completion.
- 12**
Table is not open.
- 16**
Alternate table output library was not allocated.
- 20**
Severe error.

TBSCAN—search a table

Command invocation format

```

➤ ISPEXEC — TBSCAN — table-name — { ARGLIST( name-list ) }
➤ { SAVENAME( var-name ) } { ROWID( rowid-name ) } { NEXT
                                                                ' '
                                                                PREVIOUS }
➤ { NOREAD } { POSITION( crp-name ) } { CONDLIST( condition-value-list ) } ➤

```

Call invocation format

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

OR

```

➤ CALL — ISPLINK — ('TBSCAN_<u><u>' — , — table-name — , — { name-list
                                                                ' '
                                                                }
➤ , — { var-name
        ' '
      } , — { rowid-name
              ' '
            } , — { 'NEXT_<u><u>'
                    ' '
                    'PREVIOUS'
                  }
➤ , — { 'NOREAD_<u><u>'
        ' '
      } , — { crp-name
              ' '
            } , — { condition-value-list
                    ' '
                  } ); ➤


```

Return codes

- 0**
Normal completion.
- 8**
Row does not exist, no match was found; CRP is set to TOP (zero). The rowid remains unchanged.
- 12**
Table is not open.
- 16**
Variable value has been truncated, or insufficient space is provided to return all extension variable names.
- 20**
Severe error.

TBSKIP—move the row pointer


Command invocation format



Call invocation format

➤ CALL — ISPEXEC — (buf-len, — buffer); ➤

OR



- 0**
Normal completion.
- 8**
CRP would have gone beyond the number of rows in the table. This includes a table empty condition, with CRP set to TOP (zero). The rowid remains unchanged.
- 12**
Table is not open.
- 16**
Variable value has been truncated, or insufficient space is provided to return all extension variable names.

20

Severe error.

TBSORT—sort a table

Command invocation format

► ISPEXEC — TBSORT — *table-name* — FIELDS(*sort-list*) ◄

Call invocation format

► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄

OR

► CALL — ISPLINK — ('TBSORT_...' — , — *table-name*, — *sort-list*); ◄

Return codes

0

Normal completion.

12

Table is not open.

16


Numeric convert error.

20

Severe error.

TBSTATS—retrieve table statistics

Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len* , — *buffer*); ►◄

OR

```

➤➤ CALL — ISPLINK — ('TBSTATS_' — , — table-name — , — date-created-name —
                                     ' ' —
➤➤ , — time-created-name — , — date-updated-name —
                                     ' ' —
➤➤ , — time-updated-name — , — user-name — , — row-created-name —
                                     ' ' —
➤➤ , — rownum-name — , — row-updated-name —
                                     ' ' —
➤➤ , — table-updated-name — , — service-name —
                                     ' ' —
➤➤ , — return-code-name — , — status1-name — , — status2-name —
                                     ' ' —
➤➤ , — status3-name — , — library — , — virtual-storage-size-name —
                                     ' ' —
➤➤ , — date-created-name-4-digit — , — date-updated-name-4-digit — ); ➤➤
                                     ' ' —

```

Return codes

0

Normal completion (returned even if the table does not exist).

16

Variable value has been truncated.

20

Severe error.

TBTOP—set the row pointer to the top

Command invocation format

```
➤➤ ISPEXEC — TBTOP — table-name ➤➤
```

Call invocation format

```
➤➤ CALL — ISPEXEC — (buf-len , — buffer); ➤➤
```

OR

```
➤➤ CALL — ISPLINK — ('TBTOP_...' — , — table-name); ➤➤
```

Return codes

0

Normal completion.

12

Table is not open.

20

Severe error.

TBVCLEAR—clear table variables

Command invocation format

➡ ISPEXEC — TBVCLEAR — *table-name* ➡

Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ◄◄

OR

►► CALL — ISPLINK — ('TBVCLEAR' — , — *table-name*); ◄◄

Return codes

O

Normal completion.

12

Table is not open.

20

Severe error.

TRANS—translate data from one Coded Character Set Identifier (CCSID) to another

Command invocation format

► ISPEXEC — TRANS — FRMCCSID(*from-ccsid-number*) — TOCCSID(*to-ccsid-number*) ►

FROMVAR(*from-variable-name*)

TOVAR(*to-variable-name*)

LENGTH(*data-length*)

Call invocation format

►► CALL — ISPEXEC — (*buflen*, — *buffer*); ◄◄

OR

► CALL — ISPLINK — ('TRANS_...' — ,from-ccsid-number ,to-ccsid-number ,from-variable-name →
 → , to-variable-name , data-length); ►

Return codes

- 0** Service completed successfully.
- 4** Translate tables do not support the requested "to ... from" combination. For a list of extended code page translate tables provided by ISPF, see the [z/OS ISPF Dialog Developer's Guide and Reference](#).
- 8** From variable not found.
- 16** Variable services indicated a translation error or truncation occurred storing the translated data.
- 20** Severe error.

VCOPY—create a copy of a variable

Command invocation format

```
ISPEXEC *This service does not apply to APL2 or command
        procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

► CALL — ISPLINK — ('VCOPY_...' — , — name-list , — length-array , — value-array →

→ , { 'LOCATE_...' , ' ' , 'MOVE_...' }); ►

Return codes

- 0** Normal completion.
- 8** One or more variables do not exist.
- 12** Validation failed.
- 16** Truncation has occurred during data movement (move mode only).
- 20** Severe error.

VDEFINE—define function variables

Command invocation format

```
ISPEXEC *This service does not apply to APL2 or command
        procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

```
► CALL — ISPLINK — ('VDEFINE_' — , — name-list, — variable, — format, — length —►
    , — options-list — , — user-data — , — 'LFORMAT_' — ); ◀◀
    , — ' ' — , — ' ' — , — ' ' —
```

Return codes

- 0** Normal completion.
- 8** Variable not found.
- 16** Data truncation occurred.
- 20** Severe error.

VDELETE—remove a definition of function variables

Command invocation format

```
ISPEXEC *This service does not apply to APL2 or
        command procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

```
► CALL — ISPLINK — ('VDELETE_', — name-list — ); ◀◀
    , — '*' —
```

Return codes


- 0** Normal completion.
- 8** At least one variable not found.

20

Severe error.

VERASE—remove variables from shared and/or profile pool


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►►

OR



Return codes

0

Normal completion.

8


At least one variable not found.

20

Severe error.

VGET—retrieve variables from a pool or profile or system symbol


Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len*, — *buffer*); ►►

OR




Return codes

- 0** Normal completion.
- 8** Variable not found. If the SYMDEF parameter was specified: system symbol not found.
- 12** Validation failed.
- 16** Translation error or truncation occurred during data movement.
- 20** Severe error. If the SYMDEF parameter was specified: the number of symbol names in *symname-list* exceeds the number of names in *name-list*.


VIEW—view a data set

Command invocation format




OR

►► ISPEXEC — VIEW — DATAID(*data-id*) →



OR



Call invocation format

```

➤ CALL — ISPLINK — ('VIEW_<_>' — , <_> dsname , <_> serial ➤

➤ , <_> pswd-value , <_> panel-name , <_> macro-name ➤

➤ , <_> profile-name , <_> data-id , <_> member-name ➤

➤ , <_> format-name , { 'NO_<_>' , 'YES_<_>' } , { 'YES_<_>' , 'NO_<_>' } , ➤

➤ <_> ws-filename-buffer-name , { 'YES_<_>' , 'NO_<_>' } , { 'YES_<_>' , 'NO_<_>' } ➤

➤ , <_> parm-var , <_> file-var , { 'ASCII_<_>' , 'UTF8_<_>' } ➤

➤ , <_> tabname , <_> generation ); ➤

```

OR

```

➤ CALL — ISPEXEC — (buf-len , — buffer); ➤

```

Return codes

0

Normal completion. Browse was substituted for VIEW if insufficient storage was available to read in the requested data.

Note: Data can only be saved through the CREATE or REPLACE primary commands.

9

The specified generation of the member was not found in the specified data sets.

10

Member not found.

11

A non-current generation was specified. None of the specified data sets are PDSE version 2 data sets that are configured for member generations.

12

VIEW has been disabled through the ISPF configuration table or the ws-filename-buffer-name parameter was specified.

14

Member, sequential data set, or z/OS UNIX file in use.

16

Either:

- No members matched the specified pattern
- No members in the partitioned data set.

18

A VSAM data set was specified but the ISPF Configuration Table does not allow VSAM processing.

20

Severe error; unable to continue.

VIIF—view interface

Command invocation format

You cannot use command procedures to invoke this service.

Call invocation format

```

▶ CALL — ISPLINK — ('VIIF_<u>      </u>' — , <u>data-name</u> , <u>profile-name</u> — , <u>rec-format</u> →

▶ , <u>rec-len</u> — , <u>read-routine</u> — , <u>cmd-routine</u> , <u>dialog-data</u> →

▶ , <u>edit-len</u> , <u>panel-name</u> , <u>macro-name</u> →

▶ , <u>format-name</u> , { <u>'NO_<u>      </u>'</u> , <u>'YES_<u>      </u>'</u> } , { <u>'NO_<u>      </u>'</u> , <u>'YES_<u>      </u>'</u> } →

▶ , <u>parm-var</u> , <u>write-routine</u> , { <u>'YES_<u>      </u>'</u> , <u>'NO_<u>      </u>'</u> } →

▶ , <u>tabname</u> ); ▶

```

OR

```

➤ CALL — ISPLINK — ('VIIF_____', data-name , rec-format ,
                                     rec-len , read-routine , cmd-routine , dialog-data
                                     , YES_____ , write-routine
                                     , tabname ); ➤

```

Read routine return codes

- 0**
Normal completion.
- 8**
End of data records (no data record returned).
- 16**
Read error. If a read error is encountered when the system builds the initial view display, the VIIF service terminates with a return code of 20. Otherwise, the view data is redisplayed.
- 20**
Severe error. (The VIIF service terminates immediately with a return code of 20.)

Command routine return codes

- 0**
Normal completion.
- 4**
ISPF should process the requested function.
- 12**
Command deferred; retain the command on the Command line. View data is redisplayed.
- 20**
Severe error. (The VIIF service terminates immediately with a return code of 20.)

VIIF return codes

- 0**
Normal completion, data not saved.
- 12**
View has been disabled through the configuration table.
- 16**
Unexpected return code received from a dialog-supplied routine. When an unexpected return code is received, the VIIF service terminates immediately with a return code of 16.
- 20**
Severe error; unable to continue.


VMASK—associate an edit mask with a dialog variable

Command invocation format

ISPEXEC *This service does not apply to APL2 or command procedures*

Call invocation format

►► CALL — ISPLINK — ('VMASK' — ,*name-list* →




Return codes

- 0 Normal completion
- 8 Variable not found
- 20 Severe error.

VPUT—update variables in the shared or profile pool

Command invocation format



Call invocation format

►► CALL — ISPEXEC — (*buf-len* , — *buffer*); ►◄

OR

```

➤ CALL — ISPLINK — ('VPUT_...' — , — name-list — , — {
    'ASIS_...'
    ' '
    'SHARED_...'
    'PROFILE_...'
} — ); ➤

```

Return codes

- 0** Normal completion.
- 8** Variable not found.
- 16** Truncation occurred while copying variables to the application profile pool.
- 20** Severe error.

VREPLACE—replace a variable

Command invocation format

```
ISPEXEC *This service does not apply to
        APL2 or command procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

```
➤ CALL — ISPLINK — ('VREPLACE' — , — name-list, — lengths, — values); ➤
```

Return codes

- 0** Normal completion.
- 16** Truncation has occurred during data movement.
- 20** Severe error.

VRESET—reset function variables

Command invocation format

```
ISPEXEC *This service does not apply to
        APL or command procedures*
```

Call invocation format

```
CALL ISPEXEC *This service cannot be used with this interface*
```

OR

➤ CALL — ISPLINK — ('VRESET_'); ➤

Return codes

0

Normal completion.

20

Severe error.

VSYM service—resolve system symbols

Command invocation format

➤ ISPEXEC — VSYM — *name-list* ➤

Call invocation format

➤ CALL — ISPEXEC — (*buf-len*, — *buffer*); ➤

OR

➤ CALL — ISPLINK — ('VSYM_...' — , — *name-list*); ➤

Return codes

0

Normal completion.

4

One or more symbol names not substituted (no corresponding system symbol was found).

8

Variable not found in function pool.

12

Validation failed.

16

Truncation occurred resolving system symbols.

20

Severe error.

Chapter 4. Edit macro commands

This chapter contains the syntax and return codes for the ISPF Edit macros. For a complete description of the Edit macros see *z/OS ISPF Edit and Edit Macros*.


AUTOLIST - set or query Autolist mode

Macro command syntax



Assignment statement syntax

ISREDIT — (varname) — = — AUTOLIST —



Return codes

0

Normal completion.

20

Severe error.


AUTONUM—set or query Autonum mode

Macro command syntax



Assignment statement syntax

ISREDIT — (varname) — = — AUTONUM —



Return codes

0


Normal completion.

20

Severe error.


AUTOSAVE—set or query Autosave mode

Macro command syntax



Assignment statement syntax

➤ ISREDIT — (*var1, var2*) — = — AUTOSAVE ➤



Return codes

- 0** Normal completion.
- 4** OFF NOPROMPT specified.
- 20** Severe error.

BLKSIZE—query the block size

Assignment statement syntax


➤ ISREDIT — (*varname*) — = — BLKSIZE ➤

Return codes

- 0** Normal completion.
Note: For a z/OS UNIX file, the BLKSIZE assignment statement returns a value of 0.
- 12** Syntax error.
- 20** Severe error.


BOUNDS—set or query the edit boundaries

Macro command syntax



Assignment statement syntax

>> ISREDIT — (*var1, var2*) — = — BOUNDS >>



Return codes

- 0** Normal completion.
- 4** Right boundary greater than default; default right boundary used.
- 12** Invalid boundaries specified.
- 20** Severe error.

BROWSE—browse from within an edit session

Macro command syntax

>> ISREDIT — BROWSE — *member* >>

Return codes

- 0** Normal completion
- 12** Your error (invalid member name, recovery pending)
- 20** Severe error.

BUILTIN—process a built-in command

Macro command syntax

>> ISREDIT — BUILTIN — *cmdname* >>

Return codes

- n**
Return code from the built-in command.
- 20**
Severe error.

CANCEL—cancel edit changes

Macro command syntax

►► ISREDIT — CANCEL ►◄

Return codes

- 0**
Normal completion.
- 20**
Severe error.

CAPS—set or query Caps mode

Macro command syntax

►► ISREDIT — CAPS — { ON
OFF } ►◄

Assignment statement syntax

►► ISREDIT — (*varname*) — = — CAPS ►◄


►► ISREDIT — CAPS — = — { ON
OFF } ►◄

Return codes

- 0**
Normal completion.
- 20**
Severe error.

CHANGE—change a search string

Macro command syntax



Return codes

- 0** Normal completion.
- 4** String not found.
- 8** Change error. String-2 is longer than string-1 and substitution was not performed on at least one change.
- 12** Inconsistent parameters. The string to be found will not fit between the specified columns.
- 20** Severe error.

CHANGE_COUNTS—query change counts

Assignment statement syntax


➤ ISREDIT — (var1,var2) — = — CHANGE_COUNTS —>

Return codes

- 0** Normal completion.
- 20** Severe error.

COMPARE—compare data set


Macro command syntax



Return codes

- 0** Normal completion
- 8** Member or data set not found, or an error opening the member or data set occurred.
- 12** No parameters specified, or another parameter error such as not valid NEXT or member specification.
- 20** Severe error. SuperC, allocation, or delta file error occurred.


COPY—copy data



Return codes

- 0** Normal completion.
- 8** End of data reached before last record read.
- 12** Invalid line pointer (lptr); member not found or BLDL error.
- 16** End of data reached before first record of specified range was reached.
- 20** Syntax error (invalid name, incomplete range,), or I/O error.

CUT—cut and save lines



Return codes

- 0** Normal completion.
- 12** Parameter error. Insufficient storage, or no more clipboards available.
- 20** Severe error.

DATA_CHANGED—query the data changed status

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — DATA_CHANGED ➤

Return codes

- 0** Normal completion.
- 20** Severe error.

DATA_WIDTH—query data width

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — DATA_WIDTH ➤

Return codes

- 0** Normal completion.
- 12** Invalid command format.
- 20** Severe error.

DATAID—query data ID

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — DATAID ➤

Return codes

- 0**
The data ID returned was passed to the editor.
- 4**
Data ID was generated by and will be freed by the editor.
- 8**
A previously generated data ID was returned.
- 20**
Severe error.

DATASET—query the current data set name

Assignment statement syntax

➤ ISREDIT — (*var1,var2,var3*) — = — DATASET ➤

Return codes

- 0**
Normal completion.
- 20**
Severe error.

DEFINE—define a name

Macro command syntax

➤ ISREDIT — DEFINE — *name* — {
 MACRO — CMD
 MACRO — PGM
 ALIAS — *name-2*
 NOP
 RESET
 DISABLED
 } ➤


Return codes

- 0**
Normal completion.
- 8**
RESET was attempted for a name not currently defined, or DEFINE name ALIAS name-2 requested and name-2 is a NOP.
- 12**
DEFINE was attempted for a name not currently defined.

20
Severe error (unknown command).

DELETE—delete lines

Macro command syntax



Return codes

0
Normal (lines deleted successfully).

4
No lines deleted.

8
No standard records exist.

12
Invalid line number.

20
Severe error.

DISPLAY_COLS—query display columns

Assignment statement syntax

ISREDIT — (*var1, var2*) — = — DISPLAY_COLS —

Return codes

0
Normal completion.

12
Invalid command format.

20
Severe error.

DISPLAY_LINES—query display lines

Assignment statement syntax

► ISREDIT — (*var1, var2*) — = — DISPLAY_LINES ►

Return codes

- 0**
Normal completion.
- 4**
No visible data lines.
- 8**
No existing data lines.
- 12**
Invalid command format.
- 20**
Severe error.

DOWN—scroll down

Macro command syntax

► ISREDIT — DOWN — *amt* ►

Return codes

- 0**
Normal completion.
- 2**
No more data DOWN.
- 4**
No visible lines.
- 8**
No data to display.
- 12**
Amount not specified.
- 20**
Severe error.

EDIT—edit from within an edit session

Macro command syntax

► ISREDIT — EDIT — *member* ►

Return codes

- 0**
Normal completion. Data was saved.

END edit macro

- 4**
Normal completion. Data was not saved.
- 12**
Your error (invalid member name, recovery pending).
- 14**
Member in use.
- 20**
Severe error.
- 28**
No ISREDIT MACRO statement preceded this call, or BROWSE was substituted because of the size of the member being edited.

END—end the edit session

Macro command syntax


➤➤ ISREDIT — END ➤➤

Return codes

- 0**
Normal completion.
- 4**
New member saved.
- 12**
END not done, AUTOSAVE OFF PROMPT set, or Data not saved (insufficient space).
- 20**
Severe error.

EXCLUDE—exclude lines from the panel

Macro command syntax



Return codes

- 0**
Normal completion.
- 4**
String not found.

- 8**
Line(s) not excluded.
- 12**
Inconsistent parameters
- 20**
Severe error.

EXCLUDE_COUNTS—query exclude counts

Assignment statement syntax


► ISREDIT — (*var1,var2*) — = — EXCLUDE_COUNTS ◀

Return codes

- 0**
Normal completion.
- 12**
Invalid command format.
- 20**
Severe error.

FIND—find a search string

Macro command syntax



Return codes

- 0**
Normal completion.
- 4**
String not found.
- 12**
Syntax error.
- 20**
Severe error.

FIND_COUNTS—query find counts

Assignment statement syntax

►► ISREDIT — (*var1,var2*) — = — FIND_COUNTS —◄◄

Return codes

0

Normal completion.

12


Invalid command format.

20

Severe error.

FLIP—reverse excluded status of lines

Macro command syntax

►► ISREDIT — FLIP —  —◄◄

Return codes

0

Successful completion. The excluded status of the requested lines was reversed.

20

Severe error.

FLOW_COUNTS—query flow counts

Assignment statement syntax

►► ISREDIT — (*var1,var2*) — = — FLOW_COUNTS —◄◄

Return codes

0


Normal completion.

20

Severe error.


HEX—set or query Hexadecimal mode

Macro command syntax



Assignment statement syntax

>> ISREDIT — (*var1, var2*) — = — HEX — ><



Return codes

0

Normal completion.

20

Severe error.

HIDE—hide excluded lines message

Macro command syntax

>> ISREDIT — HIDE — X — ><

Return codes

0


Normal completion.

20

Severe error.

HILITE—enhanced edit coloring

Macro command syntax



Return codes

0

Normal completion.

8

One of the following conditions:

- LOGIC or SEARCH not supported in the current environment
- Invalid language
- HILITE unavailable.

12

One of the following conditions:

- HILITE dialog is invalid from an edit macro
- HILITE not available because of the installation defaults
- HILITE not available because the edit panel in use is not enabled for enhanced color
- Other error encountered.

20

Severe error. Possibly extra parameters.

IMACRO—set or query an initial macro

Macro command syntax

➤ ISREDIT — IMACRO — *name* ➤
 NONE

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — IMACRO ➤

➤ ISREDIT — IMACRO — = — *name* ➤

Return codes

0

Normal completion.

4

IMACRO set not accepted; profile is locked.

12

Invalid name specified.

20

Severe error.

INSERT—prepare display for data insertion

Macro command syntax

➤ ISREDIT — INSERT — *lptr* — *numlines* ➤

Return codes

0

Normal completion.

12

Invalid line number.

20

Severe error.

LABEL—set or query a line label

Assignment statement syntax

➤ ISREDIT — (*var1, var2*) — = — LABEL — *lptr* ➤

➤ ISREDIT — LABEL — *lptr* — = — *labelname* — *level* ➤

Return codes

- 0**
Normal completion.
- 4**
Label name not returned, specified line has no label.
- 8**
Label set, but an existing label at the same level was deleted.
- 12**
Line number specified is beyond the end of data.
- 20**
Severe error.

LEFT—scroll left

Macro command syntax

►► ISREDIT — LEFT — *amt* ►◄

Return codes

- 0**
Normal completion.
- 4**
No visible lines.
- 8**
No data to display.
- 12**
Amount not specified.
- 20**
Severe error.

LEVEL—set or query the mod level number

Macro command syntax

►► ISREDIT — LEVEL — *num* ►◄

Assignment statement syntax

►► ISREDIT — (*varname*) — = — LEVEL ►◄

►► ISREDIT — LEVEL — = — *num* ►◄

Return codes

- 0**
Normal completion.
- 4**
Statistics mode is off; the command is ignored.
- 12**
Invalid value specified.

20

Severe error.

LF—realign data on the ASCII linefeed character

Macro command syntax

➤ ISREDIT — LF ➤

Return codes

0

Normal completion.

LINE—set or query a line from the data set

Assignment statement syntax

➤ ISREDIT — (*varname*) = — LINE — *lptr* ➤

➤ ISREDIT — LINE — *lptr* = — *data* ➤

Return codes

0

Normal completion.

4

Data truncated (line shorter than data supplied).

8

Variable not found.

12

Invalid line number.

16

Variable data truncated.

20

Severe error.

LINE_AFTER—add a line to the current data set

Assignment statement syntax

➤ ISREDIT — LINE_AFTER — *linenum* — *label* = — *DATALINE* — *INFOLINE* — *MSGLINE* — *NOTELINE* — *data* ➤

Return codes

0


Normal completion.

LINE_BEFORE edit macro

- 4**
Data truncated.
- 12**
Invalid line number.
- 20**
Severe error.

LINE_BEFORE—add a line to the current data set

Assignment statement syntax



Return codes

- 0**
Normal completion.
- 4**
Data truncated.
- 12**
Invalid line number.
- 20**
Severe error.

LINE_STATUS—query source and change information for a line in a data set

Assignment statement syntax

►► ISREDIT — (*varname*) — = — LINE_STATUS — *lptr* ►►

Return codes

- 0**
Normal completion.
- 12**
Line number not valid.
- 20**
Severe error.

LINENUM—query the line number of a labeled line

Assignment statement syntax

►► ISREDIT — (*varname*) — = — LINENUM — *label* ►►


Return codes

- 0** Normal completion.
- 4** Line 0 specified.
- 8** Label specified, but not found (variable set to 0).
- 12** Invalid line number.
- 20** Severe error.

LOCATE—locate a line

Specific locate syntax

➤ ISREDIT — LOCATE — *lptr* ➤

Generic locate syntax**Return codes**

- 0** Normal completion.
- 4** Line not located.
- 8** Empty member or data set.
- 20** Severe error.

LRECL—query the logical record length

Assignment statement syntax


➤ ISREDIT — (*varname*) — = — LRECL ➤

Return codes

- 0**
Normal completion.
- 12**
Invalid command format.
- 20**
Severe error.

MACRO—identify an edit macro

Macro command syntax



Return codes

- 0**
Normal completion.
- 8**
No parameters are permitted for this processing.
- 12**
Syntax error.
- 20**
Severe error.

MACRO_LEVEL—query the macro nesting level

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — MACRO_LEVEL ➤


Return codes

- 0**
Normal completion.
- 12**
Invalid command format.
- 20**
Severe error.

MACRO_MSG—set or query the macro message switch

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — MACRO_MSG ➤



Return codes

- 0**
Normal completion.
- 12**
Invalid command format.
- 20**
Severe error.

MASKLINE—set or query the mask line

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — MASKLINE ➤

➤ ISREDIT — MASKLINE — = — *data* ➤

Return codes

- 0**
Normal completion.
- 4**
Data truncated.
- 16**
Variable data truncated.
- 20**
Severe error.

MEMBER—query the current member name

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — MEMBER ➤

Return codes

- 0**
Normal completion.
- 12**
Invalid command format.
- 20**
Severe error.

MEND—end a macro in the batch environment

Macro command syntax

➤ ISREDIT — MEND ➤

Return codes

0

Normal completion.


20

Severe error.

Note: Only required in the MVS/370 environment.

MODEL—copy a model into the current data set

Macro command model name syntax



Macro command class name syntax

➤ ISREDIT — MODEL — CLASS — *class-name* ➤

Return codes

0

Normal completion.

4

Data truncated (the model exceeded the right-hand margin of the data being edited).


12

Invalid line pointer.

20

Severe error.

MOVE—move a data set member



Return codes

- 0**
Normal completion.
- 8**
End of data before last record read, or the specified data set is in use.
- 12**
Invalid line pointer (lptr); member not found or BLDL error.
- 16**
End of data before first record read.
- 20**
Syntax error (invalid name, incomplete range), or I/O error.

NONUMBER—turn off Number mode

Syntax

►► ISREDIT — NONUMBER ►◄

Return codes

- 0**
Normal completion.
- 20**
Severe error.


NOTES—set or query Note mode

Macro command syntax

►► ISREDIT — NOTES  ►◄

Assignment statement syntax

►► ISREDIT — (*varname*) — = — NOTES ►◄


►► ISREDIT — NOTES — =  ►◄

Return codes

- 0**
Normal completion.
- 20**
Severe error.


NULLS—set or query Nulls mode

Macro command syntax



Assignment statement syntax

➤ ISREDIT — (var1,var2) — = — NULLS ➤




Return codes

- 0 Normal completion.
- 20 Severe error.

NUMBER—set or query Number mode

Macro command syntax




Notes:

¹ STD is the default for non-COBOL data set types. COBOL is the default for COBOL data set types.

Assignment statement syntax

►► ISREDIT — (*var1,var2*) — = — NUMBER ►►



Return codes

0


Normal completion.

20

Severe error.


PACK—set or query Pack mode

Macro command syntax



Assignment statement syntax

►► ISREDIT — (*varname*) — = — PACK ►►



Return codes

0


Normal completion.

20

Severe error.

PASTE—move or copy lines from clipboard

Macro command syntax



Return codes

- 0**
Normal completion.
- 12**
Parameter error. Clipboard empty or does not exist.
- 20**
Severe error.

PRESERVE—enable saving of trailing blanks

Macro command syntax



Assignment statement syntax

➡ ISREDIT — (*varname*) — = — PRESERVE ➡




Return codes

- 0**
Normal completion.
- 6**
Record format is not variable.
- 16**
Error setting variable.
- 20**
Severe error.

PROCESS—process the panel

Macro command syntax



Return codes

- 0**
Normal completion.
- 4**
A RANGE was expected by the macro, but one was not specified; default values set.
- 8**
A DEST (destination) was expected by the macro, but one was not specified; default values set.

12

Both a RANGE and a DEST (destination) were expected by the macro, but were not specified; default values set.

16

You entered incomplete or conflicting line commands.

20

Severe error.


Note: ISPF does not consider a return code of 12 from the PROCESS edit macro command an error. A macro that receives a return code of 12 from the PROCESS edit macro does not terminate.

PROFILE—set or query the current profile

Macro command profile control syntax

➤ ISREDIT — PROFILE — 

Macro command profile lock syntax

➤ ISREDIT — PROFILE — 

Macro command profile reset syntax

➤ ISREDIT — PROFILE — RESET ➤

Assignment statement syntax

➤ ISREDIT — (var1,var2) — = — PROFILE ➤

Return codes

0

Normal completion.

20

Severe error.

RANGE_CMD—query a command that you entered

Assignment statement syntax

➤ ISREDIT — (varname) — = — RANGE_CMD ➤

Return codes

0

Normal completion.

4

Line command not set.

8

Line command setting not acceptable.

20

Severe error.

RCHANGE—repeat a change

Macro command syntax

➤ ISREDIT — RCHANGE ➤

Return codes

0

Normal completion.

4

String not found.

8

Change error (string-2 longer than string-1 and substitution was not performed on at least one change).

12

Syntax error.

20

Severe error.

RECFM—query the record format

Assignment statement syntax

➤ ISREDIT — (var1,var2) — = — RECFM ➤

Return codes

0


Normal completion.

20

Severe error.


RECOVERY—set or query Recovery mode

Macro command syntax



Assignment statement syntax

➤ ISREDIT — (var1, — var2) — = — RECOVERY ➤




Return codes

- 0** Normal completion.
- 20** Severe error.

RENUM—renumber data set lines

Macro command syntax



Notes:


- ¹ STD is the default for non-COBOL data set types. COBOL is the default for COBOL data set types.

Return codes

- 0** Normal completion.
- 20** Severe error.

REPLACE—replace a data set or data set member

Macro command syntax




Return codes

- 0 Normal completion.
- 8 Member in use.
- 12 Invalid line pointer; member not found or BLDL error.
- 20 Syntax error (invalid name, incomplete line pointer value), or I/O error.

RESET—reset the data display

Macro command syntax



Return codes

- 0 Normal completion.
- 20 Severe error.

RFIND—Repeat Find

Macro command syntax

➡ ISREDIT — RFIND ➡

Return codes

- 0 Normal completion.
- 4 String not found.
- 12 Syntax error.
- 20 Severe error (string not defined).

RIGHT—scroll right

Macro command syntax

► ISREDIT — RIGHT — *amt* ◄

Return codes

- 0** Normal completion.
- 4** No visible lines.
- 8** No data to display.
- 12** Amount not specified.
- 20** Severe error.

RMACRO—set or query the recovery macro

Macro command syntax

► ISREDIT — RMACRO —
name
NONE
 ◄

Assignment statement syntax

► ISREDIT — (*varname*) — = — RMACRO ◄

► ISREDIT — RMACRO — = —
name
NONE
 ◄

Return codes

- 0** Normal completion.
- 12** Invalid name specified.
- 20** Severe error.

SAVE—save the current data

Macro command syntax

► ISREDIT — SAVE ◄

Return codes

- 0**
Normal completion.
- 4**
New member saved.
- 12**
Data not saved; not enough PDS space or directory space.
- 20**
Severe error.

SAVE_LENGTH—set or query length for variable-length data

Macro command syntax


- ISREDIT — (*variable*) — = — SAVE_LENGTH — .*lptr* ➤
- ISREDIT — SAVE_LENGTH — .*lptr* — = — *value* ➤

Return codes

- 0**
Normal completion.
- 4**
Value supplied on set call was out of range. If the supplied length was too great, it is adjusted to equal the maximum record length. Otherwise, the length is adjusted to the length of the nonblank data portion of the record.
- 6**
Record format is not variable. Any value of an assigned request is ignored.
- 16**
Error setting variable.
- 20**
Severe error.


SCAN—set command scan mode

Macro command syntax

- ISREDIT — SCAN —  ➤


Assignment statement syntax

- ISREDIT — (*varname*) — = — SCAN ➤

- ISREDIT — SCAN — = —  ➤

Return codes

- 0**
Normal completion.
- 20**
Severe error.

SEEK—seek a data string, positioning the cursor**Macro command syntax****Return codes**

- 0**
Normal completion.
- 4**
String not found.
- 12**
Syntax error.
- 20**
Severe error.

SEEK_COUNTS—query seek counts**Assignment statement syntax**

➤ ISREDIT — (var1,var2) — = — SEEK_COUNTS ➤

Return codes

- 0**
Normal completion.
- 20**
Severe error.


SESSION—identify type of session**Assignment statement syntax**

➤ ISREDIT — (var1,var2) — = — SESSION ➤


Return codes

- 0**
Normal completion.
- 20**
Severe error.

SETUNDO—set UNDO mode


Macro command syntax**Assignment statement syntax**

➤ ISREDIT — (*varname*) — = — SETUNDO ➤

**Return codes**

- 0**
Successful completion. SETUNDO was turned on or off, or status remains unchanged because UNDO was already on or off.
- 20**
Severe error. Probably a parameter error (something other than STG, REC, or OFF was specified).


SHIFT (—shift columns left)

Macro command syntax**Return codes**

- 0**
Normal completion.
- 12**
Invalid line number.
- 20**
Severe error.

SHIFT) —shift columns right

Macro command syntax


➤ ISREDIT — SHIFT —) — *lptr* — 

Return codes

- 0** Normal completion.
- 12** Invalid line number.
- 20** Severe error.

SHIFT <—shift data left

Macro command syntax


➤ ISREDIT — SHIFT — < — *lptr* — 

Return codes

- 0** Normal completion.
- 12** Invalid line number.
- 20** Severe error.

SHIFT > —shift data right

Macro command syntax


➤ ISREDIT — SHIFT — > — *lptr* — 

Return codes

- 0** Normal completion.
- 12** Invalid line number.
- 20** Severe error.

SORT—sort data

Macro command syntax



Return codes

- 0 Normal completion.
- 4 Lines were already in sort order.
- 8 No records to sort.
- 16 Not enough storage to perform sort.
- 20 Severe error.

SOURCE—describe format of data

Macro command syntax


ISREDIT — SOURCE — *character_encoding* →

Return codes

- 0 Normal completion.


STATS—set or query Stats mode

Macro command syntax



Assignment statement syntax


►► ISREDIT — (*varname*) — = — STATS ►◄

**Return codes****0**

Normal completion.

20


Severe error.

SUBMIT—submit data for batch processing**Macro command syntax****Return codes****0**


Normal completion.

20

Severe error (submit failed).

TABS—set or query Tabs mode**Macro command syntax****Assignment statement syntax**

►► ISREDIT — (*var1, var2*) — = — TABS ►◄



Return codes

- 0**
Normal completion.
- 20**
Severe error.

TABSLINE—set or query tabs line

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — TABSLINE ➤

➤ ISREDIT — TABSLINE — = — *data* ➤

Return codes

- 0**
Normal completion.
- 4**
Data truncated.
- 8**
Invalid data detected and ignored.
- 20**
Severe error (invalid input).

TENTER—set up panel for text entry

Macro command syntax


➤ ISREDIT — TENTER — *lptr* — *numlines* ➤

Return codes

- 0**
Normal completion.
- 12**
Invalid line number.
- 20**
Severe error.

TFLOW—text flow a paragraph

Macro command syntax

➤ ISREDIT — TFLOW — *lptr* —  ➤

Return codes

- 0** Normal completion.
- 12** Invalid line number.
- 20** Severe error.

TSPLIT—text split a line

Macro command syntax

➤ ISREDIT — TSPLIT —  ➤

Return codes

- 0** Normal completion.
- 12** Invalid line number.
- 20** Severe error.

UNNUMBER—remove sequence numbers

Macro command syntax

➤ ISREDIT — UNNUMBER ➤

Return codes

- 0** Normal completion.
- 12** Number mode not on.
- 20** Severe error.

UP—scroll up

Macro command syntax

➤ ISREDIT — UP — *amt* ➤

Return codes

0

Normal completion.

2

No more data UP.

4

No visible lines.

8

No data to display.

12

Amount not specified.

20

Severe error.

USER_STATE—save or restore user state

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — USER_STATE ➤

➤ ISREDIT — USER_STATE — = — (*varname*) ➤

Return codes

0

Normal completion.

20

Severe error.

VERSION—set or query version number

Macro command syntax

➤ ISREDIT — VERSION — *num* ➤

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — VERSION ➤

➤ ISREDIT — VERSION — = — *num* ➤

Return codes

0

Normal completion.

- 4
Stats mode is off, the command is ignored.
- 12
Invalid value specified (the version must be 1 to 99).
- 20
Severe error.

VIEW—view from within an edit session

Macro command syntax

➤ ISREDIT — VIEW — *member* ➤

Return codes

- 0
Normal completion
- 12
Your error (invalid member name, recovery pending)
- 20
Severe error.

VOLUME—query volume information

Assignment statement syntax

➤ ISREDIT — (*var1,var2,var3*) — = — VOLUME ➤


Return codes

- 0
Normal completion.
- 4
The data set is a multivolume data set and the shared pool variable ZEDMVOL is set to contain all the volume serial numbers of the data set. ZEDMVOL has the length of the number of volumes times six.
- 20
Severe error.

XSTATUS—set or query exclude status of a line

Assignment statement syntax

➤ ISREDIT — (*varname*) — = — XSTATUS — *lptr* ➤

➤ ISREDIT — XSTATUS — *lptr* — = —  ➤

Return codes

- 0
Normal completion.

8

An attempt to set a line status to NX could not be performed. The line has a pending line command on it. For example, if an excluded line contains an M line command in the line command field, then the MOVE/COPY IS PENDING message is displayed and the lines cannot be shown. The reset command can be used to remove your line commands from the line command field.

12

Line number is not an existing line.

20

Severe error.


Chapter 5. SCLM services and macros

This chapter shows the syntax and return codes for the SCLM services as well as the syntax for the SCLM macros. For a complete description of the services and macros see the "SCLM Reference" section in the *z/OS ISPF Software Configuration and Library Manager Guide and Reference*.


SCLM services

ACCTINFO—retrieve accounting information

Command invocation format



Call invocation format



Return codes

0

Normal completion. An account record exactly matching the specified criteria was found and the information was stored successfully.

8

Error completion. No account record was found for the specified member.

- If FORWARD was specified then there are no accounting records for the group which match or follow the specified type and member name.
- If MATCH was specified then there is not an account record with the specified group, type and member name.
- If SEARCH was specified then there are no matching account records found when searching up the hierarchy starting from the specified group.

12

Error completion. Refer to the messages for more information.

20

Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.

24

Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

32

Severe error condition. An invalid parameter list was passed to the requested service.

34

Severe error condition. An invalid service was requested.


36




Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.



AUTHCODE—set or retrieve an AUTHCODE

Command invocation format

```

➤ FLMCMD — AUTHCODE, project — ,  ,group — ,type — ,member ➔

➤ ,  ,  ,  ➔


➤ ,  ,  ➤

```

Call invocation format

```

➤ lastrc — := — FLMLNK('AUTHCODE — 'sclm_id , — ,group — ,type — ,member ➔

➤ ,from_authcode — ,to_authcode — ,  ,dd_authmsgs — ,dd_authrept ); ➤

```

Return codes

0

Normal completion. Authcode changed or reported successfully.

2

Normal completion. Authcode not changed. One of these occurred:

- To_authcode = existing authcode (no change needed)
- From_authcode requested does not equal existing authcode (no change wanted)
- Member is not editable.

4

Warning condition. Segment exists at a lower level with an authcode not equal to the "to_authcode" which could overlay the current segment.

8

Error condition. Invalid type, member, or mode parameter. See the dd_authmsgs for details.

12

Severe error condition. Accounting record not found or severe error.

16

Severe error condition. One of these occurred:

- Not authorized to update "to_authcode", access_key mismatch, or not authorized to update data set.
- Verification failed.
- Error updating accounting record.
- Invalid group.

SCLM might not produce messages because there was an error invoking the AUTHCODE module.

20

Severe error condition. SCLM does not produce messages because the SCLM ID is not valid.

24

Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.


32

Severe error condition. SCLM does not produce messages for one of these reasons:

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.


BUILD—build a member

Command invocation format



Call invocation format

► *lastrc* — := — FLMLNK('BUILDbbb' — ,*sclm_id* — ,*group* — ,*type* — ,*member* — ►



► , *prefix_userid* — , *dd_bldmsgs* — , *dd_bldrept* — , *dd_bldlist* — , *dd_bldexit*); ►

Return codes

- 0**
Normal completion.
- 4**
Warning condition.
- 8**
Error condition.
- 12**
Severe error condition. Messages are not produced. Error invoking the Build module.
- 16**
Severe error condition. Messages are not produced. Unable to retrieve SCLM ID information.
- 20**
Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24**
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32**
Severe error condition. Messages are not produced for one of these reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34**
Severe error condition. An invalid service was requested.
- 36**
Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DBACCT—retrieve accounting records for a member

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

```
►► lastrc — := — FLMLNK('DBACCTbb', sclm_id — ,group — ,type — ,member — ,found_group →  


    ► — ,sacct_info — ,slist_info — ,msg_array); ►◄
```

Return codes

- 0** Normal completion.
- 4** Warning condition. The accounting record could not be found.
- 8** Error condition. See the `$msg_array` parameter above for more details.
- 20** Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24** Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32** Severe error condition. Messages are not produced for one of these reasons:
- Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DBUTIL—generate a tailored data set and report

Command invocation format



Call invocation format

You cannot use call procedures to start this service.

Return codes


- 0 Normal completion.
- 4 Warning condition.
- 8 Error condition.

>8


Severe error condition. Messages are not produced.

DELETE—delete database components

Command invocation format



Call invocation format




Return codes


- 0**
Normal completion.
- 4**
Warning condition. The member, accounting record, or build map were not found.
- 8**
Error condition.
- 20**
Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24**
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32**
Severe error condition. Messages are not produced for one of these reasons:
 - Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34**
Severe error condition. An invalid service was requested.
- 36**
Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

DELGROUP—delete database components from group

Command invocation format



Call invocation format



Return codes

- 0**
Normal completion.
- 4**
Warning condition.
- 8**
Error condition.
- 12**
Severe error condition. SCLM does not produce messages because there was an error invoking the DELGROUP module.
- 16**
Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.
- 20**
Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24**
Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

34

Severe error condition. An invalid service was requested.

36

Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

EDIT— edit a member of a controlled library

Command invocation format

► FLMCMD — EDIT, *project* — , *prj_def* — , *group1* — , *group2* — , *group3* — , *group4* — , *type* — , *member* — , { N / Y } — , *imac* — , *prof* — , { Y / N } — , { N / Y } — , { N / Y } — , *authcode* — , *chgcode* — , *volser* — , { N / Y } — , *dd editmsg* ; ►

Call invocation format

```

▶▶ lastrc — := — FLMLNK('EDIT', scdm_id — ,group1 — ,group2 — ,group3 — ,group4 — ,type →
    ▶▶ ,member — , — Y — ,imac — ,prof — , — Y — , — Y —
        N
        N
        N
    ▶▶ , — Y — , — Y —
        N
        N
    ▶▶ —————— );
        ,authcode ——————
            , — chgcode ——————
                ,volser ——————
                    ,dd editmsgq

```

Return codes

Possible return codes are:

O

Normal completion.

8

Error condition. See the `dd_editmsgs` for details.

- 12** Severe error condition. SCLM does not produce messages because there was an error invoking the edit module.
- 16** Verification error from a user exit routine.
- 20** Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24** Severe error condition. SCLM does not produce messages because SCLM services have not been initialized. See the SCLM Reference section in the *z/OS ISPF Software Configuration and Library Manager Guide and Reference* for information on initializing an SCLM services session.
- 32** Severe error condition. SCLM does not produce messages for one of these reasons:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of FLMLNK subroutine does not match the version of the SCLM services module.

END—end an SCLM services session

Command invocation format

You cannot use command procedures to call this service.

Call invocation format


➤ *lastrc* — := — FLMLNK('ENDbbbb', *appl_id* — ,*msg_line*); ➤

Return codes


- 0** Normal completion.
- 4** Warning condition. Unable to free an SCLM ID associated with the application ID.
- 8** Error condition.
- 24** Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32** Severe error condition. SCLM does not produce messages for one of these reasons:
- Invalid service requested
 - Invalid parameter list for the requested service
 - The version of the FLMLNK subroutines does not match the version of the SCLM services module.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

ENDEC— encode and decode members

Command invocation format



Call invocation format



Return codes

0

Normal completion. The encoding and decoding was performed.

4


Warning if ENCODE was specified, the input data set and member is already encoded. If DECODE was specified, the input data set and member is already decoded.

12

Error completion. Refer to the messages for more information.

EXPORT—extract SCLM accounting information for a group

Command invocation format



Call invocation format

```

➤ lastrc — := — FLMLNK('EXPORT' — ,sclm_id — ,group — , — Y — ,dd_msgs →
                                     N —
➤ — ,dd_rept — ); ➤

```

Return codes

- 0** Normal completion.
- 4** Warning condition.
- 8** Error condition.
- 12** Severe error condition. SCLM does not produce messages because there was an error invoking the IMPORT module.
- 16** Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.
- 20** Severe error condition. SCLM does not produced messages because the SCLM ID is invalid.
- 24** Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32** Severe error condition. SCLM does not produce messages for one of these reasons:
 - You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module (for future use).
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

FREE—free database from its association with SCLM ID

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

```

➤ lastrc — := — FLMLNK('FREE' — ,sclm_id — ,msg_line); ➤

```

Return codes

- 0** Normal completion.

- 8** Error condition.
- 24** Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32** Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

GETBLDMP—retrieve build map information

Command invocation format

```

➤ FLMCMD — GETBLDMP, project — , ————— ,group — ,type — ,member —➤
                               |
                               | prj_def
                               |
➤ ————— ,bmap_table — , ————— ➤
                               |
                               | dd_msgs
                               |

```

Call invocation format

```

➤ lastrc — := — FLMLNK('GETBLDMP', sclm_id — ,group — ,type — ,member — ,bmap_table —➤

➤ ————— ,msg_array); ➤


```

Return codes

- 0** Normal completion. A build map record was found that exactly matched the specified criteria and the information was stored successfully.
- 4** Normal completion. A build map record was found at a higher level. The information was stored successfully.
- 8** Error completion. No account record was found for the specified member.
- 12** Error completion. Refer to the messages for more information.

GETXDEP—return cross-dependency information

Command invocation format

►► FLMCMD — GETXDEP, *project* — , — *prj_def* — , — *group* — , — *type* — , — *member* — , —
 ► — *xdep_table* — , — *scope* , —  ►

Call invocation format



►► Lastrc — := — FLMLNK('GETXDEP', *sclm_id* , — *group* — , — *type* — , — *member* — , —
 ► — *xdep_table* — , — *scope* , — \$msg_array); ►►




Return codes


- 4**
The parent chain was truncated when the maximum nesting level was exceeded, or a circular reference was detected. ZSFLIMIT is non-blank on truncated rows.
- 8**
No parent data was found.
- 12**
Cross-dependency database is not active.
- 16**
Error updating ISPF table.
- 20**
Error reading the Cross-dependency database.

IMPORT—import SCLM accounting information to current project

Command invocation format

►► FLMCMD — IMPORT, *project* — , —  , *group* — , —  ►

► , —  , —  , —  ►

► , —  ►

Call invocation format

\blacktriangleright *lastrc* $\text{---} := \text{---}$ FLMLNK('IMPORTbb' --- ,*sclm_id* --- ,*group* --- , $\overbrace{\hspace{10em}}$ *authcode* --- \blacktriangleright
 \blacktriangleright , $\underbrace{\hspace{10em}}$ *change_code* --- , $\underbrace{\hspace{10em}}$ *userid* --- , $\underbrace{\hspace{10em}}$ C --- ,*dd_msgs* --- ,*dd_rept*); \blacktriangleright
 $\underbrace{\hspace{10em}}$ U ---
 $\underbrace{\hspace{10em}}$ R ---

Return codes

0

Normal completion.

4

Warning condition.

8

Error condition.

12

Severe error condition. SCLM does not produce messages because there was an error invoking the IMPORT module.

16

Severe error condition. SCLM does not produce messages because it was unable to retrieve SCLM ID information.

20

Severe error condition. SCLM does not produced messages because the SCLM ID is invalid.

24

Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

32

Severe error condition. SCLM does not produce messages for one of these reasons:

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module (for future use).

34

Severe error condition. An invalid service was requested.

36

Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

INIT—generate an SCLM ID for a database

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

```
►► lastrc — := — FLMLNK('INITbbbb', appl_id — ,project — ,prj_def — ,sclm_id — ,msg_line); ►►
```


Return codes

- 0**
Normal completion.
- 8**
Error condition.
- 24**
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32**
Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34**
Severe error condition. An invalid service was requested.
- 36**
Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

LOCK—lock a member or assign an access key

Command invocation format

```

➤ FLMCMD — LOCK, project — , — prj_def — , group — , type — , member — ➤
      , — authcode — , — access_key — , — userid — ➤

```

Call invocation format

```

➤ lastrc — := — FLMLNK('LOCKbbbb' — , sclm_id — , group — , type — , member — ➤
      , — authcode — , — access_key — , — userid — , found_group — ➤
      'b' — 'b' — 'b' —
      , max_prom_group — , sacct_info — , list_info — , msg_array); ➤

```

Return codes

- 0**
Normal completion.
- 8**
Error condition.
- 20**
Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24**
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32**
Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.

- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

34


Severe error condition. An invalid service was requested.

36


Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

MIGRATE—create accounting information for selected members

Command invocation format



Call invocation format



Return codes

0

Normal completion.

4

Warning condition. See the SCLM messages for more information.

8

Error condition. See the SCLM messages for more information.

20

Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.

24

Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

32

Severe error condition. SCLM does not produce messages for one of these reasons:

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.

NEXTGRP—find the next group in a hierarchy

Command invocation format

►► FLMCMD — NEXTGRP, *project* — , — *prj_def* — , *group* — , — *dd_msgs* — ►►

Call invocation format

►► *lastrc* — := — FLMLNK('NEXTGRP_', *sclm_id* — , *group* — , *dd_msgs*); ►►

Return codes

0

Normal completion. NEXTGRP completed successfully. Variables are set.

4

Warning condition. The group is already the top group. No variables are set.

8

Error condition. Invalid project, *prj_def*, or group name.

12

Severe error condition. SCLM might not produce messages because there was an error invoking the NEXTGRP module. For certain conditions messages are available.

20

Severe error condition. Messages are not produced. Invalid SCLM ID.

24

Severe error condition. Messages are not produced. SCLM services have not been initialized.

32

Severe error condition. Messages are not produced. One of these is true:

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

PARSE—parse a member for statistical and dependency information

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

►► *lastrc* — := — FLMLNK('PARSEbbb' — *sclm_id* — , *group* — , *type* — , *member* — , *language* — ►►


► , — Y — , *ddname* — , *\$stats_info* — , *\$list_info* — , *\$msg_array*); ►►
N

Return codes


- 0**
Normal completion.
- 4**
Warning condition. A parser error occurred.
- 8**
Error condition.
- 20**
Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24**
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32**
Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34**
Severe error condition. An invalid service was requested.
- 36**
Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

PROMOTE—promote a member from one library to another

Command invocation format



Call invocation format




Return codes

- 0** Normal completion.
- 4** Warning condition.
- 8** Error condition.
- 12** Severe error condition. Messages are not produced. Error invoking the Promote module.
- 16** Severe error condition. Messages are not produced. Unable to retrieve SCLM ID information.
- 20** Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24** Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32** Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

RPTARCH—generate an SCLM architecture report

Command invocation format

► FLMCMD — RPTARCH, *project*, — *prj_def* — ,*group* — ,*type* — ,*member* ►



Call invocation format

You cannot use call procedures to start this service.

Return codes


- 0** Normal completion.

SAVE service


- 4
Warning condition.
- 8
Error condition.
- 16
Error condition. Unable to retrieve the SCLM table.

SAVE—lock, parse, and store a member

Command invocation format



Call invocation format



Return codes

- 0
Normal completion.
- 4
Warning condition.
- 8
Error condition.
- 20
Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24
Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32
Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.

- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

34

Severe error condition. An invalid service was requested.

36

Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

SCLMINFO—return project information

Command invocation format

►► FLMCMD — SCLMINFO, *project* — , —  ►

Call invocation format

►► *lastrc* — := — FLMLNK('SCLMINFO', *sclm_id*); ►◄

Return codes

0

Normal completion.

12

Error condition.

START—generate an application ID for a service session

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

►► *lastrc* — := — FLMLNK('STARTbbb', *appl_id*); ►◄

Return codes

0

Normal completion.

12

Severe error condition. The maximum application ID limit was exceeded.

16

Severe error condition. An invalid version of the SCLM table was loaded.

20

Severe error condition. An invalid version of the multicultural support table was loaded.

24

Severe error condition. Unable to load the SCLM table.

28

Severe error condition. Unable to load the multicultural support table or the SCLM I/O load module.

32

Severe error condition. Messages are not produced. One of these is true:

STORE service

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

34

Severe error condition. An invalid service was requested.

36

Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

STORE—store member information in an accounting record

Command invocation format

You cannot use command procedures to call this service.

Call invocation format

```
► lastrc — := — FLMLNK('STOREbbb' — sclm_id — ,group,type,member — ,access_key →  
  
    ► ,language — , — userid — , — C — , — Y — ,$stats_info,$list_info →  
        'b' — U — N —  
  
    ► ,$msg_array); ◀◀
```

Return codes

0

Normal completion.

4

Warning condition.

8

Error condition.

20

Severe error condition. Messages are not produced. Invalid SCLM ID.

24

Severe error condition. Messages are not produced. SCLM services have not been initialized.

32

Severe error condition. Messages are not produced. One of these is true:

- You requested an invalid service.
- You supplied an invalid parameter list for the requested service.
- The version of the FLMLNK subroutine does not match the version of the SCLM services module.

34

Severe error condition. An invalid service was requested.

36

Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

UNLOCK—unlock a member in a development library

Command invocation format

```

▶▶ FLMCMD — UNLOCK, project — , — prj_def — , group — , type — , member →

▶ — , — access_key — ▶▶

```

Call invocation format

```

▶▶ lastrc — := — FLMLNK('UNLOCK' — , sclm_id — , group — , type — , member →

▶ — , — access_key — , msg_array — ); ▶▶

```

Return codes

- 0** Normal completion.
- 4** Warning condition.
- 8** Error condition.
- 20** Severe error condition. Messages are not produced. Invalid SCLM ID.
- 24** Severe error condition. Messages are not produced. SCLM services have not been initialized.
- 32** Severe error condition. Messages are not produced. One of these is true:
- You requested an invalid service.
 - You supplied an invalid parameter list for the requested service.
 - The version of the FLMLNK subroutine does not match the version of the SCLM services module.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

VERDEL—delete version information

Command invocation format

```

▶▶ FLMCMD — VERDEL, project — , — prj_def — , group — , type — , member — , date →

▶ — , time — , — dd_msgs — , — longdate — ▶▶

```

Call invocation format

```

➤ lastrc — := — FLMLNK('VERDEL — ',sclm_id , — ,group — ,type — ,member — ,date — ,time →
    ,msg_array — , — );
    longdate

```

Return codes

- 0** Normal completion. The audit and version information were deleted.
- 8** Error completion. No audit and version information was deleted. No audit record was found that matches the specified criteria.
- 12** Error completion. Refer to the messages for more information.
- 20** Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24** Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32** Severe error condition. An invalid parameter list was passed to the requested service.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

VERHIST—Retrieve Versioned Member Information

Command invocation format

```

➤ FLMCMD — VERHIST, project — , — ,group — ,type — ,member — ,date →
    prj_def
    ,time — ,dd_report — , — , — , —
    Y — , — , —
    N — dd_msgs — longdate

```

Call invocation format

```

➤ lastrc — := — FLMLNK('VERHIST_' — ,sclm_id , — ,group — ,type — ,member — ,date — ,time →
    ,dd_report — , — ,msg_array — , — );
    Y — , —
    N — longdate

```

Return codes

Additional special services messages are written to the FLMSGGS ddname. See the "SCLM service messages" section in [z/OS ISPF Software Configuration and Library Manager Guide and Reference](#) for more information.

Other return codes might be produced by the FLMCMD or the FLMLNK processor. See the "SCLM service return codes" section in [z/OS ISPF Software Configuration and Library Manager Guide and Reference](#) for more information.

Possible return codes are:

0

Normal completion. An audit record exactly matching the specified criteria was found and the version report was stored successfully.

8


Error completion. No audit record was found for the specified member.

12


Error completion. Refer to the messages for more information.

VERINFO—retrieve version information

Command invocation format



Call invocation format



Return codes

0

Normal completion. An audit record exactly matching the specified criteria was found and the information was stored successfully.

8

Error completion. No audit record was found for the specified member.

- If FORWARD was specified then there are no audit records for the group which match or follow the specified type, member, date and time.
- If BACKWARD was specified then there are no audit records for the group which match or precede the specified type, member, date and time.
- If MATCH was specified then there is not an audit record with the specified group, type and member name.

12

Error completion. Refer to the messages for more information.

20

Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.

24

Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.

32

Severe error condition. An invalid parameter list was passed to the requested service.

34

Severe error condition. An invalid service was requested.


36




Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.




VERRECOV—recover a version

Command invocation format

```

➤ FLMCMD — VERRECOV, project — ,  ,group — ,type — ,member — ,date →

➤ ,time — ,  ,  ,  →

➤ ,  ,  ,  ➤


```

Call invocation format

```

➤ lastrc — := — FLMLNK('VERRECOV', sclm_id , — ,group — ,type — ,member — ,date — ,time →

➤ ,to_dataset — ,to_group — ,to_type — ,authcode — ,$msg_array →

➤ ,  ); ➤

```

Return codes

0

Normal completion. The audit and version information were recovered.

- 8** Error completion. No audit and version information was recovered. No audit record was found that matches the specified criteria.
- 10** Error completion. No audit and version information was recovered. The member could not be locked with the specified authorization code.
- 12** Error completion. Refer to the messages for more information.
- 20** Severe error condition. SCLM does not produce messages because the SCLM ID is invalid.
- 24** Severe error condition. SCLM does not produce messages because SCLM services have not been initialized.
- 32** Severe error condition. An invalid parameter list was passed to the requested service.
- 34** Severe error condition. An invalid service was requested.
- 36** Severe error condition. The version of the FLMLNK subroutine does not match the version of the SCLM services module.

XDEPUPDT—Update Cross-dependency Information

Command invocation format

►► FLMCMD — XDEPUPDT, *project*, — *prj_def* — , — *group* * — , — *dd_xdeprept* — ►►

Call invocation format

►► Lastrc — := — FLMLNK('XDEPUPDT' — , — *sclm_id* — * — , — \$msg_array); ►►

SCLM macros

FLMABEG—define the project name of the project definition

Macro format

►► *name* — FLMABEG — ►►

LOC= — BELOW —

ABOVE —


FLMAEND—last macro in the project definition

Macro format

►► FLMAEND ►►


FLMAGRP—define a group of authorization codes


Macro format



FLMALLOC—define each DDname in the DDname substitution list for a translator


Macro format






FLMALTC—specify alternate control information

Macro format




FLMATVER—enable the audit and version utility


Macro format





FLMCNTRL—specify project-specific control options


Macro format
















FLMCPYLB—identify additional data sets to be concatenated to a DDname

Macro format




FLMGROUP—define one group in the project definition

Macro format




FLMINCLS—associate include-sets with types in the project hierarchy

Macro format



FLMLANGL—define a language to SCLM

Macro format



FLMLRBLD—rebuild members with a particular language after promotion**Macro format**

►► FLMLRBLD —————►
 GROUP= *group_list*

FLMPROJ—define a subproject to an SCLM project/alternate**Macro format**

►► *name* — FLMPROJ —————►
 subproj_desc

FLMNPROM—specify which SCLM editable elements may or may not be marked as non-promotable**Macro format**

►► FLMNPROM — GROUP= (*group*) , —►
 *

 ► TYPE= (*type*) , — LANG= (*lang*) —►
 * *

 ► , — NPROM= YES —►
 NO


FLMSYSLB—define a set of data sets for a language containing project macros or included members**Macro format**

►► ————— FLMSYSLB — *dataset_name* —————►
 language ,INCLS= *include_set_name*

 ► —————►
 ,VOL= *volser*


FLMTCOND—select build translators based on group and return codes

Macro format




FLMTOPTS—select the options based on group

Macro format



FLMTRNSL—define once for each translator to be invoked for a language


Macro format



Note: See the "SCLM Reference" section in the *z/OS ISPF Software Configuration and Library Manager Guide and Reference* for information about the two translators FLMPRE and FLMPST.

FLMTYPE—define one FLMTYPE in the project definition

Macro format



Chapter 6. System variables

The system variables are described with type and pool information in the following tables. The variables are also discussed with the ISPF service to which they apply.

Commonly used system variables that a dialog can access are listed below. They are grouped by topic.

The first column gives the name of the variable. The second column indicates in which pool the variable resides. The following abbreviations are used:

func

Function pool

shr

Shared pool

prof

Profile pool

any

Any pool.

The third column indicates the variable's type. The following abbreviations are used:

in

Input variable, set by a dialog to provide information to ISPF

out

Output variable, set by ISPF to provide information to dialogs

non

Non-modifiable output variable

i/o

Both an input and an output variable.

The fourth column gives the length of the variable.

The fifth column gives a brief description of the variable.

Numeric system variables set by ISPF are right-justified and padded with zeros on the left, if necessary. If a program function uses the VCOPY service to access the variable, the value will be in character string format rather than in fixed binary format.

Configuration utility

Table 6. System variables: Configuration utility				
Name	Pool	Type	Len	Description
ZCFGCPD	shr	non	10	Current Configuration module compilation date. ZCFGCPD contains the national language delimiter and contains the date in the format YYYY/MM/DD. For countries that use a delimiter other than a slash (/), that delimiter replaces the slash in the date representation.
ZFGCMPT	shr	non	5	Current Configuration module compilation time. ZFGCMPT contains the national language delimiter and contains the time in the format HH:MM. For countries that use a delimiter other than a colon (:), that delimiter replaces the colon in the time representation. Note: This field will be blank for a configuration module compiled with a previous version of ISPF.

Table 6. System variables: Configuration utility (continued)				
Name	Pool	Type	Len	Description
ZCFGKSRC	shr	non	54	Keyword source data set and member for the current configuration module. Note: This field will be blank for a configuration module compiled with a previous version of ISPF.
ZCFGVL	shr	non	8	Current Configuration module level.
ZCFGMOD	shr	non	8	Current Configuration module name.

Time and date

Table 7. System variables: Time and date				
Name	Pool	Type	Len	Description
ZDATE	shr	non	8	Current date. The format of ZDATE depends on the current national language (see ZDATEF and ZDATEFD).
ZDATEF	shr	non	8	Current national language date format using the characters DD for day, MM for month, and YY for year. ZDATEF contains the national language delimiter. For example, DD/MM/YY, YY/MM/DD, MM.DD.YY. For countries that use a delimiter other than a slash (/), that delimiter replaces the slash in the date representation.
ZDATEFD	shr	non	8	The date format as described under ZDATEF but with the national language convention instead of DD, MM, and YY.
ZDATESTD	shr	non	8	Current date with a 4-digit year (YYYY/MM/DD). The format of ZDATESTD depends on the current national language (see ZDATEF and ZDATEFD).
ZDAYOFWK	shr	non	8	The name of the day of the week.
ZDAY	shr	non	2	Day of month (2 characters)
ZJDATE	shr	non	6	Day-of-year date (format yy.ddd)
ZJ4DATE	shr	non	8	Day-of-year date (format yyyy.ddd)
ZMONTH	shr	non	2	Month of year (2 characters)
ZSTDYEAR	shr	non	4	All 4 digits of the current year (4 characters).
ZTIME	shr	non	5	Time of day (format hh:mm)
ZTIMEL	shr	non		Time of day (format hh:mm:ss:TQ —where <i>T</i> is tenths of a second, and <i>Q</i> is hundredths)
ZYEAR	shr	non	2	Year (2 characters)

The current date is displayed in the appropriate format for the session language, where DD=DAY, MM=MONTH, and YY=YEAR. For countries that use a delimiter other than a slash (/), that delimiter replaces the slash in the date representation.

General

Table 8. General variables				
Name	Pool	Type	Len	Description
Z	shr	non	0	Null Variable
ZACCTNUM	shr	non	40	The MVS account number specified at logon time.
ZAPLCNT	shr	non	4	Number of times APL invoked for a logical screen
ZAPPLID	shr	non	8	Application identifier
ZAPPTTL	any	in	N/A	Variable ZAPPTTL is no longer used by ISPF. If a dialog sets this variable, the value has no effect on ISPF processing.
ZBDMAX	shr	i/o	9	Maximum number of displays that can occur within a batch mode session. This value is obtained from the BDISPMAX keyword on the ISPSTART command.
ZBDMXCNT	shr	non	9	Count of current number of displays in a batch mode session
ZCLIENT	shr	non	4	If ISPF is communicating with a client using the JSON API, ZCLIENT will be set to a value of JSON.
ZCS	shr	non	5	Multicultural support currency symbol
ZCSDLL	shr	non	8	Variable ZCSDLL is no longer used and is set to blanks.
ZDECS	shr	non	1	Multicultural support decimal separator character
ZDEL	prof	non	1	The delimiter is used to separate stacked commands. The default delimiter is a semicolon (;).
ZEDLMSG	shr	in	79	Available for an edit macro to set the long message for the next display.
ZEDSMSG	shr	in	24	Available for an edit macro to set the short message for the next display.
ZENTKTX	any	in	12	Variable ZENTKTX is no longer used by ISPF. If a dialog sets this variable, the value has no effect on ISPF processing.
ZENVIR	shr	non	32	<p>Environment description:</p> <ul style="list-style-type: none"> Characters 1 to 8 contain the product name and sequence number, in the form ISPF x.y. The sequence number x.y has this meaning: <ul style="list-style-type: none"> 7.5 means ISPF for z/OS Version 2 Release 5.0 7.4 means ISPF for z/OS Version 2 Release 4.0 7.3 means ISPF for z/OS Version 2 Release 3.0 7.2 means ISPF for z/OS Version 2 Release 2.0 7.1 means ISPF for z/OS Version 2 Release 1.0 Note: See also the system variables ZISPFOS and ZOS390RL. Characters 9 to 16 contain the generic operating system name (MVS). Characters 17 to 24 contain the operating system environment (TSO or BATCH). Characters 25 to 32 contain blanks and are reserved.
ZEURO	shr	non	1	The EURO currency symbol.
ZGUI	shr	non	68	On a client that is using the JSON API, ZGUI is set to the value CLIENT. Otherwise, ZGUI is set to blanks.

Table 8. General variables (continued)				
Name	Pool	Type	Len	Description
ZINICMD	shr	in	1	Set the value of ZINICMD to Y in the PROC section of the primary menu to indicate that, in the initial invocation of the menu, a command has been put in the value of the ZSEL variable.
ZISPFOS	shr	non	30	The level of ISPF code that is running as part of z/OS on your system. This level might or might not match the z/OS level found in ZOS390RL.
ZISPFRC	shr	in	8	Return code from ISPSTART-selected dialog to invoking application.
ZKEYHELP	any	in	8	Keys help panel identifier. If a keys help panel is not specified on the referenced keylist, the application can provide the keys help panel name in this variable. If the help panel name is present as part of the referenced keylist definition, it takes precedence over the ZKEYHELP value. This system variable must be redefined each time the keys help panel is to change.
ZLANG	prof	non	8	Session language
ZLOGO	shr	non	3	Indicates whether the user has requested bypass of LOGO panel. NO indicates that the user has specified the NOLOGO keyword at the time ISPF was called, thus, requesting that the LOGO panel be bypassed. Otherwise, the value of the variable will be YES.
ZLOGON	shr	non	8	Stepname of TSO logon procedure
ZNESTMAC	any	in	2	When set to a value of NO, REXX and CLIST edit macros are not invoked as nested commands, even when the NESTMACS parameter is specified on the ISPSTART command.
ZMLPS	shr	non	3	Indicates whether the ISPF Profile Sharing feature is active. ZMLPS has a value of either YES or NO.
ZOS390RL	shr	non	16	Indicates the z/OS release running on your system.
ZPANELID	shr	non	8	The name of the currently displayed panel.
ZPFKEY	shr	non	4	The name of the PF key (PFxx) in effect when the user exits the panel. If ZPFKEY = PF00 then no PF key is in effect.
ZPLACE	prof	i/o	7	Command line placement (ASIS or BOTTOM)
ZPREFIX	shr	non	8	TSO user prefix
ZPROFAPP	prof	in	8	Name of application profile pool extension table
ZSCLMLVL	shr	non	60	Environment description: <ul style="list-style-type: none"> • Characters 1 to 9 contain "SCLM FOR ". • Characters 10 to 39 contain the value from ZISPFOS. • Characters 40 to 42 contain the value x.y from ZENVIR. • Characters 43 to 44 contain the SCLM function level. • Characters 45 to 51 contain the ISPF FMID. • Characters 52 to 60 contain blanks and are reserved.
ZSCRCUR	shr	non	4	Displays the number of logical screens currently in use.
ZSCREENC	shr	non	5	Cursor position within the logical screen data.
ZSCREENI	shr	non	?	Logical screen data. Size depends upon your screen size.

Table 8. General variables (continued)				
Name	Pool	Type	Len	Description
ZSCRNAME	shr	in	8	Screen name set by dialog. The screen name is in effect only for the select level in which it was defined. Option 7.3 can alter ZSCRNAME, but this will have no impact.
ZSCRMAY	shr	non	4	Displays the number of logical screens allowed by the installation.
ZSCTPREF	shr	non	4	First site command table prefix
ZSCTPRE2	shr	non	4	Second site command table prefix
ZSCTPRE3	shr	non	4	Third site command table prefix
ZSCTSRCH	shr	non	1	Search order for site command tables relative to system command table. Set to either B (Before ISP) or A (After ISP).
ZSEQ	shr	non	5	Unique number within the sysplex.
ZSM	shr	i/o	3	Indicates whether session manager panels will be used for ISPF options 4 and 6. This variable is initialized from the ISPF configuration table keyword USE_SESSION_MANAGER at startup and stored in the shared variable pool. Once initialized it can only be changed with Option 0 - Settings or by use of the RESET_USE_SESSION_MANAGER configuration option.
ZSTART	prof	in	N/A	Default command stack variable.
ZSTARTPR	prof	non	1	<p>The value of ZSTARTPR can be checked in the panel processing sections of the primary menu to determine if ISPF is processing an initial stack provided in a variable specified on the ISPF command. The following values are possible:</p> <p>N Processing of the commands in the initial command stack is completed.</p> <p>I An initial command stack was provided in a variable specified on the ISPF command. This is the initial invocation of the primary menu and the value of ZCMD is either 'ZSTART DEFAULT' or the name of a variable containing the initial command stack.</p> <p>Y The commands in the initial command stack are currently being processed.</p> <p>S No initial command stack was provided in a variable specified on the ISPF command.</p>
ZSYSICON	shr	non	8	The 8-character variable that contains the command to be executed when the system icon is double-clicked or close is selected.
ZSYSID	shr	non	8	The 8-character SYSNAME obtained from the SYS1.PARMLIB member IEASYSxx which is read at IPL time. NONAME is the default value of SYSNAME. The operator can change this value at IPL time. See the z/OS MVS Initialization and Tuning Reference for more information.

Table 8. General variables (continued)				
Name	Pool	Type	Len	Description
ZSYSNODE	shr	non	12	<p>The network node name of your installation's JES. This name identifies the local JES in a network of systems or system complexes being used for network job entry (NJE) tasks. The node name returned in ZSYSNODE derives from the NODE initialization statement of JES.</p> <p>If the system finds that the subsystem is not active, the ZSYSNODE variable contains the string -- INACTIVE -- (note the string delimiters).</p> <p>If the system finds that the subsystem is JES2 4.2 or earlier, or JES3 5.1.0 or earlier, the ZSYSNODE variable contains the string -- DOWNLEVEL -- (note the string delimiters).</p> <p>The value in ZSYSNODE remains the same throughout the ISPF session.</p> <p>Note: If, for instance, the JES subsystem is taken down during an ISPF session and the node name is changed, the value in ZSYSNODE will still contain the value as determined at ISPF initialization.</p>
ZSYSPLEX	shr	non	8	The MVS sysplex name as found in the COUPLExx or LOADxx member of SYS1.PARMLIB. If no sysplex name is specified in SYS1.PARMLIB, ZSYSPLEX contains blanks.
ZSYSPROC	shr	non	8	TSO Logon Procedure name. In foreground, will have the name of the current logon procedure; in batch, will have the value 'INIT'; a Started Task will have the Started Task procedure name.
ZTEMPF	shr	non	44	Name of temporary data set for file tailoring output
ZTEMPN	shr	non	8	DDNAME of temporary data set for file tailoring output
ZTERMCID	shr	non	5	CCSID coded character set identifier of the terminal. Set by ISPF based on the code page and character set of the terminal. If the terminal code page and character set cannot be queried or if they are not supported by ISPF, this variable will be blank.
ZTERMCP	shr	non	4	<p>CECP support 4-digit code page.</p> <p>Note: ZTERMCS is defined as character length 4. It cannot handle 5-character character sets. For example, the character set 65535 is displayed in ZTERMCS as "5535". This does not mean that ISPF has defined character set 5535 (X'159F'). Two other Z variables, ZTERMCS5 and ZTERMCP5, for character set and code page respectively, were created to handle 5-character character sets and code pages. For example, the character set 65535 is displayed in ZTERMCP5 as 65535.</p>
ZTERMCP5	shr	non	5	CECP support 5-digit code page
ZTERMCS5	shr	non	5	CECP support 5-character set
ZTERMCS	shr	non	4	CECP support 4-digit character set
ZTHS	shr	non	1	Multicultural support thousands separator character
ZTS	shr	non	1	Multicultural support time separator character
ZTSICMD	shr	non	32767	The entire initial invocation command string which invoked the ISPF environment. If storage cannot be obtained at startup, only the first 50 characters will be saved. The maximum length is 32767.
ZTSSCMD	shr	non	32767	SELECT portion of the initial invocation command. The maximum length is 32767.

Table 8. General variables (continued)				
Name	Pool	Type	Len	Description
ZUCTPREF	shr	non	4	First user command table name
ZUCTPRE2	shr	non	4	Second user command table name
ZUCTPRE3	shr	non	4	Third user command table name
ZUSER	shr	non	8	User ID
ZVERB	shr	out	8	Command verb after a SETVERB command table action
ZWINTTL	any	in	N/A	Title to be displayed in pop-up window frame
ZWSCDPG	shr	non	4	Variable ZWSCDPG is no longer used and is set to blanks.
ZWSCON	shr	non	68	Variable ZWSCON is no longer used and is set to blanks.
ZWSOPSYS	shr	non	16	Variable ZWSOPSYS is no longer used and is set to blanks.

Terminal and function keys

Table 9. System variables: Terminal and function keys				
Name	Pool	Type	Len	Description
ZCOLORS	shr	non	4	Number of colors supported by the terminal type (either 1 or 7)
ZDBCS	shr	non	3	DBCS terminal capability (YES or NO)
ZFKA	prof	non	8	Current state of the function key area form (LONG, SHORT, OFF (no display))
ZGE	shr	non	3	Terminal support for graphic escape order: YES graphic escape is supported NO graphic escape is not supported Note: On a client that is using the JSON API, ZGE will be set to NO.
ZHILITE	shr	non	3	Extended highlighting availability (YES or NO)
ZIPADDR	shr	non	15	Variable ZIPADDR is no longer used and is set to blanks.
ZIPADD6	shr	non	39	Variable ZIPADD6 is no longer used and is set to blanks.
ZIPPORT	shr	non	4	Variable ZIPPORT is no longer used and is set to zeros.
ZLUNAME	shr	non	8	VTAM® LU name of the current TSO session. Entering a TERMSTAT QUERY command will refresh the value.
ZKEYS	prof	out	4	Number of Function keys
ZKLAPPL	shr	non	4	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains the application id where the current keylist came from.
ZKLNAME	shr	non	8	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains the name of the current keylist.
ZKLTYPE	shr	non	1	If KEYLIST is ON and it is a panel with the)PANEL statement, this contains either P (for Private) or S (for Shared) for the current keylist.
ZKLUSE	prof	i/o	1	If KEYLIST is ON this contains Y, if it is OFF, it contains an N.

Table 9. System variables: Terminal and function keys (continued)				
Name	Pool	Type	Len	Description
ZPFCTL	prof	i/o	5	User authorization to use PFSHOW command <ul style="list-style-type: none"> • USER—User controls function key display with PFSHOW command • ON—Display function key definitions on all panels • OFF—Do not display function key definitions
ZPFFMT	prof	i/o	4	Number of Function key definitions displayed per line <ul style="list-style-type: none"> • SIX—Always display six keys per line • MAX—Display as many keys as will fit on each line
ZPFSET	prof	i/o	4	Function key definition set displayed <ul style="list-style-type: none"> • PRI—Primary set (1-12) • ALT—Alternate set (13-24) • ALL—All keys (1-24)
ZPFSHOW	prof	out	4	PFSHOW command status
ZPFxx	prof	i/o	255	Setting for Function keys: ZPF13-ZPF24 contain settings for the primary keys (for 12-key terminals: physical keys 1-12; for 24-key terminals: physical keys 13-24) ZPF01-ZPF12 contain settings for the alternate keys (for 24-key terminals only: physical keys 1-12) The maximum length is 255.
ZPFLxx	prof	i/o	8	Setting for Function key labels: ZPFL13-ZPFL24 contain labels for the primary keys ZPFL01-ZPFL12 contain labels for the alternate keys
ZPRIKEYS	prof	i/o	4	Indicates the set of Function keys that will be the primary keys <ul style="list-style-type: none"> • LOW—1 to 12 are primary keys • UPP—13 to 24 are primary keys
ZSCREEN	shr	non	1	Logical screen number up to 32 screens (1-9, A-W)
ZSCREEND	shr	non	4	Screen depth available for dialog use. In batch mode, this variable is set by the value specified for BATSCRD on the ISPSTART call.
ZSCREENW	shr	non	4	Screen width available for dialog use. In batch mode this variable is set by the value specified for BATSCRW on the ISPSTART call. ZSCREEND and ZSCREENW are generally the dimensions of the physical display screen. There are two exceptions: <ol style="list-style-type: none"> 1. On a 3290, if a dialog is executing on a display with a width of 160 characters and the user does a vertical split, then ZSCREENW is 80. 2. On a 3278 model 5, if a user has specified SCREEN FORMAT IS STD, then ZSCREENW is 80 and ZSCREEND is 24, rather than the maximum physical size of 132 by 27.
ZSCRMXD	shr	non	4	Maximum screen depth available for dialog use. In batch mode, this variable is set by the value specified for BATSCRD on the ISPSTART call.

Table 9. System variables: Terminal and function keys (continued)				
Name	Pool	Type	Len	Description
ZSCRMXW	shr	non	4	Maximum screen width available for dialog use. In batch mode, this variable is set by the value specified for BATSCRW on the ISPSTART call. ZSCRMXD and ZSCRMXW are identical to ZSCREEND and ZSCREENW, except for terminals on which an alternate size is available. In that case, ZSCRMXD and ZSCRMXW contain the screen configuration size that produces the largest screen. For the 3290, these variables contain sizes of the hardware partition on which ISPF is operating.
ZSPLIT	shr	non	3	Split-screen mode in effect (YES or NO)
ZSWPBR	prof	non	1	List of logical screens displayed at bottom of screen. Has a value of Y if the SWAPBAR feature is turned on. If ZSWPBAR is not present, or does not have a value of Y then when ISPF is entered, SWAPBAR is not automatically started.
ZTERM	prof	out	8	Terminal type as defined by option 0

Scrolling

Table 10. Scrolling variables				
Name	Pool	Type	Len	Description
ZAMT	prof	i/o	4	Scroll amount for functions such as Dialog Test, the Keylist Utility, the Command Table Utility, and the LIBDEF Utility
ZDYNSCR	any	in	4	If ISPF was invoked by a client and a panel with a dynamic area that can be scrolled is to be displayed, the application can set the value of ZDYNSCR to indicate whether the dynamic area can be scrolled up, down, left, or right on the next display. The variable value must be 4 bytes: <ul style="list-style-type: none"> • Byte 1 set to Y when the area can be scrolled up. • Byte 2 set to Y when the area can be scrolled down. • Byte 3 set to Y when the area can be scrolled left. • Byte 4 set to Y when the area can be scrolled right.
ZSCBR	prof	i/o	4	Scroll amount for the BROWSE service
ZSCED	prof	i/o	4	Scroll amount for the EDIT service
ZSCML	prof	i/o	4	Scroll amount for member lists
ZSCRML	shr	non	1	Specifies if ISPF should scroll to the first member selected in the member list after processing or disable the member list from automatic scrolling and instead place the cursor in front of the last member selected.
ZSCROLLA	shr	out	4	Value from scroll amount field (PAGE, MAX, number)
ZSCROLLD	any	in	4	Value to be used as default scroll value for scrollable dynamic areas and table display

Table 10. Scrolling variables (continued)				
Name	Pool	Type	Len	Description
ZSCROLLN	shr	out	4	Scroll number as computed from the value in the scroll amount field or entered as a scroll value. The maximum scroll number supported for ZSCROLLN is 9999. If a scroll value greater than 9999 is entered the value for ZSCROLLN is set to 9999.
ZSCROLNL	shr	out	8	Scroll number as computed from the value in the scroll amount field or entered as a scroll value. ZSCROLNL supports scroll numbers up to 9999999.
ZTBLSCR	any	in	4	If ISPF was invoked by a client and the application will issue a table display and use a variable model line to dynamically build the display area for the table rows, the application can set the value of ZTBLSCR to indicate whether the table display can be scrolled up, down, left, or right on the next display. The variable value must be 4 bytes: <ul style="list-style-type: none"> • Byte 1 set to Y when the table can be scrolled up. • Byte 2 set to Y when the table can be scrolled down. • Byte 3 set to Y when the table can be scrolled left. • Byte 4 set to Y when the table can be scrolled right.
ZXSMAX	shr	non	4	Maximum scroll amount allowed to be used in any scroll operation.
ZXSMIN	shr	non	4	Minimum scroll amount allowed to be used in any scroll operation.
ZUSC	prof	i/o	4	Scroll amount for the Data Set List Utility

PRINTG command

Table 11. System variables: PRINTG command				
Name	Pool	Type	Len	Description
ZASPECT	func	in	4	Aspect ratio of printed output from PRINTG
ZDEVNAM	func	in	8	Device name for PRINTG
ZFAMPRT	func	non	4	Family printer type for PRINTG

Table display service

Table 12. System variables: Table display service				
Name	Pool	Type	Len	Description
ZTDADD	func	out	3	More rows needed to satisfy scroll request (YES NO)
ZTDAMT	func	out	4	Number of rows that the dialog should add to satisfy scroll up to 9999. Set to 9999 when number of rows is greater than 9999.
ZTDAMTL	func	out	8	Number of rows that the dialog should add to satisfy scroll
ZTDLROWS	func	in	6	Number of rows in the logical table (dynamic table expansion)
ZTDLTOP	func	in	6	Maps current top row in physical table to its position in logical table.
ZTDMARK	any	in	See note	User-defined text for table display Bottom-of-Data marker Note: Value can be any length that is not more than the screen width.

Table 12. System variables: Table display service (continued)				
Name	Pool	Type	Len	Description
ZTDMMSG	any	in	8	User-defined message ID for table display top-row-displayed indicator
ZTDRET	func	in	8	Defines whether dialog wants to use scroll return feature.
ZTDROWS	func	out	6	Number of table rows upon return from table display
ZTDSCRIP	func	in/out	6	CRP of top row to be displayed after the scroll
ZTDSELS	func	out	4	Number of selected table rows upon return from each table display
ZTDSIZE	func	out	4	Size (number of model sets) of the table display scrollable section
ZTDSRID	func	out	6	Rowid of the row pointed to by ZTDSCRIP
ZTDTOP	func	out	6	Row number (CRP) of top row displayed during most recent table display
ZTDVROWS	func	out	6	Number of visible table rows upon return from table display

LIST service

Table 13. System variables: LIST service				
Name	Pool	Type	Len	Description
ZLSTLPP	shr	non	4	Number of lines per page in list data set
ZLSTNUML	shr	non	4	Number of lines written to current list data set page
ZLSTTRUN	shr	non	4	List data set record length truncation value

LOG and LIST data sets

Table 14. System variables: LOG and LIST data sets				
Name	Pool	Type	Len	Description
ZLOGNAME	shr	non	44	Contains the fully qualified data set name of the log data set.
ZLSTNAME	shr	non	44	Contains the fully qualified data set name of the list data set.

Dialog error

Table 15. System variables: Dialog error				
Name	Pool	Type	Len	Description
ZERRALRM	func	out	3	Message alarm indicator (YES or NO)
ZERRHM	func	out	8	Name of help panel associated with error message
ZERRLM	func	out	512	Long error message text
ZERRMSG	func	out	8	Error message-id
ZERRSM	func	out	24	Short error message text
ZERRTYPE	func	out	8	Error message type
ZERRWIND	func	out	6	Error message window type

Tutorial panels

Table 16. System variables: Tutorial panels

Name	Description
ZCONT	Name of next continuation panel
ZHINDEX	Name of first index panel
ZHTOP	Name of top panel
ZIND	YES specifies an index page
ZUP	Name of parent panel

Selection panels

Table 17. System variables: Selection panels

Name	Description
ZCMD	Command input field
ZPARENT	Parent menu name (when in <i>explicit chain mode</i>)
ZPRIM	YES specifies panel is a primary option menu
ZSEL	Command input field truncated at first period

DTL panels or panels containing a)PANEL section

Table 18. System variables: DTL panels or panels containing a)PANEL section

Name	Pool	Type	Len	Description
ZCURFLD	func	out	8	Name of field (or list column) containing the cursor when the user exits the panel.
ZCURINX	func	out	8	For table display panels, the current row number of the table row containing the cursor. The value ZCURINX is in character format. If the cursor is not within a table row, this value will be 0.
ZCURPOS	func	out	4	Position of the cursor within the field specified by ZCURFLD when the user exits the panel. The value in ZCURPOS is in character format. If the cursor is not within a field, ZCURPOS will contain a 1.

Note: These variables will contain the values that would result if they were set to .CURSOR, .CSRPOS, and .CSRROW, as the first statements in the panel's)PROC section.

Chapter 7. Dialog variables

This topic describes the ISPF dialog variables.

The following table lists the dialog function pool variables that are both read from and written to by several of the PDF library access services. For details of function pool variables written by other services, refer to the *z/OS ISPF Services Guide*.

The variables are listed in alphabetical order. The first column lists the variable name. The second column indicates the variable's type, which corresponds to the format parameter of the ISPF VDEFINE service. The third column specifies the variable's length, which corresponds to the length parameter of the VDEFINE service.

The fourth column lists the PDF services that either read from or write to the variable. An R in parentheses (R) after a service name indicates that the service, when called, reads from the given variable. A W in parentheses (W) after a service name indicates that the service, when called, writes to the given variable. All variables are available to a dialog unless otherwise indicated.

The last column contains a brief description of the contents of the variable and any restrictions on the value of the variable.

Table 19. Dialog function pool variables				
Variable Name	Format	Length	Service (Access)	Description
ZABSGEN	Char	8	GENLIST(W)	If ZLGENS=YES, contains the absolute generation number of the member generation.
ZCMD	Char	256	LMMDISP(W)	Primary Command field from member list panel if the command is not a valid ISPF or PDF primary command.
ZDLBLKSZ	Char	5	LMDLIST(W)	Block size.
ZDLCATNM	Char	44	LMDLIST(W)	Name of the catalog in which the data set was located.
ZDLCDATE	Char	10	LMDLIST(W)	Creation date.
ZDLDEV	Char	8	LMDLIST(W)	Device type.
ZDLDSNTP	Char	8	LMDLIST(W)	DS name type ('PDS', 'LIBRARY', or ' ').
ZDLDSORG	Char	4	LMDLIST(W)	Data set organization.
ZDLEDATE	Char	10	LMDLIST(W)	Expiration date.
ZDLEXT	Char	3	LMDLIST(W)	Number of extents used.
ZDLEXTX	Char	5	LMDLIST(W)	Number of extents used (long format).
ZDLLRECL	Char	5	LMDLIST(W)	Logical record length.
ZDLMIGR	Char	3	LMDLIST(W)	Whether the data set is migrated (YES or NO).
ZDLMVOL	Char	1	LMDLIST(W)	Multivolume indicator (Y or N).

Table 19. Dialog function pool variables (continued)				
Variable Name	Format	Length	Service (Access)	Description
ZDLOVF	Char	3	LMDLIST(W)	Whether variables ZDLEXTX and ZDLSIZEEX should be used to obtain the 'number of extents used' and 'data set size in tracks' values (YES or NO). The value is YES when the 'number of extents used' value exceeds the size of variable ZDLEXT or the 'data set size in tracks' value exceeds the size of variable ZDLSIZE.
ZDLRDATE	Char	10	LMDLIST(W)	Date last referenced.
ZDLRECFM	Char	5	LMDLIST(W)	Record format.
ZDLSIZE	Char	6	LMDLIST(W)	Data set size in tracks.
ZDLSIZEEX	Char	12	LMDLIST(W)	Data set size in tracks (long format).
ZDLSPACU	Char	10	LMDLIST(W)	Space units, one of the following values: CYLINDERS, MEGABYTES, KILOBYTES, BYTES, BLOCKS or TRACKS.
ZDLUSED	Char	3	LMDLIST(W)	Percentage of used tracks or pages (PDSE).
ZDLVOL	Char	6	LMDLIST(W)	Volume serial.
ZDSN	Char	44	LMMDISP(W)	Name of the first or only data set in the concatenation of the member list being displayed. This variable is only available for member list panels.
ZDST	Char	54	BRIF(W) EDIF (W)	Title line data name for EDIF and BRIF.
ZEDBDSN	Char	44	EDIT(R) EDREC(W)	Backup data set name for standard edit recovery.
ZEDILMSG	Char	240	Any Edit macro	Long message text. Corresponds to the first 240 bytes of the message that would be displayed if the command were entered from the command line instead of within an edit macro.
ZEDISMSG	Char	24	Any Edit macro	Short message text. Corresponds to the short message that would be displayed if the command were entered from the command line instead of within an edit macro.
ZEDITCMD	Char	8	Any Edit macro	The last primary command entered in Edit.
ZEDMSGNO	Char	8	Any Edit macro	Message ID. Corresponds to the message that would be displayed if the command were entered from the command line instead of within an edit macro.
ZEDROW	Fixed	4	EDIT(R) EDREC(W)	Row number of entry in standard edit recovery table.
ZEDSAVE	Char	8	Data_changed EDIT macro command	END command will save data (SAVE or NOSAVE).

Table 19. Dialog function pool variables (continued)				
Variable Name	Format	Length	Service (Access)	Description
ZEDTDSN	Char	44	EDIT(R) EDREC(W)	Target data set name for standard edit recovery.
ZEDTMCMD	Char	8	Any Edit macro	The edit command entered that caused an edit macro to run. Can be the macro name or other name if the edit DEFINE command was used to define an alias.
ZEDTMEM	Char	8	EDIT(R) EDREC(W)	Target member name (if applicable) for standard edit recovery.
ZEDTRD	Char	6	EDIT(R) EDREC(W)	Volume serial of target data set for standard edit recovery.
ZEDUSER	Char	1	EDIT(R) EDREC(W)	User data table extension for standard edit recovery.
ZEIBSDN	Char	54	EDIF (R) EDIREC(W)	Backup data name for EDIF edit recovery.
ZEIROW	Fixed	4	EDIF(R) EDIREC(W)	Row number of entry in EDIF edit recovery table.
ZEITDSN	Char	54	EDIF(R) EDIREC(W)	Target data name for EDIF edit recovery.
ZEIUSER	Char	1	EDIF(R) EDIREC(W)	User data table extension variable for EDIF edit recovery.
ZERRALRM	Char	3	ALL(W)	The value YES if an alarm was specified in the message definition; otherwise, the value NO. Set when ISPF services issue a return code of 8 or greater.
ZERRHM	Char	8	ALL(W)	The name of a Help panel, if one was specified in the message definition. Set when ISPF services issue a return code of 8 or greater.
ZERRLM	Char	512	ALL(W)	Long-message text in which variables have been resolved. Set when ISPF services issue a return code of 8 or greater.
ZERRMSG	Char	8	ALL(W)	Message ID. Set when ISPF services issue a return code of 8 or greater.
ZERRSM	Char	24	ALL(W)	Short-message text in which variables have been resolved. Set when ISPF services issue a return code of 8 or greater.
ZGEN	Fixed	4	Any Edit macro	The generation number for the PDSE member generation being edited. This is the value at the time that the edit session started.

<i>Table 19. Dialog function pool variables (continued)</i>				
Variable Name	Format	Length	Service (Access)	Description
ZGENH	Fixed	4	Any Edit macro	The highest generation number for the PDSE member being edited. This value is only valid when a previous generation of a member is being edited and it is the value at the time that the edit session started.
ZGRPLVL	Char	8	LMHIER (W)	ISPF table variable that contains the level of this ISPF library in the controlled hierarchy.
ZGRPNME	Char	8	LMHIER (W)	ISPF table variable that contains the ISPF library group name.
ZHIAUTO	Char	3	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) ON when AUTO language determination is enabled, otherwise OFF.
ZHILANG	Char	8	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) Programming Language name.
ZHICOLOR	Char	8	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) Coloring indicator as well as DO-IF LOGIC enablement. OFF indicates HILITE is disabled regardless of all other variable settings. Values are ON, OFF, LOGIC, IFLOGIC, and DOLOGIC.
ZHIPAREN	Char	3	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) ON when parenthesis matching is enabled, otherwise OFF.
ZHIFIND	Char	3	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) ON when Hilite FIND strings is enabled, otherwise OFF.
ZHICURSR	Char	3	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	(SHARED) ON when Hilite cursor phrase is enabled, otherwise OFF.
ZLAC	Char	2	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Authorization code of the member.
ZLALIAS	Char	8	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Name of the real member of which this member is an alias.

Table 19. Dialog function pool variables (continued)

Variable Name	Format	Length	Service (Access)	Description
ZLAMODE	Char	3	LMMDISP(W) LMMFIND(W) LMMLIST(W)	AMODE of the member.
ZLATTR	Char	20	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Load module attributes. See the z/OS ISPF Services Guide .
ZLCDATE	Char	8	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Date on which the specified member was created. A character string in the national format. For example, yy/mm/dd or mm/dd/yy. If no value exists for this variable, the PDF component will set the value to blanks.
ZLC4DATE	Char	10	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(W)	Date on which the specified member was created, in 4-character year format. A character string in the national format. For example, yyyy/mm/dd or mm/dd/yyyy. If no value exists for this variable, the PDF component will set the value to blanks.
ZLCNORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Current number of records in the specified member. A number from 0 to 65 535. If no value exists for this variable, the PDF component will set the value to blanks.
ZLGENS	Char	3	LMMDISP(R) LMMFIND(R) LMMLIST(R) GENLIST(W)	ZLGENS=YES, if the member is contained in a PDSE version 2 data set that is configured for member generations. If ZLGENS=YES, ZLGMAX, ZLGNEW, ZLGOLD, and ZLGSAV contain values.
ZLGMAX	Char	10	LMMDISP(R) LMMFIND(R) LMMLIST(R) GENLIST(W)	If ZLGENS=YES, contains the maximum number of non-current generations that can be saved for the member.
ZLGNEW	Char	10	LMMDISP(R) LMMFIND(R) LMMLIST(R) GENLIST(W)	If ZLGENS=YES, contains the absolute generation number of the newest non-current generation that is saved.
ZLGOLD	Char	10	LMMDISP(R) LMMFIND(R) LMMLIST(R) GENLIST(W)	If ZLGENS=YES, contains the absolute generation number of the oldest non-current generation that is saved.

Table 19. Dialog function pool variables (continued)

Variable Name	Format	Length	Service (Access)	Description
ZLGSAV	Char	10	LMMDISP(R) LMMFIND(R) LMMLIST(R) GENLIST(W)	If ZLGENS=YES, contains the number of non-current generations that are saved for the member.
ZLINORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Number of records in the specified member when it was first created. A number from 0 to 65 535.
ZLLIB	Fixed	4	LMMDISP(W) LMMFIND(W) LMMLIST(W) GENLIST(W)	Position of the specified member in the concatenated data sets. A number from 1 to 4.
ZLMDATE	Char	8	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Date on which the specified member was last modified. A character string in the national format. (For example, <i>yy/mm/dd</i> or <i>mm/dd/yy</i> .) If no value exists for this variable, the PDF component will set the value to blanks.
ZLM4DATE	Char	10	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(W)	Date on which the specified member was last modified, in 4-character year format. A character string in the national format. (For example, <i>yyyy/mm/dd</i> or <i>mm/dd/yyyy</i> .) If no value exists for this variable, the PDF component will set the value to blanks.
ZLMEMBER	Char	8	LMMDISP(W)	Name of the current selected member.
ZLMNORC	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	The number of records that have been modified in the specified member. A number from 0 to 65 535.
ZLMOD	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Modification level of the specified member. A number from 0 to 99.

Table 19. Dialog function pool variables (continued)

Variable Name	Format	Length	Service (Access)	Description
ZLMTIME	Char	5	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Time when the specified member was last modified. A character string in the form hh:mm.
ZLMSEC	Char	2	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Seconds value of last modified time.
ZLSSI	Char	8	LMMDISP(W) LMMFIND(W) LMMLIST(W)	SSI (System Status Index) of the load module.
ZLPDSUDA	Char	62	LMMDISP(W)	A character string containing the contents of the user data area in the PDS directory entry of the specified member if the member's statistics are not in PDF format.
ZLRMODE	Char	3	LMMDISP(W) LMMFIND(W) LMMLIST(W)	RMODE of the member.
ZLSIZE	Char	8	LMMDISP(W) LMMFIND(W) LMMLIST(W)	Load module size (in Hex).
ZLTTR	Char	6	LMMDISP(W) LMMFIND(W) LMMLIST(W)	TTR of the member.
ZLUSER	Char	7	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	<p>User ID of user who last modified the specified member; the user ID has a maximum length of 7 characters.</p> <ul style="list-style-type: none"> For services that read from this variable, you must use the ZLUSER8 variable if you want to specify an 8-character user ID. For services that write to this variable, when the user ID is an 8-character value, this variable contains the value '>7CHARS'; the 8-character user ID can be obtained from the ZLUSER8 variable.

Table 19. Dialog function pool variables (continued)

Variable Name	Format	Length	Service (Access)	Description
ZLUSER8	Char	8	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R)	User ID of the last user to change the given member. <ul style="list-style-type: none"> When 8-character user IDs are enabled on the system, the user ID has a maximum length of 8 characters. When 8-character user IDs are not enabled on the system, the user ID has a maximum length of 7 characters.
ZLVERS	Fixed	4	LMMADD(R) LMMDISP(W) LMMFIND(W) LMMLIST(W) LMMREP(R) GENLIST(W)	Version number of the specified member. A number from 1 to 99. If no value exists for this variable, the PDF component will set the value to blanks.
ZMEMCNT	Char	8	LMMLIST(W)	Number of members in the member list.
ZMLCOLS	Char	80	LMMDISP(W)	A character string that contains the member statistics column headings that appear on the member list panel display. This variable is only available for member list panels.
ZMLCR	Fixed	4	LMMDISP(W)	The relative number in the member list of the member that appears at the top of the member list display. Its range is from 1-99 999. This variable is only available for member list panels.
ZMLTR	Fixed	4	LMMDISP(W)	Number of members in the member list. Its range is from 1-99 999. This variable is only available for member list panels.
ZMSRTFLD	Char	8	ALL(W)	Contains the field name used to sort a member list. Field name corresponds to the title line used in member list panels, with the exceptions of the 'VV MM' field which is returned as VVMM, and the attributes field which is returned as ATTRIBUT.
ZRELGEN	Char	8	GENLIST(W)	If ZLGENS=YES, contains the relative generation number of the member generation.
ZSCALIAS	Char	1	LMINIT(W)	Data set name is an alias ('Y' or 'N').
ZSCLM	Char	1	LMMDISP(W) LMMFIND(W) LMMLIST(W) GENLIST(W)	Last updater of member. 'Y' indicates SCLM was last updater. 'N' indicates PDF.
ZSCMVOL	Char	1	LMINIT(W)	Data set name is multivolume ('Y' or 'N').
ZUSERMAC	Char	8	EDIT(R) EDIF(R) VIEW(R) VIIF(R)	Application-wide edit macro.

PDF non-modifiable variables

The following read-only variables are available to PDF component dialogs:

Table 20. Read-only variables available to PDF component dialogs				
Variable Name	Format	Length	Service (Access)	Description
ZCUNIT	Char	8	none	Unit name to be used for temporary allocations. This variable comes from ISPF configuration table keyword PDF_DEFAULT_UNIT.
ZCUSIZE	Fixed	4	none	Number of kilobytes available for use by the edit UNDO command when running in SETUNDO STORAGE mode. This variable comes from ISPF configuration table Keyword UNDO_STORAGE_SIZE. See z/OS ISPF Edit and Edit Macros for further information.
ZICFPRT	Char	3	none	ICF indicator. 'YES' - All foreground print requests will be processed using ICF. 'NO' - ICF will not be used. This variable comes from ISPF configuration table keyword PRINT_USING_ICF.
ZPDFREL	Char	8	none	PDF version number in the form "PDF x.y ". The string x.y identifies the version and release of z/OS: <ul style="list-style-type: none"> • 7.5 means ISPF for z/OS Version 2 Release 5.0 • 7.4 means ISPF for z/OS Version 2 Release 4.0 • 7.3 means ISPF for z/OS Version 2 Release 3.0 • 7.2 means ISPF for z/OS Version 2 Release 2.0
ZSESS	Char	8	none	This variable contains either 'Y' or 'N' and comes from the ISPF configuration table keyword USE_SESSION_MANAGER. See the description of the general system variable ZSM for additional information.
ZSWIND	Char	4	none	Sliding window value used by PDF for determining the century of 2-character years. This variable comes from ISPF configuration table keyword YEAR_2000_SLIDING_RULE. Dates less than or equal to this value are 20xx. Dates greater than this value are 19xx.

¹ Length limited only by ISPF restrictions on the length of table extension variables.

Chapter 8. Dialog Tag Language (DTL) tags

The following table is an alphabetic summary of the supported Dialog Tag Language (DTL) tags for z/OS 3.1 ISPF. The table shows the tag, tells whether an end tag is required (Yes) or optional (No), and lists the tag's attributes (if any) and the tag content (if any) in *italics>. The table also lists which tags you can nest within the tag, as well as which tags you can code the tag within.*

Table 21. Tag summary

Tag	End tag	Attributes	Nested tags	Used within
AB	Yes	MNEMGEN=YES NO ABSEPSTR=ab-separator-string ABSEPCHAR=ab-separator-character	ABC	PANEL
ABC	No	HELP=NO YES help-panel-name *help-message-id %varname *%varname PDCVAR=cdc-variable-name <i>choice-description-text</i>	COMMENT M PDC PDSEP SOURCE	AB
ACTION	No	RUN=internal-command-name %varname PARM=parameters %varname APPLCMD=NO YES TYPE=CMD PGM PANEL EXIT NEWAPPL NEWAPPL=application-id NEWWINDOW PASSLIB NEWPOOL SUSPEND SCRNAME=screen-name NOCHECK ADDDPOP OPT=option %varname MODE=LINE FSCR LANG=APL CREX BARRIER NEST SETVAR=variable-name VALUE= <u>1</u> string %varname TOGVAR=variable-name VALUE1= <u>0</u> string %varname VALUE2= <u>1</u> string %varname		CHOICE PDC

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
AREA	Yes	MARGINW= <u>1</u> n MARGIND= <u>0</u> INDENT=n DEPTH=n * EXTEND= <u>OFF</u> ON FORCE DIV= <u>NONE</u> BLANK SOLID DASH TEXT DIVWIDTH= <u>MAX</u> MIN FORMAT=START CENTER END TEXT=divider-text WIDTH=n DIR= <u>VERT</u> HORIZ	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELF SOURCE	HELP PANEL
ASSIGNI	No	VALUE=test-value RESULT=assigned-value		ASSIGNL
ASSIGNL	Yes	DESTVAR=destination-variable-name	ASSIGNI	DTAFLD
ATTENTION	Yes	text	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
ATTR	No	ATTRCHAR=code TYPE=DATAIN DATAOUT CHAR INTENS= <u>HIGH</u> LOW NON %varname CAPS=OFF ON IN OUT %varname JUST=ASIS LEFT RIGHT %varname PAD=NULLS USER char %varname PADC=NULLS USER char %varname SKIP= <u>OFF</u> ON %varname GE= <u>OFF</u> ON %varname COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname HILITE=USCORE BLINK REVERSE %varname NUMERIC= <u>OFF</u> ON %varname FORMAT=EBCDIC DBCS MIX %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PAS= <u>OFF</u> ON %varname CKBOX= <u>OFF</u> ON %varname CUADYN=CEF EE LEF NEF VOI LID LI CH CT DT ET FP NT PIN PT SAC SI SUC WASL WT %varname CSRGRP= <u>NO</u> YES n ATTN= <u>OFF</u> ON %varname		DA
BOTINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL
CAUTION	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
CHDIV	No	TYPE= <u>NONE</u> SOLID DASH TEXT GUTTER= <u>1</u> n FORMAT= <u>START</u> CENTER END <i>divider-text</i>	HP	SELF CHOICE

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
CHECKI	No	TYPE= RANGE PARM1=low-bound %varname PARM2=high-bound %varname ALPHA CHARS PARM1=EQ PARM2=character-set VALUES PARM1=EQ PARM2=value-list VALUESX PARM1=NE PARM2=value-list BIT NAME NAMEF PICT PARM1=EQ PARM2=pictstring PICTCN PARM1=mask-character PARM2=field-mask PARM3=string NUM DBCS LISTV PARM1=EQ PARM2=%varlist LISTVX PARM1=NE PARM2=%varlist ALPHAB LEN PARM1=operator %varname PARM2=length %varname EBCDIC ENUM DSNAMES DSNAMESF DSNAMESFM DSNAMESPQ DSNAMESQ MIX HEX FILEID INCLUDE PARM1=IMBLK PARM2=ALPHA ALPHAB NUM PARM3=ALPHA ALPHAB NUM		CHECKL

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
CHECKI	No	TYPE= IDATE STDDATE JDATE JSTD ITIME STDTIME IPADDR4		CHECKL
CHECKL	Yes	MSG=message-identifier	CHECKI	VARCLASS
CHOFLD	No	DATAVAR=field-data VARCLASS=variable-class-name HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname USAGE= <u>BOTH</u> IN OUT REQUIRED= <u>NO</u> YES MSG=message-identifier AUTOTAB= <u>NO</u> YES ENTWIDTH=n FLDSPACE=n ALIGN= <u>START</u> CENTER END DISPLAY= <u>YES</u> NO NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname PAS=%varname EXPAND ATTRCHANGE= <u>NO</u> YES NEW INIT=initial-value IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname ATTRCHAR=code CAPS= <u>OFF</u> ON <i>choice-description-text</i>	ACTION COMMENT HP PS RP SOURCE	CHOICE

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
CHOICE	No	NAME=choice-name HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname CHECKVAR=variable-name MATCH= <u>1</u> string NOMATCH= <u>0</u> string AUTOTAB= <u>YES</u> NO SELCHAR='char(s),n' PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname HIDE HIDEX UNAVAIL=variable-name UNAVAILMAT= <u>1</u> string TRUNC=n AUTOSEL= <u>YES</u> NO <i>choice-description-text</i>	ACTION CHOFLD COMMENT HP PS RP SOURCE	SELFLD
CMD	No	NAME=internal-command-name ALTDESCR=command-description <i>external-command-name</i>	CMDACT T	CMDTBL
CMDACT	No	ACTION= 'SELECT=select-parameters' 'ALIAS=internal-command-name parameters' PASSTHRU SETVERB BACKWARD CANCEL EXIT EXHELP FKA FORWARD HELP PANELID RETRIEVE %varname application-command ASIS		CMD

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
CMDAREA	No	HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname PMTLOC= <u>BEFORE</u> NOINIT PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname NAME=cmdarea-variable-name ENTWIDTH=n PMTTEXT= <u>YES</u> NO CMDLOC= <u>DEFAULT</u> ASIS CMDLEN= <u>DEFAULT</u> MAX AUTOTAB= <u>NO</u> YES SCROLLVAR=scroll-variable SCRVHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON PSBUTTON=cmd-pb-text PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname CAPS= <u>OFF</u> ON NOJUMP= <u>OFF</u> ON VARDCL= <u>YES</u> NO <i>command-prompt-text</i>	HP	PANEL
CMDTBL	Yes	APPLID=application-identifier SORT= <u>NO</u> YES	CMD	
COMMENT	No	TYPE= <u>END</u> CCSID PANEL ATTR ABCINIT ABCPROC INIT REINIT PROC HELP PNTS LIST <i>comment-text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP MSGMBR PANEL PDC REGION SELFELD

Table 21. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
COMPOPT	No	<u>REPLACE</u> NOREPLACE <u>SCREEN</u> DISK <u>NODBCS</u> DBCS NOKANA KANA KEYLAPPL=xxxx <u>NOPANEL</u> PANEL <u>NOMSGSUPP</u> MSGSUPP <u>NOCUASUPP</u> CUASUPP <u>PREP</u> NOPREP <u>CUAATTR</u> NOCUAATTR <u>NOLSTVIEW</u> LSTVIEW <u>STATS</u> NOSTATS <u>NOSCRIP</u> SCRIPT <u>NOLISTING</u> LISTING <u>NOFORMAT</u> FORMAT <u>NOMSGEXPAND</u> MSGEXPAND <u>LOGREPL</u> NOLOGREPL <u>LISTREPL</u> NOLISTREPL <u>ACTBAR</u> NOACTBAR <u>GUI</u> NOGUI <u>VERSION</u> NOVERSION <u>NOMERGESAREA</u> MERGESAREA <u>NODISPLAY</u> DISPLAY <u>NODISPLAYW</u> DISPLAYW <u>DSNCHK</u> NODSNCHK <u>GRAPHIC</u> NOGRAPHIC <u>ZVARS</u> NOZVARS <u>NODBALIGN</u> DBALIGN <u>NOMCOMMENT</u> MCOMMENT <u>NOVPADC</u> PADC ADD RESET <i>national-language</i>	None	
COPYR	No	<i>copyright-text</i>		

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
DA	Yes	NAME=varname EXTEND= <u>OFF</u> ON FORCE LVLINE=variable-name SCROLL= <u>OFF</u> ON CMDLINE USERMOD=usermod-code %varname DATAMOD=datamod-code %varname DEPTH=n * WIDTH=n SHADOW=shadow-name DIV= <u>NONE</u> BLANK SOLID DASH TEXT FORMAT=START CENTER END TEXT=divider-text SCROLLVAR=scroll-variable SCRVHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON INITATTR= <u>NT</u> CT ET WT WASL HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname	ATTR COMMENT SOURCE	AREA PANEL REGION
DD	No	<i>definition-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	DL
DDHD	No	<i>definition-description-header</i>	HP PS RP	DL
DIVIDER	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n NOENDATTR FORMAT=START CENTER END <i>divider-text</i>	HP	AREA DTACOL PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
DL	Yes	TSIZE= <u>10</u> 'S1, S2,... Sn' BREAK= <u>NONE</u> FIT ALL COMPACT NOSKIP INDENT=n FORMAT=START CENTER END DIVEND= <u>NO</u> YES SPLIT= <u>NO</u> YES	DD DDHD DLDIV DT DTHD DTDIV DTHDIV	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
DLDIV	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n FORMAT=START CENTER END <i>divider-text</i>	HP	DL
DT	No	FORMAT=START CENTER END NOSKIP SPLIT= <u>NO</u> YES <i>definition-term</i>	DTSEG HP PS RP	DL
DTACOL	Yes	PMTWIDTH=n * ** ENTWIDTH=n DESWIDTH=n * SELWIDTH=n * FLDSpace=n PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PMTFMT= <u>CUA</u> ISPF NONE END AUTOTAB= <u>NO</u> YES ATTRCHANGE= <u>NO</u> YES NEW PMTLOC= <u>BEFORE</u> ABOVE DBALIGN= <u>YES</u> NO PROMPT FIELD FORCE VARCLASS=variable-class-name REQUIRED= <u>NO</u> YES CAPS= <u>OFF</u> ON VARDCL= <u>YES</u> NO	COMMENT DIVIDER DTAFLD GRPHDR SELFLD SOURCE	AREA PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
DTAFLD	No	NAME=field-name DATAVAR=field-data VARCLASS=variable-class-name HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname USAGE= <u>BOTH</u> IN OUT REQUIRED= <u>NO</u> YES MSG=message-identifier AUTOTAB= <u>NO</u> YES ENTWIDTH=n PMTWIDTH=n * ** DESWIDTH=n * FLDSPACE=n ALIGN= <u>START</u> CENTER END PMTLOC= <u>BEFORE</u> ABOVE DISPLAY= <u>YES</u> NO NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PMTFMT= <u>CUA</u> ISPF NONE END PSVAR=point-and-shoot-variable %varname PSVAL=point-and-shoot-value %varname PAS=%varname CSRGRP= <u>NO</u> YES n EXPAND FLDWIDTH=n ATTRCHANGE= <u>NO</u> YES NEW INIT=initial-value DEPTH=n %varname IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname DBALIGN= <u>YES</u> NO PROMPT FIELD FORCE PMTSKIP= <u>NO</u> YES DESSKIP= <u>NO</u> YES FLDTYPE= <u>CUA</u> ISPF COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname ATTRCHAR=code CAPS= <u>OFF</u> ON NOJUMP= <u>OFF</u> ON AUTOTYPE=PROJECT GROUP1 GROUP2 GROUP3 GROUP4 TYPE MEMBER DSN AUTOVOL=volser-name AUTODMEM= <u>YES</u> NO VARDCL= <u>YES</u> NO prompt-text	ASSIGNL COMMENT DTAFLDD HP PS RP SOURCE SCRFLD	AREA DTACOL PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
DTAFLDD	No	<i>description</i>	HP PS RP	DTAFLD
DTDIV	No			DL
DTHD	No	<i>definition-term-header</i>	HP PS RP	DL
DTHDIV	No			DL
DTSEG	No			DT
FIG	Yes	FRAME= <u>RULE</u> NONE WIDTH= <u>PAGE</u> COL NOSKIP <i>figure-content</i>	DL FIGCAP HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
FIGCAP	No	<i>figure-caption-text</i>	HP PS RP	FIG
GA	No	NAME=graphic-area-name EXTEND= <u>OFF</u> ON FORCE DEPTH=n * WIDTH=n DIV= <u>NONE</u> BLANK SOLID DASH TEXT FORMAT=START CENTER END TEXT=divider-text LVLINE=variable-name		AREA PANEL REGION
GENERATE	Yes	SUBSTITUTE= <u>NO</u> YES	ATTR COMMENT SOURCE	AREA HELP PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
GRPHDR	No	FORMAT= <u>START</u> CENTER END NONE WIDTH=n FMTWIDTH=n INDENT=n HEADLINE= <u>NO</u> YES DIV= <u>NONE</u> BLANK SOLID DASH DIVLOC= <u>AFTER</u> BEFORE BOTH COMPACT STRIP <i>group-heading-text</i>	HP PS RP	AREA DTACOL PANEL REGION
HELP	Yes	NAME=help-panel-name HELP=hhelp-panel-name %varname HELPDEF=helpdef-id WIDTH= <u>50</u> n FIT DEPTH= <u>10</u> n FIT CCSID=n TUTOR KEYLIST=key-list-name KEYLTYPE= <u>PRIVATE</u> SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA= <u>NO</u> YES MSGLINE= <u>YES</u> NO IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname ZUP=zup-id ZCONT=zcont-id <i>help-panel-title</i>	AREA COMMENT DIVIDER GENERATE HP INFO REGION SOURCE TEXTLINE	
HELPDEF	No	ID=helpdef-id HELP=hhelp-panel-name %varname WIDTH=n FIT DEPTH=n FIT CCSID=n KEYLIST=key-list-name KEYLTYPE= <u>PRIVATE</u> SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA= <u>NO</u> YES IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname		
H1	No	COMPACT <i>heading-text</i>		INFO

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
H2/H3/H4	No	COMPACT <i>heading-text</i>	HP PS RP	INFO
HP	Yes	TYPE= <u>ET</u> CH CT FP LEF LI NT PT SAC TEXT WASL WT COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname INTENSE=varname <i>phrase-to-be-highlighted</i>		ATTENTION BOTINST CAUTION CHDIV CHOICE CMDAREA DD DDHD DIVIDER DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 HELP LI LINES LP LSTCOL LSTGRP NOTE NT P PANEL PD PNLINST PT SELFLD TOPINST WARNING XMP

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
INFO	Yes	WIDTH=format-width * INDENT=n	DIVIDER DL FIG Hn LINES NOTE NOTEL NT OL P PARML SL SOURCE UL XMP	AREA HELP PANEL REGION
KEYI	No	KEY=virtual-key CMD=internal-command-name CASE= <u>UPPER</u> MIXED FKA= <u>NO</u> YES LONG SHORT PARM=parm-string <i>FKA-text</i>		KEYL
KEYL	Yes	NAME=key-list-name HELP=help-panel-name ACTION=UPDATE DELETE APPLID=application-id	KEYI	
LI	No	SPACE= <u>NO</u> YES NOSKIP <i>item-text</i>	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
LINES	Yes	NOSKIP <i>text</i>	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
LIT	Yes	<i>literal-display-value</i>		XLATI
LP	No	NOSKIP <i>implied-paragraph</i>	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
LSTCOL	No	DATAVAR=column-data VARCLASS=variable-class-name HELP= <u>NO</u> YES help-panel-name * help-message-id %varname *%varname USAGE= <u>BOTH</u> IN OUT REQUIRED= <u>NO</u> YES MSG=message-id COLWIDTH=data-width ALIGN= <u>START</u> CENTER END AUTOTAB= <u>NO</u> YES LINE=n CLEAR POSITION=n FORMAT= <u>START</u> CENTER END TEXT=descriptive-text TEXTLOC= <u>BEFORE</u> AFTER TEXTFMT= <u>START</u> CENTER END TEXTLEN=n TEXTSKIP= <u>NO</u> YES NOENDATTR PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname PAS= <u>OFF</u> ON %varname CSRGRP= <u>NO</u> YES n ATTRCHANGE= <u>NO</u> YES NEW COLSPACE=n COLTYPE= <u>CUA</u> ISPF EE VOI LID COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname CAPS= <u>OFF</u> ON DISPLAY= <u>YES</u> NO VARDCL= <u>YES</u> NO <i>column-heading</i>	COMMENT HP PS RP SOURCE SCRFLD	LSTFLD LSTGRP
LSTFLD	Yes	RULES= <u>NONE</u> HORIZ VERT BOTH ROWS= <u>NOSCAN</u> SCAN %varname DIV= <u>NONE</u> BLANK SOLID DASH char SCROLLVAR=scroll-variable SCRHELP= <u>NO</u> YES scroll-help-panel-name *scroll-help-message-id %varname *%varname SCROLLTAB= <u>NO</u> YES SCRCAPS= <u>OFF</u> ON ATTRCHANGE= <u>NO</u> YES NEW VARDCL= <u>YES</u> NO	COMMENTL STCOL LSTGRP LSTVAR SOURCE	AREA PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
LSTGRP	Yes	HEADLINE= <u>NO</u> YES DASH ALIGN= <u>CENTER</u> START END <i>column-group-heading</i>	COMMENT HP LSTCOL LSTGRP LSTVAR PS RP SOURCE	LSTFLD LSTGRP
LSTVAR	No	DATAVAR=variable-model-name LINE=n <i>column-heading</i>	COMMENT HP PS RP SOURCE	LSTFLD LSTGRP
M	No	<i>mnemonic-character</i>		ABC PDC
MSG	No	SUFFIX=message-suffix-number HELP=help-panel-name %varname * MSGTYPE= <u>INFO</u> WARNING ACTION CRITICAL %varname LOCATION=AREA MODAL MODAL(L) MODELESS MODELESS (L) %varname DISP=KANA NOKANA ALARM= <u>NO</u> YES %varname ABBREV= <u>NONE</u> KEYWORD VALUE BOTH FORMAT= <u>FLOW</u> ASIS SMSG=short-message-text <i>message-text</i>	VARSUB	MSGMBR
MSGMBR	Yes	NAME=message-member-name CCSID=n WIDTH= <u>76</u> 68	COMMENTM SG	
NOTE	No	NOSKIP INDENT=n TYPE= <u>ET</u> CH CT FP LEF LI NT PT SAC TEXT WASL WT COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname TEXT=alternate-note-heading <i>note-text</i>	HP PS RP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
NOTEL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TYPE= <u>ET</u> CH CT FP LEF LI NT PT SAC TEXT WASL WT COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname TEXT=alternate-note-heading	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
NT	Yes	NOSKIP INDENT= <u>n</u> TYPE= <u>ET</u> CH CT FP LEF LI NT PT SAC TEXT WASL WT COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname TEXT=alternate-note-heading <i>note-text</i>	DL FIG HP LINES OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
OL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT= <u>n</u> TEXT=OL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
P	No	COMPACT INTENSE=varname INDENT= <u>n</u> OFFSET= <u>n</u> SPACE= <u>NO</u> YES <i>paragraph-text</i>	ATTENTION CAUTION HP PS RP WARNING	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
PANDEF	No	ID=pandef-id HELP=help-panel-name %varname DEPTH=n FIT WIDTH=n FIT %varname KEYLIST=key-list-name KEYLTYPE= <u>PRIVATE</u> SHARED APPLID=application-id CCSID=n WINDOW= <u>YES</u> NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname EXPAND=xy MERGESAREA= <u>NO</u> YES ENTKEYTEXT=enter-key-text IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname TMARGIN=n BMARGIN=n		

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
PANEL	Yes	NAME=panel-name HELP=help-panel-name %varname PANDEF=pandef-id DEPTH= <u>22</u> n FIT WIDTH= <u>76</u> n FIT %varname KEYLIST=key-list-name KEYLTYPE= <u>PRIVATE</u> SHARED APPLID=application-id CURSOR=cursor-field CSRINDEX=index-value CSRPOS=position-value CCSID=n MENU PRIME TUTOR WINDOW= <u>YES</u> NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname EXPAND=xy MSGLINE= <u>YES</u> NO TITLINE= <u>YES</u> NO CMDLINE= <u>YES</u> NO ATTRUSE= <u>NO</u> YES ALL ENDATTR= <u>DEFAULT</u> TEXT TYPE= <u>BOTH</u> GUI NOGUI SMSG=short-msg-fieldname LMSG=long-msg-fieldname ASIS ACTBAR MERGESAREA= <u>NO</u> YES PANELSTMT= <u>YES</u> NO ENTKEYTEXT=enter-key-text IMAPNAME=image-name %varname IMAPROW=n %varname IMAPCOL=n %varname TMARGIN=n BMARGIN=n ERRORCHECK= <u>NO</u> YES ZUP=zup-id ZCONT=zcont-id AUTONRET= <u>NO</u> YES AUTOTCMD= <u>NO</u> YES PROC panel-title-text	AB AREA BOTINST CMDAREA COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR HP INFO LSTFLD PNLINST REGION SELFID SOURCE TEXTLINE TOPINST	

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
PARML	Yes	TSIZE= <u>10</u> 'S1 S2... Sn' BREAK= <u>ALL</u> FIT NONE COMPACT SKIP INDENT=n FORMAT=START CENTER END DIVEND= <u>NO</u> YES SPLIT= <u>NO</u> YES	PLDIV PT PTDIV PD	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
PD	No	<i>parameter-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	PARML
PDC	No	HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname UNAVAIL=unavail-variable-name CHECKVAR=check-variable-name MATCH= <u>1</u> match-string ACC1=key1 ACC2=key2 ACC3=key3 <i>pull-down-description-text</i>	ACTION COMMENT M SOURCE	ABC
PDSEP	No			PDC
PLDIV	No	TYPE= <u>NONE</u> SOLID DASH TEXT GAP= <u>YES</u> NO GUTTER= <u>1</u> n FORMAT=START CENTER END <i>divider-text</i>	HP	PARML
PNLINST	No	COMPACT <i>instruction-text</i>	HP PS RP	AREA REGION PANEL

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
PS	Yes	VAR=point-and-shoot-variable-name %varname VALUE=point-and-shoot-value %varname * CSRGRP= <u>NO</u> YES n DEPTH=n %varname IMAPNAME=image-name %varname IMAPNAMEP=image-namep %varname PLACE= <u>ABOVE</u> BELOW LEFT RIGHT %varname <i>point-and-shoot-text</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP
PT	No	FORMAT= <u>START</u> CENTER END NOSKIP SPLIT= <u>NO</u> YES <i>parameter-term</i>	HP PS PTSEG RP	PARML
PTDIV	No			PARML
PTSEG	No			PT

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
REGION	Yes	DIR= <u>VERT</u> HORIZ INDENT=n WIDTH=n * DEPTH=n * EXTEND= <u>OFF</u> ON FORCE ALIGN= <u>YES</u> NO GRPBOX= <u>NO</u> YES GRPWIDTH=n GRPBXVAR=variable-name GRPBXMAT= <u>1</u> string LOCATION= <u>DEFAULT</u> TITLE <i>group-box-title</i>	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELFLD SOURCE	AREA HELP PANEL REGION
RP	Yes	HELP= help-panel-name help-message-id %varname *%varname <i>reference-phrase</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
SCRFLD	Yes	DISPLEN= n %varname INDVAR=ind-var INDVAL='ind-chars' LINDVAR=lind-var LINDVAL='lind-char' RINDVAR=rind-var RINDVAL='rind-char' SINDVAR=sind-var SINDVAL='sind-chars' LCOLIND=lcol-var LCOLDISP= <u>NO</u> YES RCOLIND=rcol-var RCOLDISP= <u>NO</u> YES SCALE=scale-var SCROLL= <u>ON</u> OFF %varname FLDSPOS= <u>BELOW</u> ABOVE	COMMENT SOURCE	DTAFLD LSTCOL

Table 21. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
SELFLD	Yes	NAME=field-name HELP= <u>NO</u> YES help-panel-name *help-message-id %varname *%varname TYPE= <u>SINGLE</u> MULTI MENU MODEL TUTOR PMTLOC= <u>ABOVE</u> BEFORE PMTWIDTH=n * ** SELWIDTH=n * ENTWIDTH= <u>2</u> n 'e1 e2...en' REQUIRED= <u>NO</u> YES MSG=message-identifier FCHOICE= <u>1</u> 0 AUTOTAB= <u>YES</u> NO DEPTH=n * EXTEND= <u>OFF</u> ON FORCE TRAIL='trail-var-1 trail-var-2 ... trail-var-n' CHOICECOLS= <u>1</u> n CHOICEDEPTH=n * CWIDTHS='w1 w2...wn' PAD=NULLS USER char %varname PADC=NULLS USER char %varname OUTLINE= <u>NONE</u> L R O U BOX %varname SELMSG=selfld-msg-identifier SELMSGU=selfld-msg-unavailable INIT= <u>YES</u> NO init-value VERIFY= <u>YES</u> NO REFRESH= <u>YES</u> NO SELFMT= <u>START</u> END CHKBOX= <u>YES</u> NO ZGUI= <u>YES</u> NO CSRGRP= <u>NO</u> YES n TSIZE='s1 s2...sn' LISTTYPE=RADIO LISTBOX DDLIST COMBO LISTREF=list-name LISTDEPTH=n DBALIGN= <u>YES</u> NO FIELD FORCE NOSEL=no-selection-value SELDEFAULT=x PMTSKIP= <u>NO</u> YES FLDTYPE= <u>CUA</u> ISPF COLOR=WHITE RED BLUE GREEN PINK YELLOW TURQ %varname INTENS= <u>HIGH</u> LOW NON %varname HILITE=USCORE BLINK REVERSE %varname SELCHECK= <u>NO</u> YES VARDCL= <u>YES</u> NO <i>field-prompt-text</i>	CHDIV CHOICE COMMENT HP PS RP SOURCE	AREA DTACOL PANEL REGION

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
SL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT=n TEXT='SL-heading-text'	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
SOURCE	Yes	TYPE= <u>PROC</u> REINIT INIT ABCINIT ABCPROC <i>text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP PANEL PDC REGION SELFELD
T	No			CMD
TEXTLINE	Yes		DTAFLD TEXTSEG	HELP PANEL
TEXTSEG	No	EXPAND=AFTER BEFORE BOTH WIDTH=n <i>text</i>	HP	TEXTLINE
TOPINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
UL	Yes	COMPACT NOSKIP SPACE= <u>NO</u> YES INDENT=n TEXT=UL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
VARCLASS	No	NAME=variable-class-name TYPE='CHAR maximum length' 'DBCS maximum length' 'MIXED maximum length' 'ANY maximum length' 'EBCDIC maximum length' '%varname maximum length' ITIME STDTIME IDATE STDDATE JDATE JSTD 'VMASK maximum-length' 'NUMERIC total-digits <u>0</u> fractional-digits' MSG=message-identifier	CHECKL XLATL	
VARDCL	No	NAME=name VARCLASS=variable-class-name		VARLIST
VARLIST	Yes		VARDCL	
VARSUB	No	VAR=variable-name		MSG
WARNING	Yes	text	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P

Table 21. Tag summary (continued)				
Tag	End tag	Attributes	Nested tags	Used within
XLATI	No	VALUE=internal-value <i>displayed-value</i>	LIT	XLATL
XLATL	Yes	FORMAT= <u>NONE</u> UPPER TRUNC=n char MSG=message-identifier	XLATI	VARCLASS
XMP	Yes	NOSKIP <i>text</i>	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING

Appendix A. Accessibility

Accessible publications for this product are offered through [IBM Documentation for z/OS \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS documentation see [How to Send Feedback to IBM](#) to leave documentation feedback.

Notices

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
United States of America*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Corporation
Site Counsel
2455 South Road*

Poughkeepsie, NY 12601-5400
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at ibm.com/privacy and IBM's Online Privacy Statement at ibm.com/privacy/details in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at ibm.com/software/info/product-privacy.

Policy for unsupported hardware

Various z/OS elements, such as DFSMSdfp, JES2, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Minimum supported hardware

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

Trademarks

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: [IBM Lifecycle Support for z/OS \(www.ibm.com/software/support/systemsz/lifecycle\)](http://www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

Programming Interface Information

This publication primarily documents information that is NOT intended to be used as Programming Interfaces of ISPF.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of ISPF. This information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

```
+-----Programming Interface information-----+  
  
+-----End of Programming Interface information-----+
```

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at [Copyright and Trademark information \(www.ibm.com/legal/copytrade.shtml\)](http://www.ibm.com/legal/copytrade.shtml).

Index

A

accessibility
 contact IBM [279](#)
ACCTINFO Service [183](#)
assistive technologies [279](#)
AUTHCODE Service [184](#)

C

code, return
 VERHIST service [209](#)
commands
 reading syntax diagrams [xv](#)
contact
 z/OS [279](#)

F

fragments, syntax diagrams [xv](#)

G

generating a member generation list [65](#)
GENLIST service
 description [65](#)

K

keyboard
 navigation [279](#)
 PF keys [279](#)
 shortcut keys [279](#)
keywords, syntax diagrams [xv](#)

M

member list
 generating [65](#)
multicultural support [205](#)

N

National Language Support [205](#)
navigation
 keyboard [279](#)
NLS [205](#)

P

parameters
 VERHIST service [208](#)

R

repeatable items, syntax diagrams [xv](#)
return codes
 VERHIST service [209](#)

S

service
 ACCTINFO [183](#)
 AUTHCODE [184](#)
 VERHIST [208](#)
shortcut keys [279](#)
summary of changes [xxiii](#)
syntax diagrams, how to read [xv](#)

T

trademarks [284](#)

U

user interface
 ISPF [279](#)
 TSO/E [279](#)

V

variables, syntax diagrams [xv](#)
VERHIST service [208](#)

Z

ZABSGEN [239](#)



Product Number: 5655-ZOS

SC19-3624-70

