



**Program Directory for  
AFP Conversion & Indexing Facility  
Feature of PSF for z/OS**

V04.07.00

Program Number 5655-M32

FMID HQN4470

for Use with  
z/OS

Document Date: December 2019

GI13-3009-03



**Note**

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 21.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

**Copyright International Business Machines Corporation 1993, 2019.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.



---

# Contents

<b>1.0 Introduction</b>	<b>1</b>
1.1 ACIF Description	1
1.2 ACIF FMID	2
<b>2.0 Program Materials</b>	<b>3</b>
2.1 Basic Machine-Readable Material	3
2.2 Program Publications	3
2.3 Program Source Materials	3
2.4 Publications Useful During Installation	4
<b>3.0 Program Support</b>	<b>5</b>
3.1 Program Services	5
3.2 Preventive Service Planning	5
3.3 Statement of Support Procedures	6
<b>4.0 Program and Service Level Information</b>	<b>7</b>
4.1 Program Level Information	7
4.2 Service Level Information	7
<b>5.0 Installation Requirements and Considerations</b>	<b>9</b>
5.1 Driving System Requirements	9
5.1.1 Machine Requirements	9
5.1.2 Programming Requirements	9
5.2 Target System Requirements	10
5.2.1 Machine Requirements	10
5.2.2 Programming Requirements	10
5.2.2.1 Installation Requisites	10
5.2.2.2 Operational Requisites	11
5.2.2.3 Toleration/Coexistence Requisites	11
5.2.2.4 Incompatibility (Negative) Requisites	11
5.2.3 DASD Storage Requirements	11
5.3 FMIDs Deleted	14
5.4 Special Considerations	14
5.4.1 SYS1.PARMLIB member IFAPRD00	14
<b>6.0 Installation Instructions</b>	<b>15</b>
6.1 Installing ACIF	15
6.1.1 SMP/E Considerations for Installing ACIF	15
6.1.2 SMP/E Options Subentry Values	15
6.1.3 SMP/E CALLLIBS Processing	15
6.1.4 Sample Jobs	16
6.1.5 Perform SMP/E RECEIVE	16



6.1.6 Allocate SMP/E Target and Distribution Libraries . . . . .	17
6.1.7 Allocate File System Paths . . . . .	17
6.1.8 Create DDDEF Entries . . . . .	17
6.1.9 Perform SMP/E APPLY . . . . .	17
6.1.10 Perform IVP's . . . . .	18
6.1.11 Perform SMP/E ACCEPT . . . . .	19
6.1.12 Run REPORT CROSSZONE . . . . .	20
6.1.13 Dynamic Enablement - Update PARMLIB . . . . .	20
<b>7.0 Notices . . . . .</b>	<b>21</b>
7.1 Trademarks . . . . .	21
<b>Reader's Comments . . . . .</b>	<b>25</b>

## --- **Figures**

1. Basic Material: Unlicensed Publications . . . . .	3
2. Publications Useful During Installation . . . . .	4
3. PSP Upgrade and Subset ID . . . . .	5
4. Component IDs . . . . .	6
5. Driving System Software Requirements . . . . .	10
6. Total DASD Space Required by ACIF . . . . .	11
7. Storage Requirements for ACIF Target Libraries . . . . .	13
8. Storage Requirements for ACIF Distribution Libraries . . . . .	13
9. Storage Requirements for ACIF Non-SMP/E Data Sets . . . . .	13
10. SMP/E Options Subentry Values . . . . .	15
11. Sample Installation Jobs . . . . .	16



---

## 1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of AFP Conversion & Indexing Facility. This publication refers to AFP Conversion & Indexing Facility as ACIF.

The Program Directory contains the following sections:

2.0, "Program Materials" on page 3 identifies the basic program materials and documentation for ACIF.

3.0, "Program Support" on page 5 describes the IBM support available for ACIF.

4.0, "Program and Service Level Information" on page 7 lists the APARs (program level) and PTFs (service level) that have been incorporated into ACIF.

5.0, "Installation Requirements and Considerations" on page 9 identifies the resources and considerations that are required for installing and using ACIF.

6.0, "Installation Instructions" on page 15 provides detailed installation instructions for ACIF. It also describes the procedures for activating the functions of ACIF, or refers to appropriate publications.

Before installing ACIF, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; after which, keep the documents for your reference. Section 3.2, "Preventive Service Planning" on page 5 tells you how to find any updates to the information and procedures in this program directory.

ACIF is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for ACIF are included on the CBPDO.

Do not use this program directory if you install ACIF with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

---

## 1.1 ACIF Description

ACIF is a tool that you can use to convert a line data, mixed data, unformatted ASCII, or XML print file into a MO:DCA-P document, retrieve resources that are used by the document, and index the file for later retrieval and viewing. ACIF provides these functions across systems and operating systems:

Converts traditional and record format line data, mixed data, and XML print files to MO:DCA-P documents

Creates a separate index object file from the indexing tags in a MO:DCA-P document



Retrieves and packages AFP resources that are needed for printing or viewing a MO:DCA-P document

Accepts the MO:DCA interchange sets data streams

---

## **1.2 ACIF FMID**

ACIF consists of the following FMID:

HQN4470



---

## 2.0 Program Materials

An IBM program is identified by a program number. The program number for ACIF is 5655-M32.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by ACIF. Ask your IBM representative for this information if you have not already received a copy.

---

### 2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 15 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for ACIF in the *CBPDO Memo To Users Extension*.

---

### 2.2 Program Publications

The following sections identify the basic publications for ACIF.

Figure 1 identifies the basic unlicensed publications for ACIF. Those that are in softcopy format publications can be obtained from the IBM Publications Center website at <https://www.ibm.com/support/knowledgecenter>.

<i>Figure 1. Basic Material: Unlicensed Publications</i>		
Publication Title	Form Number	Media Format
AFP Conversion & Indexing Facility: User's Guide	S550-0436	<a href="https://www.ibm.com/support/knowledgecenter">https://www.ibm.com/support/knowledgecenter</a>

---

### 2.3 Program Source Materials

No program source materials or viewable program listings are provided for ACIF.



---

## 2.4 Publications Useful During Installation

You might want to use the publications listed in Figure 2 on page 4 during the installation of ACIF.

<i>Figure 2. Publications Useful During Installation</i>		
<b>Publication Title</b>	<b>Form Number</b>	<b>Media Format</b>
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277	<a href="https://www.ibm.com/support/knowledgecenter">https://www.ibm.com/support/knowledgecenter</a>
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275	<a href="https://www.ibm.com/support/knowledgecenter">https://www.ibm.com/support/knowledgecenter</a>
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276	<a href="https://www.ibm.com/support/knowledgecenter">https://www.ibm.com/support/knowledgecenter</a>
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883	<a href="https://www.ibm.com/support/knowledgecenter">https://www.ibm.com/support/knowledgecenter</a>



---

## 3.0 Program Support

This section describes the IBM support available for ACIF.

---

### 3.1 Program Services

Contact your IBM representative for specific information about available program services.

---

### 3.2 Preventive Service Planning

Before you install ACIF, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.PRODUCTINSTALL-REQUIREDSERVICE fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.PRODUCTINSTALL-REQUIREDSERVICE)** operand on the **APPLY CHECK** command. See 6.1.9, “Perform SMP/E APPLY” on page 17 for a sample APPLY command

If you obtained ACIF as part of a CBPDO, HOLDDATA is included.

If the CBPDO for ACIF is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<http://www14.software.ibm.com/webapp/set2/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <http://www.ibm.com/support/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for ACIF are included in Figure 3.

<i>Figure 3. PSP Upgrade and Subset ID</i>		
UPGRADE	SUBSET	Description
ACIF470	HQN4470	ACIF



---

### 3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 4 on page 6 identifies the component IDs (COMPID) for ACIF.

<i>Figure 4. Component IDs</i>			
<b>FMID</b>	<b>COMPID</b>	<b>Component Name</b>	<b>RETAIN Release</b>
HQN4470	564806201	ACIF	470



---

## 4.0 Program and Service Level Information

This section identifies the program and relevant service levels of ACIF. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

---

### 4.1 Program Level Information

The following APAR fixes against previous releases of ACIF have been incorporated into this release. They are listed by FMID.

FMID HQN4460

PI92292  
PI93196  
PI95910

PI97203  
PI99611

PI10629  
PI12468

---

### 4.2 Service Level Information

No PTFs against this release of ACIF have been incorporated into the product package.

Frequently check the ACIF PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your **APPLY CHECK** command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.







---

## 5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating ACIF. The following terminology is used:

*Driving system:* the system on which SMP/E is executed to install the program.

The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.

*Target system:* the system on which the program is configured and run.

The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.

When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

---

### 5.1 Driving System Requirements

This section describes the environment of the driving system required to install ACIF.

#### 5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

#### 5.1.2 Programming Requirements



Figure 5. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	V02.02.00 or higher	N/A	No

**Note:** SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

**Note:** Installation might require migration to new z/OS releases to be service supported. See [https://www-01.ibm.com/software/support/lifecycle/index\\_z.html](https://www-01.ibm.com/software/support/lifecycle/index_z.html).

## 5.2 Target System Requirements

This section describes the environment of the target system required to install and use ACIF.

ACIF installs in the z/OS (Z038) SREL.

### 5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

### 5.2.2 Programming Requirements

#### 5.2.2.1 Installation Requisites

Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

ACIF has no mandatory installation requisites.

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

ACIF has no conditional installation requisites.



### 5.2.2.2 Operational Requisites

Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

ACIF has no mandatory operational requisites.

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

ACIF has no conditional operational requisites.

### 5.2.2.3 Toleration/Coexistence Requisites

Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

ACIF has no toleration/coexistence requisites.

### 5.2.2.4 Incompatibility (Negative) Requisites

Negative requisites identify products that must *not* be installed on the same system as this product.

ACIF has no negative requisites.

## 5.2.3 DASD Storage Requirements

ACIF libraries can reside on all supported DASD types.

Figure 6 lists the total space that is required for each type of library.

Figure 6. Total DASD Space Required by ACIF		
Library Type	Total Space Required in 3390 Trks	Description
Target	138 Tracks	
Distribution	133 Tracks	

#### Notes:



1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.

2. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.6, "Allocate SMP/E Target and Distribution Libraries" on page 17.

3. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE, with some exceptions. If the value in the "ORG" column specifies "PDS", the data set must be a PDS. If the value in "DIR Blks" column specifies "N/A", the data set must be a PDSE.

4. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

5. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can not be in the LPA, with some exceptions. If the value in the "Member Type" column specifies "LPA", it is advised to place the data set in the LPA.
- These data sets can be in the LNKLIST.
- These data sets are not required to be APF-authorized, with some exceptions. If the value in the "Member Type" column specifies "APF", the data set must be APF-authorized.



The following figures describe the target and distribution libraries and file system paths required to install ACIF. The storage requirements of ACIF must be added to the storage required by other programs that have data in the same library or path.

**Note:** Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

<i>Figure 7. Storage Requirements for ACIF Target Libraries</i>								
Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SAPKMOD1	MOD	ANY	U	PDS	U	0	125	2
SAPKSAM1	SAMP	ANY	U	PDS	FB	80	2	1
SAPKSAM2	SAMP	ANY	U	PDS	FB	80	2	1
SAPKSAM3	DATA	ANY	U	PDS	FBA	200	6	1
SAPKULIB	PROBJ	ANY	U	PDS	VBM	8205	3	1

Figure 8. Storage Requirements for ACIF Distribution Libraries						
Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AAPKMOD1	U	PDS	U	0	120	31
AAPKSAM1	U	PDS	FB	80	2	1
AAPKSAM2	U	PDS	FB	80	2	1
AAPKSAM3	U	PDS	FBA	200	6	1
AAPKULIB	U	PDS	VBM	8205	3	1

The following figures list data sets that are not used by SMP/E, but are required for ACIF to run.

<i>Figure 9 (Page 1 of 2). Storage Requirements for ACIF Non-SMP/E Data Sets</i>						
Data Set Name	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
APK.ACIF.IVPSAMP.INDEX	U	SEQ	VBM	32756	1	0



Figure 9 (Page 2 of 2). Storage Requirements for ACIF Non-SMP/E Data Sets

Data Set Name	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
APK.ACIF.IVPSAMP.OUTPUT	U	SEQ	VBM	32756	6	0
APK.ACIF.IVPSAMP.RESLIB	U	PDS	VBM	12284	2	15

## 5.3 FMIDs Deleted

Installing ACIF might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install ACIF into separate SMP/E target and distribution zones.

**Note:** These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

## 5.4 Special Considerations

### 5.4.1 SYS1.PARMLIB member IFAPRD00

The SYS1.PARMLIB member, IFAPRD00, may have been customized by IBM to enable the IBM products and optional integrated features specifically ordered by you.

Please verify that the SYS1.PARMLIB member IFAPRD00 contains the following information for ACIF and add if necessary. If the following information needs to be added, console command SET PROD=00 must be issued to activate the changes.

```
PRODUCT OWNER('IBM CORP')
  NAME('PSF for z/OS')
  ID(5655-M32)
  VERSION(*)
  RELEASE(*)
  MOD(*)
  FEATURENAME('ACIF')
  STATE(ENABLED)
```



---

## 6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of ACIF.

Please note the following points:

If you want to install ACIF into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMP/CSI and the SMP/E control data sets.

You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.

You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

---

### 6.1 Installing ACIF

#### 6.1.1 SMP/E Considerations for Installing ACIF

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of ACIF.

#### 6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 10. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

<i>Figure 10. SMP/E Options Subentry Values</i>		
Subentry	Value	Comment
DSSPACE	(60,10,35)TRK	The recommended value for ACIF
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

#### 6.1.3 SMP/E CALLLIBS Processing

ACIF uses the CALLLIBS function provided in SMP/E to resolve external references during installation. When ACIF is installed, ensure that DDDEFs exist for the following libraries:

SCEELKED

**Note:** CALLLIBS uses the previous DDDEFs only to resolve the link-edit for ACIF. These data sets are not updated during the installation of ACIF.



## 6.1.4 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install ACIF:

Figure 11. Sample Installation Jobs			
Job Name	Job Type	Description	RELFILE
APKJALOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HQN4470.F3
APKJDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HQN4470.F3

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.5, “Perform SMP/E RECEIVE” on page 16) then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 11 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the product files by submitting the following job. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1      EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN         DD DSN=IBM.HQN4470.F3,UNIT=SYSALLDA,DISP=SHR,
//           VOL=SER=filevol
//OUT        DD DSNAME=jcl-library-name,
//           DISP=(NEW,CATLG,DELETE),
//           VOL=SER=dasdvol,UNIT=SYSALLDA,
//           SPACE=(TRK,(2,1,2))
//SYSUT3     DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN      DD *
            COPY INDD=IN,OUTDD=OUT
/*
```

See the following information to update the statements in the previous sample:

IN:

**filevol** is the volume serial of the DASD device where the downloaded files reside.

OUT:

**jcl-library-name** is the name of the output data set where the sample jobs are stored.

**dasdvol** is the volume serial of the DASD device where the output data set resides.

## 6.1.5 Perform SMP/E RECEIVE

If you have obtained ACIF as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the ACIF FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.



## 6.1.6 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job APKJALOC to allocate the SMP/E target and distribution libraries for ACIF. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.7 Allocate File System Paths

## 6.1.8 Create DDDEF Entries

Edit and submit sample job APKJDDDEF to create DDDEF entries for the SMP/E target and distribution libraries for ACIF. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.9 Perform SMP/E APPLY

Perform an SMP/E APPLY CHECK for ACIF.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

- a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```



Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the `BYPASS(HOLDCLASS(HIPER))` operand to the `APPLY CHECK` command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the `SMP/E REPORT ERRSYSMODS` command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the `REPORT ERRSYSMODS` command to investigate any unresolved HIPERs. If you have received the latest `HOLDDATA`, you can also choose to use the `REPORT MISSINGFIX` command and specify Fix Category `IBM.PRODUCTINSTALL-REQUIREDSERVICE` to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

1. After you take actions that are indicated by the `APPLY CHECK`, remove the `CHECK` operand and run the job again to perform the `APPLY`.

**Note:** The `GROUPEXTEND` operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from APPLY CHECK:** You will receive a return code of 0 if this job runs correctly.

**Expected Return Codes and Messages from APPLY:** You will receive a return code of 0 if this job runs correctly.

### 6.1.10 Perform IVP's

Prior to performing the IVP's, please verify the `SYS1.PARMLIB` member `IFAPRD00` contains the following information for ACIF.



```

PRODUCT OWNER('IBM CORP')
      NAME('PSF for z/OS')
      ID(5655-M32)
      VERSION(*)
      RELEASE(*)
      MOD(*)
      FEATURENAME('ACIF')
      STATE(ENABLED)

```

The IVP job supplied for ACIF processes a sample bank statement. To run the IVP, modify the APKIVP job. This job exists in the data set APK.SAPKSAM2(APKIVP). Add a job card that contains the appropriate information for your installation, then submit the job.

This job creates the following MVS data sets:

```

APK.ACIF.IVPSAMP.INDEX
APK.ACIF.IVPSAMP.OUTPUT
APK.ACIF.IVPSAMP.RESLIB

```

The data set APK.ACIF.IVPSAMP.INDEX is a sequential file that contains the indexes to the output data set APK.ACIF.IVPSAMP.OUTPUT.

The data set APK.ACIF.IVPSAMP.RESLIB contains the following resources:

```

C0D0GT18
F1A18D1
O1A183
O1A184
T1D0BASE

```

SYSPRINT contains a list of all the input parameters that are defined in the APKIVP job, and the ACIF default parameters. The last statement is a message that the return code is "0". If the return code is "0", the IVP is completed successfully.

To print the sample output data set, PSF is required. Use your installation's normal process to print documents using the resources saved in the data set APK.ACIF.IVPSAMP.RESLIB.

## 6.1.11 Perform SMP/E ACCEPT

Perform an SMP/E ACCEPT CHECK for ACIF.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the



distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

**Note:** The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from ACCEPT CHECK:** You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

**Expected Return Codes and Messages from ACCEPT:** You will receive a return code of 0 if this job runs correctly.

## 6.1.12 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command identifies requisites for products that are installed in separate zones. This command also creates APPLY and ACCEPT commands in the SMPPUNCH data set. You can use the APPLY and ACCEPT commands to install those cross-zone requisites that the SMP/E REPORT CROSSZONE command identifies.

After you install ACIF, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on.

For more information about REPORT CROSSZONE, see the SMP/E manuals.

## 6.1.13 Dynamic Enablement - Update PARMLIB

To enable ACIF, to run with z/OS, the following entries must be in the IFAPRDxx PARMLIB member:

```
PRODUCT OWNER('IBM CORP')
NAME('PSF for z/OS')
FEATURENAME('ACIF')
VERSION(*) RELEASE(*) MOD(*)
ID('5655-M32')
STATE(ENABLED)
```



---

## 7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, New York 10504-1785  
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan, Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan

---

## 7.1 Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).















---

## Reader's Comments

**Program Directory for AFP Conversion & Indexing Facility, December 2019** We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Send your comments by emailing us at [ibmkc@us.ibm.com](mailto:ibmkc@us.ibm.com), and include the following information:

Your name and address Your email address Your telephone or fax number The publication title and order number The topic and page number related to your comment The text of your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.





Printed in USA

GI13-3009-03

